环境配置

nginx

若以前安装过, 先卸载

```
sudo apt-get --purge remove nginx
sudo apt-get --purge remove nginx-common
dpkg --get-selections|grep nginx
```

1.前置环境

```
sudo apt-get update
sudo apt-get install gcc
sudo apt-get install ruby
sudo apt-get install zlib1g
sudo apt-get install zlib1g.dev
sudo apt-get install libpcre3 libpcre3-dev
sudo apt-get install openssl libssl-dev
```

2.下载nginx源码

下载地址在https://nginx.org 源码在压缩包中附带1.22.1版本, nginx-1.22.1.tar.gz 解压到用户主目录 ~

注意:如果使用向日葵传输文件夹,文件夹的owner和gruop默认是root,对该文件夹的一切操作都需要root权限。或者也可以使用下面的方法:

```
sudo chown -R user <文件夹路径>
sudo chgrp -R user <文件夹路径>
```

3.下载nginx-http-flv-module

在压缩包中附带1.2.10版本nginx-http-flv-module-1.2.10.zip 把nginx-http-flv-module解压,移动到/usr/local目录下,并将文件夹改名为: nginx-http-flv-module

sudo mv nginx-http-flv-module-1.2.10 /usr/local/nginx-http-flv-module

进入nginx目录

cd ~/nginx-1.22.1

将nginx-http-flv-module添加到nginx中

 $\verb|sudo|./configure| --prefix=/usr/local | --with-http_ssl_module| --add-module=/usr/local/nginx-http-flv-module| --add-module=/usr/local/nginx-http-flv-module=/usr/local/nginx-http-flv-module=/usr/local/nginx-http-flv-module=/usr/local/nginx-http-flv-module=$

生成make文件

sudo make

安装

sudo make install

测试是否安装成功

nginx -v

4.配置nginx

需要修改nginx的配置文件,它的位置在nginx-1.22.1/conf/nginx.confnginx.conf文件内容如下:

```
worker_processes 10; #should be 1 for Windows, for it doesn't support Unix domain socket
#worker processes auto; #from versions 1.3.8 and 1.2.5
#worker cpu affinity 0001 0010 0100 1000; #only available on FreeBSD and Linux
#worker_cpu_affinity auto; #from version 1.9.10
error_log logs/error.log error;
#if the module is compiled as a dynamic module and features relevant
#to RTMP are needed, the command below MUST be specified and MUST be
#located before events directive, otherwise the module won't be loaded
#or will be loaded unsuccessfully when NGINX is started
#load_module modules/ngx_http_flv_live_module.so;
events {
    worker connections 10240;
}
http {
        include
                     mime.types;
        default_type application/octet-stream;
        sendfile
        keepalive_timeout 65;
        server {
                            9000; #http-flv的拉流端口
                server_name localhost【这个地方写你的ip、或者说是域名都是可以的--】; #http-flv的拉流ip
                location / {
                root
                     html;
               index index.html index.htm;
               }
           #http-flv的相关配置
               location /live{
               flv_live on; #打开HTTP播放FLV直播流功能
                chunked_transfer_encoding on;
                add_header 'Access-Control-Allow-Origin' '*';
                add_header 'Access-Control-Allow-Credentials' 'true';
                }
                location /hls{
                types {
                       application/vnd.apple.mpegurl m3u8;
                       video/mp2t ts;
                }
                root ~/nginx-1.22.1/html/hls;
                add_header 'Cache-Control' 'no-cache';
                location /dash {
                root ~/nginx-1.22.1/html/dash;
                add_header 'Cache-Control' 'no-cache';
                }
```

```
location /stat {
                #configuration of push & pull status
                rtmp_stat all;
                rtmp_stat_stylesheet stat.xsl;
                }
                location /stat.xsl {
                        root ~/nginx-1.22.1/html;
                }
                location /control {
                rtmp_control all; #configuration of control module of rtmp
                        }
                error_page
                             500 502 503 504 /50x.html;
                location = /50x.html {
                root
                      html;
                }
        }
}
rtmp_auto_push on;
rtmp_auto_push_reconnect 1s;
rtmp_socket_dir /tmp;
rtmp{
        out_queue 4096;
        out_cork 8;
        max_streams 128;
        timeout 15s;
        drop_idle_publisher 15s;
        log_interval 5s;
        log_size 1m;
        server{
            #推流端口
                listen 1935;
            #推流应用名称
                application myapp{
                 live on;
                 record off;
                 gop_cache on;
                application hls{
                        live on;
                        hls on;
                        hls_path ~/nginx-1.22.1/html/hls;
                        hls_fragment 1s;
                        hls_playlist_length 3s;
                }
```

文件中有五处路径为/nginx-1.22.1,在实际使用时要换成具体的目录,例如用户为user,那么这里就要把换成用户主目录/home/user。该文件要放到~/nginx-1.22.1/conf文件夹下

5.启动nginx

```
cd ~/nginx-1.22.1
sudo nginx -c conf/nginx.conf
sudo nginx -s reload
```

6.安装ffmpeg

sudo apt-get install ffmpeg

7.测试推流

ffmpeg -re -i rtsp://wowzaec2demo.streamlock.net/vod/mp4:BigBuckBunny_115k.mp4 -vcodec copy -acodec copy -f flv '

Docker

Docker安装

```
sudo apt-get install curl
curl -sSL https://get.daocloud.io/docker | sh
```

拉取镜像源

sudo docker pull iludfy/predict_model

Docker创建容器并启动

拉取完镜像需要挂载到容器中才能启动,命令是docker run,它的参数如下:

sudo docker run [Options] image

#参数说明

 --name="名字"
 指定容器名字

 -d
 后台方式运行

-it 使用交互方式运行,进入容器查看内容

-p 指定容器的端口

-p ip:主机端口:容器端口 配置主机端口映射到容器端口

-p 主机端口:容器端口(常用)

-p 容器端口

-P 随机指定端口

-e 环境设置

-v 容器数据卷挂载

规定端口为5000,输入下面的命令:

sudo docker run -p 5000:5000 iludfy/predict model

一个容器就已经被创建好并启动了。

端口被占用解决办法:

以ubuntu系统为例:

先查到5000端口被哪个进程占用:

sudo netstat -ntlp

查到进程id后,使用kill命令杀死进程:

sudo kill {pid}

查看刚刚创建的容器的id:

启动

sudo docker start {id}


MySQL 8.0

安装

先切换到root用户下:


sudo su

本文档中使用的操作系统是ubuntu20.04,默认使用apt下载mysql默认版本可能是mysql5,所以先去官网https://dev.mysql.com/downloads/mysql/下载mysql8的源:



MySQL Community Downloads


MySQL APT Repository



我们将下载到的 mysql-apt-config_0.8.24-1_all.deb 文件放到用户主目录下,执行下面的命令:

dpkg -i mysql-apt-config_0.8.24-1_all.deb


会出现下面的界面,选择 mysql server -> mysql-8.0 -> ok



之后我们使用下面的命令安装mysql:

apt-get upgrade
apt-get install mysql-server

安装过程中会让你设置初始密码:



若是没出错就已经安装好了,可以尝试登录一下:

mysql -u root -p

输入刚才的初始密码即可。

```
root@user-NULL:/home/user# mysql -u root -p
Enter password:
Welcome to the MySQL monitor. Commands end with ; or \g.
Your MySQL connection id is 8
Server version: 8.0.32 MySQL Community Server - GPL

Copyright (c) 2000, 2023, Oracle and/or its affiliates.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.

mysql> exit;
Bye
```

远程访问

防火墙这里先不提,需要提前配置好防火墙,开放端口。 mysql8默认只有本机可以访问,如果需要从其他机器远程访问数据库,需要进行配置。 登录数据库,查看权限表:

```
mysql -u root -p
mysql> use mysql;
mysql> select user,host from user where user='root';
```

会查询到如下结果:

这里可以看到root用户的host字段是localhost,代表root用户只有本机可以访问。把它改成%即可远程访问:

```
update user set host = '%' where user ='root';
flush privileges;
```

然后mysql就允许远程主机访问了。

Java

下载jdk

先检验是否安装java:

```
java -version
```

若没有安装java, 会得到如下输出:

```
user@user-NULL:~$ java -version
```

Command 'java' not found, but can be installed with:

```
sudo apt install openjdk-11-jre-headless  # version 11.0.18+10-0ubuntu1~20.04.1, or sudo apt install default-jre  # version 2:1.11-72  
sudo apt install openjdk-16-jre-headless  # version 16.0.1+9-1~20.04  
sudo apt install openjdk-17-jre-headless  # version 17.0.6+10-0ubuntu1~20.04.1  
sudo apt install openjdk-8-jre-headless  # version 8u362-ga-0ubuntu1~20.04.1  
sudo apt install openjdk-13-jre-headless  # version 13.0.7+5-0ubuntu1~20.04
```

上面已经自动列出可选的版本了,我们这里选择java8安装:

```
sudo apt install openjdk-8-jre-headless
sudo apt install openjdk-8-jdk-headless
```

安装好后再检查java安装:

```
user@user-NULL:~$ java -version
openjdk version "1.8.0_362"
OpenJDK Runtime Environment (build 1.8.0_362-8u362-ga-0ubuntu1~20.04.1-b09)
OpenJDK 64-Bit Server VM (build 25.362-b09, mixed mode)
user@user-NULL:~$ javac -version
javac 1.8.0_362
```

配置java环境变量

要配置环境变量,首先需要知道java的安装路径:

```
sudo update-alternatives --config java
```

得到如下输出:

链接组 java (提供 /usr/bin/java)中只有一个候选项: /usr/lib/jvm/java-8-openjdk-amd64/jre/bin/java 无需配置。

拿到路径后打开环境变量配置文件:

sudo vim /etc/environment

| JAVA_HOME="/usr/lib/jvm/java-8-openjdk-amd64/jre/bin/java" |
|--|
| 修改此文件将为系统上的所有用户设置JAVA_HOME路径。 |
| 保存文件并退出编辑器。 |
| 现在重新加载此文件: |
| source /etc/environment |
| 验证是否已设置环境变量: |
| echo \$JAVA_HOME |
| 输出路径: |
| /usr/lib/jvm/java-8-openjdk-amd64/jre/bin/java |
| 其他用户需要执行命令source /etc/environment或注销并重新登录才能应用此设置。 |

在此文件的末尾,添加java路径: