# Stock Technical Analysis with R

Section 2: Stock Technical Indicators

© Diego Fernández García 2015-2017

EXFINSIS www.exfinsis.com



#### **Course Disclaimer**

- **Course Objective.** This course has an educational and informational purpose and doesn't constitute any type of trading or investment advice. All content, including code and data, is presented with no guarantee of exactness or completeness.
- Investment Risk and Uncertainty. All course content and conclusions are based on hypothetical historical back-testing and not real trading with the possibility of future outliers not previously observed within these time series. Past performance doesn't guarantee future returns. Investment risk and uncertainty can possibly lead to its total loss for unleveraged products and even larger for leveraged ones.
- **Responsibility Disclaimer.** The instructor is not responsible for any damages caused by using course content for trading or investment decisions; exclusively transferring all this responsibility to the student. Recommending that the student does own due-diligence based on several scenarios, assumptions and consult a certified financial advisor before taking any trading or investment decision.
- **Non-endorsement.** The instructor doesn't endorse any particular trading strategy and associated stock or investment vehicle. Some are from recent inception and haven't been exposed to a major market correction. Investment vehicles have risk considerations such as liquidity, tracking error, replicating index unpredictability, note issuer credit risk, among others. Therefore, recommending again student does own due-diligence and consult a certified financial advisor before taking any trading or investment decision.



#### **Stock Technical Indicators**

- Stock technical indicators are calculated by applying a certain formula to stock prices and volume data.
- They are used to alert on the need to study price action with greater detail, confirm other technical indicators' signals or predict future stock prices direction.
- They are either plotted on top of price bars as overlays or below as oscillators and there are two main types: lagging and leading stock technical indicators.



## **Lagging Stock Technical Indicators**

- Lagging stock technical indicators are used to follow price movements by identifying uptrends or downtrends.
- They consist of simple moving averages SMA, exponential moving averages EMA, Bollinger bands BB and parabolic stop and reverse SAR among many others.



## **Moving Averages**

- Moving Averages MA are overlays that smooth stock price data to identify trends.
- Simple Moving Averages SMA and Exponential Moving Averages EMA are the most popular.

$$SMA_n = \frac{Sum_n(Close)}{n}$$

$$current \ EMA_n = \frac{2}{n+1} * (current \ Close - previous \ EMA_n) + previous \ EMA_n$$

$$initial\ EMA_n = SMA_n(n\ periods\ Close)$$



## **Bollinger Bands**

- Bollinger bands BB are overlays that identify statistically normal stock price movements. Twenty days and two standard deviations are commonly used for its calculation.
- John Bollinger. "Using Bollinger Bands". Technical Analysis of Stocks & Commodities. 1992.

$$Middle\ Band = SMA_{20}(Close)$$

$$Upper\ Band = SMA_{20}(Close) + 2 * STDEV_{20}(Close)$$

$$Lower\ Band = SMA_{20}(Close) - 2 * STDEV_{20}(Close)$$



#### Parabolic Stop and Reverse

- Parabolic stop and reverse SAR is an overlay that identifies reversal points between stock prices' uptrends and downtrends.
- J. Welles Wilder Jr. "New Concepts in Technical Trading Systems". Commodities Magazine (now Futures Magazine). 1978.
- a. Extreme Point calculation.

**EP**(**Uptrend**) = Highest High Current Uptrend

**EP**(**Downtrend**) = Lowest Low Current Downtrend



#### Parabolic Stop and Reverse

b. Acceleration Factor calculation.

AF(Uptrend) = if(New High in EP(Uptrend)):

 $Current \ AF(Uptrend) = Previous \ AF(Uptrend) + 0.02$ 

 $Else\ Current\ AF(Uptrend) = Previous\ AF(Uptrend)$ 

AF(Downtrend) = if(New Low in EP(Downtrend)):

 $Current \ AF(Downtrend) = Previous \ AF(Downtrend) + 0.02$ 

 $Else\ Current\ AF(Downtrend) = Previous\ AF(Downtrend)$ 



## Parabolic Stop and Reverse

c. Parabolic Stop and Reverse calculation.

$$Current\ SAR(Up) = Previous\ SAR(Up) + Prev.\ AF*(Prev.\ EP(Up) - Prev.\ SAR(Up))$$

$$Current\ SAR(Down) = Previous\ SAR(Dn) - Prev.\ AF*(Prev.\ SAR(Dn) - Prev.\ EP(Dn))$$



# **Leading Stock Technical Indicators**

- Leading stock technical indicators are used to lead price movements by identifying their momentum as either the tendency of rising prices to rise further or falling prices to fall further.
- Most of them are either centered or bounded oscillators and consist of average directional movement index ADX, commodity channel index CCI, moving averages convergence/divergence MACD, rate of change ROC, relative strength index RSI, stochastic momentum index SMI and Williams %R among many others.



- Average directional movement index ADX is a bounded oscillator that measures a stock price trend's strength and momentum. Fourteen days are commonly used for its calculation.
- J. Welles Wilder Jr. "New Concepts in Technical Trading Systems". Commodities Magazine (now Futures Magazine). 1978



a. Daily true range, positive/negative directional movement calculation.

```
TR(1) = Max Between(High - Low, |High - previous Close|, |Low - previous Close|)
```

$$DM(1)p = If (current \ High - previous \ High > previous \ Low - current \ Low):$$

$$DM(1)p = Max \ Between (current \ High - previous \ High, 0)$$

$$Else \ DM(1)p = 0$$

$$DM(1)n = If(previous\ Low - current\ Low > current\ High - previous\ High):$$

$$DM(1)n = Max\ Between(previous\ Low - current\ Low, 0)$$

$$Else\ DM(1)n = 0$$



b. Fourteen days smoothing with Wilder's techniques.

$$TR(14) = prev TR(14) * \left(\frac{prev TR(14)}{14}\right) + TR(1)$$

$$initial TR(14) = SMA_{14}(TR(1))$$

$$DM(14)p = prev DM(14)p * \left(\frac{prev DM(14)p}{14}\right) + DM(1)p$$

$$initial DM(14)p = SMA_{14}(DM(1)p)$$

$$DM(14)n = prev DM(14)n * \left(\frac{prev DM(14)n}{14}\right) + DM(1)n$$

$$initial DM(14)n = SMA_{14}(DM(1)n)$$

**EXFINSIS** www.exfinsis.com

c. Fourteen days positive/negative directional index calculation.

$$DI(14)p = \left| 100 * \left( \frac{DM(14)p}{TR(14)} \right) \right|$$

$$DI(14)n = \left| 100 * \left( \frac{DM(14)n}{TR(14)} \right) \right|$$



d. Fourteen days directional movement index calculation.

$$DX(14) = \left[100 * \left(\frac{Difference\ DI(14)}{Sum\ DI(14)}\right)\right]$$

$$Difference DI(14) = |DI(14)p - DI(14)n|$$

$$Sum DI(14) = DI(14)p + DI(14)n$$



e. Fourteen days average directional movement index calculation.

$$current\ ADX(14) = \frac{[(previous\ ADX(14)*13) + current\ DX(14)]}{14}$$

$$initial\ ADX(14) = SMA_{14}(DX(14))$$



# **Commodity Channel Index**

- Commodity channel index CCI is a bounded oscillator that measures a stock's price variation from its statistical mean. Twenty days and constant factor are commonly used to make sure most values fall within bands.
- Donald R. Lambert. "Commodity Channel Index: Tool for Trading Cyclic Trends".
   Commodities Magazine (now Futures Magazine). 1980
- a. Typical price calculation.

$$TP = \frac{High + Low + Close}{3}$$



# **Commodity Channel Index**

b. Typical price smoothing calculation.

$$SMA_{20}(TP) = \frac{Sum_{20}(TP)}{20}$$

c. Mean absolute deviation calculation.

$$\mathbf{MAD} = \frac{Sum_{20}|SMA_{20}(TP) - TP|}{20}$$

# **Commodity Channel Index**

d. Commodity channel index calculation.

$$\textit{CCI}(20, 0.015) = \frac{\textit{Typical Price} - \textit{SMA}(20) \textit{ of Typical Price}}{0.015*\textit{Mean Absolute Deviation}}$$



#### **MACD**

- Moving averages convergence/divergence MACD is a centered oscillator that
  measures a stock's price momentum and identifies trends. Twelve days are
  commonly used for short term smoothing, twenty six days for long term smoothing
  and nine days for signal.
- Gerald Appel. "Technical Analysis: Powerful Tools for Active Investors". FT Press. 2005.



#### **MACD**

a. Short term (twelve days) and long term (twenty six days) smoothing calculation.

$$current \ EMA_{26} = \frac{2}{26+1} * (current \ Close - previous \ EMA_{26}) + previous \ EMA_{26}$$
$$initial \ EMA_{26} = SMA_{26} (26 \ periods \ Close)$$

b. Moving average convergence/divergence indicator calculation.

$$MACD(12, 26) = EMA_{12}(Close) - EMA_{26}(Close)$$



#### **MACD**

 c. Nine days moving average convergence/divergence indicator smoothing calculation.

$$Signal(9) = EMA_9[MACD(12, 26)]$$

d. Moving average convergence/divergence indicator histogram calculation.

$$MACD\ Histogram(12, 26, 9) = MACD(12, 26) - Signal(9)$$



#### Rate of Change

 Rate of change ROC is a bounded oscillator that measures a stock's price change speed or momentum. Two hundred and fifty two days are commonly used for one business year calculation, one hundred and twenty six for one semester, sixty three for one quarter and twenty one for one month.

$$ROC(21) = \frac{Current\ Close - Close\ 21\ Days\ Ago}{Close\ 21\ Days\ Ago}*100$$



#### Relative Strength Index

- **Relative strength index RSI** is a bounded oscillator that measures a stock price trend's strength or weakness. Fourteen days are commonly used for its calculation.
- J. Welles Wilder Jr. "New Concepts in Technical Trading Systems". Commodities Magazine (now Futures Magazine). 1978.
- a. Fourteen days average gain and loss.

$$AG(14) = \frac{Sum\ Gains\ Last\ 14\ Days}{14}$$

$$AL(14) = \frac{Sum\ Losses\ Last\ 14\ Days}{14}$$



# Relative Strength Index

b. Fourteen days relative strength calculation.

$$RS(14) = \frac{Average\ Gain}{Average\ Loss}$$

c. Fourteen days relative strength index calculation.

$$RSI(14) = \frac{100}{1 + Relative\ Strength(14)}$$



#### Stochastic Momentum Index

- Stochastic momentum index SMI is a bounded oscillator that compares a stock price to its past range. Thirteen days together with two and twenty five days' data smoothing parameters are commonly used for this calculation.
- William Blau. "Trading with True Strength Index". Technical Analysis of Stocks & Commodities. 1992.
- a. Thirteen days maximum high and minimum low calculation.

$$High \, High_{13} = Max(High_{13})$$

$$Low\ Low_{13} = Min(Low_{13})$$



#### Stochastic Momentum Index

b. Twenty five days exponential moving averages calculation.

$$(i)EMA_{25}(Close - 0.5 * (High High_{13} + Low Low_{13}))$$
  
 $(ii)EMA_{25}(High High_{13} - Low Low_{13})$ 

c. Two days exponential moving averages calculation.

$$(i)EMA_2[EMA_{25}(Close - 0.5 * (High High_{13} + Low Low_{13}))]$$
  
 $(ii)EMA_2[EMA_{25}(High High_{13} - Low Low_{13})]$ 



#### Stochastic Momentum Index

d. Stochastic momentum index and signal calculation.

$$SMI(13, 2, 25) = 100 * \frac{EMA_{2}[EMA_{25}(Close - 0.5 * (High \, High_{13} + Low \, Low_{13}))]}{0.5 * [EMA_{2}(EMA_{25}(High \, High_{13} - Low \, Low_{13})]}$$

$$Signal = EMA_9(SMI)$$

#### Williams %R

- **Williams** %**R** is a bounded oscillator that compares a stock price to its past range's maximum high. Fourteen days are commonly used in its calculation.
- Larry Williams Website <a href="http://williamspercentr.com/">http://williamspercentr.com/</a>
- a. Fourteen days maximum high and minimum low calculation.

$$High \, High_{14} = Max(High_{14})$$

$$Low\ Low_{14} = Min(Low_{14})$$

b. Fourteen days Williams %R calculation.

$$Williams \%R(14) = \frac{HighHigh_{14} - Close}{HighHigh_{14} - LowLow_{14}} * (-100)$$

EXFINSIS www.exfinsis.com