read(2) — Linux manual page

NAME | SYNOPSIS | DESCRIPTION | RETURN VALUE | ERRORS | CONFORMING TO | NOTES | BUGS | SEE ALSO | COLOPHON

Search online pages

READ(2)

Linux Programmer's Manual

READ(2)

NAME

top

read - read from a file descriptor

SYNOPSIS

top

#include <unistd.h>

ssize_t read(int fd, void *buf, size_t count);

DESCRIPTION

read() attempts to read up to *count* bytes from file descriptor *fd* into the buffer starting at *buf*.

On files that support seeking, the read operation commences at the file offset, and the file offset is incremented by the number of bytes read. If the file offset is at or past the end of file, no bytes are read, and **read**() returns zero.

If count is zero, read() may detect the errors described below. In the absence of any errors, or if read() does not check for errors, a read() with a count of 0 returns zero and has no other effects.

According to POSIX.1, if *count* is greater than **SSIZE_MAX**, the result is implementation-defined; see NOTES for the upper limit on Linux.

RETURN VALUE top

On success, the number of bytes read is returned (zero indicates end of file), and the file position is advanced by this number. It is not an error if this number is smaller than the number of bytes requested; this may happen for example because fewer bytes are actually available right now (maybe because we were close to end-of-file, or because we are reading from a pipe, or from a terminal), or because **read**() was interrupted by a signal. See

also NOTES.

On error, -1 is returned, and *errno* is set to indicate the error. In this case, it is left unspecified whether the file position (if any) changes.

ERRORS top

EAGAIN The file descriptor *fd* refers to a file other than a socket and has been marked nonblocking (**O_NONBLOCK**), and the read would block. See open(2) for further details on the **O NONBLOCK** flag.

EAGAIN or EWOULDBLOCK

The file descriptor fd refers to a socket and has been marked nonblocking (O_NONBLOCK), and the read would block. POSIX.1-2001 allows either error to be returned for this case, and does not require these constants to have the same value, so a portable application should check for both possibilities.

EBADF fd is not a valid file descriptor or is not open for reading.

EFAULT buf is outside your accessible address space.

EINTR The call was interrupted by a signal before any data was read; see signal(7).

EINVAL fd is attached to an object which is unsuitable for reading; or the file was opened with the **O_DIRECT** flag, and either the address specified in buf, the value specified in count, or the file offset is not suitably aligned.

EINVAL fd was created via a call to timerfd_create(2) and the
 wrong size buffer was given to read(); see
 timerfd_create(2) for further information.

I/O error. This will happen for example when the process is in a background process group, tries to read from its controlling terminal, and either it is ignoring or blocking SIGTTIN or its process group is orphaned. It may also occur when there is a low-level I/O error while reading from a disk or tape. A further possible cause of EIO on networked filesystems is when an advisory lock had been taken out on the file descriptor and this lock has been lost. See the Lost locks section of fcntl(2) for further details.

EISDIR *fd* refers to a directory.

Other errors may occur, depending on the object connected to fd.

CONFORMING TO top

SVr4, 4.3BSD, POSIX.1-2001.

NOTES top

The types *size_t* and *ssize_t* are, respectively, unsigned and signed integer data types specified by POSIX.1.

On Linux, **read**() (and similar system calls) will transfer at most 0x7ffff000 (2,147,479,552) bytes, returning the number of bytes actually transferred. (This is true on both 32-bit and 64-bit systems.)

On NFS filesystems, reading small amounts of data will update the timestamp only the first time, subsequent calls may not do so. This is caused by client side attribute caching, because most if not all NFS clients leave st_atime (last file access time) updates to the server, and client side reads satisfied from the client's cache will not cause st_atime updates on the server as there are no server-side reads. UNIX semantics can be obtained by disabling client-side attribute caching, but in most situations this will substantially increase server load and decrease performance.

BUGS top

According to POSIX.1-2008/SUSv4 Section XSI 2.9.7 ("Thread Interactions with Regular File Operations"):

All of the following functions shall be atomic with respect to each other in the effects specified in POSIX.1-2008 when they operate on regular files or symbolic links: ...

Among the APIs subsequently listed are <code>read()</code> and <code>readv(2)</code>. And among the effects that should be atomic across threads (and processes) are updates of the file offset. However, on Linux before version 3.14, this was not the case: if two processes that share an open file description (see <code>open(2))</code> perform a <code>read()</code> (or <code>readv(2))</code> at the same time, then the I/O operations were not atomic with respect updating the file offset, with the result that the reads in the two processes might (incorrectly) overlap in the blocks of data that they obtained. This problem was fixed in Linux 3.14.

SEE ALSO top

close(2), fcntl(2), ioctl(2), lseek(2), open(2), pread(2),
readdir(2), readlink(2), readv(2), select(2), write(2), fread(3)

COLOPHON

This page is part of release 5.13 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

Linux 2021-03-22 READ(2)

Pages that refer to this page: grep(1), pv(1), strace(1), telnet-probe(1), close(2), epoll_ctl(2), eventfd(2), fanotify_init(2), fcntl(2), getrandom(2), inotify_add_watch(2), ioctl_tty(2), open(2), perf_event_open(2), perfmonctl(2), pidfd_open(2), pipe(2), prctl(2), pread(2), ptrace(2), readahead(2), readv(2), recv(2), seccomp(2), seccomp_unotify(2), select(2), select_tut(2), sendfile(2), setpgid(2), signalfd(2), socket(2), socketpair(2), syscalls(2), timerfd_create(2), userfaultfd(2), write(2), aio_error(3), aio_read(3), aio_return(3), curs_getch(3x), dbopen(3), fgetc(3), fopen(3), fread(3), getline(3), gets(3), libexpect(3), mkfifo(3), mpool(3), readdir(3), rtime(3), stdin(3), stdio(3), termios(3), xdr(3), xfsctl(3), dsp56k(4), fuse(4), lirc(4), null(4), random(4), rtc(4), st(4), proc(5), systemd.exec(5), aio(7), cpuset(7), epoll(7), fanotify(7), inode(7), inotify(7), pipe(7), signal(7), signal-safety(7), socket(7), spufs(7), system_data_types(7), vsock(7), x25(7), mount.fuse3(8), netsniff-ng(8), xfs_io(8)

Copyright and license for this manual page

HTML rendering created 2021-08-27 by Michael Kerrisk, author of *The Linux Programming Interface*, maintainer of the Linux *man-pages* project.

For details of in-depth **Linux/UNIX system programming training courses** that I teach, look here.

Hosting by jambit GmbH.

