

Red Hat Enterprise Linux 8

Using Ansible to install and manage Identity Management

Installing, configuring, managing, and maintaining Identity Management in Red Hat Enterprise Linux 8 using Red Hat Ansible Engine

Last Updated: 2021-12-03

Red Hat Enterprise Linux 8 Using Ansible to install and manage Identity Management

Installing, configuring, managing, and maintaining Identity Management in Red Hat Enterprise Linux 8 using Red Hat Ansible Engine

Legal Notice

Copyright © 2021 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java [®] is a registered trademark of Oracle and/or its affiliates.

XFS [®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack [®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This documentation collection provides instructions on how to effectively use Ansible playbooks to install, configure, manage and maintain Identity Management on Red Hat Enterprise Linux 8.

Table of Contents

MAKING OPEN SOURCE MORE INCLUSIVE	. 8
PROVIDING FEEDBACK ON RED HAT DOCUMENTATION	. 9
CHAPTER 1. ANSIBLE TERMINOLOGY	10
CHAPTER 2. INSTALLING AN IDENTITY MANAGEMENT SERVER USING AN ANSIBLE PLAYBOOK	. 11
2.1. ANSIBLE AND ITS ADVANTAGES FOR INSTALLING IDM	11
Advantages of using Ansible to install IdM	11
2.2. IDM SERVER INSTALLATION USING AN ANSIBLE PLAYBOOK	11
Overview	11
2.3. INSTALLING THE ANSIBLE-FREEIPA PACKAGE	12
2.4. ANSIBLE ROLES LOCATION IN THE FILE SYSTEM	12
2.5. DEPLOYING AN IDM SERVER WITH AN INTEGRATED CA AS THE ROOT CA USING AN ANSIBLE	
PLAYBOOK	13
2.5.1. Setting the parameters for a deployment with an integrated DNS and an integrated CA as the root CA	
2.5.2. Setting the parameters for a deployment with external DNS and an integrated CA as the root CA	16
2.5.3. Deploying an IdM server with an integrated CA as the root CA using an Ansible playbook	18
2.6. DEPLOYING AN IDM SERVER WITH AN EXTERNAL CA AS THE ROOT CA USING AN ANSIBLE PLAYBO	19 19
2.6.1. Setting the parameters for a deployment with an integrated DNS and an external CA as the root CA	19
2.6.2. Setting the parameters for a deployment with external DNS and an external CA as the root CA	22
2.6.3. Deploying an IdM server with an external CA as the root CA using an Ansible playbook	24
CHAPTER 3. INSTALLING AN IDENTITY MANAGEMENT REPLICA USING AN ANSIBLE PLAYBOOK	27
3.1. IDM REPLICA INSTALLATION USING AN ANSIBLE PLAYBOOK	27
Overview	27
3.2. SETTING THE PARAMETERS OF THE IDM REPLICA DEPLOYMENT	27
3.2.1. Specifying the base, server and client variables for installing the IdM replica	28
3.2.2. Specifying the credentials for installing the IdM replica using an Ansible playbook	30
3.3. DEPLOYING AN IDM REPLICA USING AN ANSIBLE PLAYBOOK	31
CHAPTER 4. INSTALLING AN IDENTITY MANAGEMENT CLIENT USING AN ANSIBLE PLAYBOOK	33
4.1. IDM CLIENT INSTALLATION USING AN ANSIBLE PLAYBOOK	33
Overview	33
4.2. SETTING THE PARAMETERS OF THE IDM CLIENT DEPLOYMENT	33
4.2.1. Setting the parameters of the inventory file for the autodiscovery client installation mode	34
4.2.2. Setting the parameters of the inventory file when autodiscovery is not possible during client installation	
	36
4.2.3. Checking the parameters in the install-client.yml file	38
4.2.4. Authorization options for IdM client enrollment using an Ansible playbook	38
4.3. DEPLOYING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK 4.4. TESTING AN IDENTITY MANAGEMENT CLIENT AFTER ANSIBLE INSTALLATION	40 41
4.5. UNINSTALLING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK	41
4.5. ONING FALLING AN IDIN CLIENT OSING AN ANSIBLE FLAT BOOK	41
CHAPTER 5. PREPARING YOUR ENVIRONMENT FOR MANAGING IDM USING ANSIBLE PLAYBOOKS .	43
CHAPTER 6. CONFIGURING GLOBAL IDM SETTINGS USING ANSIBLE PLAYBOOKS	45
6.1. RETRIEVING IDM CONFIGURATION USING AN ANSIBLE PLAYBOOK	45
6.2. CONFIGURING THE IDM CA RENEWAL SERVER USING AN ANSIBLE PLAYBOOK	47
6.3. CONFIGURING THE DEFAULT SHELL FOR IDM USERS USING AN ANSIBLE PLAYBOOK	48
CHAPTER 7. MANAGING USER ACCOUNTS USING ANSIBLE PLAYBOOKS	50
7.1. USER LIFE CYCLE	50

7.2. ENSURING THE PRESENCE OF AN IDM USER USING AN ANSIBLE PLAYBOOK 7.3. ENSURING THE PRESENCE OF MULTIPLE IDM USERS USING ANSIBLE PLAYBOOKS 7.4. ENSURING THE PRESENCE OF MULTIPLE IDM USERS FROM A JSON FILE USING ANSIBLE	51 53
PLAYBOOKS 7.5. ENSURING THE ABSENCE OF USERS USING ANSIBLE PLAYBOOKS	54 56
7.3. ENSURING THE ABSENCE OF USERS USING ANSIBLE PLATBOOKS	30
CHAPTER 8. MANAGING USER GROUPS USING ANSIBLE PLAYBOOKS 8.1. THE DIFFERENT GROUP TYPES IN IDM	58
8.2. DIRECT AND INDIRECT GROUP MEMBERS8.3. ENSURING THE PRESENCE OF IDM GROUPS AND GROUP MEMBERS USING ANSIBLE PLAYBOOK	59 (S
0.5. ENSONING THE TRESERVE OF IBM CROOF STAND GROOF MEMBERS GOING TRISIDEET EXTROOP	60
8.4. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE PLAYBOOKS	61
8.5. ENSURING THE ABSENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE PLAYBOOKS	62
CHAPTER 9. USING ANSIBLE PLAYBOOKS TO MANAGE SELF-SERVICE RULES IN IDM	
9.1. SELF-SERVICE ACCESS CONTROL IN IDM	65
9.2. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS PRESENT	65 67
9.3. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS ABSENT 9.4. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE HAS SPECIFIC ATTRIBUTES	68
9.5. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE DOES NOT HAVE SPECIFIC ATTRIBUTES	
5.5. OSINO ANSIDEE TO ENSORE THAT A SEEL SERVICE NOTE DOES NOT HAVE SEECILIE AT HIBOTE	70
CHAPTER 10. DELEGATING PERMISSIONS TO USER GROUPS TO MANAGE USERS USING ANSIBLE	
PLAYBOOKS	72
10.1. DELEGATION RULES	72
10.2. CREATING AN ANSIBLE INVENTORY FILE FOR IDM	72
10.3. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS PRESENT	73
10.4. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS ABSENT	75 76
10.5. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE HAS SPECIFIC ATTRIBUTES 10.6. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE DOES NOT HAVE SPECIFIC ATTRIBUTE	76 S 78
CHAPTER 11. USING ANSIBLE PLAYBOOKS TO MANAGE ROLE-BASED ACCESS CONTROL IN IDM	. 80
11.1. PERMISSIONS IN IDM	80
11.2. DEFAULT MANAGED PERMISSIONS	81
11.3. PRIVILEGES IN IDM	83
11.4. ROLES IN IDM	83
11.5. PREDEFINED ROLES IN IDENTITY MANAGEMENT	83
11.6. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE WITH PRIVILEGES IS PRESENT	84
11.7. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE IS ABSENT	86
11.8. USING ANSIBLE TO ENSURE THAT A GROUP OF USERS IS ASSIGNED TO AN IDM RBAC ROLE	87
11.9. USING ANSIBLE TO ENSURE THAT SPECIFIC USERS ARE NOT ASSIGNED TO AN IDM RBAC ROLE	89
11.10. USING ANSIBLE TO ENSURE A SERVICE IS A MEMBER OF AN IDM RBAC ROLE	90
11.11. USING ANSIBLE TO ENSURE A HOST IS A MEMBER OF AN IDM RBAC ROLE	92
11.12. USING ANSIBLE TO ENSURE A HOST GROUP IS A MEMBER OF AN IDM RBAC ROLE	93
CHAPTER 12. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PRIVILEGES	
12.1. USING ANSIBLE TO ENSURE A CUSTOM IDM RBAC PRIVILEGE IS PRESENT	96
12.2. USING ANSIBLE TO ENSURE MEMBER PERMISSIONS ARE PRESENT IN A CUSTOM IDM RBAC PRIVILEGE	97
12.3. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE DOES NOT INCLUDE A PERMISSION	97
12.4. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE DOES NOT INCLUDE A PERMISSION 12.4. USING ANSIBLE TO RENAME A CUSTOM IDM RBAC PRIVILEGE	100
12.5. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE IS ABSENT	100

CHAPTER 13. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PERMISSIONS IN IDM	104
13.1. USING ANSIBLE TO ENSURE AN RBAC PERMISSION IS PRESENT	104
13.2. USING ANSIBLE TO ENSURE AN RBAC PERMISSION WITH AN ATTRIBUTE IS PRESENT	106
13.3. USING ANSIBLE TO ENSURE AN RBAC PERMISSION IS ABSENT	107
13.4. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS A MEMBER OF AN IDM RBAC PERMISSION	109
13.5. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS NOT A MEMBER OF AN IDM RBAC PERMISSION	110
13.6. USING ANSIBLE TO RENAME AN IDM RBAC PERMISSION	111
13.7. ADDITIONAL RESOURCES	113
CHAPTER 14. USING ANSIBLE TO MANAGE THE REPLICATION TOPOLOGY IN IDM 14.1. USING ANSIBLE TO ENSURE A REPLICATION AGREEMENT EXISTS IN IDM	114 114
14.2. USING ANSIBLE TO ENSURE REPLICATION AGREEMENTS EXIST BETWEEN MULTIPLE IDM REPLIC	
11.2. GOING / MOIBEE TO ENGONE HEI EIGHTION / MOREEMENTO EXICT BETWEEN MOETH EE IBM HEI EIG	116
14.3. USING ANSIBLE TO CHECK IF A REPLICATION AGREEMENT EXISTS BETWEEN TWO REPLICAS	118
14.4. USING ANSIBLE TO VERIFY THAT A TOPOLOGY SUFFIX EXISTS IN IDM	120
14.5. USING ANSIBLE TO REINITIALIZE AN IDM REPLICA	121
14.6. USING ANSIBLE TO ENSURE A REPLICATION AGREEMENT IS ABSENT IN IDM	123
14.7. ADDITIONAL RESOURCES	124
CHAPTER 15. MANAGING HOSTS USING ANSIBLE PLAYBOOKS	125
15.1. HOSTS IN IDM	125
15.2. HOST ENROLLMENT	126
15.2.1. User privileges required for host enrollment	126
User privileges for optionally manually creating a host entry in IdM LDAP	126
User privileges for joining the client to the IdM domain	126
15.2.2. Enrollment and authentication of IdM hosts and users: comparison	127
15.2.3. Alternative authentication options for IdM hosts	128
15.3. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH FQDN USING ANSIBLE PLAYBOOKS	128
15.4. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH DNS INFORMATION USING ANSIBLE PLAYBOOKS	130
15.5. ENSURING THE PRESENCE OF MULTIPLE IDM HOST ENTRIES WITH RANDOM PASSWORDS USING	
ANSIBLE PLAYBOOKS	132
15.6. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH MULTIPLE IP ADDRESSES USING ANSIB	
PLAYBOOKS	133
15.7. ENSURING THE ABSENCE OF AN IDM HOST ENTRY USING ANSIBLE PLAYBOOKS	135
CHAPTER 16. MANAGING HOST GROUPS USING ANSIBLE PLAYBOOKS	137
16.1. HOST GROUPS IN IDM	137
16.2. ENSURING THE PRESENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	137
16.3. ENSURING THE PRESENCE OF HOSTS IN IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	139
16.4. NESTING IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	140
16.5. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM HOST GROUPS USING ANSIBLE	
PLAYBOOKS	142
16.6. ENSURING THE ABSENCE OF HOSTS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	143
16.7. ENSURING THE ABSENCE OF NESTED HOST GROUPS FROM IDM HOST GROUPS USING ANSIBLE	
PLAYBOOKS	145
16.8. ENSURING THE ABSENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	146
16.9. ENSURING THE ABSENCE OF MEMBER MANAGERS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	147
CHAPTER 17. DEFINING IDM PASSWORD POLICIES	150
17.1. WHAT IS A PASSWORD POLICY	150
17.2. PASSWORD POLICIES IN IDM	150
17.3. ENSURING THE PRESENCE OF A PASSWORD POLICY IN IDM USING AN ANSIBLE PLAYBOOK 17.4. ADDITIONAL PASSWORD POLICY OPTIONS IN IDM	152 153
17. T. ADDITIONAL I ASSINDID I OLIOT OF HONOIN IN IDIN	100

17.5. APPLYING ADDITIONAL PASSWORD POLICY OPTIONS TO AN IDM GROUP	154
CHAPTER 18. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT	
18.1. SUDO ACCESS ON AN IDM CLIENT	157 157
18.2. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE CLI 18.3. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE IDM WEB UI	157
18.4. CREATING A SUDO RULE ON THE CLI THAT RUNS A COMMAND AS A SERVICE ACCOUNT ON AN CLIENT	
18.5. CREATING A SUDO RULE IN THE IDM WEBUI THAT RUNS A COMMAND AS A SERVICE ACCOUNT O	
AN IDM CLIENT	164
18.6. ENABLING GSSAPI AUTHENTICATION FOR SUDO ON AN IDM CLIENT	170
18.7. ENABLING GSSAPI AUTHENTICATION AND ENFORCING KERBEROS AUTHENTICATION INDICATO	RS
FOR SUDO ON AN IDM CLIENT	172
18.8. SSSD OPTIONS CONTROLLING GSSAPI AUTHENTICATION FOR PAM SERVICES	174
18.9. TROUBLESHOOTING GSSAPI AUTHENTICATION FOR SUDO	176
18.10. USING AN ANSIBLE PLAYBOOK TO ENSURE SUDO ACCESS FOR AN IDM USER ON AN IDM CLIEN	
	177
CHAPTER 19. ENSURING THE PRESENCE OF HOST-BASED ACCESS CONTROL RULES IN IDM USING	
ANSIBLE PLAYBOOKS	180
19.1. HOST-BASED ACCESS CONTROL RULES IN IDM	180
19.2. ENSURING THE PRESENCE OF AN HBAC RULE IN IDM USING AN ANSIBLE PLAYBOOK	180
CHAPTER 20. VAULTS IN IDM	. 182
20.1. VAULTS AND THEIR BENEFITS	182
20.2. VAULT OWNERS, MEMBERS, AND ADMINISTRATORS	183
20.3. STANDARD, SYMMETRIC, AND ASYMMETRIC VAULTS	184
20.4. USER, SERVICE, AND SHARED VAULTS	184
20.5. VAULT CONTAINERS	184
20.6. BASIC IDM VAULT COMMANDS	185
20.7. INSTALLING THE KEY RECOVERY AUTHORITY IN IDM	185
CHAPTER 21. USING ANSIBLE TO MANAGE IDM USER VAULTS: STORING AND RETRIEVING SECRETS	187
21.1. ENSURING THE PRESENCE OF A STANDARD USER VAULT IN IDM USING ANSIBLE	187
21.2. ARCHIVING A SECRET IN A STANDARD USER VAULT IN IDM USING ANSIBLE	188
21.3. RETRIEVING A SECRET FROM A STANDARD USER VAULT IN IDM USING ANSIBLE	190
CHARTER 22 LICING ANGIRLE TO MANAGE IDM CERVICE VALUETS CTORING AND DETRIEVING SECRE	т.
CHAPTER 22. USING ANSIBLE TO MANAGE IDM SERVICE VAULTS: STORING AND RETRIEVING SECRE	. 15 . 192
22.1. ENSURING THE PRESENCE OF AN ASYMMETRIC SERVICE VAULT IN IDM USING ANSIBLE	193
22.2. ADDING MEMBER SERVICES TO AN ASYMMETRIC VAULT USING ANSIBLE	194
22.3. STORING AN IDM SERVICE SECRET IN AN ASYMMETRIC VAULT USING ANSIBLE	196
22.4. RETRIEVING A SERVICE SECRET FOR AN IDM SERVICE USING ANSIBLE	197
22.5. CHANGING AN IDM SERVICE VAULT SECRET WHEN COMPROMISED USING ANSIBLE	200
CHAPTER 23. ENSURING THE PRESENCE AND ABSENCE OF SERVICES IN IDM USING ANSIBLE	204
23.1. ENSURING THE PRESENCE OF AN HTTP SERVICE IN IDM USING AN ANSIBLE PLAYBOOK	204
23.2. ENSURING THE PRESENCE OF AN HTTP SERVICE IN IDM ON A NON-IDM CLIENT USING AN ANSI	
PLAYBOOK	206
23.3. ENSURING THE PRESENCE OF AN HTTP SERVICE ON AN IDM CLIENT WITHOUT DNS USING AN ANSIBLE PLAYBOOK	207
23.4. ENSURING THE PRESENCE OF AN EXTERNALLY SIGNED CERTIFICATE IN AN IDM SERVICE ENTR	
USING AN ANSIBLE PLAYBOOK	209
23.5. USING AN ANSIBLE PLAYBOOK TO ALLOW IDM USERS, GROUPS, HOSTS, OR HOST GROUPS TO	
CREATE A KEYTAB OF A SERVICE	211
23.6. USING AN ANSIBLE PLAYBOOK TO ALLOW IDM USERS, GROUPS, HOSTS, OR HOST GROUPS TO	

RETRIEVE A KEYTAB OF A SERVICE	213
23.7. ENSURING THE PRESENCE OF A KERBEROS PRINCIPAL ALIAS OF A SERVICE USING AN ANSIBLE	
PLAYBOOK 23.8. ENSURING THE ABSENCE OF AN HTTP SERVICE IN IDM USING AN ANSIBLE PLAYBOOK	215 217
25.5. ENSORING THE ABSENCE OF ANTITITI SERVICE IN IDM GSING AN ANSIBELT EATBOOK	217
CHAPTER 24. MANAGING GLOBAL DNS CONFIGURATION IN IDM USING ANSIBLE PLAYBOOKS 24.1. HOW IDM ENSURES THAT GLOBAL FORWARDERS FROM /ETC/RESOLV.CONF ARE NOT REMOVED	D
BY NETWORKMANAGER	219
24.2. ENSURING THE PRESENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE	220
24.3. ENSURING THE ABSENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE	222
24.4. DNS FORWARD POLICIES IN IDM	223
24.5. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT THE FORWARD FIRST POLICY IS SET IN IDM DN GLOBAL CONFIGURATION	NS 224
24.6. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT GLOBAL FORWARDERS ARE DISABLED IN IDM	
24.0. OSINO AN ANSIBELT EATBOOK TO ENSOINE THAT OLOBALT ORWANDERS ARE DISABLED IN IDIN	225
24.7. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT SYNCHRONIZATION OF FORWARD AND REVER	
LOOKUP ZONES IS DISABLED IN IDM DNS	227
CHAPTER 25. USING ANSIBLE PLAYBOOKS TO MANAGE IDM DNS ZONES	229
25.1. SUPPORTED DNS ZONE TYPES	229
25.2. CONFIGURATION ATTRIBUTES OF PRIMARY IDM DNS ZONES	230
25.3. USING ANSIBLE TO CREATE A PRIMARY ZONE IN IDM DNS	232
25.4. USING AN ANSIBLE PLAYBOOK TO ENSURE THE PRESENCE OF A PRIMARY DNS ZONE IN IDM WIT	
MULTIPLE VARIABLES	233
25.5. USING AN ANSIBLE PLAYBOOK TO ENSURE THE PRESENCE OF A ZONE FOR REVERSE DNS LOOK	KUP
WHEN AN IP ADDRESS IS GIVEN	236
CHAPTER 26. USING ANSIBLE TO MANAGE DNS LOCATIONS IN IDM	238
26.1. DNS-BASED SERVICE DISCOVERY	238
26.2. DEPLOYMENT CONSIDERATIONS FOR DNS LOCATIONS	239
26.3. DNS TIME TO LIVE (TTL)	239
26.4. USING ANSIBLE TO ENSURE AN IDM LOCATION IS PRESENT	239
26.5. USING ANSIBLE TO ENSURE AN IDM LOCATION IS ABSENT	241
26.6. ADDITIONAL RESOURCES	242
CHAPTER 27. MANAGING DNS FORWARDING IN IDM	243
27.1. THE TWO ROLES OF AN IDM DNS SERVER	243
27.2. DNS FORWARD POLICIES IN IDM	244
27.3. ADDING A GLOBAL FORWARDER IN THE IDM WEB UI	244
27.4. ADDING A GLOBAL FORWARDER IN THE CLI	247
27.5. ADDING A DNS FORWARD ZONE IN THE IDM WEB UI	248
27.6. ADDING A DNS FORWARD ZONE IN THE CLI	251
27.7. ESTABLISHING A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE	252
27.8. ENSURING THE PRESENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE	253
27.9. ENSURING THE ABSENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE	255
27.10. ENSURING DNS GLOBAL FORWARDERS ARE DISABLED IN IDM USING ANSIBLE	256
27.11. ENSURING THE PRESENCE OF A DNS FORWARD ZONE IN IDM USING ANSIBLE	257
27.12. ENSURING A DNS FORWARD ZONE HAS MULTIPLE FORWARDERS IN IDM USING ANSIBLE	259
27.13. ENSURING A DNS FORWARD ZONE IS DISABLED IN IDM USING ANSIBLE	261
27.14. ENSURING THE ABSENCE OF A DNS FORWARD ZONE IN IDM USING ANSIBLE	262
CHAPTER 28. USING ANSIBLE TO MANAGE DNS RECORDS IN IDM	265
28.1. DNS RECORDS IN IDM	265
28.2. COMMON IPA DNSRECORD-* OPTIONS	266
28.3. ENSURING THE PRESENCE OF A AND AAAA DNS RECORDS IN IDM USING ANSIBLE	268

28.4. ENSURING THE PRESENCE OF A AND PTR DNS RECORDS IN IDM USING ANSIBLE	270
28.5. ENSURING THE PRESENCE OF MULTIPLE DNS RECORDS IN IDM USING ANSIBLE	272
28.6. ENSURING THE PRESENCE OF MULTIPLE CNAME RECORDS IN IDM USING ANSIBLE	273
28.7. ENSURING THE PRESENCE OF AN SRV RECORD IN IDM USING ANSIBLE	275

MAKING OPEN SOURCE MORE INCLUSIVE

Red Hat is committed to replacing problematic language in our code, documentation, and web properties. We are beginning with these four terms: master, slave, blacklist, and whitelist. Because of the enormity of this endeavor, these changes will be implemented gradually over several upcoming releases. For more details, see our CTO Chris Wright's message.

In Identity Management, planned terminology replacements include:

- block list replaces blacklist
- allow list replaces whitelist
- secondary replaces slave
- The word *master* is being replaced with more precise language, depending on the context:
 - IdM server replaces IdM master
 - CA renewal server replaces CA renewal master
 - CRL publisher server replaces CRL master
 - *multi-supplier* replaces *multi-master*

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION

We appreciate your input on our documentation. Please let us know how we could make it better. To do so:

- For simple comments on specific passages:
 - 1. Make sure you are viewing the documentation in the *Multi-page HTML* format. In addition, ensure you see the **Feedback** button in the upper right corner of the document.
 - 2. Use your mouse cursor to highlight the part of text that you want to comment on.
 - 3. Click the Add Feedback pop-up that appears below the highlighted text.
 - 4. Follow the displayed instructions.
- For submitting more complex feedback, create a Bugzilla ticket:
 - 1. Go to the Bugzilla website.
 - 2. As the Component, use **Documentation**.
 - 3. Fill in the **Description** field with your suggestion for improvement. Include a link to the relevant part(s) of documentation.
 - 4. Click Submit Bug.

CHAPTER 1. ANSIBLE TERMINOLOGY

The chapters in this title use the official Ansible terminology. If you are not familiar with the terminology, read the official Ansible upstream documentation before proceeding, especially the following sections:

- The Basic concepts in Ansible section provides an overview of the most commonly used concepts in Ansible.
- The User guide outlines the most common situations and questions when starting to use Ansible, such as using the command line; working with an inventory; interacting with data; writing tasks, plays, and playbooks; and executing playbooks.
- How to build your inventory offers tips on how to design your inventory. An inventory is a list or a group of lists that Ansible uses to work against multiple managed nodes or hosts in your infrastructure.
- Intro to playbooks introduces the concept of an Ansible playbook as a repeatable and re-usable system for managing configurations, deploying machines, and deploying complex applications.
- The Ansible roles section explains how to automate loading variables, tasks, and handlers based on a known file structure.
- The Glossary explains terms that are used elsewhere in the Ansible documentation.

CHAPTER 2. INSTALLING AN IDENTITY MANAGEMENT SERVER USING AN ANSIBLE PLAYBOOK

2.1. ANSIBLE AND ITS ADVANTAGES FOR INSTALLING IDM

Ansible is an automation tool used to configure systems, deploy software, and perform rolling updates. Ansible includes support for Identity Management (IdM), and you can use Ansible modules to automate installation tasks such as the setup of an IdM server, replica, client, or an entire IdM topology.

Advantages of using Ansible to install IdM

The following list presents advantages of installing Identity Management using Ansible in contrast to manual installation.

- You do not need to log into the managed node.
- You do not need to configure settings on each host to be deployed individually. Instead, you can have one inventory file to deploy a complete cluster.
- You can reuse an inventory file later for management tasks, for example to add users and hosts. You can reuse an inventory file even for such tasks as are not related to IdM.

2.2. IDM SERVER INSTALLATION USING AN ANSIBLE PLAYBOOK

The following sections describe how to configure a system as an IdM server by using Ansible. Configuring a system as an IdM server establishes an IdM domain and enables the system to offer IdM services to IdM clients. The deployment is managed by the **ipaserver** Ansible role.



NOTE

Before installing an IdM server using Ansible, ensure that you understand Ansible and IdM concepts. Ensure that you understand the following terms that are used in this chapter:

- Ansible roles
- Ansible nodes
- Ansible inventory
- Ansible tasks
- Ansible modules
- Ansible plays and playbooks

Overview

The installation consists of the following parts:

- 1. Installing the ansible-freeipa package
- 2. Deploying an IdM server with an integrated CA using an Ansible playbook
- 3. Deploying an IdM server with an external CA using an Ansible-playbook

2.3. INSTALLING THE ANSIBLE-FREEIPA PACKAGE

Prerequisites

On the **managed node**:

 Ensure that the managed node is a Red Hat Enterprise Linux 8 system with a static IP address and a working package manager.

On the controller:

- Ensure that the controller is a Red Hat Enterprise Linux system with a valid subscription. If this is not the case, see the official Ansible documentation Installation guide for alternative installation instructions.
- Ensure that you can reach the managed node over the **SSH** protocol from the controller. Check that the managed node is listed in the /**root/.ssh/known_hosts** file of the controller.

Procedure

Run the following procedure on the Ansible controller.

- 1. Enable the required repository:
 - # subscription-manager repos --enable ansible-2.8-for-rhel-8-x86_64-rpms
- 2. Install Ansible:
 - # yum install ansible
- 3. Install the IdM Ansible roles:
 - # yum install ansible-freeipa

The roles are installed to the /usr/share/ansible/roles/ directory.

2.4. ANSIBLE ROLES LOCATION IN THE FILE SYSTEM

By default the **ansible-freeipa** roles are installed to the **/usr/share/ansible/roles/** directory. The structure of the **ansible-freeipa** package is as follows:

• The /usr/share/ansible/roles/ directory stores the ipaserver, ipareplica, and ipaclient roles on the Ansible controller. Each role directory stores examples, a basic overview, the licence and documentation about the role in a README.md Markdown file.

[root@server]# **Is -1** /**usr/share/ansible/roles/** ipaclient ipareplica ipaserver

 The /usr/share/doc/ansible-freeipa/ directory stores the documentation about individual roles and the topology in README.md Markdown files. It also stores the playbooks/ subdirectory (see below).

[root@server]# ls -1 /usr/share/doc/ansible-freeipa/

playbooks
README-client.md
README.md
README-replica.md
README-server.md
README-topology.md

• The /usr/share/doc/ansible-freeipa/playbooks/ directory stores the example playbooks:

[root@server]# Is -1 /usr/share/doc/ansible-freeipa/playbooks/install-client.yml
install-cluster.yml
install-replica.yml
install-server.yml
uninstall-client.yml
uninstall-cluster.yml
uninstall-replica.yml
uninstall-replica.yml
uninstall-replica.yml

2.5. DEPLOYING AN IDM SERVER WITH AN INTEGRATED CA AS THE ROOT CA USING AN ANSIBLE PLAYBOOK

Before running the **ansible-playbook** utility, set the parameters that correspond to your scenario by choosing one of the following procedures:

- Procedure with integrated DNS
- Procedure with external DNS

NOTE

The inventory files in the following procedures use the **INI** format. You can, alternatively, use the **YAML** or **JSON** formats.

2.5.1. Setting the parameters for a deployment with an integrated DNS and an integrated CA as the root CA

Complete this procedure to configure the inventory file for installing an IdM server with an integrated CA as the root CA in an environment that uses the IdM integrated DNS solution.

Procedure

- 1. Open the inventory file for editing. Specify the fully-qualified domain names (**FQDN**) of the host you want to use as an IdM server. Ensure that the **FQDN** meets the following criteria:
 - Only alphanumeric characters and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.
- 2. Specify the IdM domain and realm information.
- 3. Specify that you want to use integrated DNS by adding the following option:

ipaserver setup dns=yes

- 4. Specify the DNS forwarding settings. Choose one of the following options:
 - Use the ipaserver_auto_forwarders=yes option if you want the installer to use forwarders from the /etc/resolv.conf file. This option is not recommended if the nameserver specified in the /etc/resolv.conf file is the localhost 127.0.0.1 address or if you are on a virtual private network and the DNS servers you are using are normally unreachable from the public internet.
 - Use the ipaserver_forwarders option to specify your forwarders manually. The installation process adds the forwarder IP addresses to the /etc/named.conf file on the installed IdM server.
 - Use the **ipaserver_no_forwarders=yes** option to configure root DNS servers to be used instead.

NOTE

With no DNS forwarders, your environment will be isolated, and names from other DNS domains in your infrastructure will not be resolved.

- 5. Specify the DNS reverse record and zone settings. Choose from the following options:
 - Use the **ipaserver_allow_zone_overlap=yes** option to allow the creation of a (reverse) zone even if the zone is already resolvable.
 - Use the **ipaserver_reverse_zones** option to specify your reverse zones manually.
 - Use the **ipaserver_no_reverse=yes** option if you do not want the installer to create reverse a DNS zone.

NOTE

Using IdM to manage reverse zones is optional. You can use an external DNS service for this purpose instead.

- 6. Specify the passwords for **admin** and for the **Directory Manager**. Use the Ansible Vault to store the password, and reference the Vault file from the playbook file. Alternatively and less securely, specify the passwords directly in the inventory file.
- 7. (Optional) Specify a custom **firewalld** zone to be used by the IdM server. If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of an inventory file with the required server information (excluding the passwords)

[ipaserver] server.idm.example.com

[ipaserver:vars] ipaserver_domain=idm.example.com ipaserver_realm=IDM.EXAMPLE.COM

```
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes
[...]
```

Example of an inventory file with the required server information (including the passwords)

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234

[...]
```

Example of an inventory file with a custom firewalld zone

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
ipaserver_firewalld_zone=custom zone
```

Example playbook to set up an IdM server using admin and Directory Manager passwords stored in an Ansible Vault file

```
---
- name: Playbook to configure IPA server hosts: ipaserver become: true vars_files:
- playbook_sensitive_data.yml

roles:
- role: ipaserver state: present
```

Example playbook to set up an IdM server using admin and Directory Manager passwords from an inventory file

- name: Playbook to configure IPA server

hosts: ipaserver become: true

roles:

 role: ipaserver state: present

Additional resources

- For the forwarding policy default settings, see the **--forward-policy** description in the **ipa-dns-install(1)** man page.
- For more information about DNS variables used by the **ipaserver** role, see the DNS Variables section in the **README-server.md** file in the /usr/share/doc/ansible-freeipa directory.

2.5.2. Setting the parameters for a deployment with external DNS and an integrated CA as the root CA

Complete this procedure to configure the inventory file for installing an IdM server with an integrated CA as the root CA in an environment that uses an external DNS solution.

Procedure

- 1. Open the inventory file for editing. Specify the fully-qualified domain names (**FQDN**) of the host you want to use as an IdM server. Ensure that the **FQDN** meets the following criteria:
 - Only alphanumeric characters and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.
- 2. Specify the IdM domain and realm information.
- 3. Make sure that the **ipaserver setup dns** option is set to **no** or that it is absent.
- 4. Specify the passwords for **admin** and for the **Directory Manager**. Use the Ansible Vault to store the password, and reference the Vault file from the playbook file. Alternatively and less securely, specify the passwords directly in the inventory file.
- 5. (Optional) Specify a custom **firewalld** zone to be used by the IdM server. If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of an inventory file with the required server information (excluding the passwords)

[ipaserver] server.idm.example.com

[ipaserver:vars]

```
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
[...]
```

Example of an inventory file with the required server information (including the passwords)

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234

[...]
```

Example of an inventory file with a custom firewalld zone

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
ipaserver_firewalld_zone=custom zone
```

Example playbook to set up an IdM server using admin and Directory Manager passwords stored in an Ansible Vault file

```
---
- name: Playbook to configure IPA server hosts: ipaserver become: true vars_files:
- playbook_sensitive_data.yml

roles:
- role: ipaserver state: present
```

Example playbook to set up an IdM server using admin and Directory Manager passwords from an inventory file

```
---
- name: Playbook to configure IPA server hosts: ipaserver
```

become: true

roles:

 role: ipaserver state: present

2.5.3. Deploying an IdM server with an integrated CA as the root CA using an Ansible playbook

Complete this procedure to deploy an IdM server with an integrated certificate authority (CA) as the root CA using an Ansible playbook.

Procedure

1. Run the **ansible-playbook** command with the name of the playbook file, for example **install-server.yml**. Specify the inventory file with the **-i** option:

\$ ansible-playbook -v -i <path_to_inventory_directory>/hosts <path_to_playbooks_directory>/install-server.yml

Specify the level of verbosity by using the **-v**, **-vv**, or **-vvv** option.

You can view the output of the Ansible playbook script on the command-line interface (CLI). The following output shows that the script has run successfully as O tasks have failed:

PLAY RECAP

server.idm.example.com : ok=18 changed=10 unreachable=0 **failed=0** skipped=21 rescued=0 ignored=0

- 2. Choose one of the following options:
 - If your IdM deployment uses external DNS: add the DNS resource records contained in the /tmp/ipa.system.records.UFRPto.db file to the existing external DNS servers. The process of updating the DNS records varies depending on the particular DNS solution.

Restarting the KDC

Please add records in this file to your DNS system:
/tmp/ipa.system.records.UFRBto.db

Restarting the web server





IMPORTANT

The server installation is not complete until you add the DNS records to the existing DNS servers.

- If your IdM deployment uses integrated DNS:
 - Add DNS delegation from the parent domain to the IdM DNS domain. For example, if the IdM DNS domain is *idm.example.com*, add a name server (NS) record to the *example.com* parent domain.



IMPORTANT

Repeat this step each time after an IdM DNS server is installed.

Add an _ntp._udp service (SRV) record for your time server to your IdM DNS. The
presence of the SRV record for the time server of the newly-installed IdM server in IdM
DNS ensures that future replica and client installations are automatically configured to
synchronize with the time server used by this primary IdM server.

2.6. DEPLOYING AN IDM SERVER WITH AN EXTERNAL CA AS THE ROOT CA USING AN ANSIBLE PLAYBOOK

Before running the **ansible-playbook** utility, set the parameters that correspond to your scenario by choosing one of the following procedures:

- Procedure with integrated DNS
- Procedure with external DNS

NOTE

The inventory files in the following procedures use the **INI** format. You can, alternatively, use the **YAML** or **JSON** formats.

2.6.1. Setting the parameters for a deployment with an integrated DNS and an external CA as the root CA

Complete this procedure to configure the inventory file for installing an IdM server with an external CA as the root CA in an environment that uses the IdM integrated DNS solution.

Procedure

- 1. Open the inventory file for editing. Specify the fully-qualified domain names (**FQDN**) of the host you want to use as an IdM server. Ensure that the **FQDN** meets the following criteria:
 - Only alphanumeric characters and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.
- 2. Specify the IdM domain and realm information.
- 3. Specify that you want to use integrated DNS by adding the following option:

ipaserver_setup_dns=yes

- 4. Specify the DNS forwarding settings. Choose one of the following options:
 - Use the **ipaserver_auto_forwarders=yes** option if you want the installation process to use forwarders from the /**etc/resolv.conf** file. This option is not recommended if the nameserver specified in the /**etc/resolv.conf** file is the localhost 127.0.0.1 address or if you are on a virtual private network and the DNS servers you are using are normally unreachable from the public internet.

- Use the ipaserver_forwarders option to specify your forwarders manually. The installation process adds the forwarder IP addresses to the /etc/named.conf file on the installed IdM server.
- Use the ipaserver_no_forwarders=yes option to configure root DNS servers to be used instead.

NOTE

With no DNS forwarders, your environment will be isolated, and names from other DNS domains in your infrastructure will not be resolved.

- 5. Specify the DNS reverse record and zone settings. Choose from the following options:
 - Use the **ipaserver_allow_zone_overlap=yes** option to allow the creation of a (reverse) zone even if the zone is already resolvable.
 - Use the **ipaserver_reverse_zones** option to specify your reverse zones manually.
 - Use the **ipaserver_no_reverse=yes** option if you do not want the installation process to create reverse a DNS zone.

NOTE

Using IdM to manage reverse zones is optional. You can use an external DNS service for this purpose instead.

- 6. Specify the passwords for **admin** and for the **Directory Manager**. Use the Ansible Vault to store the password, and reference the Vault file from the playbook file. Alternatively and less securely, specify the passwords directly in the inventory file.
- 7. (Optional) Specify a custom **firewalld** zone to be used by the IdM server. If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of an inventory file with the required server information (excluding the passwords)

[ipaserver] server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes
[...]

Example of an inventory file with the required server information (including the passwords)

[ipaserver] server.idm.example.com

```
[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
[...]
```

Example of an inventory file with a custom firewalld zone

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=yes
ipaserver_auto_forwarders=yes
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
ipaserver_firewalld_zone=custom zone

[...]
```

8. Create a playbook for the first step of the installation. Enter instructions for generating the certificate signing request (CSR) and copying it from the controller to the managed node.

```
- name: Playbook to configure IPA server Step 1
 hosts: ipaserver
 become: true
 vars_files:
 - playbook_sensitive_data.yml
 vars:
  ipaserver_external_ca: yes
 roles:
 - role: ipaserver
  state: present
 post tasks:
 - name: Copy CSR /root/ipa.csr from node to "{{ groups.ipaserver[0] + '-ipa.csr' }}"
  fetch:
    src: /root/ipa.csr
    dest: "{{ groups.ipaserver[0] + '-ipa.csr' }}"
    flat: yes
```

9. Create another playbook for the final step of the installation.

--- name: Playbook to configure IPA server Step -1
hosts: ipaserver

```
become: true
vars_files:
- playbook_sensitive_data.yml
vars:
  ipaserver_external_cert_files: "/root/chain.crt"

pre_tasks:
- name: Copy "{{ groups.ipaserver[0] + '-chain.crt' }}" to /root/chain.crt on node
copy:
    src: "{{ groups.ipaserver[0] + '-chain.crt' }}"
    dest: "/root/chain.crt"
    force: yes

roles:
- role: ipaserver
state: present
```

Additional resources

- For the forwarding policy default settings, see the **--forward-policy** description in the **ipa-dns-install(1)** man page.
- For more information about DNS variables used by the **ipaserver** role, see the DNS Variables section in the **README-server.md** file in the /usr/share/doc/ansible-freeipa directory.

2.6.2. Setting the parameters for a deployment with external DNS and an external CA as the root CA

Complete this procedure to configure the inventory file for installing an IdM server with an external CA as the root CA in an environment that uses an external DNS solution.

Procedure

- 1. Open the inventory file for editing. Specify the fully-qualified domain names (**FQDN**) of the host you want to use as an IdM server. Ensure that the **FQDN** meets the following criteria:
 - Only alphanumeric characters and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.
- 2. Specify the IdM domain and realm information.
- 3. Make sure that the **ipaserver_setup_dns** option is set to **no** or that it is absent.
- 4. Specify the passwords for **admin** and for the **Directory Manager**. Use the Ansible Vault to store the password, and reference the Vault file from the playbook file. Alternatively and less securely, specify the passwords directly in the inventory file.
- 5. (Optional) Specify a custom **firewalld** zone to be used by the IdM server. If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of an inventory file with the required server information (excluding the passwords)

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
[...]
```

Example of an inventory file with the required server information (including the passwords)

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234

[...]
```

Example of an inventory file with a custom firewalld zone

```
[ipaserver]
server.idm.example.com

[ipaserver:vars]
ipaserver_domain=idm.example.com
ipaserver_realm=IDM.EXAMPLE.COM
ipaserver_setup_dns=no
ipaadmin_password=MySecretPassword123
ipadm_password=MySecretPassword234
ipaserver_firewalld_zone=custom zone

[...]
```

6. Create a playbook for the first step of the installation. Enter instructions for generating the certificate signing request (CSR) and copying it from the controller to the managed node.

--
 name: Playbook to configure IPA server Step 1
 hosts: ipaserver
 become: true
 vars_files:

```
- playbook_sensitive_data.yml
vars:
    ipaserver_external_ca: yes

roles:
- role: ipaserver
    state: present

post_tasks:
- name: Copy CSR /root/ipa.csr from node to "{{ groups.ipaserver[0] + '-ipa.csr' }}"
    fetch:
        src: /root/ipa.csr
        dest: "{{ groups.ipaserver[0] + '-ipa.csr' }}"
    flat: yes
```

7. Create another playbook for the final step of the installation.

```
-name: Playbook to configure IPA server Step -1
hosts: ipaserver
become: true
vars_files:
- playbook_sensitive_data.yml
vars:
    ipaserver_external_cert_files: "/root/chain.crt"

pre_tasks:
- name: Copy "{{ groups.ipaserver[0] + '-chain.crt' }}" to /root/chain.crt on node
copy:
    src: "{{ groups.ipaserver[0] + '-chain.crt' }}"
    dest: "/root/chain.crt"
    force: yes

roles:
- role: ipaserver
state: present
```

Additional resources

• For details on the options available to you when installing an IdM server with external DNS and an externally signed CA, see Installing an IdM server: Without integrated DNS, with an external CA as the root CA.

2.6.3. Deploying an IdM server with an external CA as the root CA using an Ansible playbook

Complete this procedure to deploy an IdM server with an external certificate authority (CA) as the root CA using an Ansible playbook.

Procedure

1. Run the **ansible-playbook** command with the name of the playbook file that contains instructions for the first step of the installation, for example **install-server-step1.yml**. Specify the inventory file with the **-i** option:

\$ ansible-playbook -v -i <path_to_inventory_directory>/host.server <path to playbooks directory>/install-server-step1.yml

Specify the level of verbosity by using the **-v**, **-vv** or **-vvv** option.

You can view the output of the Ansible playbook script on the command-line interface (CLI). The following output shows that the script has run successfully as O tasks have failed:

PLAY RECAP

server.idm.example.com : ok=18 changed=10 unreachable=0 **failed=0** skipped=21 rescued=0 ignored=0

- 2. Locate the **ipa.csr** certificate signing request file on the controller and submit it to the external CA.
- 3. Place the IdM CA certificate signed by the external CA in the controller file system so that the playbook in the next step can find it.
- 4. Run the **ansible-playbook** command with the name of the playbook file that contains instructions for the final step of the installation, for example **install-server-step2.yml**. Specify the inventory file with the **-i** option:

\$ ansible-playbook -v -i <path_to_inventory_directory>/host.server <path_to_playbooks_directory>/install-server-step2.yml

- 5. Choose one of the following options:
 - If your IdM deployment uses external DNS: add the DNS resource records contained in the /tmp/ipa.system.records.UFRPto.db file to the existing external DNS servers. The process of updating the DNS records varies depending on the particular DNS solution.

...
Restarting the KDC
Please add records in this file to your DNS system:
/tmp/ipa.system.records.UFRBto.db
Restarting the web server



IMPORTANT

The server installation is not complete until you add the DNS records to the existing DNS servers.

- If your IdM deployment uses integrated DNS:
 - Add DNS delegation from the parent domain to the IdM DNS domain. For example, if the IdM DNS domain is *idm.example.com*, add a name server (NS) record to the example.com parent domain.



IMPORTANT

Repeat this step each time after an IdM DNS server is installed.

Add an _ntp._udp service (SRV) record for your time server to your IdM DNS. The
presence of the SRV record for the time server of the newly-installed IdM server in IdM
DNS ensures that future replica and client installations are automatically configured to
synchronize with the time server used by this primary IdM server.

Additional resources

- Inventory basics: formats, hosts, and groups
- You can see sample Ansible playbooks for installing an IdM server and a list of possible variables in the **ansible-freeipa** upstream documentation.

CHAPTER 3. INSTALLING AN IDENTITY MANAGEMENT REPLICA USING AN ANSIBLE PLAYBOOK

3.1. IDM REPLICA INSTALLATION USING AN ANSIBLE PLAYBOOK

The following sections describe how to configure a system as an IdM replica by using Ansible. Configuring a system as an IdM replica enrolls it into an IdM domain and enables the system to use IdM services on IdM servers in the domain.

The deployment is managed by the **ipareplica** Ansible role. The role can use the autodiscovery mode for identifying the IdM servers, domain and other settings. However, if you deploy multiple replicas in a tierlike model, with different groups of replicas being deployed at different times, you must defined specific servers or replicas for each group.



NOTE

Before installing an IdM replica using Ansible, ensure that you understand Ansible and IdM concepts. Ensure that you understand the following terms that are used in this chapter:

- Ansible roles
- Ansible nodes
- Ansible inventory
- Ansible tasks
- Ansible modules
- Ansible plays and playbooks

Overview

The installation consists of the following parts:

- 1. Setting the parameters of the IdM replica deployment
 - Specifying the base, server and client variables for installing the IdM replica
 - Specifying the credentials for installing the IdM replica using an Ansible playbook
- 2. Deploying an IdM replica using an Ansible playbook

Prerequisites

• You have installed the ansible-freeipa package on the Ansible control node.

3.2. SETTING THE PARAMETERS OF THE IDM REPLICA DEPLOYMENT

Before you deploy a target host as an IdM replica, configure the following settings:

- Specify the base, server and client variables for installing the IdM replica.
- Specify the credentials for installing the IdM replica using an Ansible playbook.

3.2.1. Specifying the base, server and client variables for installing the IdM replica

Complete this procedure to configure the inventory file for installing an IdM replica.

Procedure

- Open the inventory file for editing. Specify the fully-qualified domain names (FQDN) of the hosts to become IdM replicas. The FQDNs must be valid DNS names:
 - Only numbers, alphabetic characters, and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case.

Example of a simple inventory hosts file with only the replicas' FQDN defined

```
[ipareplicas]
replica1.idm.example.com
replica2.idm.example.com
replica3.idm.example.com
[...]
```

If the IdM server is already deployed and the SRV records are set properly in the IdM DNS zone, the script automatically discovers all the other required values.

2. Optionally, provide additional information in the inventory file based on which of the following scenarios is closest to yours:

• Scenario 1

If you want to avoid autodiscovery and have all replicas listed in the **[ipareplicas]** section use a specific IdM server, set the server in the **[ipaservers]** section of the inventory file.

Example inventory hosts file with the FQDN of the IdM server and replicas defined

```
[ipaservers]
server.idm.example.com
```

[ipareplicas] replica1.idm.example.com replica2.idm.example.com replica3.idm.example.com [...]

Scenario 2

Alternatively, if you want to avoid autodiscovery but want to deploy specific replicas with specific servers, set the servers for specific replicas individually in the **[ipareplicas]** section in the inventory file.

Example inventory file with a specific IdM server defined for a specific replica

[ipaservers] server.idm.example.com replica1.idm.example.com [ipareplicas]
replica2.idm.example.com
replica3.idm.example.com ipareplica_servers=replica1.idm.example.com

In the example above, **replica3.idm.example.com** uses the already deployed **replica1.idm.example.com** as its replication source.

Scenario 3

If you are deploying several replicas in one batch and time is a concern to you, multitier replica deployment can be useful for you. Define specific groups of replicas in the inventory file, for example [ipareplicas_tier1] and [ipareplicas_tier2], and design separate plays for each group in the install-replica.yml playbook.

Example inventory file with replica tiers defined

[ipaservers] server.idm.example.com

[ipareplicas_tier1]

replica1.idm.example.com

[ipareplicas_tier2]

replica2.idm.example.com \

ipareplica_servers=replica1.idm.example.com,server.idm.example.com

The first entry in **ipareplica_servers** will be used. The second entry will be used as a fallback option. When using multiple tiers for deploying IdM replicas, you must have separate tasks in the playbook to first deploy replicas from tier1 and then replicas from tier2:

Example of a playbook file with different plays for different replica groups

- name: Playbook to configure IPA replicas (tier1)

hosts: ipareplicas_tier1

become: true

roles:

 role: ipareplica state: present

- name: Playbook to configure IPA replicas (tier2)

hosts: ipareplicas_tier2

become: true

roles:

 role: ipareplica state: present

Scenario 4

If you want the replica to use a specified **firewalld** zone instead of the default one, you can specify it in the inventory file. This can be useful, for example, when you want to use an internal **firewalld** zone for your IdM installation instead of a public zone that is set as default.

and the contract of the contra

If you do not set a custom zone, IdM will add its services to the default **firewalld** zone. The predefined default zone is **public**.



IMPORTANT

The specified **firewalld** zone must exist and be permanent.

Example of a simple inventory hosts file with a custom firewalld zone

[ipaservers] server.idm.example.com

[ipareplicas]
replica1.idm.example.com
replica2.idm.example.com
replica3.idm.example.com
[...]

[ipareplicas:vars]
ipareplica_firewalld_zone=custom zone

3.2.2. Specifying the credentials for installing the IdM replica using an Ansible playbook

Complete this procedure to configure the authorization for installing the IdM replica.

Procedure

- 1. Specify the password of a user authorized to deploy replicas for example the IdM admin.
 - Red Hat recommends using the Ansible Vault to store the password, and referencing the Vault file from the playbook file, for example **install-replica.yml**:

Example playbook file using principal from inventory file and password from an Ansible Vault file

- name: Playbook to configure IPA replicas

hosts: ipareplicas become: true vars_files:

- playbook_sensitive_data.yml

roles:

 role: ipareplica state: present

For details how to use Ansible Vault, see the official Ansible Vault documentation.

Less securely, provide the credentials of admin directly in the inventory file. Use the
ipaadmin_password option in the [ipareplicas:vars] section of the inventory file. The
inventory file and the install-replica.yml playbook file can then look as follows:

Example inventory hosts.replica file

[...]
[ipareplicas:vars]
ipaadmin_password=Secret123

Example playbook using principal and password from inventory file

- name: Playbook to configure IPA replicas

hosts: ipareplicas become: true

roles:

 role: ipareplica state: present

Alternatively but also less securely, provide the credentials of another user authorized to
deploy a replica directly in the inventory file. To specify a different authorized user, use the
ipaadmin_principal option for the user name, and the ipaadmin_password option for the
password. The inventory file and the install-replica.yml playbook file can then look as
follows:

Example inventory hosts.replica file

[...]
[ipareplicas:vars]
ipaadmin_principal=my_admin
ipaadmin_password=my_admin_secret123

Example playbook using principal and password from inventory file

- name: Playbook to configure IPA replicas

hosts: ipareplicas become: true

roles:

 role: ipareplica state: present

Additional resources

• For details on the options accepted by the **ipareplica** Ansible role, see the /usr/share/ansible/roles/ipareplica/README.md Markdown file.

3.3. DEPLOYING AN IDM REPLICA USING AN ANSIBLE PLAYBOOK

Complete this procedure to use an Ansible playbook to deploy an IdM replica.

Procedure

 To install an IdM replica using an Ansible playbook, use the ansible-playbook command with the name of the playbook file, for example install-replica.yml. Specify the inventory file with the -i option:

\$ ansible-playbook -v -i <path_to_inventory_directory>/hosts.replica <path_to_playbooks_directory>/install-replica.yml

Specify the level of verbosity by using the **-v**, **-vv** or **-vvv** option.

Ansible informs you about the execution of the Ansible playbook script. The following output shows that the script has run successfully as 0 tasks have failed:

PLAY RECAP

replica.idm.example.com : ok=18 changed=10 unreachable=0 **failed=0** skipped=21 rescued=0 ignored=0

You have now installed an IdM replica.

CHAPTER 4. INSTALLING AN IDENTITY MANAGEMENT CLIENT USING AN ANSIBLE PLAYBOOK

4.1. IDM CLIENT INSTALLATION USING AN ANSIBLE PLAYBOOK

The following sections describe how to configure a system as an Identity Management (IdM) client by using Ansible. Configuring a system as an IdM client enrolls it into an IdM domain and enables the system to use IdM services on IdM servers in the domain.

The deployment is managed by the **ipaclient** Ansible role. By default, the role uses the autodiscovery mode for identifying the IdM servers, domain and other settings. The role can be modified to have the Ansible playbook use the settings specified, for example in the inventory file.



NOTE

Before installing an IdM client using Ansible, ensure that you understand Ansible and IdM concepts. Ensure that you understand the following terms that are used in this chapter:

- Ansible roles
- Ansible nodes
- Ansible inventory
- Ansible tasks
- Ansible modules
- Ansible plays and playbooks

Overview

The installation consists of the following parts:

- 1. Setting the parameters of the IdM client deployment to correspond to your deployment scenario:
 - Setting the parameters of the inventory file for the autodiscovery client installation mode;
 - Setting the parameters of the inventory file for when autodiscovery is not possible during client installation;
- 2. Checking the parameters in install-client.yml;
- 3. Deploying an IdM client using an Ansible playbook;
- 4. Testing an Identity Management client after installation .

The chapter also includes a section describing how to uninstall an IdM client.

Prerequisites

• You have installed the ansible-freeipa package on the Ansible control node.

4.2. SETTING THE PARAMETERS OF THE IDM CLIENT DEPLOYMENT

Before you deploy a target host as an IdM client, configure the deployment instructions on the control node. Additionally, configure the target host parameters depending on which of the following options you are planning:

- Using the autodiscovery client installation mode
- Specifying the **FQDN** of the IdM server and the domain or realm information .

4.2.1. Setting the parameters of the inventory file for the autodiscovery client installation mode

To install an Identity Management client using an Ansible playbook, provide the following information in an inventory file, for example **inventory/hosts**:

- the information about the host
- the authorization for the task

The inventory file can be in one of many formats, depending on the inventory plugins you have. The **INI-like** format is one of Ansible's defaults and is used in the examples below.



NOTE

To use smart cards with the graphical user interface in RHEL, ensure that you include the **ipaclient_mkhomedir** variable in your Ansible playbook.

Procedure

- 1. Specify the fully-qualified hostname (**FQDN**) of the host to become an IdM client. The fully qualified domain name must be a valid DNS name:
 - Only numbers, alphabetic characters, and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case. No capital letters are allowed.
 If the SRV records are set properly in the IdM DNS zone, the script automatically discovers all the other required values.

Example of a simple inventory hosts file with only the client FQDN defined

[ipaclients] client.idm.example.com [...]

- 2. Specify the credentials for enrolling the client. The following authentication methods are available:
 - The password of a user authorized to enroll clients This is the default option.
 - Red Hat recommends using the Ansible Vault to store the password, and referencing the Vault file from the playbook file, for example **install-client.yml**, directly:

Example playbook file using principal from inventory file and password from an Ansible Vault file

- name: Playbook to configure IPA clients with username/password

hosts: ipaclients become: true vars_files:

- playbook_sensitive_data.yml

roles:

- role: ipaclient state: present

• Less securely, provide the credentials of admin using the ipaadmin_password option in the [ipaclients:vars] section of the inventory/hosts file. Alternatively, to specify a different authorized user, use the ipaadmin_principal option for the user name, and the ipaadmin_password option for the password. The inventory/hosts inventory file and the install-client.yml playbook file can then look as follows:

Example inventory hosts file

[...]
[ipaclients:vars]
ipaadmin_principal=my_admin
ipaadmin_password=Secret123

Example Playbook using principal and password from inventory file

- name: Playbook to unconfigure IPA clients

hosts: ipaclients become: true

roles:

role: ipaclient state: true

- The **client keytab** from the previous enrollment if it is still available:
 - This option is available if the system was previously enrolled as an Identity Management client. To use this authentication method, uncomment the #ipaclient_keytab option, specifying the path to the file storing the keytab, for example in the [ipaclient:vars] section of inventory/hosts.
- A random, one-time password (OTP) to be generated during the enrollment. To use this
 authentication method, use the ipaclient_use_otp=yes option in your inventory file. For
 example, you can uncomment the ipaclient_use_otp=yes option in the [ipaclients:vars]
 section of the inventory/hosts file. Note that with OTP you must also specify one of the
 following options:
 - The password of a user authorized to enroll clients for example by providing a value for ipadmin_password in the [ipaclients:vars] section of the inventory/hosts file.
 - The admin keytab, for example by providing a value for ipaadmin_keytab in the [ipaclients:vars] section of inventory/hosts.

Additional resources

• For details on the options accepted by the **ipaclient** Ansible role, see the /usr/share/ansible/roles/ipaclient/README.md README file.

4.2.2. Setting the parameters of the inventory file when autodiscovery is not possible during client installation

To install an Identity Management client using an Ansible playbook, provide the following information in an inventory file, for example **inventory/hosts**:

- the information about the host, the IdM server and the IdM domain or the IdM realm
- the authorization for the task

The inventory file can be in one of many formats, depending on the inventory plugins you have. The **INI-like** format is one of Ansible's defaults and is used in the examples below.



NOTE

To use smart cards with the graphical user interface in RHEL, ensure that you include the **ipaclient_mkhomedir** variable in your Ansible playbook.

Procedure

- 1. Specify the fully-qualified hostname (**FQDN**) of the host to become an IdM client. The fully qualified domain name must be a valid DNS name:
 - Only numbers, alphabetic characters, and hyphens (-) are allowed. For example, underscores are not allowed and can cause DNS failures.
 - The host name must be all lower-case. No capital letters are allowed.
- 2. Specify other options in the relevant sections of the **inventory/hosts** file:
 - the **FQDN** of the servers in the **[ipaservers]** section to indicate which IdM server the client will be enrolled with
 - one of the two following options:
 - the **ipaclient_domain** option in the **[ipaclients:vars]** section to indicate the DNS domain name of the IdM server the client will be enrolled with
 - the **ipaclient_realm** option in the **[ipaclients:vars]** section to indicate the name of the Kerberos realm controlled by the IdM server

Example of an inventory hosts file with the client FQDN, the server FQDN and the domain defined

[ipaclients]
client.idm.example.com
[ipaservers]
server.idm.example.com
[ipaclients:vars]
ipaclient_domain=idm.example.com

- 3. Specify the credentials for enrolling the client. The following authentication methods are available:
 - The password of a user authorized to enroll clients This is the default option.
 - Red Hat recommends using the Ansible Vault to store the password, and referencing the Vault file from the playbook file, for example **install-client.yml**, directly:

Example playbook file using principal from inventory file and password from an Ansible Vault file

- name: Playbook to configure IPA clients with username/password

hosts: ipaclients become: true vars_files:

- playbook_sensitive_data.yml

roles:

 role: ipaclient state: present

• Less securely, provide the credentials of admin using the ipaadmin_password option in the [ipaclients:vars] section of the inventory/hosts file. Alternatively, to specify a different authorized user, use the ipaadmin_principal option for the user name, and the ipaadmin_password option for the password. The install-client.yml playbook file can then look as follows:

Example inventory hosts file

[...]
[ipaclients:vars]
ipaadmin_principal=my_admin
ipaadmin_password=Secret123

Example Playbook using principal and password from inventory file

- name: Playbook to unconfigure IPA clients

hosts: ipaclients become: true

roles:

 role: ipaclient state: true

- The **client keytab** from the previous enrollment if it is still available:
 - This option is available if the system was previously enrolled as an Identity Management client. To use this authentication method, uncomment the **ipaclient_keytab** option, specifying the path to the file storing the keytab, for example in the **[ipaclient:vars]** section of **inventory/hosts**.
- A random, one-time password (OTP) to be generated during the enrollment. To use this
 authentication method, use the ipaclient_use_otp=yes option in your inventory file. For
 example, you can uncomment the #ipaclient_use_otp=yes option in the [ipaclients:vars]

section of the **inventory/hosts** file. Note that with OTP you must also specify one of the following options:

- The password of a user authorized to enroll clients for example by providing a value for ipadmin_password in the [ipaclients:vars] section of the inventory/hosts file.
- The admin keytab, for example by providing a value for ipaadmin_keytab in the [ipaclients:vars] section of inventory/hosts.

Additional resources

• For details on the options accepted by the **ipaclient** Ansible role, see the /usr/share/ansible/roles/ipaclient/README.md README file.

4.2.3. Checking the parameters in the install-client.yml file

The install-client.yml playbook file contains instructions for the IdM client deployment.

• Open the file and check if the instructions in the playbook correspond to what you are planning for your deployment. The contents typically look like this:

- name: Playbook to configure IPA clients with username/password

hosts: ipaclients become: true

roles:

 role: ipaclient state: present

This is what the individual entries mean:

- The hosts entry specifies the section of the **inventory/hosts** file where the ansible script searches the **FQDNs** of the hosts on which the **ipa-client-install** script shall be run.
- The **become: true** entry specifies that root's credentials will be invoked during the execution of the **ipa-client-install** script.
- The **role: ipaclient** entry specifies the role that will be installed on the host: in this case, it is the ipa client role.
- The **state: present** entry specifies that the client should be installed rather than uninstalled (**absent**).

4.2.4. Authorization options for IdM client enrollment using an Ansible playbook

This referential section presents individual authorization options for IdM client enrollment with examples of inventory and playbook files.

Table 4.1. Authorization options for IdM client enrollment using Ansible

Authorizat ion option	Note	Example inventory file	Example install-client.yml playbook file
Password of a user authorized to enroll a client: Option 1	Password stored in Ansible vault	[ipaclients:vars] []	- name: Playbook to configure IPA clients with username/password hosts: ipaclients become: true vars_files: - playbook_sensitive_data.yml roles: - role: ipaclient state: present
Password of a user authorized to enroll a client: Option 2	Password stored in inventory file	[ipaclients:vars] ipaadmin_password=Secret123	- name: Playbook to configure IPA clients hosts: ipaclients become: true roles: - role: ipaclient state: true
A random, one-time password (OTP): Option 1	OTP + administrat or password	[ipaclients:vars] ipaadmin_password=Secret123 ipaclient_use_otp=yes	- name: Playbook to configure IPA clients hosts: ipaclients become: true roles: - role: ipaclient state: true
A random, one-time password (OTP): Option 2	OTP + an admin keytab	[ipaclients:vars] ipaadmin_keytab=/tmp/admin.ke ytab ipaclient_use_otp=yes	- name: Playbook to configure IPA clients hosts: ipaclients become: true roles: - role: ipaclient state: true

Authorizat ion option	Note	Example inventory file	Example install-client.yml playbook file
The client keytab from the previous enrollment		[ipaclients:vars] ipaclient_keytab=/tmp/krb5.keyta b	 name: Playbook to configure IPA clients hosts: ipaclients become: true roles: role: ipaclient state: true

4.3. DEPLOYING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK

Complete this procedure to use an Ansible playbook to deploy an IdM client in your IdM environment.

Procedure

 To install an IdM client using an Ansible playbook, use the ansible-playbook command with the name of the playbook file, for example install-client.yml. Specify the inventory file with the -i option:

\$ ansible-playbook -v -i inventory/hosts install-client.yml

Specify the level of verbosity by using the **-v**, **-vv** or **-vvv** option.

Ansible informs you about the execution of the Ansible playbook script. The following output shows that the script has run successfully as no tasks have failed:

PLAY RECAP

client1.idm.example.com : ok=18 changed=10 unreachable=0 failed=0 skipped=21 rescued=0 ignored=0



NOTE

Ansible uses different colors to provide different types of information about the running process. You can modify the default colors in the **[colors]** section of the **/etc/ansible/ansible.cfg** file:

[colors]
[...]
#error = red
#debug = dark gray
#deprecate = purple
#skip = cyan
#unreachable = red
#ok = green
#changed = yellow
[...]

You have now installed an IdM client on your host using an Ansible playbook.

4.4. TESTING AN IDENTITY MANAGEMENT CLIENT AFTER ANSIBLE INSTALLATION

The command-line interface (CLI) informs you that the **ansible-playbook** command was successful, but you can also do your own test.

To test that the Identity Management client can obtain information about users defined on the server, check that you are able to resolve a user defined on the server. For example, to check the default **admin** user.

[user@client1 ~]\$ **id admin** uid=1254400000(admin) gid=1254400000(admins) groups=1254400000(admins)

To test that authentication works correctly, **su** - as another already existing IdM user:

[user@client1 ~]\$ **su - idm_user**Last login: Thu Oct 18 18:39:11 CEST 2018 from 192.168.122.1 on pts/0
[idm_user@client1 ~]\$

4.5. UNINSTALLING AN IDM CLIENT USING AN ANSIBLE PLAYBOOK

Complete this procedure to use an Ansible playbook to uninstall your host as an IdM client.

Prerequisites

• IdM administrator credentials.

Procedure

• To uninstall the IdM client, use the **ansible-playbook** command with the name of the playbook file, for example **uninstall-client.yml**. Specify the inventory file with the **-i** option and, optionally, specify the level of verbosity by using the **-v**, **-vv** or **-vvv** options:

\$ ansible-playbook -v -i inventory/hosts uninstall-client.yml



IMPORTANT

The uninstallation of the client only removes the basic IdM configuration from the host but leaves the configuration files on the host in case you decide to re-install the client. In addition, the uninstallation has the following limitations:

- It does not remove the client host entry from the IdM LDAP server. The uninstallation only unenrolls the host.
- It does not remove any services residing on the client from IdM.
- It does not remove the DNS entries for the client from the IdM server.
- It does not remove the old principals for keytabs other than /etc/krb5.keytab.

Note that the uninstallation does remove all certificates that were issued for the host by the IdM CA.

Additional resources

• For more information on how to remove the IdM client configuration from both the host and the IdM environment completely, see the manual procedure for Uninstalling an IdM client.

CHAPTER 5. PREPARING YOUR ENVIRONMENT FOR MANAGING IDM USING ANSIBLE PLAYBOOKS

As a system administrator managing Identity Management (IdM), when working with Red Hat Ansible Engine, it is good practice to do the following:

- Create a subdirectory dedicated to Ansible playbooks in your home directory, for example ~/MyPlaybooks.
- Copy and adapt sample Ansible playbooks from the /usr/share/doc/ansible-freeipa/* and /usr/share/doc/rhel-system-roles/* directories and subdirectories into your ~/MyPlaybooks directory.
- Include your inventory file in your ~/MyPlaybooks directory.

Using this practice, you can find all your playbooks in one place and you can run your playbooks without invoking root privileges.



NOTE

You only need **root** privileges on the managed nodes to execute the **ipaserver**, **ipareplica**, **ipaclient** and **ipabackup ansible-freeipa** roles. These roles require privileged access to directories and the **dnf** software package manager.

This section describes how to create the ~/MyPlaybooks directory and configure it so that you can use it to store and run Ansible playbooks.

Prerequisites

- You have installed an IdM server on your managed nodes, **server.idm.example.com** and **replica.idm.example.com**.
- You have configured DNS and networking so you can log in to the managed nodes, server.idm.example.com and replica.idm.example.com, directly from the control node.
- You know the IdM admin password.

Procedure

1. Create a directory for your Ansible configuration and playbooks in your home directory:

\$ mkdir ~/MyPlaybooks/

2. Change into the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks

3. Create the ~/MyPlaybooks/ansible.cfg file with the following content:

[defaults] inventory = /home/your_username/MyPlaybooks/inventory

[privilege_escalation] become=True

4. Create the ~/MyPlaybooks/inventory file with the following content:

[eu]
server.idm.example.com

[us]
replica.idm.example.com

[ipaserver:children]
eu
us

This configuration defines two host groups, **eu** and **us**, for hosts in these locations. Additionally, this configuration defines the **ipaserver** host group, which contains all hosts from the **eu** and **us** groups.

5. [Optional] Create an SSH public and private key. To simplify access in your test environment, do not set a password on the private key:

\$ ssh-keygen

6. Copy the SSH public key to the IdM **admin** account on each managed node:

\$ ssh-copy-id admin@server.idm.example.com \$ ssh-copy-id admin@replica.idm.example.com

These commands require that you enter the IdM **admin** password.

Additional resources

- For more information on installing an IdM server using an Ansible playbook, see Installing an Identity Management server using an Ansible playbook.
- For an overview of available formats for an Ansible inventory file including examples, see How to build your inventory.

CHAPTER 6. CONFIGURING GLOBAL IDM SETTINGS USING ANSIBLE PLAYBOOKS

Using the Ansible config module, you can retrieve and set global configuration parameters for Identity Management (IdM).

This chapter includes the following sections:

- Retrieving IdM configuration using an Ansible playbook
- Configuring the IdM CA renewal server using an Ansible playbook
- Configuring the default shell for IdM users using an Ansible playbook

6.1. RETRIEVING IDM CONFIGURATION USING AN ANSIBLE **PLAYBOOK**

The following procedure describes how you can use an Ansible playbook to retrieve information about the current global IdM configuration.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define the IdM server from which you want to retrieve the IdM configuration in the [ipaserver] section. For example, to instruct Ansible to retrieve the data from **server.idm.example.com**, enter:

```
[ipaserver]
server.idm.example.com
```

2. Open the /usr/share/doc/ansible-freeipa/playbooks/config/retrieve-config.yml Ansible playbook file for editing:

```
- name: Playbook to handle global IdM configuration
hosts: ipaserver
 become: no
 gather_facts: no
 tasks:
 - name: Query IPA global configuration
```

ipaconfig:

ipaadmin_password: Secret123

register: serverconfig

debug:

msg: "{{ serverconfig }}"

- 3. Adapt the file by changing the following:
 - The password of IdM administrator.
 - Other values, if necessary.
- 4. Save the file.
- 5. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
/usr/share/doc/ansible-freeipa/playbooks/config/retrieve-config.yml
[...]
TASK [debug]
ok: [server.idm.example.com] => {
  "msg": {
     "ansible_facts": {
       "discovered_interpreter_
     "changed": false,
     "config": {
       "ca_renewal_master_server": "server.idm.example.com",
       "configstring": [
          "AllowNThash",
          "KDC:Disable Last Success"
       "defaultgroup": "ipausers",
       "defaultshell": "/bin/bash",
       "emaildomain": "idm.example.com",
       "enable migration": false,
       "groupsearch": [
          "cn",
          "description"
       "homedirectory": "/home",
       "maxhostname": "64",
       "maxusername": "64",
       "pac_type": [
          "MS-PAC",
          "nfs:NONE"
       "pwdexpnotify": "4",
       "searchrecordslimit": "100",
       "searchtimelimit": "2",
       "selinuxusermapdefault": "unconfined_u:s0-s0:c0.c1023",
       "selinuxusermaporder": [
          "guest u:s0$xguest u:s0$user
       "usersearch": [
          "uid",
          "givenname",
          "sn",
          "telephonenumber",
          "ou",
          "title"
```

```
},
"failed": false
}
}
```

6.2. CONFIGURING THE IDM CA RENEWAL SERVER USING AN ANSIBLE PLAYBOOK

In an Identity Management (IdM) deployment that uses an embedded certificate authority (CA), the CA renewal server maintains and renews IdM system certificates. It ensures robust IdM deployments.

For more details on the role of the IdM CA renewal server, see Using IdM CA renewal server.

The following procedure describes how you can use an Ansible playbook to configure the IdM CA renewal server.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.

Procedure

1. Optional: Identify the current IdM CA renewal server:

```
$ ipa config-show | grep 'CA renewal'
IPA CA renewal master: server.idm.example.com
```

2. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver] server.idm.example.com
```

3. Open the /usr/share/doc/ansible-freeipa/playbooks/config/set-ca-renewal-master-server.yml Ansible playbook file for editing:

```
---
- name: Playbook to handle global DNS configuration
hosts: ipaserver
become: no
gather_facts: no

tasks:
- name: set ca_renewal_master_server
ipaconfig:
    ipaadmin_password: SomeADMINpassword
    ca_renewal_master_server: carenewal.idm.example.com
```

- 4. Adapt the file by changing:
 - The password of IdM administrator set by the **ipaadmin_password** variable.
 - The name of the CA renewal server set by the **ca_renewal_master_server** variable.

- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file and the inventory file:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/config/set-ca-renewal-master-server.yml

Verification steps

You can verify that the CA renewal server has been changed:

1. Log into **ipaserver** as IdM administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Request the identity of the IdM CA renewal server:

\$ ipa config-show | grep 'CA renewal' IPA CA renewal master: carenewal.idm.example.com

The output shows the **carenewal.idm.example.com** server is the new CA renewal server.

6.3. CONFIGURING THE DEFAULT SHELL FOR IDM USERS USING AN ANSIBLE PLAYBOOK

The shell is a program that accepts and interprets commands. Several shells are available in Red Hat Enterprise Linux (RHEL), such as **bash**, **sh**, **ksh**, **zsh**, **fish**, and others. **Bash**, or /**bin/bash**, is a popular shell on most Linux systems, and it is normally the default shell for user accounts on RHEL.

The following procedure describes how you can use an Ansible playbook to configure **sh**, an alternative shell, as the default shell for IdM users.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.

Procedure

- 1. Optional: Use the **retrieve-config.yml** Ansible playbook to identify the current shell for IdM users. See Retrieving IdM configuration using an Ansible playbook for details.
- 2. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

 Open the /usr/share/doc/ansible-freeipa/playbooks/config/ensure-config-options-areset.yml Ansible playbook file for editing:

- name: Playbook to ensure some config options are set

hosts: ipaserver become: true

tasks:

Set defaultlogin and maxusername

- ipaconfig:

ipaadmin_password: Secret123

defaultshell: /bin/bash maxusername: 64

- 4. Adapt the file by changing the following:
 - The password of IdM administrator set by the **ipaadmin_password** variable.
 - The default shell of the IdM users set by the **defaultshell** variable into /bin/sh.
- 5. Save the file.
- 6. Run the Ansible playbook. Specify the playbook file and the inventory file:

\$ ansible-playbook -v -i *path_to_inventory_directory*/inventory.file /usr/share/doc/ansible-freeipa/playbooks/config/ensure-config-options-are-set.yml

Verification steps

You can verify that the default user shell has been changed by starting a new session in IdM:

1. Log into **ipaserver** as IdM administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server /]\$

2. Display the current shell:

[admin@server /]\$ echo "\$SHELL" /bin/sh

The logged-in user is using the **sh** shell.

Additional resources

- You can see sample Ansible playbooks for configuring global IdM settings and a list of possible variables in the README-config.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory.
- You can see sample Ansible playbooks for various IdM configuration-related operations in the /usr/share/doc/ansible-freeipa/playbooks/config directory.

CHAPTER 7. MANAGING USER ACCOUNTS USING ANSIBLE PLAYBOOKS


You can manage users in IdM using Ansible playbooks. After presenting the user life cycle, this chapter describes how to use Ansible playbooks for the following operations:

- Ensuring the presence of a single user listed directly in the YML file.
- Ensuring the presence of multiple users listed directly in the YML file.
- Ensuring the presence of multiple users listed in a JSON file that is referenced from the YML file.
- Ensuring the absence of users listed directly in the YML file.

7.1. USER LIFE CYCLE

Identity Management (IdM) supports three user account states:

- **Stage** users are not allowed to authenticate. This is an initial state. Some of the user account properties required for active users cannot be set, for example, group membership.
- Active users are allowed to authenticate. All required user account properties must be set in this state.
- **Preserved** users are former active users that are considered inactive and cannot authenticate to IdM. Preserved users retain most of the account properties they had as active users, but they are not part of any user groups.



You can delete user entries permanently from the IdM database.



IMPORTANT

Deleted user accounts cannot be restored. When you delete a user account, all the information associated with the account is permanently lost.

A new administrator can only be created by a user with administrator rights, such as the default admin user. If you accidentally delete all administrator accounts, the Directory Manager must create a new administrator manually in the Directory Server.



WARNING

Do not delete the **admin** user. As **admin** is a pre-defined user required by IdM, this operation causes problems with certain commands. If you want to define and use an alternative admin user, disable the pre-defined **admin** user with **ipa user-disable admin** after you granted admin permissions to at least one different user.



WARNING

Do not add local users to IdM. The Name Service Switch (NSS) always resolves IdM users and groups before resolving local users and groups. This means that, for example, IdM group membership does not work for local users.

7.2. ENSURING THE PRESENCE OF AN IDM USER USING AN ANSIBLE PLAYBOOK

The following procedure describes ensuring the presence of a user in IdM using an Ansible playbook.

Prerequisites

- You know the IdM administator password.
- The ansible-freeipa package is installed on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the data of the user whose presence in IdM you want to ensure. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/user/add-user.yml file. For example, to create user named idm_user and add Password123 as the user password:

- name: Playbook to handle users

hosts: ipaserver become: true

tasks:

- name: Create user idm_user

ipauser:

ipaadmin_password: MySecret123

name: idm_user first: Alice last: Acme

uid: 1000111 gid: 10011

phone: "+555123457"

email: idm_user@acme.com

passwordexpiration: "2023-01-19 23:59:59"

password: "Password123" update_password: on_create

You must use the following options to add a user:

• name: the login name

• first: the first name string

• last: the last name string

For the full list of available user options, see the /usr/share/doc/ansible-freeipa/README-user.md Markdown file.



NOTE

If you use the **update_password: on_create** option, Ansible only creates the user password when it creates the user. If the user is already created with a password, Ansible does not generate a new password.

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/add-ldM-user.yml

Verification steps

- You can verify if the new user account exists in IdM by using the **ipa user-show** command:
 - 1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin
Password for admin@IDM.EXAMPLE.COM:

3. Request information about idm_user.

\$ ipa user-show idm user

User login: idm_user First name: Alice Last name: Acme

The user named *idm_user* is present in IdM.

7.3. ENSURING THE PRESENCE OF MULTIPLE IDM USERS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of multiple users in IdM using an Ansible playbook.

Prerequisites

- You know the IdM administator password.
- You have installed the ansible-freeipa package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

 Create an Ansible playbook file with the data of the users whose presence you want to ensure in IdM. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansiblefreeipa/playbooks/user/ensure-users-present.yml file. For example, to create users idm_user_1, idm_user_2, and idm_user_3, and add Password123 as the password of idm_user_1:

- name: Playbook to handle users

hosts: ipaserver become: true

tasks:

- name: Create user idm_users

ipauser:

ipaadmin_password: MySecret123

users

- name: idm user 1

first: Alice last: Acme uid: 10001 gid: 10011

phone: "+555123457"

email: idm_user@acme.com

passwordexpiration: "2023-01-19 23:59:59"

password: "Password123"

- name: idm_user_2

first: Bob last: Acme uid: 100011 gid: 10011

- name: idm_user_3

first: Eve last: Acme uid: 1000111 gid: 10011



NOTE

If you do not specify the **update_password**: **on_create** option, Ansible re-sets the user password every time the playbook is run: if the user has changed the password since the last time the playbook was run, Ansible re-sets password.

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/add-users.yml

Verification steps

- You can verify if the user account exists in IdM by using the **ipa user-show** command:
 - 1. Log into **ipaserver** as administrator:

\$ ssh administrator@server.idm.example.com Password: [admin@server /]\$

2. Display information about idm_user_1:

\$ ipa user-show idm_user_1
User login: idm_user_1
First name: Alice
Last name: Acme
Password: True
....

The user named *idm_user_1* is present in IdM.

7.4. ENSURING THE PRESENCE OF MULTIPLE IDM USERS FROM A JSON FILE USING ANSIBLE PLAYBOOKS

The following procedure describes how you can ensure the presence of multiple users in IdM using an Ansible playbook. The users are stored in a **JSON** file.

Prerequisites

- You know the IdM administator password.
- You have installed the ansible-freeipa package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver] server.idm.example.com
```

2. Create an Ansible playbook file with the necessary tasks. Reference the **JSON** file with the data of the users whose presence you want to ensure. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/ensure-users-present-ymlfile.yml file:

```
---
- name: Ensure users' presence
hosts: ipaserver
become: true

tasks:
- name: Include users.json
include_vars:
file: users.json

- name: Users present
ipauser:
ipaadmin_password: MySecret123
users: "{{ users }}"
```

3. Create the **users.json** file, and add the IdM users into it. To simplify this step, you can copy and modify the example in the /**usr/share/doc/ansible-freeipa/playbooks/user/users.json** file. For example, to create users *idm_user_1*, *idm_user_2*, and *idm_user_3*, and add *Password123* as the password of *idm_user_1*:

```
{
  "users": [
    {
      "name": "idm_user_1",
      "first": "Alice",
      "password": "Password123"
    },
    {
      "name": "idm_user_2",
      "first": "Bob",
      "last": "Acme"
    },
    {
      "name": "idm_user_3",
      "first": "Eve",
      "last": "Acme"
    }
    ]
}
```

4. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-users-present-jsonfile.yml

Verification steps

- You can verify if the user accounts are present in IdM using the **ipa user-show** command:
 - 1. Log into **ipaserver** as administrator:

\$ ssh administrator@server.idm.example.com Password: [admin@server /]\$

2. Display information about idm_user_1:

\$ ipa user-show idm_user_1
User login: idm_user_1
First name: Alice
Last name: Acme
Password: True
....

The user named idm_user_1 is present in IdM.

7.5. ENSURING THE ABSENCE OF USERS USING ANSIBLE PLAYBOOKS

The following procedure describes how you can use an Ansible playbook to ensure that specific users are absent from IdM.

Prerequisites

- You know the IdM administator password.
- You have installed the ansible-freeipa package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

 Create an Ansible playbook file with the users whose absence from IdM you want to ensure. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansiblefreeipa/playbooks/user/ensure-users-present.yml file. For example, to delete users idm_user_1, idm_user_2, and idm_user_3:

- name: Playbook to handle users

hosts: ipaserver become: true

tasks:

- name: Delete users idm_user_1, idm_user_2, idm_user_3

ipauser:

ipaadmin_password: MySecret123

users:

name: idm_user_1name: idm_user_2name: idm_user_3state: absent

3. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/delete-users.yml

Verification steps

You can verify that the user accounts do not exist in IdM by using the **ipa user-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh administrator@server.idm.example.com Password: [admin@server/]\$

2. Request information about idm_user_1:

```
$ ipa user-show idm_user_1 ipa: ERROR: idm_user_1: user not found
```

The user named *idm_user_1* does not exist in IdM.

Additional resources

- You can see sample Ansible playbooks for other IdM user-related actions such as preserving, deleting, enabling, disabling, unlocking and undeleting users in the README-user.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of ipauser variables.
- You can also see sample Ansible playbooks in the /usr/share/doc/ansible-freeipa/playbooks/user directory.

CHAPTER 8. MANAGING USER GROUPS USING ANSIBLE PLAYBOOKS

This section introduces user group management using Ansible playbooks.

A user group is a set of users with common privileges, password policies, and other characteristics.

A user group in Identity Management (IdM) can include:

- IdM users
- other IdM user groups
- external users, which are users that exist outside of IdM

The section includes the following topics:

- The different group types in IdM
- Direct and indirect group members
- Ensuring the presence of IdM groups and group members using Ansible playbooks
- Ensuring the presence of member managers in IDM user groups using Ansible playbooks
- Ensuring the absence of member managers in IDM user groups using Ansible playbooks

8.1. THE DIFFERENT GROUP TYPES IN IDM

IdM supports the following types of groups:

POSIX groups (the default)

POSIX groups support Linux POSIX attributes for their members. Note that groups that interact with Active Directory cannot use POSIX attributes.

POSIX attributes identify users as separate entities. Examples of POSIX attributes relevant to users include **uidNumber**, a user number (UID), and **gidNumber**, a group number (GID).

Non-POSIX groups

Non-POSIX groups do not support POSIX attributes. For example, these groups do not have a GID defined

All members of this type of group must belong to the IdM domain.

External groups

Use external groups to add group members that exist in an identity store outside of the IdM domain, such as:

- A local system
- An Active Directory domain
- A directory service

External groups do not support POSIX attributes. For example, these groups do not have a GID defined.

Table 8.1. User groups created by default

Group name	Default group members
ipausers	All IdM users
admins	Users with administrative privileges, including the default admin user
editors	This is a legacy group that no longer has any special privileges
trust admins	Users with privileges to manage the Active Directory trusts

When you add a user to a user group, the user gains the privileges and policies associated with the group. For example, to grant administrative privileges to a user, add the user to the **admins** group.



WARNING

Do not delete the **admins** group. As **admins** is a pre-defined group required by IdM, this operation causes problems with certain commands.

In addition, IdM creates *user private groups* by default whenever a new user is created in IdM. For more information about private groups, see Adding users without a private group.


8.2. DIRECT AND INDIRECT GROUP MEMBERS

User group attributes in IdM apply to both direct and indirect members: when group B is a member of group A, all users in group B are considered indirect members of group A.

For example, in the following diagram:

- User 1 and User 2 are *direct members* of group A.
- User 3, User 4, and User 5 are indirect members of group A.

Figure 8.1. Direct and Indirect Group Membership



84_RHEL_0420

If you set a password policy for user group A, the policy also applies to all users in user group B.

8.3. ENSURING THE PRESENCE OF IDM GROUPS AND GROUP MEMBERS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of IdM groups and group members - both users and user groups - using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.
- The users you want to reference in your Ansible playbook exist in IdM. For details on ensuring the presence of users using Ansible, see Managing user accounts using Ansible playbooks.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary user and group information:

 name: Playbook to handle groups hosts: ipaserver become: true

tasks:

- name: Create group ops with gid 1234

ipagroup:

ipaadmin_password: MySecret123

name: ops gidnumber: 1234

- name: Create group sysops

ipagroup:

ipaadmin_password: MySecret123

name: sysops

user:
- idm_user

- name: Create group appops

ipagroup:

ipaadmin_password: MySecret123

name: appops

- name: Add group members sysops and appops to group ops

ipagroup:

ipaadmin_password: MySecret123

name: ops group: - sysops - appops 3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/add-group-members.yml

Verification steps

You can verify if the **ops** group contains **sysops** and **appops** as direct members and **idm_user** as an indirect member by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server /]\$

2. Display information about ops:

ipaserver]\$ ipa group-show ops Group name: ops GID: 1234

Member groups: sysops, appops Indirect Member users: idm_user

The appops and sysops groups - the latter including the idm_user user - exist in IdM.

Additional resources

• For more information about ensuring the presence of user groups using Ansible, see the /usr/share/doc/ansible-freeipa/README-group.md Markdown file.

8.4. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of IdM member managers - both users and user groups - using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.
- You must have the name of the user or group you are adding as member managers and the name of the group you want them to manage.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the necessary user and group member management information:

- name: Playbook to handle membership management

hosts: ipaserver become: true

tasks:

- name: Ensure user test is present for group_a

ipagroup:

ipaadmin password: MySecret123

name: group a

membermanager_user: test

- name: Ensure group_admins is present for group_a

ipagroup:

ipaadmin_password: MySecret123

name: group_a

membermanager_group: group_admins

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/add-member-managers-user-groups.yml

Verification steps

You can verify if the **group_a** group contains **test** as a member manager and **group_admins** is a member manager of **group_a** by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server /]\$

2. Display information about managergroup1:

ipaserver]\$ ipa group-show group_a

Group name: group_a GID: 1133400009

Membership managed by groups: group_admins

Membership managed by users: test

Additional resources

- See ipa host-add-member-manager --help.
- See the **ipa** man page.

8.5. ENSURING THE ABSENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the absence of IdM member managers - both users and user groups - using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.
- You must have the name of the existing member manager user or group you are removing and the name of the group they are managing.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the necessary user and group member management information:

- name: Playbook to handle membership management

hosts: ipaserver become: true

tasks:

- name: Ensure member manager user and group members are absent for group_a

ipagroup:

ipaadmin_password: MySecret123

name: group_a

membermanager_user: test

membermanager_group: group_admins

action: member state: absent

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-member-managers-are-absent.yml

Verification steps

You can verify if the **group_a** group does not contain **test** as a member manager and **group_admins** as a member manager of **group_a** by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Display information about group_a:

ipaserver]\$ ipa group-show group_a
Group name: group_a
GID: 1133400009

Additional resources

- See ipa host-remove-member-manager --help.
- See the **ipa** man page.

CHAPTER 9. USING ANSIBLE PLAYBOOKS TO MANAGE SELF-SERVICE RULES IN IDM

This section introduces self-service rules in Identity Management (IdM) and describes how to create and edit self-service access rules using Ansible playbooks. Self-service access control rules allow an IdM entity to perform specified operations on its IdM Directory Server entry.

This section covers the following topics:

- Self-service access control in IdM
- Using Ansible to ensure that a self-service rule is present
- Using Ansible to ensure that a self-service rule is absent
- Using Ansible to ensure that a self-service rule has specific attributes
- Using Ansible to ensure that a self-service rule does not have specific attributes

9.1. SELF-SERVICE ACCESS CONTROL IN IDM

Self-service access control rules define which operations an Identity Management (IdM) entity can perform on its IdM Directory Server entry: for example, IdM users have the ability to update their own passwords.

This method of control allows an authenticated IdM entity to edit specific attributes within its LDAP entry, but does not allow **add** or **delete** operations on the entire entry.



WARNING

Be careful when working with self-service access control rules: configuring access control rules improperly can inadvertently elevate an entity's privileges.

9.2. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS PRESENT

The following procedure describes how to use an Ansible playbook to define self-service rules and ensure their presence on an Identity Management (IdM) server. In this example, the new **Users can manage their own name details** rule grants users the ability to change their own **givenname**, **displayname**, **title** and **initials** attributes. This allows them to, for example, change their display name or initials if they want to.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.

- You have installed the ansible-freeipa package.
- In the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **selfservice-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/selfservice/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-present.yml selfservice-present-copy.yml

- 3. Open the **selfservice-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaselfservice** task section:
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the new self-service rule.
 - Set the permission variable to a comma-separated list of permissions to grant: read and write.
 - Set the **attribute** variable to a list of attributes that users can manage themselves: **givenname**, **displayname**, **title**, and **initials**.

This is the modified Ansible playbook file for the current example:

- name: Self-service present

hosts: ipaserver become: true

tasks:

- name: Ensure self-service rule "Users can manage their own name details" is present ipaselfservice:

ipaadmin password: Secret123

name: "Users can manage their own name details"

permission: read, write

attribute:

- givenname
- displayname
- title
- initials
- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory selfservice-present-copy.yml

Additional resources

- For more information on the concept of self-service rules, see Self-service access control in IdM.
- For more sample Ansible playbooks that use the **ipaselfservice** module, see:
 - The README-selfservice.md file available in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the ipaselfservice variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/selfservice directory.

9.3. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS ABSENT

The following procedure describes how to use an Ansible playbook to ensure a specified self-service rule is absent from your IdM configuration. The example below describes how to make sure the **Users can manage their own name details** self-service rule does not exist in IdM. This will ensure that users cannot, for example, change their own display name or initials.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - In the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

- 1. Navigate to the ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Make a copy of the **selfservice-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/selfservice/ directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-absent.yml selfservice-absent-copy.yml
- 3. Open the **selfservice-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaselfservice** task section:
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the self-service rule.
 - Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Self-service absent

hosts: ipaserver become: true

tasks:

- name: Ensure self-service rule "Users can manage their own name details" is absent ipaselfservice:

ipaadmin password: Secret123

name: "Users can manage their own name details"

state: absent

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory selfservice-absent-copy.yml

Additional resources

- For more information on the concept of self-service rules, see Self-service access control in IdM.
- For more sample Ansible playbooks that use the **ipaselfservice** module, see:
 - The **README-selfservice.md** file available in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipaselfservice** variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/selfservice directory.

9.4. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE HAS SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that an already existing self-service rule has specific settings. In the example, you ensure the **Users can manage their own name details** self-service rule also has the **surname** member attribute.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - In the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
- The Users can manage their own name details elf-service rule exists in IdM.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **selfservice-member-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/selfservice/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-member-present.yml selfservice-member-present-copy.yml

- 3. Open the **selfservice-member-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaselfservice** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the self-service rule to modify.
 - Set the attribute variable to surname.
 - Set the action variable to member.

This is the modified Ansible playbook file for the current example:

- name: Self-service member present

hosts: ipaserver become: true

tasks:

- name: Ensure selfservice "Users can manage their own name details" member attribute surname is present

ipaselfservice:

ipaadmin_password: Secret123

name: "Users can manage their own name details"

attribute:
- surname
action: member

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory selfservice-member-present-copy.yml

Additional resources

- For more information on the concept of self-service rules, see Self-service access control in IdM.
- For more sample Ansible playbooks that use the **ipaselfservice** module, see:

- The **README-selfservice.md** file available in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipaselfservice** variables.
- The /usr/share/doc/ansible-freeipa/playbooks/selfservice directory.

9.5. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE DOES NOT HAVE SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that a self-service rule does not have specific settings. You can use this playbook to make sure a self-service rule does not grant undesired access. In the example, you ensure the **Users can manage their own name details**self-service rule does not have the **givenname** and **surname** member attributes.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - In the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
- The Users can manage their own name details elf-service rule exists in IdM.

Procedure

- 1. Navigate to the ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Make a copy of the **selfservice-member-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/selfservice/ directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-member-absent.yml selfservice-member-absent-copy.yml
- Open the selfservice-member-absent-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaselfservice** task section:
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the name variable to the name of the self-service rule you want to modify.
 - Set the **attribute** variable to **givenname** and **surname**.
 - Set the action variable to member.
 - Set the state variable to absent.

This is the modified Ansible playbook file for the current example:

- name: Self-service member absent

hosts: ipaserver become: true

tasks:

- name: Ensure selfservice "Users can manage their own name details" member attributes givenname and surname are absent

ipaselfservice:

ipaadmin_password: Secret123

name: "Users can manage their own name details"

attribute:
- givenname
- surname
action: membe

action: member state: absent

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory selfservice-member-absent-copy.yml

Additional resources

- For more information on the concept of self-service rules, see Self-service access control in IdM.
- For more sample Ansible playbooks that use the **ipaselfservice** module, see:
 - The **README-selfservice.md** file available in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipaselfservice** variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/selfservice directory.

CHAPTER 10. DELEGATING PERMISSIONS TO USER GROUPS TO MANAGE USERS USING ANSIBLE PLAYBOOKS

Delegation is one of the access control methods in IdM, along with self-service rules and role-based access control (RBAC). You can use delegation to assign permissions to one group of users to manage entries for another group of users.

This section covers the following topics:

- Delegation rules
- Creating the Ansible inventory file for IdM
- Using Ansible to ensure that a delegation rule is present
- Using Ansible to ensure that a delegation rule is absent
- Using Ansible to ensure that a delegation rule has specific attributes
- Using Ansible to ensure that a delegation rule does not have specific attributes

10.1. DELEGATION RULES

You can delegate permissions to user groups to manage users by creating delegation rules.

Delegation rules allow a specific user group to perform write (edit) operations on specific attributes for users in another user group. This form of access control rule is limited to editing the values of a subset of attributes you specify in a delegation rule; it does not grant the ability to add or remove whole entries or control over unspecified attributes.

Delegation rules grant permissions to existing user groups in IdM. You can use delegation to, for example, allow the **managers** user group to manage selected attributes of users in the **employees** user group.

10.2. CREATING AN ANSIBLE INVENTORY FILE FOR IDM

When working with Ansible, it is good practice to create, in your home directory, a subdirectory dedicated to Ansible playbooks that you copy and adapt from the /usr/share/doc/ansible-freeipa/* and /usr/share/doc/rhel-system-roles/* subdirectories. This practice has the following advantages:

- You can find all your playbooks in one place.
- You can run your playbooks without invoking **root** privileges.

Procedure

- 1. Create a directory for your Ansible configuration and playbooks in your home directory:
 - \$ mkdir ~/MyPlaybooks/
- 2. Change into the ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks

3. Create the ~/MyPlaybooks/ansible.cfg file with the following content:

```
[defaults]
inventory = /home/<username>/MyPlaybooks/inventory

[privilege_escalation]
become=True
```

4. Create the ~/MyPlaybooks/inventory file with the following content:

```
[eu]
server.idm.example.com

[us]
replica.idm.example.com

[ipaserver:children]
eu
us
```

This configuration defines two host groups, **eu** and **us**, for hosts in these locations. Additionally, this configuration defines the **ipaserver** host group, which contains all hosts from the **eu** and **us** groups.

10.3. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS PRESENT

The following procedure describes how to use an Ansible playbook to define privileges for a new IdM delegation rule and ensure its presence. In the example, the new **basic manager attributes** delegation rule grants the **managers** group the ability to read and write the following attributes for members of the **employees** group:

- businesscategory
- departmentnumber
- employeenumber
- employeetype

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
 - Your Ansible inventory file is located in the ~/MyPlaybooks/ directory.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **delegation-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/delegation/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-present.yml delegation-present-copy.yml

- 3. Open the **delegation-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipadelegation** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the new delegation rule.
 - Set the permission variable to a comma-separated list of permissions to grant: read and write.
 - Set the **attribute** variable to a list of attributes the delegated user group can manage: **businesscategory**, **departmentnumber**, **employeenumber**, and **employeetype**.
 - Set the **group** variable to the name of the group that is being given access to view or modify attributes.
 - Set the **membergroup** variable to the name of the group whose attributes can be viewed or modified.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage a delegation rule

hosts: ipaserver become: true

tasks:

- name: Ensure delegation "basic manager attributes" is present ipadelegation:

ipaadmin_password: Secret123 name: "basic manager attributes"

permission: read, write

attribute:

- businesscategory
- departmentnumber
- employeenumber
- employeetype

group: managers

membergroup: employees

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i ~/MyPlaybooks/inventory delegation-present-copy.yml

Additional resources

- For more information on the concept of a delegation rule, see Delegation rules.
- For more sample Ansible playbooks that use the **ipadelegation** module, see:
 - The **README-delegation.md** file available in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipadelegation** variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/ipadelegation directory.

10.4. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS ABSENT

The following procedure describes how to use an Ansible playbook to ensure a specified delegation rule is absent from your IdM configuration. The example below describes how to make sure the custom **basic** manager attributes delegation rule does not exist in IdM.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
 - Your Ansible inventory file is located in the ~/MyPlaybooks/ directory.

Procedure

- 1. Navigate to the ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks>/
- 2. Make a copy of the **delegation-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/delegation/ directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-present.yml delegation-absent-copy.yml
- 3. Open the **delegation-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipadelegation** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the delegation rule.

• Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Delegation absent

hosts: ipaserver become: true

tasks:

- name: Ensure delegation "basic manager attributes" is absent ipadelegation:

ipaadmin_password: Secret123 name: "basic manager attributes"

state: absent

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i ~/MyPlaybooks/inventory delegation-absent-copy.yml

Additional resources

- For more information on the concept of a delegation rule, see Delegation rules.
- For more sample Ansible playbooks that use the **ipadelegation** module, see:
 - The **README-delegation.md** file available in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipadelegation** variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/ipadelegation directory.

10.5. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE HAS SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that a delegation rule has specific settings. You can use this playbook to modify a delegation role you have previously created. In the example, you ensure the **basic manager attributes** delegation rule only has the **departmentnumber** member attribute.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
 - Your Ansible inventory file is located in the ~/MyPlaybooks/ directory.

The basic manager attributes delegation rule exists in IdM.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **delegation-member-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/delegation/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-member-present.yml delegation-member-present-copy.yml

- 3. Open the **delegation-member-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipadelegation** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the delegation rule to modify.
 - Set the attribute variable to departmentnumber.
 - Set the action variable to member.

This is the modified Ansible playbook file for the current example:

- name: Delegation member present

hosts: ipaserver become: true

tasks:

- name: Ensure delegation "basic manager attributes" member attribute departmentnumber is present

ipadelegation:

ipaadmin_password: Secret123 name: "basic manager attributes"

attribute:

- departmentnumber action: member

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i ~/ MyPlaybooks/inventory delegation-member-present-copy.yml

Additional resources

• For more information on the concept of a delegation rule, see Delegation rules.

- For more sample Ansible playbooks that use the **ipadelegation** module, see:
 - The **README-delegation.md** file available in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipadelegation** variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/ipadelegation directory.

10.6. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE DOES NOT HAVE SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that a delegation rule does not have specific settings. You can use this playbook to make sure a delegation role does not grant undesired access. In the example, you ensure the **basic manager attributes** delegation rule does not have the **employeenumber** and **employeetype** member attributes.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
 - Your Ansible inventory file is located in the ~/MyPlaybooks/ directory.
- The basic manager attributes delegation rule exists in IdM.

Procedure

- 1. Navigate to the ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Make a copy of the **delegation-member-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/delegation/ directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-member-absent.yml delegation-member-absent-copy.yml
- 3. Open the **delegation-member-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipadelegation** task section:
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the delegation rule to modify.
 - Set the attribute variable to employeenumber and employeetype.
 - Set the action variable to member.

• Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Delegation member absent

hosts: ipaserver become: true

tasks:

- name: Ensure delegation "basic manager attributes" member attributes employeenumber and employeetype are absent

ipadelegation:

ipaadmin_password: Secret123 name: "basic manager attributes"

attribute:

- employeenumber

- employeetype action: member state: absent

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i ~/MyPlaybooks/inventory delegation-member-absent-copy.yml

Additional resources

- For more information on the concept of a delegation rule, see Delegation rules.
- For more sample Ansible playbooks that use the **ipadelegation** module, see:
 - The **README-delegation.md** file available in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipadelegation** variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/ipadelegation directory.

CHAPTER 11. USING ANSIBLE PLAYBOOKS TO MANAGE ROLE-BASED ACCESS CONTROL IN IDM

Role-based access control (RBAC) is a policy-neutral access-control mechanism defined around roles and privileges. The components of RBAC in Identity Management (IdM) are roles, privileges and permissions:

- **Permissions** grant the right to perform a specific task such as adding or deleting users, modifying a group, enabling read-access, etc.
- Privileges combine permissions, for example all the permissions needed to add a new user.
- Roles grant a set of privileges to users, user groups, hosts or host groups.

Especially in large companies, using RBAC can help create a hierarchical system of administrators with their individual areas of responsibility.

This chapter describes the following operations performed when managing RBAC using Ansible playbooks:

- Permissions in IdM
- Default managed permissions
- Privileges in IdM
- Roles in IdM
- Predefined roles in IdM
- Using Ansible to ensure an IdM RBAC role with privileges is present
- Using Ansible to ensure an IdM RBAC role is absent
- Using Ansible to ensure that a group of users is assigned to an IdM RBAC role
- Using Ansible to ensure that specific users are not assigned to an IdM RBAC role
- Using Ansible to ensure a service is a member of an IdM RBAC role
- Using Ansible to ensure a host is a member of an IdM RBAC role
- Using Ansible to ensure a host group is a member of an IdM RBAC role

11.1. PERMISSIONS IN IDM

Permissions are the lowest level unit of role-based access control, they define operations together with the LDAP entries to which those operations apply. Comparable to building blocks, permissions can be assigned to as many privileges as needed.

One or more **rights** define what operations are allowed:

- write
- read
- search

- compare
- add
- delete
- all

These operations apply to three basic targets:

- **subtree**: a domain name (DN); the subtree under this DN
- target filter: an LDAP filter
- target: DN with possible wildcards to specify entries

Additionally, the following convenience options set the corresponding attribute(s):

- type: a type of object (user, group, etc); sets subtree and target filter
- memberof: members of a group; sets a target filter
- **targetgroup**: grants access to modify a specific group (such as granting the rights to manage group membership); sets a **target**

With IdM permissions, you can control which users have access to which objects and even which attributes of these objects. IdM enables you to allow or block individual attributes or change the entire visibility of a specific IdM function, such as users, groups, or sudo, to all anonymous users, all authenticated users, or just a certain group of privileged users.

For example, the flexibility of this approach to permissions is useful for an administrator who wants to limit access of users or groups only to the specific sections these users or groups need to access and to make the other sections completely hidden to them.



NOTE

A permission cannot contain other permissions.

11.2. DEFAULT MANAGED PERMISSIONS

Managed permissions are permissions that come by default with IdM. They behave like other permissions created by the user, with the following differences:

- You cannot delete them or modify their name, location, and target attributes.
- They have three sets of attributes:
 - Default attributes, the user cannot modify them, as they are managed by IdM
 - o Included attributes, which are additional attributes added by the user
 - Excluded attributes, which are attributes removed by the user

A managed permission applies to all attributes that appear in the default and included attribute sets but not in the excluded set.



NOTE

While you cannot delete a managed permission, setting its bind type to permission and removing the managed permission from all privileges effectively disables it.

Names of all managed permissions start with **System:**, for example **System: Add Sudo rule** or **System: Modify Services**. Earlier versions of IdM used a different scheme for default permissions. For example, the user could not delete them and was only able to assign them to privileges. Most of these default permissions have been turned into managed permissions, however, the following permissions still use the previous scheme:

- Add Automember Rebuild Membership Task
- Add Configuration Sub-Entries
- Add Replication Agreements
- Certificate Remove Hold
- Get Certificates status from the CA
- Read DNA Range
- Modify DNA Range
- Read PassSync Managers Configuration
- Modify PassSync Managers Configuration
- Read Replication Agreements
- Modify Replication Agreements
- Remove Replication Agreements
- Read LDBM Database Configuration
- Request Certificate
- Request Certificate ignoring CA ACLs
- Request Certificates from a different host
- Retrieve Certificates from the CA
- Revoke Certificate
- Write IPA Configuration



NOTE

If you attempt to modify a managed permission from the command line, the system does not allow you to change the attributes that you cannot modify, the command fails. If you attempt to modify a managed permission from the Web UI, the attributes that you cannot modify are disabled.

11.3. PRIVILEGES IN IDM

A privilege is a group of permissions applicable to a role.

While a permission provides the rights to do a single operation, there are certain IdM tasks that require multiple permissions to succeed. Therefore, a privilege combines the different permissions required to perform a specific task.

For example, setting up an account for a new IdM user requires the following permissions:

- Creating a new user entry
- Resetting a user password
- Adding the new user to the default IPA users group

Combining these three low-level tasks into a higher level task in the form of a custom privilege named, for example, **Add User** makes it easier for a system administrator to manage roles. IdM already contains several default privileges. Apart from users and user groups, privileges are also assigned to hosts and host groups, as well as network services. This practice permits a fine-grained control of operations by a set of users on a set of hosts using specific network services.



NOTE

A privilege may not contain other privileges.

11.4. ROLES IN IDM

A role is a list of privileges that users specified for the role possess.

In effect, permissions grant the ability to perform given low-level tasks (create a user entry, add an entry to a group, etc.), privileges combine one or more of these permissions needed for a higher-level task (such as creating a new user in a given group). Roles gather privileges together as needed: for example, a User Administrator role would be able to add, modify, and delete users.



IMPORTANT

Roles are used to classify permitted actions. They are not used as a tool to implement privilege separation or to protect from privilege escalation.



NOTE

Roles can not contain other roles.

11.5. PREDEFINED ROLES IN IDENTITY MANAGEMENT

Red Hat Identity Management provides the following range of pre-defined roles:

Table 11.1. Predefined Roles in Identity Management

Role	Privilege	Description
Helpdesk	Modify Users and Reset passwords, Modify Group membership	Responsible for performing simple user administration tasks

Role	Privilege	Description
IT Security Specialist	Netgroups Administrators, HBAC Administrator, Sudo Administrator	Responsible for managing security policy such as host-based access controls, sudo rules
IT Specialist	Host Administrators, Host Group Administrators, Service Administrators, Automount Administrators	Responsible for managing hosts
Security Architect	Delegation Administrator, Replication Administrators, Write IPA Configuration, Password Policy Administrator	Responsible for managing the Identity Management environment, creating trusts, creating replication agreements
User Administrator	User Administrators, Group Administrators, Stage User Administrators	Responsible for creating users and groups

11.6. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE WITH PRIVILEGES IS PRESENT

To exercise more granular control over role-based access (RBAC) to resources in Identity Management (IdM) than the default roles provide, create a custom role.

The following procedure describes how to use an Ansible playbook to define privileges for a new IdM custom role and ensure its presence. In the example, the new **user_and_host_administrator** role contains a unique combination of the following privileges that are present in IdM by default:

- Group Administrators
- User Administrators
- Stage User Administrators
- Group Administrators

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/<MyPlaybooks>/ directory.

Procedure

1. Navigate to the ~/<MyPlaybooks>/ directory:

\$ cd ~/<MyPlaybooks>/

2. Make a copy of the **role-member-user-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-user-present.yml role-member-user-present-copy.yml

- 3. Open the role-member-user-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the new role.
 - Set the **privilege** list to the names of the IdM privileges that you want to include in the new role.
 - Optionally, set the user variable to the name of the user to whom you want to grant the new role.
 - Optionally, set the **group** variable to the name of the group to which you want to grant the new role.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage IPA role with members.

hosts: ipaserver become: yes gather_facts: no

tasks:

- iparole:

ipaadmin_password: Secret123 name: user_and_host_administrator

user: idm_user01 group: idm_group01

privilege:

- Group Administrators
- User Administrators
- Stage User Administrators
- Group Administrators
- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i ~/<*MyPlaybooks>*/inventory role-member-user-present-copy.yml

Additional resources

- For more information on how to use Ansible Vault to store a password in a separate file or to encrypt it as a variable in the playbook file, see Encrypting content with Ansible Vault.
- For more information on the concept of role in IdM, see Roles in IdM.
- For more sample Ansible playbooks that use the **iparole** module, see:
 - The **README-role** file available in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **iparole** variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/iparole directory.

11.7. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE IS ABSENT

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to ensure the absence of an obsolete role so that no administrator assigns it to any user accidentally.

The following procedure describes how to use an Ansible playbook to ensure a role is absent. The example below describes how to make sure the custom **user_and_host_administrator** role does not exist in IdM.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/<MyPlaybooks>/ directory.

Procedure

1. Navigate to the ~/<MyPlaybooks>/ directory:

\$ cd ~/<MyPlaybooks>/

2. Make a copy of the **role-is-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-is-absent.yml role-is-absent-copy.yml

- 3. Open the role-is-absent-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role.
 - Ensure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage IPA role with members.

hosts: ipaserver become: yes gather_facts: no

tasks:
- iparole:

ipaadmin_password: Secret123 name: user and host administrator

state: absent

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i ~/<MyPlaybooks>/inventory role-is-absent-copy.yml

Additional resources

- For more information on how to use Ansible Vault to store a password in a separate file or to encrypt it as a variable in the playbook file, see Encrypting content with Ansible Vault.
- For more information on the concept of role in IdM, see Roles in IdM.
- For more sample Ansible playbooks that use the **iparole** module, see:
 - The **README-role** Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the iparole variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/iparole directory.

11.8. USING ANSIBLE TO ENSURE THAT A GROUP OF USERS IS ASSIGNED TO AN IDM RBAC ROLE

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to assign a role to a specific group of users, for example junior administrators.

The following example describes how to use an Ansible playbook to ensure the built-in IdM RBAC **helpdesk** role is assigned to **junior_sysadmins**.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/<MyPlaybooks>/ directory.

Procedure

1. Navigate to the ~/<MyPlaybooks>/ directory:

\$ cd ~/<MyPlaybooks>/

2. Make a copy of the **role-member-group-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-group-present.yml role-member-group-present-copy.yml

- 3. Open the role-member-group-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role you want to assign.
 - Set the **group** variable to the name of the group.
 - Set the **action** variable to **member**.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage IPA role with members.

hosts: ipaserver become: yes gather facts: no

tasks:

- iparole:

ipaadmin_password: Secret123

name: helpdesk

group: junior_sysadmins

action: member

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i ~/<*MyPlaybooks>*/inventory role-member-group-present-copy.yml

Additional resources

- For more information on how to use Ansible Vault to store a password in a separate file or to encrypt it as a variable in the playbook file, see Encrypting content with Ansible Vault.
- For more information on the concept of role in IdM, see Roles in IdM.
- For more sample Ansible playbooks that use the iparole module, see the README-role
 Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains
 the definitions of the iparole variables.

 For more sample Ansible playbooks that use the iparole module, see the /usr/share/doc/ansible-freeipa/playbooks/iparole directory.

11.9. USING ANSIBLE TO ENSURE THAT SPECIFIC USERS ARE NOT ASSIGNED TO AN IDM RBAC ROLE

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to ensure that an RBAC role is not assigned to specific users after they have, for example, moved to different positions within the company.

The following procedure describes how to use an Ansible playbook to ensure that the users named user_01 and user_02 are not assigned to the helpdesk role.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/<MyPlaybooks>/ directory.

Procedure

1. Navigate to the ~/<MyPlaybooks>/ directory:

\$ cd ~/<MyPlaybooks>/

2. Make a copy of the **role-member-user-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-user-absent.yml role-member-user-absent-copy.yml

- 3. Open the role-member-user-absent-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role you want to assign.
 - Set the **user** list to the names of the users.
 - Set the action variable to member.
 - Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage IPA role with members.

hosts: ipaserver

become: yes gather_facts: no

tasks:

- iparole:

ipaadmin_password: Secret123

name: helpdesk

user

- user 01

- user_02

action: member state: absent

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i ~/<*MyPlaybooks>*/inventory role-member-user-absent-copy.yml

Additional resources

- For more information on how to use Ansible Vault to store a password in a separate file or to encrypt it as a variable in the playbook file, see Encrypting content with Ansible Vault.
- For more information on the concept of role in IdM, see Roles in IdM.
- For more sample Ansible playbooks that use the **iparole** module, see the **README-role**Markdown file available in the /**usr/share/doc/ansible-freeipa/** directory. The file also contains the definitions of the **iparole** variables.
- For more sample Ansible playbooks that use the iparole module, see the /usr/share/doc/ansible-freeipa/playbooks/iparole directory.

11.10. USING ANSIBLE TO ENSURE A SERVICE IS A MEMBER OF AN IDM RBAC ROLE

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to ensure that a specific service that is enrolled into IdM is a member of a particular role. The following example describes how to ensure that the custom **web_administrator** role can manage the **HTTP** service that is running on the **clientO1.idm.example.com** server.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/<MyPlaybooks>/ directory.
- The web_administrator role exists in IdM.

• The HTTP/client01.idm.example.com@IDM.EXAMPLE.COM service exists in IdM.

Procedure

1. Navigate to the ~/<MyPlaybooks>/ directory:

\$ cd ~/<MyPlaybooks>/

2. Make a copy of the **role-member-service-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-service-present-absent.yml role-member-service-present-copy.yml

- 3. Open the role-member-service-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role you want to assign.
 - Set the **service** list to the name of the service.
 - Set the action variable to member.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage IPA role with members.

hosts: ipaserver become: yes gather_facts: no

tasks:

- iparole:

ipaadmin_password: Secret123 name: web_administrator

service:

- HTTP/client01.idm.example.com

action: member

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i ~/<MyPlaybooks>/inventory role-member-service-present-copy.yml

Additional resources

• For more information on how to use Ansible Vault to store a password in a separate file or to encrypt it as a variable in the playbook file, see Encrypting content with Ansible Vault.

- For more information on the concept of role in IdM, see Roles in IdM.
- For more sample Ansible playbooks that use the **iparole** module, see the **README-role** Markdown file available in the /**usr/share/doc/ansible-freeipa/** directory. The file also contains the definitions of the **iparole** variables.
- For more sample Ansible playbooks that use the **iparole** module, see the /usr/share/doc/ansible-freeipa/playbooks/iparole directory.

11.11. USING ANSIBLE TO ENSURE A HOST IS A MEMBER OF AN IDM RBAC ROLE

As a system administrator managing role-based access control in Identity Management (IdM), you may want to ensure that a specific host or host group is associated with a specific role. The following example describes how to ensure that the custom **web_administrator** role can manage the **clientO1.idm.example.com** IdM host on which the **HTTP** service is running.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/<MyPlaybooks>/ directory.
- The web_administrator role exists in IdM.
- The client01.idm.example.com host exists in IdM.

Procedure

- 1. Navigate to the ~/<MyPlaybooks>/ directory:
 - \$ cd ~/<MyPlaybooks>/
- 2. Make a copy of the **role-member-host-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-host-present.yml role-member-host-present-copy.yml
- 3. Open the role-member-host-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role you want to assign.
 - Set the **host** list to the name of the host.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage IPA role with members.

hosts: ipaserver become: yes gather_facts: no

tasks:

- iparole:

ipaadmin_password: Secret123 name: web administrator

host:

- client01.idm.example.com

action: member

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i ~/<*MyPlaybooks>*/inventory role-member-host-present-copy.yml

Additional resources

- For more information on how to use Ansible Vault to store a password in a separate file or to encrypt it as a variable in the playbook file, see Encrypting content with Ansible Vault.
- For more information on the concept of role in IdM, see Roles in IdM.
- For more sample Ansible playbooks that use the **iparole** module, see the **README-role**Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the **iparole** variables.
- For more sample Ansible playbooks that use the iparole module, see the /usr/share/doc/ansible-freeipa/playbooks/iparole directory.

11.12. USING ANSIBLE TO ENSURE A HOST GROUP IS A MEMBER OF AN IDM RBAC ROLE

As a system administrator managing role-based access control in Identity Management (IdM), you may want to ensure that a specific host or host group is associated with a specific role. The following example describes how to ensure that the custom **web_administrator** role can manage the **web_servers** group of IdM hosts on which the **HTTP** service is running.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/<MyPlaybooks>/ directory.

- The web_administrator role exists in IdM.
- The web_servers host group exists in IdM.

Procedure

1. Navigate to the ~/<MyPlaybooks>/ directory:

\$ cd ~/<MyPlaybooks>/

2. Make a copy of the **role-member-hostgroup-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/role/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-hostgroup-present.yml role-member-hostgroup-present-copy.yml

- 3. Open the role-member-hostgroup-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role you want to assign.
 - Set the **hostgroup** list to the name of the hostgroup.

This is the modified Ansible playbook file for the current example:

- name: Playbook to manage IPA role with members.

hosts: ipaserver become: yes gather_facts: no

tasks:

- iparole:

ipaadmin_password: Secret123 name: web administrator

hostgroup:web_serversaction: member

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i ~/<MyPlaybooks>/inventory role-member-hostgroup-present-copy.yml

Additional resources

• For more information on how to use Ansible Vault to store a password in a separate file or to encrypt it as a variable in the playbook file, see Encrypting content with Ansible Vault.

- For more information on the concept of role in IdM, see Roles in IdM.
- For more sample Ansible playbooks that use the **iparole** module, see the **README-role** Markdown file available in the /**usr/share/doc/ansible-freeipa/** directory. The file also contains the definitions of the **iparole** variables.
- For more sample Ansible playbooks that use the **iparole** module, see the /usr/share/doc/ansible-freeipa/playbooks/iparole directory.

CHAPTER 12. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PRIVILEGES

Role-based access control (RBAC) is a policy-neutral access-control mechanism defined around roles, privileges, and permissions. Especially in large companies, using RBAC can help create a hierarchical system of administrators with their individual areas of responsibility.

This chapter describes the following operations for using Ansible playbooks to manage RBAC privileges in Identity Management (IdM):

- Using Ansible to ensure a custom RBAC privilege is present
- Using Ansible to ensure member permissions are present in a custom IdM RBAC privilege
- Using Ansible to ensure an IdM RBAC privilege does not include a permission
- Using Ansible to rename a custom IdM RBAC privilege
- Using Ansible to ensure an IdM RBAC privilege is absent

Prerequisites

• You understand the concepts and principles of RBAC.

12.1. USING ANSIBLE TO ENSURE A CUSTOM IDM RBAC PRIVILEGE IS PRESENT

To have a fully-functioning custom privilege in Identity Management (IdM) role-based access control (RBAC), you need to proceed in stages:

- 1. Create a privilege with no permissions attached.
- 2. Add permissions of your choice to the privilege.

The following procedure describes how to create an empty privilege using an Ansible playbook so that you can later add permissions to it. The example describes how to create a privilege named **full_host_administration** that is meant to combine all IdM permissions related to host administration.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/MyPlaybooks/ directory.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **privilege-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/privilege/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-present.yml privilege-present.yml privilege-present.yml

- 3. Open the **privilege-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaprivilege** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the new privilege, **full_host_administration**.
 - Optionally, describe the privilege using the **description** variable.

This is the modified Ansible playbook file for the current example:

- name: Privilege present example

hosts: ipaserver become: true

tasks:

 name: Ensure privilege full_host_administration is present ipaprivilege:

ipaadmin_password: Secret123 name: full host administration

description: This privilege combines all IdM permissions related to host

administration

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory privilege-present-copy.yml

12.2. USING ANSIBLE TO ENSURE MEMBER PERMISSIONS ARE PRESENT IN A CUSTOM IDM RBAC PRIVILEGE

To have a fully-functioning custom privilege in Identity Management (IdM) role-based access control (RBAC), you need to proceed in stages:

- 1. Create a privilege with no permissions attached.
- 2. Add permissions of your choice to the privilege.

The following procedure describes how to use an Ansible playbook to add permissions to a privilege created in the previous step. The example describes how to add all IdM permissions related to host administration to a privilege named **full_host_administration**. By default, the permissions are distributed between the **Host Enrollment**, **Host Administrators** and **Host Group Administrator** privileges.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/MyPlaybooks/ directory.
- The *full_host_administration* privilege exists. For information on how to create a privilege using Ansible, see Using Ansible to ensure a custom IdM RBAC privilege is present.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **privilege-member-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/privilege/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-member-present.yml privilege-member-present-copy.yml

- 3. Open the privilege-member-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaprivilege** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the privilege.
 - Set the **permission** list to the names of the permissions that you want to include in the privilege.
 - Make sure that the **action** variable is set to **member**.

This is the modified Ansible playbook file for the current example:

- name: Privilege member present example

hosts: ipaserver become: true

tasks:

- name: Ensure that permissions are present for the "full_host_administration" privilege ipaprivilege:

ipaadmin_password: Secret123 name: full_host_administration permission:

- "System: Add krbPrincipalName to a Host"
- "System: Enroll a Host"
- "System: Manage Host Certificates"
- "System: Manage Host Enrollment Password"

- "System: Manage Host Keytab"
- "System: Manage Host Principals"
- "Retrieve Certificates from the CA"
- "Revoke Certificate"
- "System: Add Hosts"
- "System: Add krbPrincipalName to a Host"
- "System: Enroll a Host"
- "System: Manage Host Certificates"
- "System: Manage Host Enrollment Password"
- "System: Manage Host Keytab"
- "System: Manage Host Keytab Permissions"
- "System: Manage Host Principals"
- "System: Manage Host SSH Public Keys"
- "System: Manage Service Keytab"
- "System: Manage Service Keytab Permissions"
- "System: Modify Hosts"
- "System: Remove Hosts"
- "System: Add Hostgroups"
- "System: Modify Hostgroup Membership"
- "System: Modify Hostgroups"
- "System: Remove Hostgroups"
- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory privilege-member-present-copy.yml

12.3. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE DOES NOT INCLUDE A PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control.

The following procedure describes how to use an Ansible playbook to remove a permission from a privilege. The example describes how to remove the **Request Certificates ignoring CA ACLs** permission from the default **Certificate Administrators** privilege because, for example, the administrator considers it a security risk.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/MyPlaybooks/ directory.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **privilege-member-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/privilege/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-member-absent.yml privilege-member-absent-copy.yml

- 3. Open the **privilege-member-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaprivilege** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the privilege.
 - Set the **permission** list to the names of the permissions that you want to remove from the privilege.
 - Make sure that the **action** variable is set to **member**.
 - Make sure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Privilege absent example

hosts: ipaserver become: true

tasks:

- name: Ensure that the "Request Certificate ignoring CA ACLs" permission is absent from the "Certificate Administrators" privilege

ipaprivilege:

ipaadmin_password: Secret123 name: Certificate Administrators permission:

- "Request Certificate ignoring CA ACLs"

action: member state: absent

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory privilege-member-absent-copy.yml

12.4. USING ANSIBLE TO RENAME A CUSTOM IDM RBAC PRIVILEGE

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control.

The following procedure describes how to rename a privilege because, for example, you have removed a few permissions from it. As a result, the name of the privilege is no longer accurate. In the example, the administrator renames a **full_host_administration** privilege to **limited_host_administration**.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/MyPlaybooks/ directory.
- The *full_host_administration* privilege exists. For more information on how to add a privilege, see Using Ansible to ensure a custom IdM RBAC privilege is present.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **privilege-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/privilege/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-present.yml rename-privilege.yml

- 3. Open the **rename-privilege.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaprivilege** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the current name of the privilege.
 - Add the **rename** variable and set it to the new name of the privilege.
 - Add the **state** variable and set it to **renamed**.
- 5. Rename the playbook itself, for example:

- name: Rename a privilege

hosts: ipaserver become: true

6. Rename the task in the playbook, for example:

[...] tasks:

- name: Ensure the full_host_administration privilege is renamed to

```
limited_host_administration ipaprivilege:
```

[...]

This is the modified Ansible playbook file for the current example:

- name: Rename a privilege

hosts: ipaserver become: true

tasks:

- name: Ensure the full_host_administration privilege is renamed to limited host administration

ipaprivilege:

ipaadmin_password: Secret123 name: full_host_administration rename: limited_host_administration

state: renamed

- 7. Save the file.
- 8. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory rename-privilege.yml

12.5. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE IS ABSENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control. The following procedure describes how to use an Ansible playbook to ensure that an RBAC privilege is absent. The example describes how to ensure that the **CA administrator** privilege is absent. As a result of the procedure, the **admin** administrator becomes the only user capable of managing certificate authorities in IdM.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- You have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the ~/MyPlaybooks/ directory.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **privilege-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/privilege/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-absent.yml privilege-absent-copy.yml

- 3. Open the **privilege-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipaprivilege** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the privilege you want to remove.
 - Make sure that the **state** variable is set it to **absent**.
- 5. Rename the task in the playbook, for example:

[...]

tasks:

- name: Ensure privilege "CA administrator" is absent ipaprivilege:

[..._.

This is the modified Ansible playbook file for the current example:

- name: Privilege absent example

hosts: ipaserver become: true

tasks:

- name: Ensure privilege "CA administrator" is absent ipaprivilege:

ipaadmin_password: Secret123

name: CA administrator

state: absent

- 6. Save the file.
- 7. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory privilege-absent-copy.yml

Additional resources

- For more information on the concept of a privilege in IdM RBAC, see Privileges in IdM.
- For more information on the concept of a permission in IdM RBAC, see Permissions in IdM.
- For more sample Ansible playbooks that use the **ipaprivilege** module, see the **README- privilege** file available in the /**usr/share/doc/ansible-freeipa/** directory. The file also contains the definitions of the **ipaprivilege** variables.
- For more sample Ansible playbooks that use the **ipaprivilege** module, see the /usr/share/doc/ansible-freeipa/playbooks/ipaprivilege directory.

CHAPTER 13. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PERMISSIONS IN IDM

Role-based access control (RBAC) is a policy-neutral access control mechanism defined around roles, privileges, and permissions. Especially in large companies, using RBAC can help create a hierarchical system of administrators with their individual areas of responsibility.

This chapter describes the following operations performed when managing RBAC permissions in Identity Management (IdM) using Ansible playbooks:

- Using Ansible to ensure an RBAC permission is present
- Using Ansible to ensure an RBAC permission with an attribute is present
- Using Ansible to ensure an RBAC permission is absent
- Using Ansible to ensure an attribute is a member of an IdM RBAC permission
- Using Ansible to ensure an attribute is not a member of an IdM RBAC permission
- Using Ansible to rename an IdM RBAC permission

Prerequisites

• You understand the concepts and principles of RBAC.

13.1. USING ANSIBLE TO ENSURE AN RBAC PERMISSION IS PRESENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure a permission is present in IdM so that it can be added to a privilege. The example describes how to ensure the following target state:

- The **MyPermission** permission exists.
- The **MyPermission** permission can only be applied to hosts.
- A user granted a privilege that contains the permission can do all of the following possible operations on an entry:
 - Write
 - Read
 - Search
 - Compare
 - Add
 - Delete

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- The example assumes that you have created and configured the ~/MyPlaybooks/ directory as a central location to store copies of sample playbooks.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **permission-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-present.yml permission-present-copy.yml

- 3. Open the **permission-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.
 - Set the object_type variable to host.
 - Set the **right** variable to **all**.

This is the modified Ansible playbook file for the current example:

- name: Permission present example

hosts: ipaserver become: true

tasks:

- name: Ensure that the "MyPermission" permission is present

ipapermission:

ipaadmin_password: Secret123

name: MyPermission object_type: host

right: all

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory permission-present-copy.yml

13.2. USING ANSIBLE TO ENSURE AN RBAC PERMISSION WITH AN ATTRIBUTE IS PRESENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure a permission is present in IdM so that it can be added to a privilege. The example describes how to ensure the following target state:

- The MyPermission permission exists.
- The **MyPermission** permission can only be used to add hosts.
- A user granted a privilege that contains the permission can do all of the following possible operations on a host entry:
 - Write
 - Read
 - Search
 - Compare
 - Add
 - Delete
- The host entries created by a user that is granted a privilege that contains the **MyPermission** permission can have a **description** value.



NOTE

The type of attribute that you can specify when creating or modifying a permission is not constrained by the IdM LDAP schema. However, specifying, for example, **attrs: car_licence** if the **object_type** is **host** later results in the **ipa: ERROR: attribute "car-license" not allowed** error message when you try to exercise the permission and add a specific car licence value to a host.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- The example assumes that you have created and configured the ~/MyPlaybooks/ directory as a central location to store copies of sample playbooks.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **permission-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-present.yml permission-present-with-attribute.yml

- 3. Open the **permission-present-with-attribute.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.
 - Set the **object_type** variable to **host**.
 - Set the **right** variable to **all**.
 - Set the **attrs** variable to **description**.

This is the modified Ansible playbook file for the current example:

- name: Permission present example

hosts: ipaserver become: true

tasks:

- name: Ensure that the "MyPermission" permission is present with an attribute ipapermission:

ipaadmin_password: Secret123

name: MyPermission object_type: host

right: all

attrs: description

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory permission-present-with-attribute.yml

Additional resources

• For more information on the IdM schema, see User and group schema in *Linux Domain Identity*, *Authentication and Policy Guide* in RHEL 7.

13.3. USING ANSIBLE TO ENSURE AN RBAC PERMISSION IS ABSENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure a permission is absent in IdM so that it cannot be added to a privilege.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- The example assumes that you have created and configured the ~/MyPlaybooks/ directory as a central location to store copies of sample playbooks.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **permission-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-absent.yml permission-absent-copy.yml

- 3. Open the **permission-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.

This is the modified Ansible playbook file for the current example:

- name: Permission absent example

hosts: ipaserver become: true

tasks:

- name: Ensure that the "MyPermission" permission is absent

ipapermission:

ipaadmin_password: Secret123

name: MyPermission

state: absent

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory permission-absent-copy.yml

13.4. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS A MEMBER OF AN IDM RBAC PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure that an attribute is a member of an RBAC permission in IdM. As a result, a user with the permission can create entries that have the attribute.

The example describes how to ensure that the host entries created by a user with a privilege that contains the **MyPermission** permission can have **gecos** and **description** values.



NOTE

The type of attribute that you can specify when creating or modifying a permission is not constrained by the IdM LDAP schema. However, specifying, for example, **attrs: car_licence** if the **object_type** is **host** later results in the **ipa: ERROR: attribute "car-license" not allowed** error message when you try to exercise the permission and add a specific car licence value to a host.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- The example assumes that you have created and configured the ~/MyPlaybooks/ directory as a central location to store copies of sample playbooks.
- The **MyPermission** permission exists.

Procedure

- 1. Navigate to the ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Make a copy of the **permission-member-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-member-present.yml permission-member-present-copy.yml

- 3. Open the **permission-member-present-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the name of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.
 - Set the attrs list to the description and gecos variables.

• Make sure the **action** variable is set to **member**.

This is the modified Ansible playbook file for the current example:

- name: Permission member present example

hosts: ipaserver become: true

tasks:

- name: Ensure that the "gecos" and "description" attributes are present in

"MyPermission"

ipapermission:

ipaadmin_password: Secret123

name: MyPermission

attrs:

- description

- gecos

action: member

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory permission-member-present-copy.yml

13.5. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS NOT A MEMBER OF AN IDM RBAC PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure that an attribute is not a member of an RBAC permission in IdM. As a result, when a user with the permission creates an entry in IdM LDAP, that entry cannot have a value associated with the attribute.

The example describes how to ensure the following target state:

- The MyPermission permission exists.
- The host entries created by a user with a privilege that contains the **MyPermission** permission cannot have the **description** attribute.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- The example assumes that you have created and configured the ~/MyPlaybooks/ directory as a central location to store copies of sample playbooks.
- The **MyPermission** permission exists.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **permission-member-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-member-absent.yml permission-member-absent-copy.yml

- 3. Open the **permission-member-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.
 - Set the attrs variable to description.
 - Set the action variable to member.
 - Make sure the **state** variable is set to **absent**

This is the modified Ansible playbook file for the current example:

- name: Permission absent example

hosts: ipaserver become: true

tasks:

- name: Ensure that an attribute is not a member of "MyPermission" ipapermission:

ipaadmin_password: Secret123

name: MyPermission attrs: description action: member state: absent

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory permission-member-absent-copy.yml

13.6. USING ANSIBLE TO RENAME AN IDM RBAC PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control.

The following procedure describes how to use an Ansible playbook to rename a permission. The example describes how to rename **MyPermission** to **MyNewPermission**.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- The example assumes that you have created and configured the ~/MyPlaybooks/ directory as a central location to store copies of sample playbooks.
- The MyPermission exists in IdM.
- The MyNewPermission does not exist in IdM.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **permission-renamed.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/permission/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-renamed.yml permission-renamed-copy.yml

- 3. Open the **permission-renamed-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.

This is the modified Ansible playbook file for the current example:

- name: Permission present example

hosts: ipaserver become: true

tasks:

- name: Rename the "MyPermission" permission

ipapermission:

ipaadmin_password: Secret123

name: MyPermission rename: MyNewPermission

state: renamed

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory permission-renamed-copy.yml

13.7. ADDITIONAL RESOURCES

- For more information on the concept of a permission in IdM RBAC, see Permissions in IdM.
- For more information on the concept of a privilege in IdM RBAC, see Privileges in IdM.
- For more sample Ansible playbooks that use the **ipapermission** module, see the **README- permission** file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the **ipapermission** variables.
- For more sample Ansible playbooks that use the **ipapermission** module, see the /usr/share/doc/ansible-freeipa/playbooks/ipapermission directory.

CHAPTER 14. USING ANSIBLE TO MANAGE THE REPLICATION TOPOLOGY IN IDM

You can maintain multiple Identity Management (IdM) servers and let them replicate each other for redundancy purposes to mitigate or prevent server loss. For example, if one server fails, the other servers keep providing services to the domain. You can also recover the lost server by creating a new replica based on one of the remaining servers.

Data stored on an IdM server is replicated based on replication agreements: when two servers have a replication agreement configured, they share their data. The data that is replicated is stored in the topology **suffixes**. When two replicas have a replication agreement between their suffixes, the suffixes form a topology **segment**.

This chapter describes how to use **Red Hat Ansible Engine** to manage IdM replication agreements, topology segments, and topology suffixes. The chapter contains the following sections:

- Using Ansible to ensure a replication agreement exists in IdM
- Using Ansible to ensure replication agreements exist between multiple IdM replicas
- Using Ansible to check if a replication agreement exists between two replicas
- Using Ansible to verify that a topology suffix exists in IdM
- Using Ansible to re-initialize an IdM replica
- Using Ansible to ensure a replication agreement is absent in IdM

14.1. USING ANSIBLE TO ENSURE A REPLICATION AGREEMENT EXISTS IN IDM

Data stored on an Identity Management (IdM) server is replicated based on replication agreements: when two servers have a replication agreement configured, they share their data. Replication agreements are always bilateral: the data is replicated from the first replica to the other one as well as from the other replica to the first one.

This section describes how to use an Ansible playbook to ensure that a replication agreement of the **domain** type exists between **server.idm.example.com** and **replica.idm.example.com**.

Prerequisites

- Ensure that you understand the recommendations for designing your IdM topology listed in Connecting the replicas in a topology.
- You know the IdM **admin** password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - In the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **add-topologysegment.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/topology/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/add-topologysegment.yml add-topologysegment-copy.yml

- 3. Open the add-topologysegment-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipatopologysegment** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the suffix variable to either domain or ca, depending on what type of segment you
 want to add.
 - Set the **left** variable to the name of the IdM server that you want to be the left node of the replication agreement.
 - Set the **right** variable to the name of the IdM server that you want to be the right node of the replication agreement.
 - Ensure that the **state** variable is set to **present**.

This is the modified Ansible playbook file for the current example:

- name: Playbook to handle topologysegment

hosts: ipaserver become: true

tasks:

- name: Add topology segment

ipatopologysegment:

ipaadmin_password: Secret123

suffix: domain

left: server.idm.example.com right: replica.idm.example.com

state: present

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory add-topologysegment-copy.yml

Additional resources

• For more information on the concept of topology agreements, suffixes, and segments, see Explaining Replication Agreements, Topology Suffixes, and Topology Segments .

- For more sample Ansible playbooks that use the **ipatopologysegment** module, see:
 - The **README-topology.md** file in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipatopologysegment** variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/topology directory.

14.2. USING ANSIBLE TO ENSURE REPLICATION AGREEMENTS EXIST BETWEEN MULTIPLE IDM REPLICAS

Data stored on an Identity Management (IdM) server is replicated based on replication agreements: when two servers have a replication agreement configured, they share their data. Replication agreements are always bilateral: the data is replicated from the first replica to the other one as well as from the other replica to the first one.

This section describes how to ensure replication agreements exist between multiple pairs of replicas in IdM.

Prerequisites

- Ensure that you understand the recommendations for designing your IdM topology listed in Connecting the replicas in a topology
- You know the IdM **admin** password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - In the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

- 1. Navigate to your ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Copy the **add-topologysegments.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/topology/ directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/add-topologysegments.yml add-topologysegments-copy.yml
- 3. Open the add-topologysegments-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **vars** section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - For every topology segment, add a line in the ipatopology_segments section and set the following variables:

- Set the **suffix** variable to either **domain** or **ca**, depending on what type of segment you want to add.
- Set the **left** variable to the name of the IdM server that you want to be the left node of the replication agreement.
- Set the **right** variable to the name of the IdM server that you want to be the right node of the replication agreement.
- 5. In the **tasks** section of the **add-topologysegments-copy.yml** file, ensure that the **state** variable is set to **present**.

This is the modified Ansible playbook file for the current example:

```
- name: Add topology segments
hosts: ipaserver
become: true
 gather_facts: false
vars:
  ipaadmin password: Secret123
  ipatopology_segments:
  - {suffix: domain, left: replica1.idm.example.com , right: replica2.idm.example.com }
  - {suffix: domain, left: replica2.idm.example.com , right: replica3.idm.example.com }
  - {suffix: domain, left: replica3.idm.example.com , right: replica4.idm.example.com }
  - {suffix: domain+ca, left: replica4.idm.example.com , right: replica1.idm.example.com }
tasks:
 - name: Add topology segment
  ipatopologysegment:
   ipaadmin_password: "{{ ipaadmin_password }}"
   suffix: "{{ item.suffix }}"
   name: "{{ item.name | default(omit) }}"
   left: "{{ item.left }}"
   right: "{{ item.right }}"
   state: present
   #state: absent
   #state: checked
   #state: reinitialized
  loop: "{{ ipatopology_segments | default([]) }}"
```

- 6. Save the file.
- 7. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory add-topologysegments-copy.yml

Additional resources

- For more information on the concept of topology agreements, suffixes, and segments, see Explaining Replication Agreements, Topology Suffixes, and Topology Segments.
- For more sample Ansible playbooks that use the **ipatopologysegment** module, see:

- The **README-topology.md** file in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipatopologysegment** variables.
- The /usr/share/doc/ansible-freeipa/playbooks/topology directory.

14.3. USING ANSIBLE TO CHECK IF A REPLICATION AGREEMENT EXISTS BETWEEN TWO REPLICAS

Data stored on an Identity Management (IdM) server is replicated based on replication agreements: when two servers have a replication agreement configured, they share their data. Replication agreements are always bilateral: the data is replicated from the first replica to the other one as well as from the other replica to the first one.

This section describes how to verify that replication agreements exist between multiple pairs of replicas in IdM.

Prerequisites

- Ensure that you understand the recommendations for designing your Identity Management (IdM) topology listed in Connecting the replicas in a topology.
- You know the IdM **admin** password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - In the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

- 1. Navigate to your ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Copy the **check-topologysegments.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/topology/ directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/check-topologysegments.yml check-topologysegments-copy.yml
- 3. Open the **check-topologysegments-copy.yml** file for editing.
- 4. Adapt the file by setting the following variables in the **vars** section:
 - Set the **ipaadmin password** variable to the password of the IdM **admin**.
 - For every topology segment, add a line in the ipatopology_segments section and set the following variables:
 - Set the **suffix** variable to either **domain** or **ca**, depending on the type of segment you are adding.

- Set the **left** variable to the name of the IdM server that you want to be the left node of the replication agreement.
- Set the **right** variable to the name of the IdM server that you want to be the right node of the replication agreement.
- 5. In the **tasks** section of the **check-topologysegments-copy.yml** file, ensure that the **state** variable is set to **present**.

This is the modified Ansible playbook file for the current example:

```
- name: Add topology segments
 hosts: ipaserver
 become: true
 gather facts: false
 vars:
  ipaadmin_password: Secret123
  ipatopology segments:
  - {suffix: domain, left: replica1.idm.example.com, right: replica2.idm.example.com }
  - {suffix: domain, left: replica2.idm.example.com , right: replica3.idm.example.com }
  - {suffix: domain, left: replica3.idm.example.com, right: replica4.idm.example.com}
  - {suffix: domain+ca, left: replica4.idm.example.com, right:
replica1.idm.example.com }
 tasks:
 - name: Check topology segment
  ipatopologysegment:
   ipaadmin_password: "{{ ipaadmin_password }}"
   suffix: "{{ item.suffix }}"
   name: "{{ item.name | default(omit) }}"
   left: "{{ item.left }}"
   right: "{{ item.right }}"
   state: checked
  loop: "{{ ipatopology_segments | default([]) }}"
```

- 6. Save the file.
- 7. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory check-topologysegments-copy.yml

Additional resources

- For more information on the concept of topology agreements, suffixes, and segments, see Explaining Replication Agreements, Topology Suffixes, and Topology Segments.
- For more sample Ansible playbooks that use the **ipatopologysegment** module, see:
 - The **README-topology.md** file in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipatopologysegment** variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/topology directory.

14.4. USING ANSIBLE TO VERIFY THAT A TOPOLOGY SUFFIX EXISTS IN IDM

In the context of replication agreements in Identity Management (IdM), topology suffixes store the data that is replicated. IdM supports two types of topology suffixes: **domain** and **ca**. Each suffix represents a separate back end, a separate replication topology. When a replication agreement is configured, it joins two topology suffixes of the same type on two different servers.

The **domain** suffix contains all domain-related data, such as users, groups, and policies. The **ca** suffix contains data for the Certificate System component. It is only present on servers with a certificate authority (CA) installed.

This section describes how to use an Ansible playbook to ensure that a topology suffix exists in IdM. The example describes how to ensure that the **domain** suffix exists in IdM.

Prerequisites

- You know the IdM **admin** password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - In the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **verify-topologysuffix.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/topology/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/ verify-topologysuffix.yml verify-topologysuffix-copy.yml

- 3. Open the verify-topologysuffix-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipatopologysuffix** section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **suffix** variable to **domain**. If you are verifying the presence of the **ca** suffix, set the variable to **ca**.
 - Ensure that the **state** variable is set to **verified**. No other option is possible.

This is the modified Ansible playbook file for the current example:

- name: Playbook to handle topologysuffix

hosts: ipaserver become: true

tasks:

- name: Verify topology suffix

ipatopologysuffix:

ipaadmin_password: Secret123

suffix: domain state: verified

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory verify-topologysuffix-copy.yml

Additional resources

- For more information on the concept of topology agreements, suffixes, and segments, see Explaining Replication Agreements, Topology Suffixes, and Topology Segments.
- For more sample Ansible playbooks that use the **ipatopologysegment** module, see:
 - The README-topology.md file in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the ipatopologysuffix variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/topology directory.

14.5. USING ANSIBLE TO REINITIALIZE AN IDM REPLICA

If a replica has been offline for a long period of time or its database has been corrupted, you can reinitialize it. reinitialization refreshes the replica with an updated set of data. reinitialization can, for example, be used if an authoritative restore from backup is required.



NOTE

In contrast to replication updates, during which replicas only send changed entries to each other, reinitialization refreshes the whole database.

The local host on which you run the command is the reinitialized replica. To specify the replica from which the data is obtained, use the **direction** option.

This section describes how to use an Ansible playbook to reinitialize the **domain** data on **replica.idm.example.com** from **server.idm.example.com**.

Prerequisites

- You know the IdM **admin** password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.

• In the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to your ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Copy the **reinitialize-topologysegment.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/topology/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/reinitialize-topologysegment.yml reinitialize-topologysegment-copy.yml

- 3. Open the reinitialize-topologysegment-copy.yml file for editing.
- 4. Adapt the file by setting the following variables in the **ipatopologysegment** section:
 - Set the **ipaadmin password** variable to the password of the IdM **admin**.
 - Set the **suffix** variable to **domain**. If you are reinitializing the **ca** data, set the variable to **ca**.
 - Set the **left** variable to the left node of the replication agreement.
 - Set the **right** variable to the right node of the replication agreement.
 - Set the **direction** variable to the direction of the reinitializing data. The **left-to-right** direction means that data flows from the left node to the right node.
 - Ensure that the **state** variable is set to **reinitialized**.
 This is the modified Ansible playbook file for the current example:

- name: Playbook to handle topologysegment

hosts: ipaserver become: true

tasks:

- name: Reinitialize topology segment

ipatopologysegment:

ipaadmin_password: Secret123

suffix: domain

left: server.idm.example.com right: replica.idm.example.com

direction: left-to-right state: reinitialized

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory reinitialize-topologysegment-copy.yml

Additional resources

- For more information on the concept of topology agreements, suffixes, and segments, see Explaining Replication Agreements, Topology Suffixes, and Topology Segments.
- For more sample Ansible playbooks that use the **ipatopologysegment** module, see:
 - The **README-topology.md** file in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipatopologysegment** variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/topology directory.

14.6. USING ANSIBLE TO ENSURE A REPLICATION AGREEMENT IS ABSENT IN IDM

Data stored on an Identity Management (IdM) server is replicated based on replication agreements: when two servers have a replication agreement configured, they share their data. Replication agreements are always bilateral: the data is replicated from the first replica to the other one as well as from the other replica to the first one.

This section describes how to ensure a replication agreement between two replicas does not exist in IdM. The example describes how to ensure a replication agreement of the **domain** type does not exist between the **replicaO1.idm.example.com** and **replicaO2.idm.example.com** IdM servers.

Prerequisites

- Ensure that you understand the recommendations for designing your IdM topology listed in Connecting the replicas in a topology
- You know the IdM **admin** password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the ansible-freeipa package.
 - In the ~/MyPlaybooks/ directory, you have created an Ansible inventory file with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

- 1. Navigate to your ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Copy the **delete-topologysegment.yml** Ansible playbook file located in the /usr/share/doc/ansible-freeipa/playbooks/topology/ directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/topology/delete-topologysegment.yml delete-topologysegment-copy.yml
- 3. Open the **delete-topologysegment-copy.yml** file for editing.
- 4. Adapt the file by setting the following variables in the **ipatopologysegment** task section:

- Set the **ipaadmin_password** variable to the password of the IdM **admin**.
- Set the **suffix** variable to **domain**. Alternatively, if you are ensuring that the **ca** data are not replicated between the left and right nodes, set the variable to **ca**.
- Set the **left** variable to the name of the IdM server that is the left node of the replication agreement.
- Set the **right** variable to the name of the IdM server that is the right node of the replication agreement.
- Ensure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

- name: Playbook to handle topologysegment

hosts: ipaserver become: true

tasks:

- name: Delete topology segment

ipatopologysegment:

ipaadmin_password: Secret123

suffix: domain

left: replica01.idm.example.com right: replica02.idm.example.com:

state: absent

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory delete-topologysegment-copy.yml

Additional resources

- For more information on the concept of topology agreements, suffixes, and segments, see Explaining Replication Agreements, Topology Suffixes, and Topology Segments.
- For more sample Ansible playbooks that use the **ipatopologysegment** module, see:
 - The **README-topology.md** file in the /usr/share/doc/ansible-freeipa/ directory. This file also contains the definitions of the **ipatopologysegment** variables.
 - The /usr/share/doc/ansible-freeipa/playbooks/topology directory.

14.7. ADDITIONAL RESOURCES

- For more information on how to plan the topology of your IdM deployment, see Planning the replica topology.
- For more information on how to install an IdM replica, see Installing an IdM replica.

CHAPTER 15. MANAGING HOSTS USING ANSIBLE PLAYBOOKS

Ansible is an automation tool used to configure systems, deploy software, and perform rolling updates. Ansible includes support for Identity Management (IdM), and you can use Ansible modules to automate host management.

This chapter describes the following concepts and operations performed when managing hosts and host entries using Ansible playbooks:

- Hosts in IdM
- Host enrollment
- Ensuring the presence of IdM host entries that are only defined by their FQDNs
- Ensuring the presence of IdM host entries with IP addresses
- Ensuring the presence of multiple IdM host entries with random passwords
- Ensuring the presence of an IdM host entry with multiple IP addresses
- Ensuring the absence of IdM host entries

15.1. HOSTS IN IDM

Identity Management (IdM) manages these identities:

- Users
- Services
- Hosts

A host represents a machine. As an IdM identity, a host has an entry in the IdM LDAP, that is the 389 Directory Server instance of the IdM server.

The host entry in IdM LDAP is used to establish relationships between other hosts and even services within the domain. These relationships are part of *delegating* authorization and control to hosts within the domain. Any host can be used in **host-based access control** (HBAC) rules.

IdM domain establishes a commonality between machines, with common identity information, common policies, and shared services. Any machine that belongs to a domain functions as a client of the domain, which means it uses the services that the domain provides. IdM domain provides three main services specifically for machines:

- DNS
- Kerberos
- Certificate management

Hosts in IdM are closely connected with the services running on them:

Service entries are associated with a host.

• A host stores both the host and the service Kerberos principals.

15.2. HOST ENROLLMENT

This section describes enrolling hosts as IdM clients and what happens during and after the enrollment. The section compares the enrollment of IdM hosts and IdM users. The section also outlines alternative types of authentication available to hosts.

Enrolling a host consists of:

- Creating a host entry in IdM LDAP: possibly using the **ipa host-add** command in IdM CLI, or the equivalent IdM Web UI operation.
- Configuring IdM services on the host, for example the System Security Services Daemon (SSSD), Kerberos, and certmonger, and joining the host to the IdM domain.

The two actions can be performed separately or together.

If performed separately, they allow for dividing the two tasks between two users with different levels of privilege. This is useful for bulk deployments.

The **ipa-client-install** command can perform the two actions together. The command creates a host entry in IdM LDAP if that entry does not exist yet, and configures both the Kerberos and SSSD services for the host. The command brings the host within the IdM domain and allows it to identify the IdM server it will connect with. If the host belongs to a DNS zone managed by IdM, **ipa-client-install** adds DNS records for the host too. The command must be run on the client.

15.2.1. User privileges required for host enrollment

The host enrollment operation requires authentication to prevent an unprivileged user from adding unwanted machines to the IdM domain. The privileges required depend on several factors, for example:

- If a host entry is created separately from running **ipa-client-install**
- If a one-time password (OTP) is used for enrollment

User privileges for optionally manually creating a host entry in IdM LDAP

The user privilege required for creating a host entry in IdM LDAP using the **ipa host-add** CLI command or the IdM Web UI is **Host Administrators**. The **Host Administrators** privilege can be obtained through the **IT Specialist** role.

User privileges for joining the client to the IdM domain

Hosts are configured as IdM clients during the execution of the **ipa-client-install** command. The level of credentials required for executing the **ipa-client-install** command depends on which of the following enrolling scenarios you find yourself in:

- The host entry in IdM LDAP does not exist. For this scenario, you need a full administrator's credentials or the **Host Administrators** role. A full administrator is a member of the **admins** group. The **Host Administrators** role provides privileges to add hosts and enroll hosts. For details about this scenario, see Installing a client using user credentials: interactive installation.
- The host entry in IdM LDAP exists. For this scenario, you need a limited administrator's credentials to execute **ipa-client-install** successfully. The limited administrator in this case has the **Enrollment Administrator** role, which provides the **Host Enrollment** privilege. For details, see Installing a client using user credentials: interactive installation.

• The host entry in IdM LDAP exists, and an OTP has been generated for the host by a full or limited administrator. For this scenario, you can install an IdM client as an ordinary user if you run the **ipa-client-install** command with the **--password** option, supplying the correct OTP. For details, see Installing a client by using a one-time password: Interactive installation.

After enrollment, IdM hosts authenticate every new session to be able to access IdM resources. Machine authentication is required for the IdM server to trust the machine and to accept IdM connections from the client software installed on that machine. After authenticating the client, the IdM server can respond to its requests.

15.2.2. Enrollment and authentication of IdM hosts and users: comparison

There are many similarities between users and hosts in IdM. This section describes some of the similarities that can be observed during the enrollment stage as well as those that concern authentication during the deployment stage.

- The enrollment stage (Table 15.1, "User and host enrollment"):
 - An administrator can create an LDAP entry for both a user and a host before the user or host actually join IdM: for the stage user, the command is **ipa stageuser-add**; for the host, the command is **ipa host-add**.
 - A file containing a *key table* or, abbreviated, keytab, a symmetric key resembling to some extent a user password, is created during the execution of the **ipa-client-install** command on the host, resulting in the host joining the IdM realm. Analogically, a user is asked to create a password when they activate their account, thus joining the IdM realm.
 - While the user password is the default authentication method for a user, the keytab is the default authentication method for a host. The keytab is stored in a file on the host.

Table 15.1. User and host enrollment

Action	User	Host
Pre-enrollment	\$ ipa stageuser-add user_name [- -password]	\$ ipa host-add host_name [random]
Activating the account	\$ ipa stageuser-activate user_name	\$ ipa-client install [password] (must be run on the host itself)

- The deployment stage (Table 15.2, "User and host session authentication"):
 - When a user starts a new session, the user authenticates using a password; similarly, every time it is switched on, the host authenticates by presenting its keytab file. The System Security Services Daemon (SSSD) manages this process in the background.
 - If the authentication is successful, the user or host obtains a Kerberos ticket granting ticket (TGT).
 - The TGT is then used to obtain specific tickets for specific services.

Table 15.2. User and host session authentication

	User	Host
Default means of authentication	Password	Keytabs
Starting a session (ordinary user)	\$ kinit user_name	[switch on the host]
The result of successful authentication	TGT to be used to obtain access to specific services	TGT to be used to obtain access to specific services

TGTs and other Kerberos tickets are generated as part of the Kerberos services and policies defined by the server. The initial granting of a Kerberos ticket, the renewing of the Kerberos credentials, and even the destroying of the Kerberos session are all handled automatically by the IdM services.

15.2.3. Alternative authentication options for IdM hosts

Apart from keytabs, IdM supports two other types of machine authentication:

- SSH keys. The SSH public key for the host is created and uploaded to the host entry. From there, the System Security Services Daemon (SSSD) uses IdM as an identity provider and can work in conjunction with OpenSSH and other services to reference the public keys located centrally in IdM.
- Machine certificates. In this case, the machine uses an SSL certificate that is issued by the IdM
 server's certificate authority and then stored in IdM's Directory Server. The certificate is then
 sent to the machine to present when it authenticates to the server. On the client, certificates are
 managed by a service called certmonger.

15.3. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH FQDN USING ANSIBLE PLAYBOOKS

This section describes ensuring the presence of host entries in Identity Management (IdM) using Ansible playbooks. The host entries are only defined by their **fully-qualified domain names** (FQDNs).

Specifying the **FQDN** name of the host is enough if at least one of the following conditions applies:

- The IdM server is not configured to manage DNS.
- The host does not have a static IP address or the IP address is not known at the time the host is
 configured. Adding a host defined only by an FQDN essentially creates a placeholder entry in the
 IdM DNS service. For example, laptops may be preconfigured as IdM clients, but they do not
 have IP addresses at the time they are configured. When the DNS service dynamically updates
 its records, the host's current IP address is detected and its DNS record is updated.



NOTE

Without Ansible, host entries are created in IdM using the **ipa host-add** command. The result of adding a host to IdM is the state of the host being present in IdM. Because of the Ansible reliance on idempotence, to add a host to IdM using Ansible, you must create a playbook in which you define the state of the host as present: **state:** present.

Prerequisites

- You know the IdM administrator password.
- The ansible-freeipa package is installed on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

 Create an Ansible playbook file with the FQDN of the host whose presence in IdM you want to ensure. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/host/add-host.yml file:

 name: Host present hosts: ipaserver become: true

tasks:

- name: Host host01.idm.example.com present

ipahost:

ipaadmin_password: MySecret123 name: host01.idm.example.com

state: present force: yes

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-host-is-present.yml



NOTE

The procedure results in a host entry in the IdM LDAP server being created but not in enrolling the host into the IdM Kerberos realm. For that, you must deploy the host as an IdM client. For details, see Installing an Identity Management client using an Ansible playbook.

Verification steps

1. Log in to your IdM server as admin:

\$ ssh admin@server.idm.example.com

Password:

2. Enter the **ipa host-show** command and specify the name of the host:

\$ ipa host-show host01.idm.example.com

Host name: host01.idm.example.com

Principal name: host/host01.idm.example.com@IDM.EXAMPLE.COM Principal alias: host/host01.idm.example.com@IDM.EXAMPLE.COM

Password: False Keytab: False

Managed by: host01.idm.example.com

The output confirms that **hostO1.idm.example.com** exists in IdM.

15.4. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH DNS INFORMATION USING ANSIBLE PLAYBOOKS

This section describes ensuring the presence of host entries in Identity Management (IdM) using Ansible playbooks. The host entries are defined by their **fully-qualified domain names** (FQDNs) and their IP addresses.



NOTE

Without Ansible, host entries are created in IdM using the **ipa host-add** command. The result of adding a host to IdM is the state of the host being present in IdM. Because of the Ansible reliance on idempotence, to add a host to IdM using Ansible, you must create a playbook in which you define the state of the host as present: **state: present**.

Prerequisites

- You know the IdM administrator password.
- The ansible-freeipa package is installed on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the **fully-qualified domain name** (FQDN) of the host whose presence in IdM you want to ensure. In addition, if the IdM server is configured to manage DNS and you know the IP address of the host, specify a value for the **ip_address** parameter. The IP address is necessary for the host to exist in the DNS resource records. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/host/host-present.yml file. You can also include other, additional information:

 name: Host present hosts: ipaserver become: true

tasks:

- name: Ensure host01.idm.example.com is present

ipahost:

ipaadmin_password: MySecret123 name: host01.idm.example.com description: Example host ip address: 192.168.0.123

locality: Lab

ns_host_location: Lab ns_os_version: CentOS 7

ns_hardware_platform: Lenovo T61

mac address:

- "08:00:27:E3:B1:2D" - "52:54:00:BD:97:1E"

state: present

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-host-is-present.yml



NOTE

The procedure results in a host entry in the IdM LDAP server being created but not in enrolling the host into the IdM Kerberos realm. For that, you must deploy the host as an IdM client. For details, see Installing an Identity Management client using an Ansible playbook.

Verification steps

1. Log in to your IdM server as admin:

\$ ssh admin@server.idm.example.com Password:

2. Enter the **ipa host-show** command and specify the name of the host:

\$ ipa host-show host01.idm.example.com

Host name: host01.idm.example.com

Description: Example host

Locality: Lab Location: Lab

Platform: Lenovo T61

Operating system: CentOS 7

Principal name: host/host01.idm.example.com@IDM.EXAMPLE.COM Principal alias: host/host01.idm.example.com@IDM.EXAMPLE.COM

MAC address: 08:00:27:E3:B1:2D, 52:54:00:BD:97:1E

Password: False Keytab: False

Managed by: host01.idm.example.com

The output confirms host01.idm.example.com exists in IdM.

15.5. ENSURING THE PRESENCE OF MULTIPLE IDM HOST ENTRIES WITH RANDOM PASSWORDS USING ANSIBLE PLAYBOOKS

The **ipahost** module allows the system administrator to ensure the presence or absence of multiple host entries in IdM using just one Ansible task. This section describes how to ensure the presence of multiple host entries that are only defined by their **fully-qualified domain names** (FQDNs). Running the Ansible playbook generates random passwords for the hosts.



NOTE

Without Ansible, host entries are created in IdM using the **ipa host-add** command. The result of adding a host to IdM is the state of the host being present in IdM. Because of the Ansible reliance on idempotence, to add a host to IdM using Ansible, you must create a playbook in which you define the state of the host as present: **state: present**.

Prerequisites

- You know the IdM administrator password.
- The ansible-freeipa package is installed on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the fully-qualified domain name (FQDN) of the hosts whose presence in IdM you want to ensure. To make the Ansible playbook generate a random password for each host even when the host already exists in IdM and update_password is limited to on_create, add the random: yes and force: yes options. To simplify this step, you can copy and modify the example from the /usr/share/doc/ansible-freeipa/README-host.md Markdown file:

- name: Ensure hosts with random password

hosts: ipaserver become: true

tasks:

- name: Hosts host01.idm.example.com and host02.idm.example.com present with random passwords

ipahost:

ipaadmin_password: MySecret123

hosts

- name: host01.idm.example.com

random: yes force: yes

- name: host02.idm.example.com

random: yes force: yes register: ipahost 3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hosts-are-present.yml

[...]

TASK [Hosts host01.idm.example.com and host02.idm.example.com present with random passwords]

changed: [r8server.idm.example.com] => {"changed": true, "host":

"host02.idm.example.com": {"randompassword": "5VdLgrf3wvojmACdHC3uA3s"}}}



NOTE

To deploy the hosts as IdM clients using random, one-time passwords (OTPs), see Authorization options for IdM client enrollment using an Ansible playbook or Installing a client by using a one-time password: Interactive installation.

Verification steps

1. Log in to your IdM server as admin:

\$ ssh admin@server.idm.example.com

Password:

2. Enter the **ipa host-show** command and specify the name of one of the hosts:

\$ ipa host-show host01.idm.example.com

Host name: host01.idm.example.com

Password: True Keytab: False

Managed by: host01.idm.example.com

The output confirms host01.idm.example.com exists in IdM with a random password.

15.6. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH MULTIPLE IP ADDRESSES USING ANSIBLE PLAYBOOKS

This section describes how to ensure the presence of a host entry in Identity Management (IdM) using Ansible playbooks. The host entry is defined by its **fully-qualified domain name** (FQDN) and its multiple IP addresses.



NOTE

In contrast to the **ipa host** utility, the Ansible **ipahost** module can ensure the presence or absence of several IPv4 and IPv6 addresses for a host. The **ipa host-mod** command cannot handle IP addresses.

Prerequisites

- You know the IdM administrator password.
- The ansible-freeipa package is installed on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file. Specify, as the name of the ipahost variable, the fully-qualified domain name (FQDN) of the host whose presence in IdM you want to ensure. Specify each of the multiple IPv4 and IPv6 ip_address values on a separate line by using the -ip_address syntax. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/host/host-member-ipaddresses-present.yml file. You can also include additional information:

- name: Host member IP addresses present

hosts: ipaserver become: true

tasks:

- name: Ensure host101.example.com IP addresses present

ipahost:

ipaadmin_password: MySecret123 name: host01.idm.example.com

ip_address: - 192.168.0.123

- fe80::20c:29ff:fe02:a1b3

- 192.168.0.124

- fe80::20c:29ff:fe02:a1b4

force: yes

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-host-with-multiple-IP-addreses-is-present.yml



NOTE

The procedure creates a host entry in the IdM LDAP server but does not enroll the host into the IdM Kerberos realm. For that, you must deploy the host as an IdM client. For details, see Installing an Identity Management client using an Ansible playbook.

Verification steps

1. Log in to your IdM server as admin:

\$ ssh admin@server.idm.example.com Password:

2. Enter the **ipa host-show** command and specify the name of the host:

\$ ipa host-show host01.idm.example.com

Principal name: host/host01.idm.example.com@IDM.EXAMPLE.COM Principal alias: host/host01.idm.example.com@IDM.EXAMPLE.COM

Password: False Keytab: False

Managed by: host01.idm.example.com

The output confirms that host01.idm.example.com exists in IdM.

3. To verify that the multiple IP addresses of the host exist in the IdM DNS records, enter the **ipa dnsrecord-show** command and specify the following information:

The name of the IdM domain

• The name of the host

\$ ipa dnsrecord-show idm.example.com host01

[...]

Record name: host01

A record: 192.168.0.123, 192.168.0.124

AAAA record: fe80::20c:29ff:fe02:a1b3, fe80::20c:29ff:fe02:a1b4

The output confirms that all the IPv4 and IPv6 addresses specified in the playbook are correctly associated with the **host01.idm.example.com** host entry.

15.7. ENSURING THE ABSENCE OF AN IDM HOST ENTRY USING ANSIBLE PLAYBOOKS

This section describes how to ensure the absence of host entries in Identity Management (IdM) using Ansible playbooks.

Prerequisites

IdM administrator credentials

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

 Create an Ansible playbook file with the fully-qualified domain name (FQDN) of the host whose absence from IdM you want to ensure. If your IdM domain has integrated DNS, use the updatedns: yes option to remove the associated records of any kind for the host from the DNS.

To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/host/delete-host.yml file:

 name: Host absent hosts: ipaserver become: true

tasks:

name: Host host01.idm.example.com absent ipahost:

ipaadmin_password: MySecret123 name: host01.idm.example.com

updatedns: yes state: absent

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-host-absent.yml



NOTE

The procedure results in:

- The host not being present in the IdM Kerberos realm.
- The host entry not being present in the IdM LDAP server.

To remove the specific IdM configuration of system services, such as System Security Services Daemon (SSSD), from the client host itself, you must run the **ipa-client-install -- uninstall** command on the client. For details, see Uninstalling an IdM client.

Verification steps

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Display information about *hostO1.idm.example.com*:

\$ ipa host-show host01.idm.example.com ipa: ERROR: host01.idm.example.com: host not found

The output confirms that the host does not exist in IdM.

Additional resources

- You can see the definitions of the ipahost variables as well as sample Ansible playbooks for ensuring the presence, absence, and disablement of hosts in the /usr/share/doc/ansiblefreeipa/README-host.md Markdown file.
- Additional playbooks are in the /usr/share/doc/ansible-freeipa/playbooks/host directory.

CHAPTER 16. MANAGING HOST GROUPS USING ANSIBLE PLAYBOOKS

This chapter introduces host groups in Identity Management (IdM) and describes using Ansible to perform the following operations involving host groups in Identity Management (IdM):

- Host groups in IdM
- Ensuring the presence of IdM host groups
- Ensuring the presence of hosts in IdM host groups
- Nesting IdM host groups
- Ensuring the presence of member managers in IdM host groups
- Ensuring the absence of hosts from IdM host groups
- Ensuring the absence of nested host groups from IdM host groups
- Ensuring the absence of member managers from IdM host groups

16.1. HOST GROUPS IN IDM

IdM host groups can be used to centralize control over important management tasks, particularly access control.

Definition of host groups

A host group is an entity that contains a set of IdM hosts with common access control rules and other characteristics. For example, you can define host groups based on company departments, physical locations, or access control requirements.

A host group in IdM can include:

- IdM servers and clients
- Other IdM host groups

Host groups created by default

By default, the IdM server creates the host group **ipaservers** for all IdM server hosts.

Direct and indirect group members

Group attributes in IdM apply to both direct and indirect members: when host group B is a member of host group A, all members of host group B are considered indirect members of host group A.

16.2. ENSURING THE PRESENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes how to ensure the presence of host groups in Identity Management (IdM) using Ansible playbooks.



NOTE

Without Ansible, host group entries are created in IdM using the **ipa hostgroup-add** command. The result of adding a host group to IdM is the state of the host group being present in IdM. Because of the Ansible reliance on idempotence, to add a host group to IdM using Ansible, you must create a playbook in which you define the state of the host group as present: **state: present**.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

[ipaserver] server.idm.example.com

Create an Ansible playbook file with the necessary host group information. For example, to
ensure the presence of a host group named databases, specify name: databases in the
ipahostgroup task. To simplify this step, you can copy and modify the example in the
/usr/share/doc/ansible-freeipa/playbooks/user/ensure-hostgroup-is-present.yml file.

- name: Playbook to handle hostgroups

hosts: ipaserver become: true

tasks:

Ensure host-group databases is present

- ipahostgroup:

ipaadmin_password: MySecret123

name: databases state: present

In the playbook, **state: present** signifies a request to add the host group to IdM unless it already exists there.

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hostgroup-is-present.yml

Verification steps

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com Password: [admin@server /]\$ 2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Display information about the host group whose presence in IdM you wanted to ensure:

\$ ipa hostgroup-show databases

Host-group: databases

The databases host group exists in IdM.

16.3. ENSURING THE PRESENCE OF HOSTS IN IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes how to ensure the presence of hosts in host groups in Identity Management (IdM) using Ansible playbooks.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.
- The hosts you want to reference in your Ansible playbook exist in IdM. For details, see Ensuring the presence of an IdM host entry using Ansible playbooks.
- The host groups you reference from the Ansible playbook file have been added to IdM. For details, see Ensuring the presence of IdM host groups using Ansible playbooks.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the necessary host information. Specify the name of the host group using the **name** parameter of the **ipahostgroup** variable. Specify the name of the host with the **host** parameter of the **ipahostgroup** variable. To simplify this step, you can copy and modify the examples in the /usr/share/doc/ansible-

freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-present-in-hostgroup.yml file:

- name: Playbook to handle hostgroups

hosts: ipaserver become: true

tasks:

Ensure host-group databases is present

- ipahostgroup:

ipaadmin_password: MySecret123

name: databases

host:

- db.idm.example.com

action: member

This playbook adds the **db.idm.example.com** host to the **databases** host group. The **action: member** line indicates that when the playbook is run, no attempt is made to add the **databases** group itself. Instead, only an attempt is made to add **db.idm.example.com** to **databases**.

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hosts-or-hostgroups-are-present-in-hostgroup.yml

Verification steps

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com

Password:

[admin@server/]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Display information about a host group to see which hosts are present in it:

\$ ipa hostgroup-show databases

Host-group: databases

Member hosts: db.idm.example.com

The **db.idm.example.com** host is present as a member of the **databases** host group.

16.4. NESTING IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes ensuring the presence of nested host groups in Identity Management (IdM) host groups using Ansible playbooks.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.
- The host groups you reference from the Ansible playbook file exist in IdM. For details, see Ensuring the presence of IdM host groups using Ansible playbooks.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the necessary host group information. To ensure that a nested host group A exists in a host group B: in the Ansible playbook, specify, among the ipahostgroup variables, the name of the host group B using the name variable. Specify the name of the nested hostgroup A with the hostgroup variable. To simplify this step, you can copy and modify the examples in the /usr/share/doc/ansible-

freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-present-in-hostgroup.yml file:

- name: Playbook to handle hostgroups

hosts: ipaserver become: true

tasks:

Ensure hosts and hostgroups are present in existing databases hostgroup

- ipahostgroup:

ipaadmin_password: MySecret123

name: databases hostgroup: - mysql-server - oracle-server action: member

This Ansible playbook ensures the presence of the **myqsl-server** and **oracle-server** host groups in the **databases** host group. The **action: member** line indicates that when the playbook is run, no attempt is made to add the **databases** group itself to IdM.

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hosts-or-hostgroups-are-present-in-hostgroup.yml

Verification steps

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Display information about the host group in which nested host groups are present:

\$ ipa hostgroup-show databases

Host-group: databases

Member hosts: db.idm.example.com

Member host-groups: mysql-server, oracle-server

The mysql-server and oracle-server host groups exist in the databases host group.

16.5. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of member managers in IdM hosts and host groups using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.
- You must have the name of the host or host group you are adding as member managers and the name of the host group you want them to manage.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the necessary host and host group member management information:

- name: Playbook to handle host group membership management

hosts: ipaserver become: true

tasks:

- name: Ensure member manager user example_member is present for group_name ipahostgroup:

ipaadmin password: MySecret123

name: group name

membermanager_user: example_member

- name: Ensure member manager group project_admins is present for group_name ipahostgroup:

ipaadmin_password: MySecret123

name: group_name

membermanager_group: project_admins

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/add-member-managers-host-groups.yml

Verification steps

You can verify if the **group_name** group contains **example_member** and **project_admins** as member managers by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Display information about testhostgroup:

ipaserver]\$ ipa hostgroup-show group_name

Host-group: group_name

Member hosts: server.idm.example.com Member host-groups: testhostgroup2

Membership managed by groups: project_admins Membership managed by users: example_member

Additional resources

- See ipa hostgroup-add-member-manager --help.
- See the **ipa** man page.

16.6. ENSURING THE ABSENCE OF HOSTS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes how to ensure the absence of hosts from host groups in Identity Management (IdM) using Ansible playbooks.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.
- The hosts you want to reference in your Ansible playbook exist in IdM. For details, see Ensuring the presence of an IdM host entry using Ansible playbooks.
- The host groups you reference from the Ansible playbook file exist in IdM. For details, see Ensuring the presence of IdM host groups using Ansible playbooks.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

[ipaserver] server.idm.example.com

2. Create an Ansible playbook file with the necessary host and host group information. Specify the name of the host group using the **name** parameter of the **ipahostgroup** variable. Specify the name of the host whose absence from the host group you want to ensure using the **host** parameter of the **ipahostgroup** variable. To simplify this step, you can copy and modify the examples in the /usr/share/doc/ansible-freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-absent-in-hostgroup.yml file:

- name: Playbook to handle hostgroups

hosts: ipaserver become: true

tasks:

Ensure host-group databases is absent

- ipahostgroup:

ipaadmin_password: MySecret123

name: databases

host:

- db.idm.example.com

action: member state: absent

This playbook ensures the absence of the **db.idm.example.com** host from the **databases** host group. The **action: member** line indicates that when the playbook is run, no attempt is made to remove the **databases** group itself.

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hosts-or-hostgroups-are-absent-in-hostgroup.yml

Verification steps

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com Password:

[admin@server /]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Display information about the host group and the hosts it contains:

\$ ipa hostgroup-show databases

Host-group: databases

Member host-groups: mysql-server, oracle-server

The **db.idm.example.com** host does not exist in the **databases** host group.

16.7. ENSURING THE ABSENCE OF NESTED HOST GROUPS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes how to ensure the absence of nested host groups from outer host groups in Identity Management (IdM) using Ansible playbooks.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.
- The host groups you reference from the Ansible playbook file exist in IdM. For details, see Ensuring the presence of IdM host groups using Ansible playbooks.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

[ipaserver] server.idm.example.com

Create an Ansible playbook file with the necessary host group information. Specify, among the ipahostgroup variables, the name of the outer host group using the name variable. Specify the
name of the nested hostgroup with the hostgroup variable. To simplify this step, you can copy
and modify the examples in the /usr/share/doc/ansible-

freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-absent-in-hostgroup.yml file:

- name: Playbook to handle hostgroups

hosts: ipaserver become: true

tasks:

Ensure hosts and hostgroups are absent in existing databases hostgroup

- ipahostgroup:

ipaadmin password: MySecret123

name: databases

hostgroup:

- mysql-server

- oracle-server

action: member state: absent

This playbook makes sure that the **mysql-server** and **oracle-server** host groups are absent from the **databases** host group. The **action: member** line indicates that when the playbook is run, no attempt is made to ensure the **databases** group itself is deleted from IdM.

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hosts-or-hostgroups-are-absent-in-hostgroup.vml

Verification steps

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin

Password for admin@IDM.EXAMPLE.COM:

3. Display information about the host group from which nested host groups should be absent:

\$ ipa hostgroup-show databases

Host-group: databases

The output confirms that the **mysql-server** and **oracle-server** nested host groups are absent from the outer **databases** host group.

16.8. ENSURING THE ABSENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes how to ensure the absence of host groups in Identity Management (IdM) using Ansible playbooks.



NOTE

Without Ansible, host group entries are removed from IdM using the **ipa hostgroup-del** command. The result of removing a host group from IdM is the state of the host group being absent from IdM. Because of the Ansible reliance on idempotence, to remove a host group from IdM using Ansible, you must create a playbook in which you define the state of the host group as absent: **state: absent**

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

[ipaserver] server.idm.example.com 2. Create an Ansible playbook file with the necessary host group information. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/user/ensure-hostgroup-is-absent.yml file.

- name: Playbook to handle hostgroups

hosts: ipaserver become: true

tasks:

- Ensure host-group databases is absent

ipahostgroup:

ipaadmin_password: MySecret123

name: databases state: absent

This playbook ensures the absence of the **databases** host group from IdM. The **state: absent** means a request to delete the host group from IdM unless it is already deleted.

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-hostgroup-is-absent.yml

Verification steps

1. Log into **ipaserver** as admin:

\$ ssh admin@server.idm.example.com Password: [admin@server /]\$

2. Request a Kerberos ticket for admin:

\$ kinit admin
Password for admin@IDM.EXAMPLE.COM:

3. Display information about the host group whose absence you ensured:

\$ ipa hostgroup-show databases ipa: ERROR: databases: host group not found

The databases host group does not exist in IdM.

16.9. ENSURING THE ABSENCE OF MEMBER MANAGERS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the absence of member managers in IdM hosts and host groups using an Ansible playbook.

Prerequisites

• You know the IdM administrator password.

- You have installed the ansible-freeipa package on the Ansible controller.
- You must have the name of the user or user group you are removing as member managers and the name of the host group they are managing.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary host and host group member management information:

- name: Playbook to handle host group membership management

hosts: ipaserver become: true

tasks:

- name: Ensure member manager host and host group members are absent for

group_name ipahostgroup:

ipaadmin_password: MySecret123

name: group_name

membermanager_user: example_member membermanager_group: project_admins

action: member state: absent

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-member-managers-host-groups-are-absent.yml

Verification steps

You can verify if the **group_name** group does not contain **example_member** or **project_admins** as member managers by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

\$ ssh admin@server.idm.example.com Password: [admin@server/]\$

2. Display information about testhostgroup:

ipaserver]\$ ipa hostgroup-show group name

Host-group: group name

Member hosts: server.idm.example.com Member host-groups: testhostgroup2

Additional resources

- See ipa hostgroup-add-member-manager --help.
- See the **ipa** man page.

CHAPTER 17. DEFINING IDM PASSWORD POLICIES

This chapter describes Identity Management (IdM) password policies and how to add a new password policy in IdM using an Ansible playbook.

17.1. WHAT IS A PASSWORD POLICY

A password policy is a set of rules that passwords must meet. For example, a password policy can define the minimum password length and the maximum password lifetime. All users affected by this policy are required to set a sufficiently long password and change it frequently enough to meet the specified conditions. In this way, password policies help reduce the risk of someone discovering and misusing a user's password.

17.2. PASSWORD POLICIES IN IDM

Passwords are the most common way for Identity Management (IdM) users to authenticate to the IdM Kerberos domain. Password policies define the requirements that these IdM user passwords must meet.



NOTE

The IdM password policy is set in the underlying LDAP directory, but the Kerberos Key Distribution Center (KDC) enforces the password policy.

Password policy attributes lists the attributes you can use to define a password policy in IdM.

Table 17.1. Password Policy Attributes

Attribute	Explanation	Example
Max lifetime	The maximum amount of time in days that a password is valid before a user must reset it.	Max lifetime = 90 User passwords are valid only for 90 days. After that, IdM prompts users to change them.
Min lifetime	The minimum amount of time in hours that must pass between two password change operations.	Min lifetime = 1 After users change their passwords, they must wait at least 1 hour before changing them again.
History size	The number of previous passwords that are stored. A user cannot reuse a password from their password history but can reuse old passwords that are not stored.	History size = 0 In this case, the password history is empty and users can reuse any of their previous passwords.

Attribute	Explanation	Example
Character classes	The number of different character classes the user must use in the password. The character classes are: * Uppercase characters * Lowercase characters * Digits * Special characters, such as comma (,), period (.), asterisk (*) * Other UTF-8 characters Using a character three or more times in a row decreases the character class by one. For example: * Secret1 has 3 character classes: uppercase, lowercase, digits * Secret111 has 2 character classes: uppercase, lowercase, digits, and a -1 penalty for using 1 repeatedly	Character classes = 0 The default number of classes required is 0. To configure the number, run the ipa pwpolicy-mod command with the-minclasses option. See also the Important note below this table.
Min length	The minimum number of characters in a password. If any of the additional password policy options are set, then the minimum length of passwords is 6 regardless of the value to which the Min length option is set.	Min length = 8 Users cannot use passwords shorter than 8 characters.
Max failures	The maximum number of failed login attempts before IdM locks the user account.	Max failures = 6 IdM locks the user account when the user enters a wrong password 7 times in a row.
Failure reset interval	The amount of time in seconds after which IdM resets the current number of failed login attempts.	Failure reset interval = 60 If the user waits for more than 1 minute after the number of failed login attempts defined in Max failures , the user can attempt to log in again without risking a user account lock.
Lockout duration	The amount of time in seconds that the user account is locked after the number of failed login attempts defined in Max failures .	Lockout duration = 600 Users with locked accounts are unable to log in for 10 minutes.



IMPORTANT

Use the English alphabet and common symbols for the character classes requirement if you have a diverse set of hardware that may not have access to international characters and symbols. For more information about character class policies in passwords, see What characters are valid in a password? in Red Hat Knowledgebase.

17.3. ENSURING THE PRESENCE OF A PASSWORD POLICY IN IDM USING AN ANSIBLE PLAYBOOK

This section describes how to ensure the presence of a password policy in Identity Management (IdM) using an Ansible playbook.

In the default **global_policy** password policy in IdM, the number of different character classes in the password is set to 0. The history size is also set to 0.

Complete this procedure to enforce a stronger password policy for an IdM group using an Ansible playbook.



NOTE

You can only define a password policy for an IdM group. You cannot define a password policy for an individual user.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller.
- You know the IdM administrator password.
- The group for which you are ensuring the presence of a password policy exists in IdM.

Procedure

1. Create an inventory file, for example **inventory.file**, and define the **FQDN** of your IdM server in the **[ipaserver]** section:

[ipaserver] server.idm.example.com

2. Create your Ansible playbook file that defines the password policy whose presence you want to ensure. To simplify this step, copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/pwpolicy/pwpolicy_present.yml file:

 name: Tests hosts: ipaserver become: true

tasks:

- name: Ensure presence of pwpolicy for group ops

ipapwpolicy:

ipaadmin_password: MySecret123

name: ops

minlife: 7 maxlife: 49 history: 5 priority: 1

lockouttime: 300 minlength: 8 minclasses: 4 maxfail: 3 failinterval: 5

For details on what the individual variables mean, see Password policy attributes.

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory_/new_pwpolicy_present.yml

You have successfully used an Ansible playbook to ensure that a password policy for the **ops** group is present in IdM.



IMPORTANT

The priority of the **ops** password policy is set to 1, whereas the **global_policy** password policy has no priority set. For this reason, the **ops** policy automatically supersedes **global_policy** for the **ops** group and is enforced immediately.

global_policy serves as a fallback policy when no group policy is set for a user, and it can never take precedence over a group policy.

Additional resources

- For more details about using Ansible to define password policies in IdM and about playbook variables, see the README-pwpolicy.md Markdown file available in the /usr/share/doc/ansiblefreeipa/ directory.
- For more details about how password policy priorities work in IdM, see Password policy priorities in RHEL 7 documentation.

17.4. ADDITIONAL PASSWORD POLICY OPTIONS IN IDM

As an Identity Management (IdM) administrator, you can strengthen the default password requirements by enabling additional password policy options based on the **libpwquality** feature set. The additional password policy options include the following:

--maxrepeat

Specifies the maximum acceptable number of same consecutive characters in the new password.

--maxsequence

Specifies the maximum length of monotonic character sequences in the new password. Examples of such a sequence are **12345** or **fedcb**. Most such passwords will not pass the simplicity check. The only exception is when the sequence is only a minor part of the password.

--dictcheck

If nonzero, checks whether the password, with possible modifications, matches a word in a dictionary. Currently **libpwquality** performs the dictionary check using the **cracklib** library.

--usercheck

If nonzero, checks whether the password, with possible modifications, contains the user name in some form. It is not performed for user names shorter than 3 characters.

You cannot apply the additional password policy options to existing passwords. If you apply any of the additional options, IdM automatically sets the **--minlength** option, the minimum number of characters in a password, to **6** characters.



NOTE

In a mixed environment with RHEL 7 and RHEL 8 servers, you can enforce the additional password policy settings only on servers running on RHEL 8.4 and later. If a user is logged in to an IdM client and the IdM client is communicating with an IdM server running on RHEL 8.3 or earlier, then the new password policy requirements set by the system administrator will not be applied. To ensure consistent behavior, upgrade or update all servers to RHEL 8.4 and later.

Additional resources:

- Applying additional password policies to an IdM group
- pwquality(3) man page

17.5. APPLYING ADDITIONAL PASSWORD POLICY OPTIONS TO AN IDM GROUP

This section describes how to apply additional password policy options in Identity Management (IdM). The example describes how to strengthen the password policy for the **managers** group by making sure that the new passwords do not contain the users' respective user names and that the passwords contain no more than two identical characters in succession.

Prerequisites

- You are logged in as an IdM administrator.
- The **managers** group exists in IdM.
- The managers password policy exists in IdM.

Procedure

1. Apply the user name check to all new passwords suggested by the users in the managers group:



NOTE

\$ ipa pwpolicy-mod --usercheck=True managers

If you do not specify the name of the password policy, the default **global_policy** is modified.

2. Set the maximum number of identical consecutive characters to 2 in the **managers** password policy:

\$ ipa pwpolicy-mod --maxrepeat=2 managers

A password now will not be accepted if it contains more than 2 identical consecutive characters. For example, the **eR873mUi111YJQ** combination is unacceptable because it contains three **1**s in succession.

Verification

1. Add a test user named test_user:

\$ ipa user-add test_user First name: test Last name: user -----Added user "test_user" ------

- 2. Add the test user to the managers group:
 - a. In the IdM Web UI, click Identity → Groups → User Groups.
 - b. Click managers.
 - c. Click Add.
 - d. In the Add users into user group 'managers' page, check test_user.
 - e. Click the > arrow to move the user to the **Prospective** column.
 - f. Click Add.
- 3. Reset the password for the test user:
 - a. Go to **Identity** → **Users**.
 - b. Click test_user.
 - c. In the **Actions** menu, click **Reset Password**.
 - d. Enter a temporary password for the user.
- 4. On the command line, try to obtain a Kerberos ticket-granting ticket (TGT) for the test_user:

\$ kinit test_user

- a. Enter the temporary password.
- b. The system informs you that you must change your password. Enter a password that contains the user name of **test_user**:

Password expired. You must change it now. Enter new password: Enter it again:



NOTE

Kerberos does not have fine-grained error password policy reporting and, in certain cases, does not provide a clear reason why a password was rejected.

c. The system informs you that the entered password was rejected. Enter a password that contains three or more identical characters in succession:

Password change rejected: Password not changed. Unspecified password quality failure while trying to change password. Please try again.

Enter new password:

Enter it again:

d. The system informs you that the entered password was rejected. Enter a password that meets the criteria of the **managers** password policy:

Password change rejected: Password not changed. Unspecified password quality failure while trying to change password. Please try again.

Enter new password:

Enter it again:

5. View the obtained TGT:

\$ klist

Ticket cache: KCM:0:33945

Default principal: test_user@IDM.EXAMPLE.COM

Valid starting Expires Service principal 07/07/2021 12:44:44 07/08/2021 12:44:44 krbtgt@IDM.EXAMPLE.COM@IDM.EXAMPLE.COM

The managers password policy now works correctly for users in the managers group.

Additional resources

• Additional password policies in IdM

CHAPTER 18. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT

18.1. SUDO ACCESS ON AN IDM CLIENT

System administrators can grant **sudo** access to allow non-root users to execute administrative commands that are normally reserved for the **root** user. Consequently, when users need to perform an administrative command normally reserved for the **root** user, they precede that command with **sudo**. After entering their password, the command is executed as if they were the **root** user. To execute a **sudo** command as another user or group, such as a database service account, you can configure a *RunAs alias* for a **sudo** rule.

If a Red Hat Enterprise Linux (RHEL) 8 host is enrolled as an Identity Management (IdM) client, you can specify **sudo** rules defining which IdM users can perform which commands on the host in the following ways:

- Locally in the /etc/sudoers file
- Centrally in IdM

This section describes creating a **central sudo** rule for an IdM client using the command line interface (CLI) and the IdM Web UI.

In RHEL 8.4 and later, you can also configure password-less authentication for **sudo** using the Generic Security Service Application Programming Interface (GSSAPI), the native way for UNIX-based operating systems to access and authenticate Kerberos services. You can use the **pam_sss_gss.so** Pluggable Authentication Module (PAM) to invoke GSSAPI authentication via the SSSD service, allowing users to authenticate to the **sudo** command with a valid Kerberos ticket.

Additional resources

• For details on creating local **sudo** rules on a RHEL host, see Managing sudo access.

18.2. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE CLI

In Identity Management (IdM), you can grant **sudo** access for a specific command to an IdM user account on a specific IdM host. First, add a **sudo** command and then create a **sudo** rule for one or more commands.

For example, complete this procedure to create the **idm_user_reboot** sudo rule to grant the **idm_user** account the permission to run the /usr/sbin/reboot command on the **idmclient** machine.

Prerequisites

- You are logged in as IdM administrator.
- You have created a user account for idm_user in IdM and unlocked the account by creating a
 password for the user. For details on adding a new IdM user using the CLI, see Adding users
 using the command line.
- No local **idm_user** account is present on the **idmclient** host. The **idm_user** user is not listed in the local /etc/passwd file.

Procedure

1. Retrieve a Kerberos ticket as the IdM admin.

[root@idmclient ~]# kinit admin

2. Add the /usr/sbin/reboot command to the IdM database of sudo commands:

```
[root@idmclient ~]# ipa sudocmd-add /usr/sbin/reboot
------
Added Sudo Command "/usr/sbin/reboot"
------
Sudo Command: /usr/sbin/reboot
```

3. Create a **sudo** rule named **idm_user_reboot**:

```
[root@idmclient ~]# ipa sudorule-add idm_user_reboot
-----
Added Sudo Rule "idm_user_reboot"
------
Rule name: idm_user_reboot
Enabled: TRUE
```

4. Add the /usr/sbin/reboot command to the idm_user_reboot rule:

```
[root@idmclient ~]# ipa sudorule-add-allow-command idm_user_reboot --sudocmds
'/usr/sbin/reboot'
Rule name: idm_user_reboot
Enabled: TRUE
Sudo Allow Commands: /usr/sbin/reboot
-------
Number of members added 1
```

5. Apply the **idm user reboot** rule to the IdM **idmclient** host:

6. Add the idm_user account to the idm_user_reboot rule:

```
[root@idmclient ~]# ipa sudorule-add-user idm_user_reboot --users idm_user
Rule name: idm_user_reboot
Enabled: TRUE
Users: idm_user
Hosts: idmclient.idm.example.com
Sudo Allow Commands: /usr/sbin/reboot
```

Number of members added 1



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification steps

- 1. Log in to the **idmclient** host as the **idm user** account.
- 2. Display which **sudo** rules the **idm_user** account is allowed to perform.

```
[idm_user@idmclient ~]$ sudo -I

Matching Defaults entries for idm_user on idmclient:
    !visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,
    env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR

LS_COLORS",
    env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
    env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT

LC_MESSAGES",
    env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER LC_TELEPHONE",
    env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS_XKB_CHARSET XAUTHORITY

KRB5CCNAME",
    secure_path=/sbin\:/bin\:/usr/sbin\:/usr/bin
```

3. Reboot the machine using **sudo**. Enter the password for **idm_user** when prompted:

User **idm user** may run the following commands on **idmclient**:

[idm_user@idmclient ~]\$ **sudo** /**usr**/**sbin**/**reboot** [sudo] password for idm_user:

18.3. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE IDM WEB UI

In Identity Management (IdM), you can grant **sudo** access for a specific command to an IdM user account on a specific IdM host. First, add a **sudo** command and then create a **sudo** rule for one or more commands.

Complete this procedure to create the **idm_user_reboot** sudo rule to grant the **idm_user** account the permission to run the /usr/sbin/reboot command on the **idmclient** machine.

Prerequisites

• You are logged in as IdM administrator.

(root) /usr/sbin/reboot


You have created a user account for idm_user in IdM and unlocked the account by creating a
password for the user. For details on adding a new IdM user using the command-line interface,
see Adding users using the command line.

• No local **idm_user** account is present on the **idmclient** host. The **idm_user** user is not listed in the local /etc/passwd file.

Procedure

- 1. Add the /usr/sbin/reboot command to the IdM database of sudo commands:
 - a. Navigate to Policy → Sudo → Sudo Commands.
 - b. Click **Add** in the upper right corner to open the **Add sudo command** dialog box.
 - c. Enter the command you want the user to be able to perform using **sudo**: /usr/sbin/reboot.

Figure 18.1. Adding IdM sudo command



- d. Click Add.
- 2. Use the new **sudo** command entry to create a sudo rule to allow **idm_user** to reboot the **idmclient** machine:
 - a. Navigate to Policy → Sudo → Sudo rules.
 - b. Click **Add** in the upper right corner to open the **Add sudo rule** dialog box.
 - c. Enter the name of the **sudo** rule: **idm_user_reboot**.
 - d. Click Add and Edit
 - e. Specify the user:
 - i. In the Who section, check the Specified Users and Groups radio button.
 - ii. In the **User category the rule applies to** subsection, click **Add** to open the **Add users** into sudo rule "idm_user_reboot" dialog box.
 - iii. In the Add users into sudo rule "idm_user_reboot" dialog box in the Available column, check the idm_user checkbox, and move it to the Prospective column.

- iv. Click Add.
- f. Specify the host:
 - i. In the Access this host section, check the Specified Hosts and Groups radio button.
 - ii. In the **Host category this rule applies to** subsection, click **Add** to open the **Add hosts** into sudo rule "idm_user_reboot" dialog box.
 - iii. In the Add hosts into sudo rule "idm_user_reboot" dialog box in the Available column, check the idmclient.idm.example.com checkbox, and move it to the Prospective column.
 - iv. Click Add.
- g. Specify the commands:
 - i. In the Command category the rule applies to subsection of the Run Commands section, check the Specified Commands and Groups radio button.
 - ii. In the **Sudo Allow Commands** subsection, click **Add** to open the **Add allow sudo commands into sudo rule "idm_user_reboot"** dialog box.
 - iii. In the Add allow sudo commands into sudo rule "idm_user_reboot" dialog box in the Available column, check the /usr/sbin/reboot checkbox, and move it to the Prospective column.
 - iv. Click Add to return to the idm_sudo_reboot page.

Adding IdM sudo rule

- + image::IdM-sudo-rule-WebUI.png[A screenshot of an overview of the sudo rule that was added. There is a "Who" section with a table of users the rule applies to. There is an "Access this host" section with a table of hosts that the rule applies to. There is a "Run Commands" section with a table of commands that pertain to the rule.]
- a. Click Save in the top left corner.

The new rule is enabled by default.



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification steps

- 1. Log in to idmclient as idm_user.
- 2. Reboot the machine using **sudo**. Enter the password for **idm_user** when prompted:

\$ sudo /usr/sbin/reboot [sudo] password for idm_user:

If the **sudo** rule is configured correctly, the machine reboots.

18.4. CREATING A SUDO RULE ON THE CLI THAT RUNS A COMMAND AS A SERVICE ACCOUNT ON AN IDM CLIENT

In IdM, you can configure a **sudo** rule with a *RunAs alias* to run a **sudo** command as another user or group. For example, you might have an IdM client that hosts a database application, and you need to run commands as the local service account that corresponds to that application.

Use this example to create a **sudo** rule on the command line called **run_third-party-app_report** to allow the **idm_user** account to run the **/opt/third-party-app/bin/report** command as the **thirdpartyapp** service account on the **idmclient** host.

Prerequisites

- You are logged in as IdM administrator.
- You have created a user account for idm_user in IdM and unlocked the account by creating a
 password for the user. For details on adding a new IdM user using the CLI, see Adding users
 using the command line.
- No local **idm_user** account is present on the **idmclient** host. The **idm_user** user is not listed in the local /etc/passwd file.
- You have a custom application named third-party-app installed on the idmclient host.
- The **report** command for the **third-party-app** application is installed in the **/opt/third-party-app/bin/report** directory.
- You have created a local service account named **thirdpartyapp** to execute commands for the **third-party-app** application.

Procedure

1. Retrieve a Kerberos ticket as the IdM admin.

[root@idmclient ~]# kinit admin

2. Add the /opt/third-party-app/bin/report command to the IdM database of sudo commands:

```
[root@idmclient ~]# ipa sudocmd-add /opt/third-party-app/bin/report
------

Added Sudo Command "/opt/third-party-app/bin/report"
------

Sudo Command: /opt/third-party-app/bin/report
```

3. Create a sudo rule named run third-party-app report:

```
[root@idmclient ~]# ipa sudorule-add run_third-party-app_report
------
Added Sudo Rule "run_third-party-app_report"
-------
Rule name: run_third-party-app_report
Enabled: TRUE
```

4. Use the **--users=**<**user**> option to specify the RunAs user for the **sudorule-add-runasuser** command:

[root@idmclient ~]# ipa sudorule-add-runasuser run_third-party-app_report -- users=thirdpartyapp

Rule name: run_third-party-app_report

Enabled: TRUE

RunAs External User: thirdpartyapp

Number of members added 1

The user (or group specified with the **--groups=*** option) can be external to IdM, such as a local service account or an Active Directory user. Do not add a % prefix for group names.

5. Add the /opt/third-party-app/bin/report command to the idm user reboot rule:

[root@idmclient ~]# ipa sudorule-add-allow-command run_third-party-app_report -- sudocmds '/opt/third-party-app/bin/report'

Rule name: run third-party-app report

Enabled: TRUE

Sudo Allow Commands: /opt/third-party-app/bin/report

RunAs External User: thirdpartyapp

Number of members added 1

6. Apply the run_third-party-app_report rule to the IdM idmclient host:

[root@idmclient ~]# ipa sudorule-add-host run_third-party-app_report --hosts idmclient.idm.example.com

Rule name: run_third-party-app_report

Enabled: TRUE

Hosts: idmclient.idm.example.com

Sudo Allow Commands: /opt/third-party-app/bin/report

RunAs External User: thirdpartyapp

Number of members added 1

7. Add the idm user account to the run third-party-app report rule:

[root@idmclient ~]# ipa sudorule-add-user run_third-party-app_report --users idm_user

Rule name: run_third-party-app_report

Enabled: TRUE Users: idm_user

Hosts: idmclient.idm.example.com

Sudo Allow Commands: /opt/third-party-app/bin/report

RunAs External User: thirdpartyapp

Number of members added 1



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification steps

- 1. Log in to the **idmclient** host as the **idm user** account.
- 2. Test the new sudo rule:
 - a. Display which **sudo** rules the **idm_user** account is allowed to perform.

```
[idm_user@idmclient ~]$ sudo -I

Matching Defaults entries for idm_user@idm.example.com on idmclient:

!visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,
    env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR

LS_COLORS",
    env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
    env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT

LC_MESSAGES",
    env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER

LC_TELEPHONE",
    env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS_XKB_CHARSET

XAUTHORITY KRB5CCNAME",
    secure_path=/sbin\:/bin\:/usr/sbin\:/usr/bin
```

User idm_user@idm.example.com may run the following commands on idmclient: (thirdpartyapp) /opt/third-party-app/bin/report

b. Run the **report** command as the **thirdpartyapp** service account.

[idm_user@idmclient ~]\$ **sudo -u** *thirdpartyapp* /opt/third-party-app/bin/report [sudo] password for idm_user@idm.example.com: Executing report...
Report successful.

18.5. CREATING A SUDO RULE IN THE IDM WEBUI THAT RUNS A COMMAND AS A SERVICE ACCOUNT ON AN IDM CLIENT

In IdM, you can configure a **sudo** rule with a *RunAs alias* to run a **sudo** command as another user or group. For example, you might have an IdM client that hosts a database application, and you need to run commands as the local service account that corresponds to that application.

Use this example to create a **sudo** rule in the IdM WebUI called **run_third-party-app_report** to allow the **idm_user** account to run the **/opt/third-party-app/bin/report** command as the **thirdpartyapp** service account on the **idmclient** host.


Prerequisites

- You are logged in as IdM administrator.
- You have created a user account for idm_user in IdM and unlocked the account by creating a
 password for the user. For details on adding a new IdM user using the CLI, see Adding users
 using the command line.


- No local **idm_user** account is present on the **idmclient** host. The **idm_user** user is not listed in the local /etc/passwd file.
- You have a custom application named **third-party-app** installed on the **idmclient** host.
- The **report** command for the **third-party-app** application is installed in the **/opt/third-party-app/bin/report** directory.
- You have created a local service account named thirdpartyapp to execute commands for the third-party-app application.

Procedure


- 1. Add the /opt/third-party-app/bin/report command to the IdM database of sudo commands:
 - a. Navigate to **Policy** → **Sudo** → **Sudo** Commands.
 - b. Click Add in the upper right corner to open the Add sudo command dialog box.
 - c. Enter the command: /opt/third-party-app/bin/report.




- d. Click Add.
- 2. Use the new **sudo** command entry to create the new **sudo** rule:
 - a. Navigate to Policy \rightarrow Sudo \rightarrow Sudo rules.
 - b. Click **Add** in the upper right corner to open the **Add sudo rule** dialog box.
 - c. Enter the name of the **sudo** rule: **run_third-party-app_report**.




- d. Click Add and Edit
- e. Specify the user:
 - i. In the **Who** section, check the **Specified Users and Groups** radio button.
 - ii. In the **User category the rule applies to** subsection, click **Add** to open the **Add users into sudo rule "run_third-party-app_report"** dialog box.
 - iii. In the Add users into sudo rule "run_third-party-app_report" dialog box in the Available column, check the idm_user checkbox, and move it to the Prospective column.



- iv. Click Add.
- f. Specify the host:
 - i. In the Access this host section, check the Specified Hosts and Groups radio button.
 - ii. In the **Host category this rule applies to** subsection, click **Add** to open the **Add hosts** into sudo rule "run_third-party-app_report" dialog box.
 - iii. In the Add hosts into sudo rule "run_third-party-app_report" dialog box in the Available column, check the idmclient.idm.example.com checkbox, and move it to the Prospective column.




- iv. Click Add.
- g. Specify the commands:
 - i. In the Command category the rule applies to subsection of the Run Commands section, check the Specified Commands and Groups radio button.
 - ii. In the **Sudo Allow Commands** subsection, click **Add** to open the **Add allow sudo commands into sudo rule "run_third-party-app_report"** dialog box.
 - iii. In the Add allow sudo commands into sudo rule "run_third-party-app_report" dialog box in the Available column, check the /opt/third-party-app/bin/report checkbox, and move it to the Prospective column.



- iv. Click Add to return to the run_third-party-app_report page.
- h. Specify the RunAs user:
 - i. In the As Whom section, check the Specified Users and Groups radio button.
 - ii. In the RunAs Users subsection, click Add to open the Add RunAs users into sudo rule "run_third-party-app_report" dialog box.


iii. In the Add RunAs users into sudo rule "run_third-party-app_report" dialog box, enter the **thirdpartyapp** service account in the **External** box and move it to the **Prospective** column.



- iv. Click Add to return to the run_third-party-app_report page.
- i. Click **Save** in the top left corner.

The new rule is enabled by default.

Figure 18.2. Details of the sudo rule





NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification steps

- 1. Log in to the **idmclient** host as the **idm_user** account.
- 2. Test the new sudo rule:
 - a. Display which **sudo** rules the **idm_user** account is allowed to perform.

[idm_user@idmclient ~]\$ **sudo -l**Matching Defaults entries for idm_user@idm.example.com on idmclient:
!visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,

```
env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR
LS_COLORS",
    env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
    env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT
LC_MESSAGES",
    env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER
LC_TELEPHONE",
    env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS _XKB_CHARSET
XAUTHORITY KRB5CCNAME",
    secure_path=/sbin\:/bin\:/usr/sbin\:/usr/bin
```

User idm_user@idm.example.com may run the following commands on idmclient: (thirdpartyapp) /opt/third-party-app/bin/report

b. Run the **report** command as the **thirdpartyapp** service account.

[idm_user@idmclient ~]\$ sudo -u thirdpartyapp /opt/third-party-app/bin/report [sudo] password for idm_user@idm.example.com:
Executing report...
Report successful.

18.6. ENABLING GSSAPI AUTHENTICATION FOR SUDO ON AN IDM CLIENT

The following procedure describes enabling Generic Security Service Application Program Interface (GSSAPI) authentication on an IdM client for the **sudo** and **sudo -i** commands via the **pam_sss_gss.so** PAM module. With this configuration, IdM users can authenticate to the **sudo** command with their Kerberos ticket.

Prerequisites

- You have created a **sudo** rule for an IdM user that applies to an IdM host. For this example, you have created the **idm_user_reboot sudo** rule to grant the **idm_user** account the permission to run the /usr/sbin/reboot command on the **idmclient** host.
- The **idmclient** host is running RHEL 8.4 or later.
- You need root privileges to modify the /etc/sssd/sssd.conf file and PAM files in the /etc/pam.d/ directory.

Procedure

- 1. Open the /etc/sssd/sssd.conf configuration file.
- 2. Add the following entry to the **[domain/**name] section.

```
[domain/<domain_name>]
pam_gssapi_services = sudo, sudo-i
```

- 3. Save and close the /etc/sssd/sssd.conf file.
- 4. Restart the SSSD service to load the configuration changes.

[root@idmclient ~]# systemctl restart sssd

_

- 5. Open the /etc/pam.d/sudo PAM configuration file.
- 6. Add the following entry as the first line of the **auth** section in the /etc/pam.d/sudo file.

#%PAM-1.0

auth sufficient pam_sss_gss.so
auth include system-auth
account include system-auth
password include system-auth
session include system-auth

- 7. Save and close the /etc/pam.d/sudo file.
- 8. Open the /etc/pam.d/sudo-i PAM configuration file.
- 9. Add the following entry as the first line of the **auth** section in the /etc/pam.d/sudo-i file.

#%PAM-1.0

auth sufficient pam_sss_gss.so
auth include sudo
account include sudo
password include sudo
session optional pam_keyinit.so force revoke
session include sudo

10. Save and close the /etc/pam.d/sudo-i file.

Verification steps

1. Log into the host as the **idm_user** account.

[root@idm-client ~]# **ssh -l** *idm_user@idm.example.com* **localhost** idm_user@idm.example.com's password:

2. Verify that you have a ticket-granting ticket as the idm_user account.

[idmuser@idmclient ~]\$ klist Ticket cache: KCM:1366201107

Default principal: idm_user@IDM.EXAMPLE.COM

Valid starting Expires Service principal 01/08/2021 09:11:48 01/08/2021 19:11:48 krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM renew until 01/15/2021 09:11:44

3. (Optional) If you do not have Kerberos credentials for the **idm_user** account, destroy your current Kerberos credentials and request the correct ones.

[idm_user@idmclient ~]\$ kdestroy -A

[idm_user@idmclient ~]\$ kinit idm_user@IDM.EXAMPLE.COM Password for idm_user@idm.example.com:

4. Reboot the machine using **sudo**, without specifying a password.

[idm_user@idmclient ~]\$ sudo /usr/sbin/reboot

Additional resources

- The GSSAPI entry in the IdM terminology listing
- Granting sudo access to an IdM user on an IdM client using IdM Web UI
- Granting sudo access to an IdM user on an IdM client using the CLI.
- pam sss gss (8) man page
- sssd.conf (5) man page

18.7. ENABLING GSSAPI AUTHENTICATION AND ENFORCING KERBEROS AUTHENTICATION INDICATORS FOR SUDO ON AN IDM CLIENT

The following procedure describes enabling Generic Security Service Application Program Interface (GSSAPI) authentication on an IdM client for the **sudo** and **sudo -i** commands via the **pam_sss_gss.so** PAM module. Additionally, only users who have logged in with a smart card will authenticate to those commands with their Kerberos ticket.



NOTE

You can use this procedure as a template to configure GSSAPI authentication with SSSD for other PAM-aware services, and further restrict access to only those users that have a specific authentication indicator attached to their Kerberos ticket.

Prerequisites

- You have created a **sudo** rule for an IdM user that applies to an IdM host. For this example, you
 have created the **idm_user_reboot sudo** rule to grant the **idm_user** account the permission to
 run the /usr/sbin/reboot command on the **idmclient** host.
- You have configured smart card authentication for the **idmclient** host.
- The **idmclient** host is running RHEL 8.4 or later.
- You need root privileges to modify the /etc/sssd/sssd.conf file and PAM files in the /etc/pam.d/ directory.

Procedure

- 1. Open the /etc/sssd/sssd.conf configuration file.
- 2. Add the following entries to the **[domain/**mailto:redomain_name) section.

```
[domain/<domain_name>]
pam_gssapi_services = sudo, sudo-i
pam_gssapi_indicators_map = sudo:pkinit, sudo-i:pkinit
```

- 3. Save and close the /etc/sssd/sssd.conf file.
- 4. Restart the SSSD service to load the configuration changes.

[root@idmclient ~]# systemctl restart sssd

- 5. Open the /etc/pam.d/sudo PAM configuration file.
- 6. Add the following entry as the first line of the **auth** section in the /etc/pam.d/sudo file.

#%PAM-1.0

auth sufficient pam_sss_gss.so
auth include system-auth
account include system-auth
password include system-auth
session include system-auth

- 7. Save and close the /etc/pam.d/sudo file.
- 8. Open the /etc/pam.d/sudo-i PAM configuration file.
- 9. Add the following entry as the first line of the auth section in the /etc/pam.d/sudo-i file.

#%PAM-1.0

auth sufficient pam_sss_gss.so
auth include sudo
account include sudo
password include sudo
session optional pam_keyinit.so force revoke
session include sudo

10. Save and close the /etc/pam.d/sudo-i file.

Verification steps

1. Log into the host as the **idm_user** account and authenticate with a smart card.

[root@idmclient ~]# ssh -l idm_user@idm.example.com localhost PIN for smart_card

2. Verify that you have a ticket-granting ticket as the smart card user.

[idm_user@idmclient ~]\$ klist
Ticket cache: KEYRING:persistent:1358900015:krb_cache_TObtNMd
Default principal: idm_user@IDM.EXAMPLE.COM

Valid starting Expires Service principal
02/15/2021 16:29:48 02/16/2021 02:29:48

krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM renew until 02/22/2021 16:29:44

3. Display which **sudo** rules the **idm user** account is allowed to perform.

[idm_user@idmclient ~]\$ sudo -I

Matching Defaults entries for idmuser on idmclient:

!visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin, env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR LS COLORS",

env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT
LC MESSAGES",

env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER LC_TELEPHONE", env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS _XKB_CHARSET XAUTHORITY KRB5CCNAME",

secure path=/sbin\:/bin\:/usr/sbin\:/usr/bin

User idm_user may run the following commands on idmclient: (root) /usr/sbin/reboot

4. Reboot the machine using **sudo**, without specifying a password.

[idm_user@idmclient ~]\$ sudo /usr/sbin/reboot

Additional resources

- The GSSAPI entry in the IdM terminology listing
- Configuring Identity Management for smart card authentication
- Kerberos authentication indicators
- Granting sudo access to an IdM user on an IdM client using IdM Web UI
- Granting sudo access to an IdM user on an IdM client using the CLI.
- pam_sss_gss (8) man page
- sssd.conf (5) man page

18.8. SSSD OPTIONS CONTROLLING GSSAPI AUTHENTICATION FOR PAM SERVICES

You can use the following options for the /etc/sssd/sssd.conf configuration file to adjust the GSSAPI configuration within the SSSD service.

pam_gssapi_services

GSSAPI authentication with SSSD is disabled by default. You can use this option to specify a comma-separated list of PAM services that are allowed to try GSSAPI authentication using the **pam_sss_gss.so** PAM module. To explicitly disable GSSAPI authentication, set this option to -.

pam_gssapi_indicators_map

This option only applies to Identity Management (IdM) domains. Use this option to list Kerberos authentication indicators that are required to grant PAM access to a service. Pairs must be in the format *PAM_service>*: <required_authentication_indicator>_.

Valid authentication indicators are:

- **otp** for two-factor authentication
- radius for RADIUS authentication

- **pkinit** for PKINIT, smart card, or certificate authentication
- hardened for hardened passwords

pam_gssapi_check_upn

This option is enabled and set to **true** by default. If this option is enabled, the SSSD service requires that the user name matches the Kerberos credentials. If **false**, the **pam_sss_gss.so** PAM module authenticates every user that is able to obtain the required service ticket.

Examples

The following options enable Kerberos authentication for the **sudo** and **sudo-i** services, requires that **sudo** users authenticated with a one-time password, and user names must match the Kerberos principal. Because these settings are in the **[pam]** section, they apply to all domains:

```
[pam]

pam_gssapi_services = sudo, sudo-i

pam_gssapi_indicators_map = sudo:otp

pam_gssapi_check_upn = true
```

You can also set these options in individual **[domain]** sections to overwrite any global values in the **[pam]** section. The following options apply different GSSAPI settings to each domain:

For the idm.example.com domain

- Enable GSSAPI authentication for the **sudo** and **sudo -i** services.
- Require certificate or smart card authentication authenticators for the **sudo** command.
- Require one-time password authentication authenticators for the **sudo -i** command.
- Enforce matching user names and Kerberos principals.

For the ad.example.com domain

- Enable GSSAPI authentication only for the **sudo** service.
- Do not enforce matching user names and principals.

```
[domain/idm.example.com]

pam_gssapi_services = sudo, sudo-i

pam_gssapi_indicators_map = sudo:pkinit, sudo-i:otp

pam_gssapi_check_upn = true
...

[domain/ad.example.com]

pam_gssapi_services = sudo

pam_gssapi_check_upn = false
...
```

Additional resources

• Kerberos authentication indicators

18.9. TROUBLESHOOTING GSSAPI AUTHENTICATION FOR SUDO

If you are unable to authenticate to the **sudo** service with a Kerberos ticket from IdM, use the following scenarios to troubleshoot your configuration.

Prerequisites

- You have enabled GSSAPI authentication for the **sudo** service. See Enabling GSSAPI authentication for sudo on an IdM client.
- You need root privileges to modify the /etc/sssd/sssd.conf file and PAM files in the /etc/pam.d/ directory.

Procedure

• If you see the following error, the Kerberos service might not able to resolve the correct realm for the service ticket based on the host name:

Server not found in Kerberos database

In this situation, add the hostname directly to **[domain_realm]** section in the /etc/krb5.conf Kerberos configuration file:

```
[idm-user@idm-client ~]$ cat /etc/krb5.conf
...

[domain_realm]
    .example.com = EXAMPLE.COM
    example.com = EXAMPLE.COM
    server.example.com = EXAMPLE.COM
```

If you see the following error, you do not have any Kerberos credentials:

No Kerberos credentials available

In this situation, retrieve Kerberos credentials with the **kinit** utility or authenticate with SSSD:

[idm-user@idm-client ~]\$ kinit idm-user@IDM.EXAMPLE.COM Password for idm-user@idm.example.com:

• If you see either of the following errors in the /var/log/sssd/sssd_pam.log log file, the Kerberos credentials do not match the username of the user currently logged in:

User with UPN [<UPN>] was not found.

UPN [<UPN>] does not match target user [<username>].

In this situation, verify that you authenticated with SSSD, or consider disabling the **pam_gssapi_check_upn** option in the **/etc/sssd/sssd.conf** file:

```
[idm-user@idm-client ~]$ cat /etc/sssd/sssd.conf ...
```

pam_gssapi_check_upn = false

- For additional troubleshooting, you can enable debugging output for the **pam_sss_gss.so** PAM module.
 - Add the **debug** option at the end of all **pam_sss_gss.so** entries in PAM files, such as /etc/pam.d/sudo and /etc/pam.d/sudo-i:

```
[root@idm-client ~]# cat /etc/pam.d/sudo
#%PAM-1.0
auth sufficient pam_sss_gss.so debug
auth include system-auth
account include system-auth
password include system-auth
session include system-auth
```

```
[root@idm-client ~]# cat /etc/pam.d/sudo-i
#%PAM-1.0
auth sufficient pam_sss_gss.so debug
auth include sudo
account include sudo
password include sudo
session optional pam_keyinit.so force revoke
session include sudo
```

• Try to authenticate with the **pam_sss_gss.so** module and review the console output. In this example, the user did not have any Kerberos credentials.

```
[idm-user@idm-client ~]$ sudo ls -l /etc/sssd/sssd.conf
pam sss gss: Initializing GSSAPI authentication with SSSD
pam_sss_gss: Switching euid from 0 to 1366201107
pam_sss_gss: Trying to establish security context
pam_sss_gss: SSSD User name: idm-user@idm.example.com
pam_sss_gss: User domain: idm.example.com
pam_sss_gss: User principal:
pam sss gss: Target name: host@idm.example.com
pam_sss_gss: Using ccache: KCM:
pam_sss_gss: Acquiring credentials, principal name will be derived
pam_sss_gss: Unable to read credentials from [KCM:] [maj:0xd0000, min:0x96c73ac3]
pam sss gss: GSSAPI: Unspecified GSS failure. Minor code may provide more
information
pam sss gss: GSSAPI: No credentials cache found
pam_sss_gss: Switching euid from 1366200907 to 0
pam sss gss: System error [5]: Input/output error
```

18.10. USING AN ANSIBLE PLAYBOOK TO ENSURE SUDO ACCESS FOR AN IDM USER ON AN IDM CLIENT

In Identity Management (IdM), you can ensure **sudo** access to a specific command is granted to an IdM user account on a specific IdM host.

Complete this procedure to ensure a **sudo** rule named **idm_user_reboot** exists. The rule grants **idm_user** the permission to run the /**usr/sbin/reboot** command on the **idmclient** machine.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller.
- You know the IdM administrator password.
- You have ensured the presence of a user account for idm_user in IdM and unlocked the
 account by creating a password for the user. For details on adding a new IdM user using the
 command-line interface, see Adding users using the command line.
- No local idm_user account exists on idmclient. The idm_user user is not listed in the /etc/passwd file on idmclient.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaservers** in it:

[ipaservers] server.idm.example.com

- 2. Add one or more **sudo** commands:
 - a. Create an ensure-reboot-sudocmd-is-present.yml Ansible playbook that ensures the presence of the /usr/sbin/reboot command in the IdM database of sudo commands. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansiblefreeipa/playbooks/sudocmd/ensure-sudocmd-is-present.yml file:

- name: Playbook to manage sudo command

hosts: ipaserver become: true

tasks:

Ensure sudo command is present

- ipasudocmd:

ipaadmin_password: MySecret123

name: /usr/sbin/reboot

state: present

b. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-reboot-sudocmd-is-present.yml

- 3. Create a **sudo** rule that references the commands:
 - a. Create an ensure-sudorule-for-idmuser-on-idmclient-is-present.yml Ansible playbook that uses the sudo command entry to ensure the presence of a sudo rule. The sudo rule allows idm_user to reboot the idmclient machine. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/sudorule/ensuresudorule-is-present.yml file:

 name: Tests hosts: ipaserver become: true

tasks:

Ensure a sudorule is present granting idm_user the permission to run /usr/sbin/reboot on idmclient

- ipasudorule:

ipaadmin_password: MySecret123

name: idm_user_reboot description: A test sudo rule. allow_sudocmd: /usr/sbin/reboot host: idmclient.idm.example.com

user: idm_user state: present

b. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-sudorule-for-idmuser-on-idmclient-is-present.yml

Verification steps

Test that the **sudo** rule whose presence you have ensured on the IdM server works on **idmclient** by verifying that **idm_user** can reboot **idmclient** using **sudo**. Note that it can take a few minutes for the changes made on the server to take effect on the client.

- 1. Log in to idmclient as idm_user.
- 2. Reboot the machine using **sudo**. Enter the password for **idm_user** when prompted:

\$ sudo /usr/sbin/reboot [sudo] password for idm_user:

If **sudo** is configured correctly, the machine reboots.

Additional materials

 For more details on how to apply **sudo** commands, command groups, and rules in IdM using an Ansible playbook including the descriptions of playbook variables, see the READMEsudocmd.md, README-sudocmdgroup.md, and README-sudorule.md Markdown files available in the /usr/share/doc/ansible-freeipa/ directory.

CHAPTER 19. ENSURING THE PRESENCE OF HOST-BASED ACCESS CONTROL RULES IN IDM USING ANSIBLE PLAYBOOKS

This chapter describes Identity Management (IdM) host-based access policies and how to define them using Ansible.

Ansible is an automation tool used to configure systems, deploy software, and perform rolling updates. It includes support for Identity Management (IdM).

19.1. HOST-BASED ACCESS CONTROL RULES IN IDM

Host-based access control (HBAC) rules define which users or user groups can access which hosts or host groups by using which services or services in a service group. As a system administrator, you can use HBAC rules to achieve the following goals:

- Limit access to a specified system in your domain to members of a specific user group.
- Allow only a specific service to be used to access systems in your domain.

By default, IdM is configured with a default HBAC rule named **allow_all**, which means universal access to every host for every user via every relevant service in the entire IdM domain.

You can fine-tune access to different hosts by replacing the default **allow_all** rule with your own set of HBAC rules. For centralized and simplified access control management, you can apply HBAC rules to user groups, host groups, or service groups instead of individual users, hosts, or services.

19.2. ENSURING THE PRESENCE OF AN HBAC RULE IN IDM USING AN ANSIBLE PLAYBOOK

This section describes how to ensure the presence of a host-based access control (HBAC) rule in Identity Management (IdM) using an Ansible playbook.

Prerequisites

- The ansible-freeipa package is installed on the Ansible controller.
- You know the IdM administrator password.
- The users and user groups you want to use for your HBAC rule exist in IdM. See Managing user accounts using Ansible playbooks and Ensuring the presence of IdM groups and group members using Ansible playbooks for details.
- The hosts and host groups to which you want to apply your HBAC rule exist in IdM. See
 Managing hosts using Ansible playbooks and Managing host groups using Ansible playbooks for
 details.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

[ipaserver] server.idm.example.com 2. Create your Ansible playbook file that defines the HBAC policy whose presence you want to ensure. To simplify this step, you can copy and modify the example in the /usr/share/doc/ansible-freeipa/playbooks/hbacrule/ensure-hbacrule-allhosts-present.yml file:

- name: Playbook to handle hbacrules

hosts: ipaserver become: true

tasks:

Ensure idm_user can access client.idm.example.com via the sshd service

- ipahbacrule:

ipaadmin_password: MySecret123

name: login user: idm_user

host: client.idm.example.com

hbacsvc: - sshd

state: present

3. Run the playbook:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file path_to_playbooks_directory/ensure-new-hbacrule-present.yml

Verification steps

- 1. Log in to the IdM Web UI as administrator.
- 2. Navigate to Policy → Host-Based-Access-Control → HBAC Test
- 3. In the **Who** tab, select idm_user.
- 4. In the Accessing tab, select client.idm.example.com.
- 5. In the Via service tab, select sshd.
- 6. In the Rules tab, select login.
- 7. In the **Run test** tab, click the **Run test** button. If you see ACCESS GRANTED, the HBAC rule is implemented successfully.

Additional resources

For more details about and examples of, configuring HBAC services, service groups, and rules using Ansible, see the README-hbacsvc.md, README-hbacsvcgroup.md, and README-hbacrule.md Markdown files. These files are available in the /usr/share/doc/ansible-freeipa directory. Also see the playbooks available in the relevant subdirectories of the /usr/share/doc/ansible-freeipa/playbooks directory.

CHAPTER 20. VAULTS IN IDM

This chapter describes vaults in Identity Management (IdM). It introduces the following topics:

- The concept of the vault.
- The different roles associated with a vault .
- The different types of vaults available in IdM based on the level of security and access control .
- The different types of vaults available in IdM based on ownership .
- The concept of vault containers.
- The basic commands for managing vaults in IdM .
- Installing the key recovery authority (KRA), which is a prerequisite for using vaults in IdM .

20.1. VAULTS AND THEIR BENEFITS

A vault is a useful feature for those Identity Management (IdM) users who want to keep all their sensitive data stored securely but conveniently in one place. This section explains the various types of vaults and their uses, and which vault you should choose based on your requirements.

A vault is a secure location in (IdM) for storing, retrieving, sharing, and recovering a secret. A secret is security-sensitive data, usually authentication credentials, that only a limited group of people or entities can access. For example, secrets include:

- passwords
- PINs
- private SSH keys

A vault is comparable to a password manager. Just like a password manager, a vault typically requires a user to generate and remember one primary password to unlock and access any information stored in the vault. However, a user can also decide to have a standard vault. A standard vault does not require the user to enter any password to access the secrets stored in the vault.



NOTE

The purpose of vaults in IdM is to store authentication credentials that allow you to authenticate to external, non-IdM-related services.

Other important characteristics of the IdM vaults are:

- Vaults are only accessible to the vault owner and those IdM users that the vault owner selects to be the vault members. In addition, the IdM administrator has access to the vault.
- If a user does not have sufficient privileges to create a vault, an IdM administrator can create the vault and set the user as its owner.
- Users and services can access the secrets stored in a vault from any machine enrolled in the IdM domain.

• One vault can only contain one secret, for example, one file. However, the file itself can contain multiple secrets such as passwords, keytabs or certificates.



NOTE

Vault is only available from the IdM command line (CLI), not from the IdM Web UI.

20.2. VAULT OWNERS, MEMBERS, AND ADMINISTRATORS

Identity Management (IdM) distinguishes the following vault user types:

Vault owner

A vault owner is a user or service with basic management privileges on the vault. For example, a vault owner can modify the properties of the vault or add new vault members.

Each vault must have at least one owner. A vault can also have multiple owners.

Vault member

A vault member is a user or service that can access a vault created by another user or service.

Vault administrator

Vault administrators have unrestricted access to all vaults and are allowed to perform all vault operations.



NOTE

Symmetric and asymmetric vaults are protected with a password or key and apply special access control rules (see Vault types). The administrator must meet these rules to:

- Access secrets in symmetric and asymmetric vaults.
- Change or reset the vault password or key.

A vault administrator is any user with the **Vault Administrators** privilege. In the context of the role-based access control (RBAC) in IdM, a privilege is a group of permissions that you can apply to a role.

Vault User

The vault user represents the user in whose container the vault is located. The **Vault user** information is displayed in the output of specific commands, such as **ipa vault-show**:

\$ ipa vault-show my_vault Vault name: my_vault Type: standard Owner users: user Vault user: user

For details on vault containers and user vaults, see Vault containers.

Additional resources

• Certain owner and member privileges depend on the type of the vault. See Standard, symmetric and asymmetric vaults for details.

20.3. STANDARD, SYMMETRIC, AND ASYMMETRIC VAULTS

Based on the level of security and access control, IdM classifies vaults into the following types:

Standard vaults

Vault owners and vault members can archive and retrieve the secrets without having to use a password or key.

Symmetric vaults

Secrets in the vault are protected with a symmetric key. Vault owners and members can archive and retrieve the secrets, but they must provide the vault password.

Asymmetric vaults

Secrets in the vault are protected with an asymmetric key. Users archive the secret using a public key and retrieve it using a private key. Vault members can only archive secrets, while vault owners can do both, archive and retrieve secrets.

20.4. USER, SERVICE, AND SHARED VAULTS

Based on ownership, IdM classifies vaults into several types. The table below contains information about each type, its owner and use.

Table 20.1. IdM vaults based on ownership

Туре	Description	Owner	Note
User vault	A private vault for a user	A single user	Any user can own one or more user vaults if allowed by IdM administrator
Service vault	A private vault for a service	A single service	Any service can own one or more user vaults if allowed by IdM administrator
Shared vault	A vault shared by multiple users and services	The vault administrator who created the vault	Users and services can own one or more user vaults if allowed by IdM administrator. The vault administrators other than the one that created the vault also have full access to the vault.

20.5. VAULT CONTAINERS

A vault container is a collection of vaults. The table below lists the default vault containers that Identity Management (IdM) provides.

Table 20.2. Default vault containers in IdM

Туре	Description	Purpose
User container	A private container for a user	Stores user vaults for a particular user
Service container	A private container for a service	Stores service vaults for a particular service

Туре	Description	Purpose
Shared container	A container for multiple users and services	Stores vaults that can be shared by multiple users or services

IdM creates user and service containers for each user or service automatically when the first private vault for the user or service is created. After the user or service is deleted, IdM removes the container and its contents.

20.6. BASIC IDM VAULT COMMANDS

This section describes basic commands you can use to manage Identity Management (IdM) vaults. The table below contains a list of **ipa vault-*** commands with the explanation of their purpose.



NOTE

Before running any **ipa vault-*** command, install the Key Recovery Authority (KRA) certificate system component on one or more of the servers in your IdM domain. For details, see Installing the Key Recovery Authority in IdM.

Table 20.3. Basic IdM vault commands with explanations

Command	Purpose	
ipa help vault	Displays conceptual information about IdM vaults and sample vault commands.	
ipa vault-addhelp, ipa vault-findhelp	Adding the help option to a specific ipa vault-* command displays the options and detailed help available for that command.	
ipa vault-show user_vaultuser idm_user	When accessing a vault as a vault member, you must specify the vault owner. If you do not specify the vault owner, IdM informs you that it did not find the vault: [admin@server ~]\$ ipa vault-show user_vault ipa: ERROR: user_vault: vault not found	
ipa vault-show shared_vault shared	When accessing a shared vault, you must specify that the vault you want to access is a shared vault. Otherwise, IdM informs you it did not find the vault: [admin@server ~]\$ ipa vault-show shared_vault ipa: ERROR: shared_vault: vault not found	

20.7. INSTALLING THE KEY RECOVERY AUTHORITY IN IDM

This section describes how you can enable vaults in Identity Management (IdM) by installing the Key Recovery Authority (KRA) Certificate System (CS) component.

Prerequisites

• You are logged in as IdM administrator.

• You are logged in as root on an IdM client.

Procedure

Install the KRA:

ipa-kra-install



IMPORTANT

You can install the first KRA of an IdM cluster on a hidden replica. However, installing additional KRAs requires temporarily activating the hidden replica before you install the KRA clone on a non-hidden replica. Then you can hide the originally hidden replica again.



NOTE

To make the vault service highly available, install the KRA on two IdM servers or more.

Additional resources

- For more information on how to activate an IdM replica and how to hide it, see Demoting or promoting hidden replicas.
- For more information on hidden replicas in IdM, see The hidden replica mode.

CHAPTER 21. USING ANSIBLE TO MANAGE IDM USER VAULTS: STORING AND RETRIEVING SECRETS

This chapter describes how to manage user vaults in Identity Management using the Ansible **vault** module. Specifically, it describes how a user can use Ansible playbooks to perform the following three consecutive actions:

- Create an user vault in IdM .
- Store a secret in the vault .
- Retrieve a secret from the vault .

The user can do the storing and the retrieving from two different IdM clients.

Prerequisites

 The Key Recovery Authority (KRA) Certificate System component has been installed on one or more of the servers in your IdM domain. For details, see Installing the Key Recovery Authority in IdM.

21.1. ENSURING THE PRESENCE OF A STANDARD USER VAULT IN IDM USING ANSIBLE

This section shows how an Identity Management (IdM) user can use an Ansible playbook to create a vault container with one or more private vaults to securely store sensitive information. In the example used in the procedure below, the <code>idm_user</code> user creates a vault of the standard type named <code>my_vault</code>. The standard vault type ensures that <code>idm_user</code> will not be required to authenticate when accessing the file. <code>idm_user</code> will be able to retrieve the file from any IdM client to which the user is logged in.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller, that is the host on which you execute the steps in the procedure.
- You know the password of idm user.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/vault directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/vault
- 2. Create an inventory file, for example inventory.file:
 - \$ touch inventory.file
- 3. Open **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

4. Make a copy of the ensure-standard-vault-is-present.yml Ansible playbook file. For example:

\$ cp ensure-standard-vault-is-present.yml ensure-standard-vault-is-present-copy.yml

- 5. Open the **ensure-standard-vault-is-present-copy.yml** file for editing.
- 6. Adapt the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_principal** variable to **idm_user**.
 - Set the **ipaadmin_password** variable to the password of **idm_user**.
 - Set the **user** variable to **idm_user**.
 - Set the **name** variable to **my_vault**.
 - Set the vault_type variable to standard.
 This the modified Ansible playbook file for the current example:

name: Tests
 hosts: ipaserver
 become: true
 gather_facts: false

tasks:

- ipavault:

ipaadmin_principal: idm_user

ipaadmin_password: idm_user_password

user: idm_user name: my_vault vault_type: standard

- 7. Save the file.
- 8. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-standard-vault-is-present-copy.yml

21.2. ARCHIVING A SECRET IN A STANDARD USER VAULT IN IDM USING ANSIBLE

This section shows how an Identity Management (IdM) user can use an Ansible playbook to store sensitive information in a personal vault. In the example used, the **idm_user** user archives a file with sensitive information named **password.txt** in a vault named **my_vault**.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller, that is the host on which you execute the steps in the procedure.
- You know the password of idm_user.
- idm_user is the owner, or at least a member user of my_vault.

• You have access to password.txt, the secret that you want to archive in my_vault.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/vault directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/vault

2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure server.idm.example.com, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **data-archive-in-symmetric-vault.yml** Ansible playbook file but replace "symmetric" by "standard". For example:

\$ cp data-archive-in-symmetric-vault.yml data-archive-in-standard-vault-copy.yml

- 4. Open the data-archive-in-standard-vault-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_principal** variable to **idm_user**.
 - Set the **ipaadmin_password** variable to the password of **idm_user**.
 - Set the **user** variable to **idm_user**.
 - Set the **name** variable to **my_vault**.
 - Set the **in** variable to the full path to the file with sensitive information.
 - Set the action variable to member.
 This the modified Ansible playbook file for the current example:

name: Tests
 hosts: ipaserver
 become: true
 gather_facts: false

tasks:

- ipavault:

ipaadmin_principal: idm_user

ipaadmin_password: idm_user_password

user: idm_user name: my_vault

in: /usr/share/doc/ansible-freeipa/playbooks/vault/password.txt

action: member

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file data-archive-in-standard-vault-copy.yml

21.3. RETRIEVING A SECRET FROM A STANDARD USER VAULT IN IDM USING ANSIBLE

This section shows how an Identity Management (IdM) user can use an Ansible playbook to retrieve a secret from the user personal vault. In the example used in the procedure below, the <code>idm_user</code> user retrieves a file with sensitive data from a vault of the standard type named <code>my_vault</code> onto an IdM client named <code>hostO1</code>. <code>idm_user</code> does not have to authenticate when accessing the file. <code>idm_user</code> can use Ansible to retrieve the file from any IdM client on which Ansible is installed.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the password of idm_user.
- idm_user is the owner of my_vault.
- idm_user has stored a secret in my_vault.
- Ansible can write into the directory on the IdM host into which you want to retrieve the secret.
- idm_user can read from the directory on the IdM host into which you want to retrieve the secret.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/vault directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/vault
- 2. Open your inventory file and mention, in a clearly defined section, the IdM client onto which you want to retrieve the secret. For example, to instruct Ansible to retrieve the secret onto host01.idm.example.com, enter:

[ipahost] host01.idm.example.com

- 3. Make a copy of the **retrive-data-symmetric-vault.yml** Ansible playbook file. Replace "symmetric" with "standard". For example:
 - \$ cp retrive-data-symmetric-vault.yml retrieve-data-standard-vault.yml-copy.yml
- 4. Open the **retrieve-data-standard-vault.yml-copy.yml** file for editing.
- 5. Adapt the file by setting the **hosts** variable to **ipahost**.
- 6. Adapt the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin principal** variable to **idm_user**.
 - Set the **ipaadmin_password** variable to the password of **idm_user**.

- Set the **user** variable to **idm_user**.
- Set the **name** variable to **my_vault**.
- Set the **out** variable to the full path of the file into which you want to export the secret.
- Set the **state** variable to **retrieved**.
 This the modified Ansible playbook file for the current example:

name: Tests
 hosts: ipahost
 become: true
 gather_facts: false

tasks:

- ipavault:

ipaadmin_principal: idm_user

ipaadmin_password: idm_user_password

user: idm_user name: my_vault

out: /tmp/password_exported.txt

state: retrieved

- 7. Save the file.
- 8. Run the playbook:

\$ ansible-playbook -v -i inventory.file retrieve-data-standard-vault.yml-copy.yml

Verification steps

1. SSH to host01 as user01:

\$ ssh user01@host01.idm.example.com

2. View the file specified by the **out** variable in the Ansible playbook file:

\$ vim /tmp/password_exported.txt

You can now see the exported secret.

For more information about using Ansible to manage IdM vaults and user secrets and about playbook variables, see the README-vault.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory and the sample playbooks available in the /usr/share/doc/ansible-freeipa/playbooks/vault/ directory.

CHAPTER 22. USING ANSIBLE TO MANAGE IDM SERVICE VAULTS: STORING AND RETRIEVING SECRETS

This section shows how an administrator can use the **ansible-freeipa vault** module to securely store a service secret in a centralized location.

The vault used in the example is asymmetric, which means that in order to use it, the administrator needs to perform the following steps:

- 1. Generate a private key using, for example, the **openssI** utility.
- 2. Generate a public key based on the private key.

The service secret is encrypted with the public key when an administrator archives it into the vault. Afterwards, a service instance hosted on a specific machine in the domain retrieves the secret using the private key. Only the service and the administrator are allowed to access the secret.

If the secret is compromised, the administrator can replace it in the service vault and then redistribute it to those individual service instances that have not been compromised.

Prerequisites

 The Key Recovery Authority (KRA) Certificate System component has been installed on one or more of the servers in your IdM domain. For details, see Installing the Key Recovery Authority in IdM.

This section includes these procedures:

- Ensuring the presence of an asymmetric service vault in IdM using Ansible
- Storing an IdM service secret in an asymmetric vault using Ansible
- Retrieving a service secret for an IdM service using Ansible
- Changing an IdM service vault secret when compromised using Ansible

In the procedures:

- admin is the administrator who manages the service password.
- private-key-to-an-externally-signed-certificate.pem is the file containing the service secret, in this case a private key to an externally signed certificate. Do not confuse this private key with the private key used to retrieve the secret from the vault.
- **secret_vault** is the vault created to store the service secret.
- HTTP/webserver1.idm.example.com is the service that is the owner of the vault.
- HTTP/webserver2.idm.example.com and HTTP/webserver3.idm.example.com are the vault member services.
- **service-public.pem** is the service public key used to encrypt the password stored in **password_vault**.
- service-private.pem is the service private key used to decrypt the password stored in secret_vault.

22.1. ENSURING THE PRESENCE OF AN ASYMMETRIC SERVICE VAULT IN IDM USING ANSIBLE

This section shows how an Identity Management (IdM) administrator can use an Ansible playbook to create a service vault container with one or more private vaults to securely store sensitive information. In the example used in the procedure below, the administrator creates an asymmetric vault named secret_vault. This ensures that the vault members have to authenticate using a private key in order to retrieve the secret in the vault. The vault members will be able to retrieve the file from any IdM client.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the **IdM administrator** password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/vault directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/vault
- 2. Obtain the public key of the service instance. For example, using the **openssI** utility:
 - a. Generate the **service-private.pem** private key.

```
$ openssl genrsa -out service-private.pem 2048
Generating RSA private key, 2048 bit long modulus
.+++
e is 65537 (0x10001)
```

b. Generate the **service-public.pem** public key based on the private key.

 $\$ openssI rsa -in service-private.pem -out service-public.pem -pubout writing RSA key

3. Optional: Create an inventory file if it does not exist, for example inventory.file:

\$ touch inventory.file

4. Open your inventory file and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

5. Make a copy of the **ensure-asymmetric-vault-is-present.yml** Ansible playbook file. For example:

\$ cp ensure-asymmetric-vault-is-present.yml ensure-asymmetric-service-vault-is-present-copy.yml

- 6. Open the ensure-asymmetric-vault-is-present-copy.yml file for editing.
- 7. Add a task that copies the **service-public.pem** public key from the Ansible controller to the **server.idm.example.com** server.
- 8. Modify the rest of the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin password** variable to the IdM administrator password.
 - Define the name of the vault using the name variable, for example secret_vault.
 - Set the **vault_type** variable to **asymmetric**.
 - Set the **service** variable to the principal of the service that owns the vault, for example **HTTP/webserver1.idm.example.com**.
 - Set the public_key_file to the location of your public key.
 This is the modified Ansible playbook file for the current example:

name: Tests
 hosts: ipaserver
 become: true
 gather_facts: false

tasks:

- name: Copy public key to ipaserver.

copy:

src: /path/to/service-public.pem

dest: /usr/share/doc/ansible-freeipa/playbooks/vault/service-public.pem

mode: 0600

- name: Add data to vault, from a LOCAL file.

ipavault:

ipaadmin password: Secret123

name: secret_vault vault_type: asymmetric

service: HTTP/webserver1.idm.example.com

public_key_file: /usr/share/doc/ansible-freeipa/playbooks/vault/service-public.pem

- 9. Save the file.
- 10. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-asymmetric-service-vault-is-present-copy.yml

22.2. ADDING MEMBER SERVICES TO AN ASYMMETRIC VAULT USING ANSIBLE

This section shows how an Identity Management (IdM) administrator can use an Ansible playbook to add member services to a service vault so that they can all retrieve the secret stored in the vault. In the example used in the procedure below, the IdM administrator adds the

HTTP/webserver2.idm.example.com and HTTP/webserver3.idm.example.com service principals to the secret_vault vault that is owned by HTTP/webserver1.idm.example.com.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the **IdM administrator** password.
- You have created an asymmetric vault to store the service secret.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/vault directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/vault
- 2. Optional: Create an inventory file if it does not exist, for example inventory.file:
 - \$ touch inventory.file
- 3. Open your inventory file and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 4. Make a copy of the data-archive-in-asymmetric-vault.yml Ansible playbook file. For example:
 - \$ cp data-archive-in-asymmetric-vault.yml add-services-to-an-asymmetric-vault.yml
- 5. Open the data-archive-in-asymmetric-vault-copy.yml file for editing.
- 6. Modify the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_password** variable to the IdM administrator password.
 - Set the **name** variable to the name of the vault, for example **secret_vault**.
 - Set the **service** variable to the service owner of the vault, for example **HTTP/webserver1.idm.example.com**.
 - Define the services that you want to have access to the vault secret using the services variable.
 - Set the action variable to member.
 This the modified Ansible playbook file for the current example:

name: Tests
 hosts: ipaserver
 become: true
 gather_facts: false

tasks:

ipavault:

ipaadmin_password: Secret123

name: secret_vault

service: HTTP/webserver1.idm.example.com

services:

- HTTP/webserver2.idm.example.com- HTTP/webserver3.idm.example.com
- action: member
- 7. Save the file.
- 8. Run the playbook:

\$ ansible-playbook -v -i inventory.file add-services-to-an-asymmetric-vault.yml

22.3. STORING AN IDM SERVICE SECRET IN AN ASYMMETRIC VAULT USING ANSIBLE

This section shows how an Identity Management (IdM) administrator can use an Ansible playbook to store a secret in a service vault so that it can be later retrieved by the service. In the example used in the procedure below, the administrator stores a **PEM** file with the secret in an asymmetric vault named **secret_vault**. This ensures that the service will have to authenticate using a private key in order to retrieve the secret from the vault. The vault members will be able to retrieve the file from any IdM client.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.
- You have created an asymmetric vault to store the service secret.
- The secret is stored locally on the Ansible controller, for example in the /usr/share/doc/ansible-freeipa/playbooks/vault/private-key-to-an-externally-signed-certificate.pem file.

Procedure

- Navigate to the /usr/share/doc/ansible-freeipa/playbooks/vault directory:
 - $\$\ cd\ /usr/share/doc/ansible-freeipa/playbooks/vault$
- 2. Optional: Create an inventory file if it does not exist, for example inventory.file:
 - \$ touch inventory.file
- 3. Open your inventory file and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:
 - [ipaserver] server.idm.example.com
- 4. Make a copy of the data-archive-in-asymmetric-vault.yml Ansible playbook file. For example:

\$ cp data-archive-in-asymmetric-vault.yml data-archive-in-asymmetric-vault-copy.yml

- 5. Open the data-archive-in-asymmetric-vault-copy.yml file for editing.
- 6. Modify the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_password** variable to the IdM administrator password.
 - Set the **name** variable to the name of the vault, for example **secret_vault**.
 - Set the **service** variable to the service owner of the vault, for example HTTP/webserver1.idm.example.com.
 - Set the in variable to "{{ lookup('file', 'private-key-to-an-externally-signedcertificate.pem') | b64encode }}". This ensures that Ansible retrieves the file with the private key from the working directory on the Ansible controller rather than from the IdM server.
 - Set the **action** variable to **member**. This the modified Ansible playbook file for the current example:

- name: Tests hosts: ipaserver become: true gather_facts: false

tasks:

ipavault:

ipaadmin_password: Secret123

name: secret vault

service: HTTP/webserver1.idm.example.com

in: "{{ lookup('file', 'private-key-to-an-externally-signed-certificate.pem') | b64encode }}"

action: member

- 7. Save the file.
- 8. Run the playbook:

\$ ansible-playbook -v -i inventory.file data-archive-in-asymmetric-vault-copy.yml

22.4. RETRIEVING A SERVICE SECRET FOR AN IDM SERVICE USING **ANSIBLE**

This section shows how an Identity Management (IdM) user can use an Ansible playbook to retrieve a secret from a service vault on behalf of the service. In the example used in the procedure below, running the playbook retrieves a PEM file with the secret from an asymmetric vault named secret_vault, and stores it in the specified location on all the hosts listed in the Ansible inventory file as ipaservers.

The services authenticate to IdM using keytabs, and they authenticate to the vault using a private key. You can retrieve the file on behalf of the service from any IdM client on which ansible-freeipa is installed.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.
- You have created an asymmetric vault to store the service secret.
- You have archived the secret in the vault.
- You have stored the private key used to retrieve the service vault secret in the location specified by the **private_key_file** variable on the Ansible controller.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/vault directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/vault
- 2. Optional: Create an inventory file if it does not exist, for example inventory.file:
 - \$ touch inventory.file
- 3. Open your inventory file and define the following hosts:
 - Define your IdM server in the [ipaserver] section.
 - Define the hosts onto which you want to retrieve the secret in the **[webservers]** section. For example, to instruct Ansible to retrieve the secret to **webserver1.idm.example.com**, **webserver2.idm.example.com**, and **webserver3.idm.example.com**, enter:

[ipaserver] server.idm.example.com

[webservers] webserver1.idm.example.com webserver2.idm.example.com webserver3.idm.example.com

- 4. Make a copy of the retrieve-data-asymmetric-vault.yml Ansible playbook file. For example:
 - \$ cp retrieve-data-asymmetric-vault.yml retrieve-data-asymmetric-vault-copy.yml
- 5. Open the **retrieve-data-asymmetric-vault-copy.yml** file for editing.
- 6. Modify the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **name** variable to the name of the vault, for example **secret_vault**.
 - Set the **service** variable to the service owner of the vault, for example **HTTP/webserver1.idm.example.com**.
 - Set the private_key_file variable to the location of the private key used to retrieve the service vault secret.

- Set the **out** variable to the location on the IdM server where you want to retrieve the **private-key-to-an-externally-signed-certificate.pem** secret, for example the current working directory.
- Set the action variable to member.
 This the modified Ansible playbook file for the current example:

-name: Retrieve data from vault
hosts: ipaserver
become: no
gather_facts: false

tasks:
- name: Retrieve data from the service vault
ipavault:
 ipaadmin_password: Secret123
 name: secret_vault
 service: HTTP/webserver1.idm.example.com
 vault_type: asymmetric
 private_key: "{{ lookup('file', 'service-private.pem') | b64encode }}"
 out: private-key-to-an-externally-signed-certificate.pem
 state: retrieved

7. Add a section to the playbook that retrieves the data file from the IdM server to the Ansible controller:

--- name: Retrieve data from vault
hosts: ipaserver
become: no
gather_facts: false
tasks:
[...]
- name: Retrieve data file
fetch:
 src: private-key-to-an-externally-signed-certificate.pem
 dest: ./
flat: yes
 mode: 0600

8. Add a section to the playbook that transfers the retrieved **private-key-to-an-externally-signed-certificate.pem** file from the Ansible controller on to the webservers listed in the **webservers** section of the inventory file:

--- name: Send data file to webservers become: no gather_facts: no hosts: webservers tasks:
- name: Send data to webservers copy:

src: private-key-to-an-externally-signed-certificate.pem

dest: /etc/pki/tls/private/httpd.key

mode: 0444

- 9. Save the file.
- 10. Run the playbook:

\$ ansible-playbook -v -i inventory.file retrieve-data-asymmetric-vault-copy.yml

22.5. CHANGING AN IDM SERVICE VAULT SECRET WHEN COMPROMISED USING ANSIBLE

This section shows how an Identity Management (IdM) administrator can reuse an Ansible playbook to change the secret stored in a service vault when a service instance has been compromised. The scenario in the following example assumes that on **webserver3.idm.example.com**, the retrieved secret has been compromised, but not the key to the asymmetric vault storing the secret. In the example, the administrator reuses the Ansible playbooks used when storing a secret in an asymmetric vault and retrieving a secret from the asymmetric vault onto IdM hosts. At the start of the procedure, the IdM administrator stores a new **PEM** file with a new secret in the asymmetric vault, adapts the inventory file so as not to retrieve the new secret on to the compromised web server, **webserver3.idm.example.com**, and then re-runs the two procedures.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the **IdM administrator** password.
- You have created an asymmetric vault to store the service secret.
- You have generated a new httpd key for the web services running on IdM hosts to replace the compromised old key.
- The new httpd key is stored locally on the Ansible controller, for example in the /usr/share/doc/ansible-freeipa/playbooks/vault/private-key-to-an-externally-signed-certificate.pem file.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/vault directory:
 - $\$\ cd\ /usr/share/doc/ansible-freeipa/playbooks/vault$
- 2. Open your inventory file and make sure that the following hosts are defined correctly:
 - The IdM server in the [ipaserver] section.
 - The hosts onto which you want to retrieve the secret in the **[webservers]** section. For example, to instruct Ansible to retrieve the secret to **webserver1.idm.example.com** and **webserver2.idm.example.com**, enter:

[ipaserver]

server.idm.example.com

[webservers] webserver1.idm.example.com webserver2.idm.example.com



IMPORTANT

Make sure that the list does not contain the compromised webserver, in the current example webserver3.idm.example.com.

- 3. Open the data-archive-in-asymmetric-vault-copy.yml file for editing.
- 4. Modify the file by setting the following variables in the **ipavault** task section:
 - Set the **ipaadmin_password** variable to the IdM administrator password.
 - Set the name variable to the name of the vault, for example secret_vault.
 - Set the **service** variable to the service owner of the vault, for example HTTP/webserver.idm.example.com.
 - Set the in variable to "{{ lookup('file', 'new-private-key-to-an-externally-signed-certificate.pem') | b64encode }}". This ensures that Ansible retrieves the file with the private key from the working directory on the Ansible controller rather than from the IdM server.
 - Set the action variable to member.
 This the modified Ansible playbook file for the current example:

```
-name: Tests
hosts: ipaserver
become: true
gather_facts: false

tasks:
- ipavault:
    ipaadmin_password: Secret123
    name: secret_vault
    service: HTTP/webserver.idm.example.com
    in: "{{ lookup('file', 'new-private-key-to-an-externally-signed-certificate.pem') | b64encode
}}"
    action: member
```

- 5. Save the file.
- 6. Run the playbook:

\$ ansible-playbook -v -i inventory.file data-archive-in-asymmetric-vault-copy.yml

- 7. Open the retrieve-data-asymmetric-vault-copy.yml file for editing.
- 8. Modify the file by setting the following variables in the **ipavault** task section:

- Set the **ipaadmin_password** variable to your IdM administrator password.
- Set the **name** variable to the name of the vault, for example **secret_vault**.
- Set the **service** variable to the service owner of the vault, for example HTTP/webserver1.idm.example.com.
- Set the private_key_file variable to the location of the private key used to retrieve the service vault secret.
- Set the **out** variable to the location on the IdM server where you want to retrieve the **new-private-key-to-an-externally-signed-certificate.pem** secret, for example the current working directory.
- Set the action variable to member.
 This the modified Ansible playbook file for the current example:

-name: Retrieve data from vault
hosts: ipaserver
become: no
gather_facts: false

tasks:
-name: Retrieve data from the service vault
ipavault:
ipaadmin_password: Secret123
name: secret_vault
service: HTTP/webserver1.idm.example.com
vault_type: asymmetric
private_key: "{{ lookup('file', 'service-private.pem') | b64encode }}"
out: new-private-key-to-an-externally-signed-certificate.pem
state: retrieved

9. Add a section to the playbook that retrieves the data file from the IdM server to the Ansible controller:

--- name: Retrieve data from vault
hosts: ipaserver
become: yes
gather_facts: false
tasks:
[...]
- name: Retrieve data file
fetch:
 src: new-private-key-to-an-externally-signed-certificate.pem
 dest: ./
 flat: yes
 mode: 0600

10. Add a section to the playbook that transfers the retrieved **new-private-key-to-an-externally-signed-certificate.pem** file from the Ansible controller on to the webservers listed in the **webservers** section of the inventory file:

- name: Send data file to webservers

become: yes gather_facts: no hosts: webservers

tasks:

- name: Send data to webservers

copv:

src: new-private-key-to-an-externally-signed-certificate.pem

dest: /etc/pki/tls/private/httpd.key

mode: 0444

- 11. Save the file.
- 12. Run the playbook:

\$ ansible-playbook -v -i inventory.file retrieve-data-asymmetric-vault-copy.yml

Additional resources

For more information about using Ansible to manage IdM vaults and service secrets and about playbook variables, see the README-vault.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory and the sample playbooks available in the /usr/share/doc/ansible-freeipa/playbooks/vault/ directory.

CHAPTER 23. ENSURING THE PRESENCE AND ABSENCE OF SERVICES IN IDM USING ANSIBLE

With the Ansible **service** module, Identity Management (IdM) administrator can ensure that specific services that are not native to IdM are present or absent in IdM. For example, you can use the **service** module to:

- Check that a manually installed service is present on an IdM client and automatically install that service if it is absent. For details, see:
 - Ensuring the presence of an HTTP service in IdM on an IdM client.
 - Ensuring the presence of an HTTP service in IdM on a non-IdM client.
 - Ensuring the presence of an HTTP service on an IdM client without DNS.
- Check that a service enrolled in IdM has a certificate attached and automatically install that certificate if it is absent. For details, see:
- Ensuring the presence of an externally-signed certificate in an IdM service entry.
- Allow IdM users and hosts to retrieve and create the service keytab. For details, see:
 - Allowing IdM users, groups, hosts, or host groups to create a keytab of a service.
 - Allowing IdM users, groups, hosts, or host groups to retrieve a keytab of a service.
- Allow IdM users and hosts to add a Kerberos alias to a service. For details, see:
 - Ensuring the presence of a Kerberos principal alias for a service.
- Check that a service is not present on an IdM client and automatically remove that service if it is present. For details, see:
 - Ensuring the absence of an HTTP service in IdM on an IdM client.

23.1. ENSURING THE PRESENCE OF AN HTTP SERVICE IN IDM USING AN ANSIBLE PLAYBOOK

This section describes how to ensure the presence of an HTTP server in IdM using an Ansible playbook.

Prerequisites

- The system to host the HTTP service is an IdM client.
- You have the IdM administrator password.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-copy.yml

4. Open the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-copy.yml Ansible playbook file for editing:

- name: Playbook to manage IPA service.

hosts: ipaserver become: true gather_facts: false

tasks:

Ensure service is present

- ipaservice:

ipaadmin_password: Secret123 name: HTTP/client.idm.example.com

- 5. Adapt the file:
 - Change the IdM administrator password defined by the **ipaadmin_password** variable.
 - Change the name of your IdM client on which the HTTP service is running, as defined by the name variable of the ipaservice task.
- 6. Save and exit the file.
- 7. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-copy.yml

Verification steps

- 1. Log into the IdM Web UI as IdM administrator.
- 2. Navigate to **Identity** → **Services**.

If HTTP/client.idm.example.com@IDM.EXAMPLE.COM is listed in the Services list, the Ansible playbook has been successfully added to IdM.

Additional resources

 You can secure the communication between the HTTP server and browser clients by adding TLS encryption to an Apache HTTP Server. You can request a certificate for the HTTP service from an IdM certificate authority. For more
information, see the procedure described in Obtaining an IdM certificate for a service using
certmonger.

23.2. ENSURING THE PRESENCE OF AN HTTP SERVICE IN IDM ON A NON-IDM CLIENT USING AN ANSIBLE PLAYBOOK

This section describes how to ensure the presence of an HTTP server in IdM on a host that is not an IdM client using an Ansible playbook. By adding the HTTP server to IdM you are also adding the host to IdM.

Prerequisites

- You have installed an HTTP service on your host.
- The host on which you have set up HTTP is not an IdM client. Otherwise, follow the steps in Ensuring the presence of an HTTP service in IdM using an Ansible playbook.
- You have the IdM administrator password.
- The DNS A record or the AAAA record if IPv6 is used for the host is available.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-without-host-check.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-without-host-check.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-without-host-check-copy.yml

4. Open the copied file, /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-without-host-check-copy.yml, for editing. Locate the ipaadmin_password and name variables in the ipaservice task:

- name: Playbook to manage IPA service.

hosts: ipaserver become: true gather_facts: false

tasks:

Ensure service is present

- ipaservice:

ipaadmin_password: MyPassword123 name: HTTP/www2.example.com

skip host check: yes

- 5. Adapt the file:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **name** variable to the name of the host on which the HTTP service is running.
- 6. Save and exit the file.
- 7. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-without-host-check-copy.yml

Verification steps

- 1. Log into the IdM Web UI as IdM administrator.
- 2. Navigate to **Identity** → **Services**.

You can now see HTTP/client.idm.example.com@IDM.EXAMPLE.COM listed in the Services list.

Additional resources

• You can secure the communication between the HTTP server and the browser clients by adding TLS encryption to an Apache HTTP Server.

23.3. ENSURING THE PRESENCE OF AN HTTP SERVICE ON AN IDM CLIENT WITHOUT DNS USING AN ANSIBLE PLAYBOOK

This section describes how to ensure the presence of an HTTP server running on an IdM client that has no DNS entry using an Ansible playbook. The scenario implied is that the IdM host has no DNS A entry available – or no DNS AAAA entry if IPv6 is used instead of IPv4.

Prerequisites

- The system to host the HTTP service is enrolled in IdM.
- The DNS A or DNS AAAA record for the host may not exist. Otherwise, if the DNS record for the host does exist, follow the procedure in Ensuring the presence of an HTTP service in IdM using an Ansible playbook.
- You have the IdM administrator password.

Procedure

1. Create an inventory file, for example **inventory.file**:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-with-host-force.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-with-host-force.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-with-host-force-copy.yml

4. Open the copied file, /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-with-host-force-copy.yml, for editing. Locate the ipaadmin_password and name variables in the ipaservice task:

- name: Playbook to manage IPA service.

hosts: ipaserver become: true gather_facts: false

tasks:

Ensure service is present

- ipaservice:

ipaadmin_password: MyPassword123

name: HTTP/ihavenodns.info

force: yes

- 5. Adapt the file:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **name** variable to the name of the host on which the HTTP service is running.
- 6. Save and exit the file.
- 7. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-is-present-with-host-force-copy.yml

Verification steps

- 1. Log into the IdM Web UI as IdM administrator.
- 2. Navigate to **Identity** → **Services**.

You can now see HTTP/client.idm.example.com@IDM.EXAMPLE.COM listed in the Services list.

Additional resources

• You can secure the communication between the Apache HTTP server and browser clients by adding TLS encryption to the Apache HTTP Server.

23.4. ENSURING THE PRESENCE OF AN EXTERNALLY SIGNED CERTIFICATE IN AN IDM SERVICE ENTRY USING AN ANSIBLE PLAYBOOK

This section describes how to use the **ansible-freeipa service** module to ensure that a certificate issued by an external certificate authority (CA) is attached to the IdM entry of the HTTP service. Having the certificate of an HTTP service signed by an external CA rather than the IdM CA is particularly useful if your IdM CA uses a self-signed certificate.

Prerequisites

- You have installed an HTTP service on your host.
- You have enrolled the HTTP service into IdM.
- You have the IdM administrator password.
- You have an externally signed certificate whose Subject corresponds to the principal of the HTTP service.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-certificate-present.yml file, for example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-member-certificate-present.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-member-certificate-present-copy.yml

- 4. Optional: If the certificate is in the Privacy Enhanced Mail (PEM) format, convert the certificate to the Distinguished Encoding Rules (DER) format for easier handling through the command-line interface (CLI):
 - \$ openssl x509 -outform der -in cert1.pem -out cert1.der
- 5. Decode the **DER** file to standard output using the **base64** command. Use the **-w0** option to disable wrapping:

\$ base64 cert1.der -w0
MIIC/zCCAeegAwIBAgIUV74O+4kXeg21o4vxfRRtyJm...

- 6. Copy the certificate from the standard output to the clipboard.
- 7. Open the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-certificate-present-copy.yml file for editing and view its contents:

- name: Service certificate present.

hosts: ipaserver become: true gather_facts: false

tasks:

Ensure service certificate is present

- ipaservice:

ipaadmin_password: MyPassword123 name: HTTP/www.example.com

certificate: |

- MIICBjCCAW8CFHnm32VcXaUDGfEGdDL/...

[...]

action: member state: present

- 8. Adapt the file:
 - Replace the certificate, defined using the certificate variable, with the certificate you copied from the CLI. Note that if you use the certificate: variable with the "|" pipe character as indicated, you can enter the certificate THIS WAY rather than having it to enter it in a single line. This makes reading the certificate easier.
 - Change the IdM administrator password, defined by the **ipaadmin password** variable.
 - Change the name of your IdM client on which the HTTP service is running, defined by the **name** variable.
 - Change any other relevant variables.
- 9. Save and exit the file.
- 10. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-member-certificate-present-copy.yml

Verification steps

- 1. Log into the IdM Web UI as IdM administrator.
- 2. Navigate to **Identity** → **Services**.
- 3. Click the name of the service with the newly added certificate, for example HTTP/client.idm.example.com.

In the Service Certificate section on the right, you can now see the newly added certificate.

23.5. USING AN ANSIBLE PLAYBOOK TO ALLOW IDM USERS, GROUPS, HOSTS, OR HOST GROUPS TO CREATE A KEYTAB OF A SERVICE

A keytab is a file containing pairs of Kerberos principals and encrypted keys. Keytab files are commonly used to allow scripts to automatically authenticate using Kerberos, without requiring human interaction or access to password stored in a plain-text file. The script is then able to use the acquired credentials to access files stored on a remote system.

As an Identity Management (IdM) administrator, you can allow other users to retrieve or even create a keytab for a service running in IdM. By allowing specific users and user groups to create keytabs, you can delegate the administration of the service to them without sharing the IdM administrator password. This delegation provides a more fine-grained system administration.

This section describes how you can allow specific IdM users, user groups, hosts, and host groups to create a keytab for the HTTP service running on an IdM client. Specifically, it describes how you can allow the **userO1** IdM user to create a keytab for the HTTP service running on an IdM client named **client.idm.example.com**.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.
- You have enrolled the HTTP service into IdM.
- The system to host the HTTP service is an IdM client.
- The IdM users and user groups that you want to allow to create the keytab exist in IdM.
- The IdM hosts and host groups that you want to allow to create the keytab exist in IdM.

Procedure

1. Create an inventory file, for example **inventory.file**:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-allow_create_keytab-present.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-memberallow_create_keytab-present.yml /usr/share/doc/ansiblefreeipa/playbooks/service/service-member-allow_create_keytab-present-copy.yml

4. Open the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-allow_create_keytab-present-copy.yml Ansible playbook file for editing.

- 5. Adapt the file by changing the following:
 - The IdM administrator password specified by the **ipaadmin_password** variable.
 - The name of your IdM client on which the HTTP service is running. In the current example, it is HTTP/client.idm.example.com
 - The names of IdM users that are listed in the **allow_create_keytab_user:** section. In the current example, it is **user01**.
 - The names of IdM user groups that are listed in the **allow_create_keytab_group:** section.
 - The names of IdM hosts that are listed in the allow_create_keytab_host: section.
 - The names of IdM host groups that are listed in the **allow_create_keytab_hostgroup:** section.
 - The name of the task specified by the **name** variable in the **tasks** section. After being adapted for the current example, the copied file looks like this:

- name: Service member allow create keytab present

hosts: ipaserver become: true

tasks:

- name: Service HTTP/client.idm.example.com members allow_create_keytab present for user01

ipaservice:

ipaadmin_password: Secret123 name: HTTP/client.idm.example.com allow_create_keytab_user:

- user01

action: member

- 6. Save the file.
- 7. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-member-allow_create_keytab-present-copy.yml

Verification steps

1. SSH to an IdM server as an IdM user that has the privilege to create a keytab for the particular HTTP service:

\$ ssh user01@server.idm.example.com Password:

2. Use the **ipa-getkeytab** command to generate the new keytab for the HTTP service:

\$ ipa-getkeytab -s server.idm.example.com -p HTTP/client.idm.example.com -k /etc/httpd/conf/krb5.keytab

The **-s** option specifies a Key Distribution Center (KDC) server to generate the keytab.

The **-p** option specifies the principal whose keytab you want to create.

The **-k** option specifies the keytab file to append the new key to. The file will be created if it does not exist.

If the command does not result in an error, you have successfully created a keytab of HTTP/client.idm.example.com as user01.

23.6. USING AN ANSIBLE PLAYBOOK TO ALLOW IDM USERS, GROUPS, HOSTS, OR HOST GROUPS TO RETRIEVE A KEYTAB OF A SERVICE

A keytab is a file containing pairs of Kerberos principals and encrypted keys. Keytab files are commonly used to allow scripts to automatically authenticate using Kerberos, without requiring human interaction or access to a password stored in a plain-text file. The script is then able to use the acquired credentials to access files stored on a remote system.

As IdM administrator, you can allow other users to retrieve or even create a keytab for a service running in IdM.

This section describes how you can allow specific IdM users, user groups, hosts, and host groups to retrieve a keytab for the HTTP service running on an IdM client. Specifically, it describes how to allow the user01 IdM user to retrieve the keytab of the HTTP service running on client.idm.example.com.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.
- You have enrolled the HTTP service into IdM.
- The IdM users and user groups that you want to allow to retrieve the keytab exist in IdM.
- The IdM hosts and host groups that you want to allow to retrieve the keytab exist in IdM.

Procedure

- 1. Create an inventory file, for example inventory.file:
 - \$ touch inventory.file
- 2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

 Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-memberallow_retrieve_keytab-present.yml Ansible playbook file. For example: \$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-memberallow_retrieve_keytab-present.yml /usr/share/doc/ansiblefreeipa/playbooks/service/service-member-allow_retrieve_keytab-present-copy.yml

- 4. Open the copied file, /usr/share/doc/ansible-freeipa/playbooks/service/service-member-allow_retrieve_keytab-present-copy.yml, for editing:
- 5. Adapt the file:
 - Set the **ipaadmin password** variable to your IdM administrator password.
 - Set the **name** variable of the **ipaservice** task to the principal of the HTTP service. In the current example, it is **HTTP/client.idm.example.com**
 - Specify the names of IdM users in the **allow_retrieve_keytab_group:** section. In the current example, it is **user01**.
 - Specify the names of IdM user groups in the **allow retrieve keytab group:** section.
 - Specify the names of IdM hosts in the **allow retrieve keytab group:** section.
 - Specify the names of IdM host groups in the **allow_retrieve_keytab_group:** section.
 - Specify the name of the task using the **name** variable in the **tasks** section. After being adapted for the current example, the copied file looks like this:

- name: Service member allow_retrieve_keytab present

hosts: ipaserver become: true

tasks:

- name: Service HTTP/client.idm.example.com members allow_retrieve_keytab present for user01

ipaservice:

ipaadmin_password: Secret123 name: HTTP/client.idm.example.com

allow_retrieve_keytab_user:

- user01

action: member

- 6. Save the file.
- 7. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-member-allow_retrieve_keytab-present-copy.yml

Verification steps

1. SSH to an IdM server as an IdM user with the privilege to retrieve a keytab for the HTTP service:

\$ ssh user01@server.idm.example.com Password:

2. Use the **ipa-getkeytab** command with the **-r** option to retrieve the keytab:

\$ ipa-getkeytab -r -s server.idm.example.com -p HTTP/client.idm.example.com -k /etc/httpd/conf/krb5.keytab

The **-s** option specifies a Key Distribution Center (KDC) server from which you want to retrieve the keytab.

The **-p** option specifies the principal whose keytab you want to retrieve.

The **-k** option specifies the keytab file to which you want to append the retrieved key. The file will be created if it does not exist.

If the command does not result in an error, you have successfully retrieved a keytab of HTTP/client.idm.example.com as user01.

23.7. ENSURING THE PRESENCE OF A KERBEROS PRINCIPAL ALIAS OF A SERVICE USING AN ANSIBLE PLAYBOOK

In some scenarios, it is beneficial for IdM administrator to enable IdM users, hosts, or services to authenticate against Kerberos applications using a Kerberos principal alias. These scenarios include:

- The user name changed, but the user should be able to log into the system using both the previous and new user names.
- The user needs to log in using the email address even if the IdM Kerberos realm differs from the email domain.

This section describes how to create the principal alias of HTTP/mycompany.idm.example.com for the HTTP service running on client.idm.example.com.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible controller.
- You have set up an HTTP service on your host.
- You have enrolled the HTTP service into IdM.
- The host on which you have set up HTTP is an IdM client.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-principal-present.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-member-principal-present.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-member-principal-present-copy.yml

- 4. Open the /usr/share/doc/ansible-freeipa/playbooks/service/service-member-principal-present-copy.yml Ansible playbook file for editing.
- 5. Adapt the file by changing the following:
 - The IdM administrator password specified by the **ipaadmin_password** variable.
 - The name of the service specified by the **name** variable. This is the canonical principal name of the service. In the current example, it is **HTTP/client.idm.example.com**.
 - The Kerberos principal alias specified by the **principal** variable. This is the alias you want to
 add to the service defined by the **name** variable. In the current example, it is
 host/mycompany.idm.example.com.
 - The name of the task specified by the **name** variable in the **tasks** section. After being adapted for the current example, the copied file looks like this:

- name: Service member principal present

hosts: ipaserver become: true

tasks:

- name: Service HTTP/client.idm.example.com member principals host/mycompany.idm.exmaple.com present

ipaservice:

ipaadmin_password: Secret123 name: HTTP/client.idm.example.com principal:

host/mycompany.idm.example.com

action: member

- 6. Save the file.
- 7. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service/service-member-principal-present-copy.yml

If running the playbook results in 0 unreachable and 0 failed tasks, you have successfully created the **host/mycompany.idm.example.com** Kerberos principal for the **HTTP/client.idm.example.com** service.

Additional resources

• For more information on Kerberos principal aliases and managing them without Ansible, see Managing Kerberos principal aliases for users, hosts, and services.

23.8. ENSURING THE ABSENCE OF AN HTTP SERVICE IN IDM USING AN ANSIBLE PLAYBOOK

This section describes how to unenroll a service from IdM. More specifically, it describes how to use an Ansible playbook to ensure the absence of an HTTP server named **HTTP/client.idm.example.com** in IdM.

Prerequisites

• You have the IdM administrator password.

Procedure

1. Create an inventory file, for example inventory.file:

\$ touch inventory.file

2. Open the **inventory.file** and define the IdM server that you want to configure in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-absent.yml Ansible playbook file. For example:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/service/service-is-absent.yml /usr/share/doc/ansible-freeipa/playbooks/service/service-is-absent-copy.yml

- 4. Open the /usr/share/doc/ansible-freeipa/playbooks/service/service-is-absent-copy.yml Ansible playbook file for editing.
- 5. Adapt the file by changing the following:
 - The IdM administrator password defined by the **ipaadmin password** variable.
 - The Kerberos principal of the HTTP service, as defined by the **name** variable of the **ipaservice** task.

After being adapted for the current example, the copied file looks like this:

- name: Playbook to manage IPA service.

hosts: ipaserver become: true gather_facts: false

tasks:

Ensure service is absent

- ipaservice:

ipaadmin_password: Secret123 name: HTTP/client.idm.example.com

state: absent

6. Save and exit the file.

7. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i path_to_inventory_directory/inventory.file /usr/share/doc/ansible-freeipa/playbooks/service-is-absent-copy.yml

Verification steps

- 1. Log into the IdM Web UI as IdM administrator.
- 2. Navigate to **Identity** → **Services**.

If you cannot see the HTTP/client.idm.example.com@IDM.EXAMPLE.COM service in the Services list, you have successfully ensured its absence in IdM.

Additional resources

- You can see sample Ansible playbooks for ensuring the presence and absence of services in IdM including a list of possible variables in the README-service.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory.
- You can see sample Ansible playbooks for ensuring the presence and absence of services in IdM in the /usr/share/doc/ansible-freeipa/playbooks/config directory.

CHAPTER 24. MANAGING GLOBAL DNS CONFIGURATION IN IDM USING ANSIBLE PLAYBOOKS

Using the Red Hat Ansible Engine **dnsconfig** module, you can configure global configuration for Identity Management (IdM) DNS. Settings defined in global DNS configuration are applied to all IdM DNS servers. However, the global configuration has lower priority than the configuration for a specific IdM DNS zone.

The **dnsconfig** module supports the following variables:

- The global forwarders, specifically their IP addresses and the port used for communication.
- The global forwarding policy: only, first, or none. For more details on these types of DNS forward policies, see DNS forward policies in IdM.
- The synchronization of forward lookup and reverse lookup zones.

Prerequisites

- DNS service is installed on the IdM server. For more information about how to install an IdM server with integrated DNS, see one of the following links:
 - Installing an IdM server: With integrated DNS, with an integrated CA as the root CA
 - Installing an IdM server: With integrated DNS, with an external CA as the root CA
 - Installing an IdM server: With integrated DNS, without a CA

This chapter includes the following sections:

- How IdM ensures that global forwarders from /etc/resolv.conf are not removed by NetworkManager
- Ensuring the presence of a DNS global forwarder in IdM using Ansible
- Ensuring the absence of a DNS global forwarder in IdM using Ansible
- An introduction to DNS forward policies in IdM
- Using an Ansible playbook to ensure that the forward first policy is set in IdM DNS global configuration
- Using an Ansible playbook to ensure that global forwarders are disabled in IdM DNS
- Using an Ansible playbook to ensure that synchronization of forward and reverse lookup zones is disabled in IdM DNS

24.1. HOW IDM ENSURES THAT GLOBAL FORWARDERS FROM /ETC/RESOLV.CONF ARE NOT REMOVED BY NETWORKMANAGER

Installing Identity Management (IdM) with integrated DNS configures the /etc/resolv.conf file to point to the 127.0.0.1 localhost address:

Generated by NetworkManager search idm.example.com nameserver 127.0.0.1

In certain environments, such as networks that use **Dynamic Host Configuration Protocol** (DHCP), the **NetworkManager** service may revert changes to the /etc/resolv.conf file. To make the DNS configuration persistent, the IdM DNS installation process also configures the **NetworkManager** service in the following way:

 The DNS installation script creates an /etc/NetworkManager/conf.d/zzz-ipa.conf NetworkManager configuration file to control the search order and DNS server list:

auto-generated by IPA installer [main] dns=default [global-dns] searches=\$DOMAIN [global-dns-domain-*] servers=127.0.0.1

 The NetworkManager service is reloaded, which always creates the /etc/resolv.conf file with the settings from the last file in the /etc/NetworkManager/conf.d/ directory. This is in this case the zzz-ipa.conf file.



IMPORTANT

Do not modify the /etc/resolv.conf file manually.

24.2. ENSURING THE PRESENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure the presence of a DNS global forwarder in IdM. In the example procedure below, the IdM administrator ensures the presence of a DNS global forwarder to a DNS server with an Internet Protocol (IP) v4 address of **7.7.9.9** and IP v6 address of **2001:db8::1:0** on port **53**.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig

2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the **forwarders-absent.yml** Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-presence-of-a-global-forwarder.yml
- 4. Open the **ensure-presence-of-a-global-forwarder.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to ensure the presence of a global forwarder in IdM DNS**.
 - b. In the tasks section, change the name of the task to Ensure the presence of a DNS global forwarder to 7.7.9.9 and 2001:db8::1:0 on port 53.
 - c. In the **forwarders** section of the **ipadnsconfig** portion:
 - i. Change the first **ip_address** value to the IPv4 address of the global forwarder: **7.7.9.9**.
 - ii. Change the second **ip_address** value to the IPv6 address of the global forwarder: **2001:db8::1:0**.
 - iii. Verify the **port** value is set to **53**.
 - d. Change the **state** to **present**.

This the modified Ansible playbook file for the current example:

- name: Playbook to ensure the presence of a global forwarder in IdM DNS

hosts: ipaserver become: true

tasks:

- name: Ensure the presence of a DNS global forwarder to 7.7.9.9 and 2001:db8::1:0 on port

ipadnsconfig:

forwarders:

- ip_address: 7.7.9.9

- ip address: 2001:db8::1:0

port: 53 state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-presence-of-a-global-forwarder.yml

Additional resources

 You can see more sample Ansible playbooks for the ansible-freeipa ipadnsconfig module in the README-dnsconfig.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of ipadnsconfig variables.

24.3. ENSURING THE ABSENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure the absence of a DNS global forwarder in IdM. In the example procedure below, the IdM administrator ensures the absence of a DNS global forwarder to a DNS server with an Internet Protocol (IP) v4 address of **8.8.6.6** and IP v6 address of **2001:4860:4860:18800** on port **53**.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the **forwarders-absent.yml** Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-absence-of-a-global-forwarder.yml
- 4. Open the **ensure-absence-of-a-global-forwarder.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the name variable for the playbook to Playbook to ensure the absence of a global forwarder in IdM DNS.
 - b. In the tasks section, change the name of the task to Ensure the absence of a DNS global forwarder to 8.8.6.6 and 2001:4860:4860:4860:3800 on port 53.
 - c. In the **forwarders** section of the **ipadnsconfig** portion:
 - i. Change the first ip address value to the IPv4 address of the global forwarder: 8.8.6.6.
 - ii. Change the second **ip_address** value to the IPv6 address of the global forwarder: **2001:4860:4860::8800**.
 - iii. Verify the port value is set to 53.

d. Verify the state is set to absent.

This the modified Ansible playbook file for the current example:

- name: Playbook to ensure the absence of a global forwarder in IdM DNS

hosts: ipaserver become: true

tasks:

- name: Ensure the absence of a DNS global forwarder to 8.8.6.6 and

2001:4860:4860::8800 on port 53

ipadnsconfig: forwarders:

- ip_address: 8.8.6.6

- ip_address: 2001:4860:4860::8800

port: 53 state: absent

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-absence-of-a-global-forwarder.yml

Additional resources

 You can see more sample Ansible playbooks for the ansible-freeipa ipadnsconfig module in the README-dnsconfig.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of ipadnsconfig variables.

24.4. DNS FORWARD POLICIES IN IDM

IdM supports the **first** and **only** standard BIND forward policies, as well as the **none** IdM-specific forward policy.

Forward first (default)

The IdM BIND service forwards DNS queries to the configured forwarder. If a query fails because of a server error or timeout, BIND falls back to the recursive resolution using servers on the Internet. The **forward first** policy is the default policy, and it is suitable for optimizing DNS traffic.

Forward only

The IdM BIND service forwards DNS queries to the configured forwarder. If a query fails because of a server error or timeout, BIND returns an error to the client. The **forward only** policy is recommended for environments with split DNS configuration.

None (forwarding disabled)

DNS queries are not forwarded with the **none** forwarding policy. Disabling forwarding is only useful as a zone-specific override for global forwarding configuration. This option is the IdM equivalent of specifying an empty list of forwarders in BIND configuration.



NOTE

You cannot use forwarding to combine data in IdM with data from other DNS servers. You can only forward queries for specific subzones of the primary zone in IdM DNS.

By default, the BIND service does not forward queries to another server if the queried DNS name belongs to a zone for which the IdM server is authoritative. In such a situation, if the queried DNS name cannot be found in the IdM database, the **NXDOMAIN** answer is returned. Forwarding is not used.

Example 24.1. Example Scenario

The IdM server is authoritative for the **test.example**. DNS zone. BIND is configured to forward queries to the DNS server with the **192.0.2.254** IP address.

When a client sends a query for the **nonexistent.test.example**. DNS name, BIND detects that the IdM server is authoritative for the **test.example**. zone and does not forward the query to the **192.0.2.254.** server. As a result, the DNS client receives the **NXDomain** error message, informing the user that the queried domain does not exist.

24.5. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT THE FORWARD FIRST POLICY IS SET IN IDM DNS GLOBAL CONFIGURATION

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure that global forwarding policy in IdM DNS is set to **forward first**.

If you use the **forward first** DNS forwarding policy, DNS queries are forwarded to the configured forwarder. If a query fails because of a server error or timeout, BIND falls back to the recursive resolution using servers on the Internet. The forward first policy is the default policy. It is suitable for traffic optimization.

Prerequisites

- You have installed the **ansible-freeipa** package on the Ansible controller, the host on which you execute the procedure. For more information, see Installing the ansible-freeipa package.
- You know the IdM administrator password.
- Your IdM environment contains an integrated DNS server.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig

2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **set-configuration.yml** Ansible playbook file. For example:

\$ cp set-configuration.yml set-forward-policy-to-first.yml

- 4. Open the **set-forward-policy-to-first.yml** file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsconfig** task section:
 - Set the **ipaadmin password** variable to your IdM administrator password.
 - Set the **forward_policy** variable to **first**.

 Delete all the other lines of the original playbook that are irrelevant. This is the modified Ansible playbook file for the current example:

- name: Playbook to set global forwarding policy to first

hosts: ipaserver become: true

tasks:

- name: Set global forwarding policy to first.

ipadnsconfig:

ipaadmin_password: Secret123

forward_policy: first

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file set-forward-policy-to-first.yml

Additional resources

- For more information on forwarding policy types available in IdM DNS, see DNS forward policies in IdM
- For more sample Ansible playbooks using the **ansible-freeipa ipadnsconfig** module, see the **README-dnsconfig.md** Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the **ipadnsconfig** variables.
- For more sample Ansible playbooks using the **ipadnsconfig** module, see the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory.

24.6. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT GLOBAL FORWARDERS ARE DISABLED IN IDM DNS

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure that global forwarders are disabled in IdM DNS. The disabling is done by setting the **forward_policy** variable to **none**.

Disabling global forwarders causes DNS queries not to be forwarded. Disabling forwarding is only useful as a zone-specific override for global forwarding configuration. This option is the IdM equivalent of specifying an empty list of forwarders in BIND configuration.

Prerequisites

- You have installed the **ansible-freeipa** package on the Ansible controller, the host on which you execute the procedure. For more information, see Installing the ansible-freeipa package.
- You know the IdM administrator password.
- Your IdM environment contains an integrated DNS server.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig

2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the disable-global-forwarders.yml Ansible playbook file. For example:

 $\$\ cp\ disable-global-forwarders.yml\ disable-global-forwarders-copy.yml$

- 4. Open the disable-global-forwarders-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsconfig** task section:
 - Set the **ipaadmin password** variable to your IdM administrator password.
 - Set the **forward_policy** variable to **none**. This is the modified Ansible playbook file for the current example:

- name: Playbook to disable global DNS forwarders

hosts: ipaserver become: true

tasks:

- name: Disable global forwarders.

ipadnsconfig:

ipaadmin password: Secret123

forward_policy: none

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file disable-global-forwarders-copy.yml

Additional resources

- For more information on forwarding policy types available in IdM DNS, see DNS forward policies in IdM.
- For more sample Ansible playbooks using the ansible-freeipa ipadnsconfig module, see the README-dnsconfig.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the ipadnsconfig variables.
- For more sample Ansible playbooks using the **ipadnsconfig** module, see the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory.

24.7. USING AN ANSIBLE PLAYBOOK TO ENSURE THAT SYNCHRONIZATION OF FORWARD AND REVERSE LOOKUP ZONES IS DISABLED IN IDM DNS

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure that forward and reverse lookup zones are not synchronized in IdM DNS.

Prerequisites

- You have installed the **ansible-freeipa** package on the Ansible controller, the host on which you execute the procedure. For more information, see Installing the ansible-freeipa package.
- You know the IdM administrator password.
- Your IdM environment contains an integrated DNS server.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the disallow-reverse-sync.yml Ansible playbook file. For example:
 - \$ cp disallow-reverse-sync.yml disallow-reverse-sync-copy.yml
- 4. Open the disallow-reverse-sync-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsconfig** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.

• Set the **allow_sync_ptr** variable to **no**.

This is the modified Ansible playbook file for the current example:

- name: Playbook to disallow reverse record synchronization

hosts: ipaserver become: true

tasks:

- name: Disallow reverse record synchronization.

ipadnsconfig:

ipaadmin_password: Secret123

allow_sync_ptr: no

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file disallow-reverse-sync-copy.yml

Additional resources

- For more sample Ansible playbooks using the **ansible-freeipa ipadnsconfig** module, see the **README-dnsconfig.md** Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the **ipadnsconfig** variables.
- For more sample Ansible playbooks using the **ipadnsconfig** module, see the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory.

CHAPTER 25. USING ANSIBLE PLAYBOOKS TO MANAGE IDM DNS ZONES

As Identity Management (IdM) administrator, you can manage how IdM DNS zones work using the **dnszone** module available in the **ansible-freeipa** package. The chapter describes the following topics and procedures:

- What DNS zone types are supported in IdM
- What DNS attributes you can configure in IdM
- How to use an Ansible playbook to create a primary zone in IdM DNS
- How to use an Ansible playbook to ensure the presence of a primary IdM DNS zone with multiple variables
- How to use an Ansible playbook to ensure the presence of a zone for reverse DNS lookup when an IP address is given

Prerequisites

 DNS service is installed on the IdM server. For more information about how to use Red Hat Ansible Engine to install an IdM server with integrated DNS, see Installing an Identity Management server using an Ansible playbook.

25.1. SUPPORTED DNS ZONE TYPES

Identity Management (IdM) supports two types of DNS zones: *primary* and *forward* zones. This section describes these two types of zones and includes an example scenario for DNS forwarding.



NOTE

This guide uses the BIND terminology for zone types which is different from the terminology used for Microsoft Windows DNS. Primary zones in BIND serve the same purpose as *forward lookup zones* and *reverse lookup zones* in Microsoft Windows DNS. Forward zones in BIND serve the same purpose as *conditional forwarders* in Microsoft Windows DNS.

Primary DNS zones

Primary DNS zones contain authoritative DNS data and can accept dynamic DNS updates. This behavior is equivalent to the **type master** setting in standard BIND configuration. You can manage primary zones using the **ipa dnszone-*** commands.

In compliance with standard DNS rules, every primary zone must contain **start of authority** (SOA) and **nameserver** (NS) records. IdM generates these records automatically when the DNS zone is created, but you must copy the NS records manually to the parent zone to create proper delegation.

In accordance with standard BIND behavior, queries for names for which the server is not authoritative are forwarded to other DNS servers. These DNS servers, so called forwarders, may or may not be authoritative for the query.

Example 25.1. Example scenario for DNS forwarding

The IdM server contains the **test.example.** primary zone. This zone contains an NS delegation record for the **sub.test.example.** name. In addition, the **test.example.** zone is configured with the **192.0.2.254** forwarder IP address for the **sub.text.example** subzone.

A client querying the name **nonexistent.test.example.** receives the **NXDomain** answer, and no forwarding occurs because the IdM server is authoritative for this name.

On the other hand, querying for the **host1.sub.test.example.** name is forwarded to the configured forwarder **192.0.2.254** because the IdM server is not authoritative for this name.

Forward DNS zones

From the perspective of IdM, forward DNS zones do not contain any authoritative data. In fact, a forward "zone" usually only contains two pieces of information:

- A domain name
- The IP address of a DNS server associated with the domain

All queries for names belonging to the domain defined are forwarded to the specified IP address. This behavior is equivalent to the **type forward** setting in standard BIND configuration. You can manage forward zones using the **ipa dnsforwardzone-*** commands.

Forward DNS zones are especially useful in the context of IdM-Active Directory (AD) trusts. If the IdM DNS server is authoritative for the **idm.example.com** zone and the AD DNS server is authoritative for the **ad.example.com** zone, then **ad.example.com** is a DNS forward zone for the **idm.example.com** primary zone. That means that when a query comes from an IdM client for the IP address of **somehost.ad.example.com**, the query is forwarded to an AD domain controller specified in the **ad.example.com** IdM DNS forward zone.

25.2. CONFIGURATION ATTRIBUTES OF PRIMARY IDM DNS ZONES

Identity Management (IdM) creates a new zone with certain default configuration, such as the refresh periods, transfer settings, or cache settings. In IdM DNS zone attributes, you can find the attributes of the default zone configuration that you can modify using one of the following options:

- The **dnszone-mod** command in the command-line interface (CLI). For more information, see Editing the configuration of a primary DNS zone in IdM CLI.
- The IdM Web UI. For more information, see Editing the configuration of a primary DNS zone in IdM Web UI.
- An Ansible playbook that uses the **ipadnszone** module. For more information, see Managing DNS zones in IdM.

Along with setting the actual information for the zone, the settings define how the DNS server handles the start of authority (SOA) record entries and how it updates its records from the DNS name server.

Table 25.1. IdM DNS zone attributes

Attribute	ansible-freeipa variable	Description
Authoritative name server	name_server	Sets the domain name of the primary DNS name server, also known as SOA MNAME.
		By default, each IdM server advertises itself in the SOA MNAME field. Consequently, the value stored in LDAP using name-server is ignored.
Administrator e- mail address	admin_email	Sets the email address to use for the zone administrator. This defaults to the root account on the host.
SOA serial	serial	Sets a serial number in the SOA record. Note that IdM sets the version number automatically and users are not expected to modify it.
SOA refresh	refresh	Sets the interval, in seconds, for a secondary DNS server to wait before requesting updates from the primary DNS server.
SOA retry	retry	Sets the time, in seconds, to wait before retrying a failed refresh operation.
SOA expire	expire	Sets the time, in seconds, that a secondary DNS server will try to perform a refresh update before ending the operation attempt.
SOA minimum	minimum	Sets the time to live (TTL) value in seconds for negative caching according to RFC 2308.
SOA time to live	ttl	Sets TTL in seconds for records at zone apex. In zone example.com , for instance, all records (A, NS, or SOA) under name example.com are configured, but no other domain names, like test.example.com , are affected.
Default time to live	default_ttl	Sets the default time to live (TTL) value in seconds for negative caching for all values in a zone that never had an individual TTL value set before. Requires a restart of the named-pkcs11 service on all IdM DNS servers after changes to take effect.
BIND update policy	update_policy	Sets the permissions allowed to clients in the DNS zone.
Dynamic update	dynamic_updat e=TRUE FALSE	Enables dynamic updates to DNS records for clients.
		Note that if this is set to false, IdM client machines will not be able to add or update their IP address.
Allow transfer	allow_transfer=s tring	Gives a list of IP addresses or network names which are allowed to transfer the given zone, separated by semicolons (;).
		Zone transfers are disabled by default. The default allow_transfer value is none .

Attribute	ansible-freeipa variable	Description
Allow query	allow_query	Gives a list of IP addresses or network names which are allowed to issue DNS queries, separated by semicolons (;).
Allow PTR sync	allow_sync_ptr= 1 0	Sets whether A or AAAA records (forward records) for the zone will be automatically synchronized with the PTR (reverse) records.
Zone forwarders	forwarder=IP_add ress	Specifies a forwarder specifically configured for the DNS zone. This is separate from any global forwarders used in the IdM domain. To specify multiple forwarders, use the option multiple times.
Forward policy	forward_policy= none only first	Specifies the forward policy. For information about the supported policies, see DNS forward policies in IdM.

Additional resources

 You can see more definitions of the attributes of the ansible-freeipa ipadnszone module in the README-dnszone.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory.

25.3. USING ANSIBLE TO CREATE A PRIMARY ZONE IN IDM DNS

This section shows how an Identity Management (IdM) administrator can use an Ansible playbook to ensure that a primary DNS zone exists. In the example used in the procedure below, an IdM administrator ensures the presence of the **zone.idm.example.com** DNS zone.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnszone
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com 3. Make a copy of the **dnszone-present.yml** Ansible playbook file. For example:

\$ cp dnszone-present.yml dnszone-present-copy.yml

- 4. Open the dnszone-present-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnszone** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **zone_name** variable to **zone.idm.example.com**.

 This is the modified Ansible playbook file for the current example:

- name: Ensure dnszone present

hosts: ipaserver become: true

tasks:

- name: Ensure zone is present.

ipadnszone:

ipaadmin_password: Secret123 zone_name: zone.idm.example.com

state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file dnszone-present-copy.yml

Additional resources

- For more information on DNS zone, see Supported DNS zone types.
- You can see more sample Ansible playbooks for the ansible-freeipa ipadnszone module in the README-dnszone.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the ipadnszone variables.
- You can see sample Ansible playbooks for the ipadnszone module in the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory.

25.4. USING AN ANSIBLE PLAYBOOK TO ENSURE THE PRESENCE OF A PRIMARY DNS ZONE IN IDM WITH MULTIPLE VARIABLES

This section shows how an Identity Management (IdM) administrator can use an Ansible playbook to ensure that a primary DNS zone exists. In the example used in the procedure below, an IdM administrator ensures the presence of the **zone.idm.example.com** DNS zone. The Ansible playbook configures multiple parameters of the zone.

Prerequisites

• You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.

• You know the IdM administrator password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnszone
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the dnszone-all-params.yml Ansible playbook file. For example:
 - \$ cp dnszone-all-params.yml dnszone-all-params-copy.yml
- 4. Open the dnszone-all-params-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnszone** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **zone_name** variable to **zone.idm.example.com**.
 - Set the **allow_sync_ptr** variable to true if you want to allow the synchronization of forward and reverse records, that is the synchronization of A and AAAA records with PTR records.
 - Set the **dynamic_update** variable to true to enable IdM client machines to add or update their IP addresses.
 - Set the **dnssec** variable to true to allow inline DNSSEC signing of records in the zone.
 - Set the **allow_transfer** variable to the IP addresses of secondary name servers in the zone.
 - Set the allow_query variable to the IP addresses or networks that are allowed to issue queries.
 - Set the **forwarders** variable to the IP addresses of global forwarders.
 - Set the **serial** variable to the SOA record serial number.
 - Define the refresh, retry, expire, minimum, ttl, and default_ttl values for DNS records in the zone.
 - Define the NSEC3PARAM record for the zone using the **nsec3param_rec** variable.
 - Set the skip_overlap_check variable to true to force DNS creation even if it overlaps with an existing zone.
 - Set the skip_nameserver_check to true to force DNS zone creation even if the nameserver is not resolvable.
 - This is the modified Ansible playbook file for the current example:

- name: Ensure dnszone present

hosts: ipaserver become: true

tasks:

- name: Ensure zone is present.

ipadnszone:

ipaadmin_password: Secret123 zone_name: zone.idm.example.com

allow_sync_ptr: true dynamic_update: true

dnssec: true allow_transfer: - 1.1.1.1

- 2.2.2.2

allow_query:

- 1.1.1.1 - 2.2.2.2

forwarders:

ip_address: 8.8.8.8ip_address: 8.8.4.4

port: 52 serial: 1234 refresh: 3600 retry: 900 expire: 1209600

minimum: 3600

ttl: 60

default_ttl: 90

 $name_server: server.idm.example.com.$

admin_email: admin.admin@idm.example.com nsec3param_rec: "1 7 100 0123456789abcdef"

skip_overlap_check: true skip_nameserver_check: true

state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file dnszone-all-params-copy.yml

Additional resources

- For more information on DNS zone, see Supported DNS zone types.
- For more information on what DNS zone attributes you can configure in IdM, see Configuration attributes of primary IdM DNS zones.
- You can see more sample Ansible playbooks for the ansible-freeipa ipadnszone module in the README-dnszone.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the ipadnszone variables.

 You can see sample Ansible playbooks for the ipadnszone module in the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory.

25.5. USING AN ANSIBLE PLAYBOOK TO ENSURE THE PRESENCE OF A ZONE FOR REVERSE DNS LOOKUP WHEN AN IP ADDRESS IS GIVEN

This section shows how an Identity Management (IdM) administrator can use an Ansible playbook to ensure that a reverse DNS zone exists. In the example used in the procedure below, an IdM administrator ensures the presence of a reverse DNS lookup zone using the IP address and prefix length of an IdM host.

Providing the prefix length of the IP address of your DNS server using the **name_from_ip** variable allows you to control the zone name. If you do not state the prefix length, the system queries DNS servers for zones and, based on the **name_from_ip** value of **192.168.1.2**, the query can return any of the following DNS zones:

- 1.168.192.in-addr.arpa.
- 168.192.in-addr.arpa.
- 192.in-addr.arpa.

Because the zone returned by the query might not be what you expect, **name_from_ip** can only be used with the **state** option set to **present** to prevent accidental removals of zones.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnszone
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:
 - [ipaserver] server.idm.example.com
- 3. Make a copy of the **dnszone-reverse-from-ip.yml** Ansible playbook file. For example:
 - \$ cp dnszone-reverse-from-ip.yml dnszone-reverse-from-ip-copy.yml
- 4. Open the dnszone-reverse-from-ip-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnszone** task section:
 - Set the **ipaadmin password** variable to your IdM administrator password.

• Set the **name_from_ip** variable to the IP of your IdM nameserver, and provide its prefix length.

This is the modified Ansible playbook file for the current example:

- name: Ensure dnszone present

hosts: ipaserver become: true

tasks:

- name: Ensure zone for reverse DNS lookup is present.

ipadnszone:

ipaadmin_password: Secret123 name_from_ip: 192.168.1.2/24

state: present register: result

- name: Display inferred zone name.

debug:

msg: "Zone name: {{ result.dnszone.name }}"

The playbook creates a zone for reverse DNS lookup from the **192.168.1.2** IP address and its prefix length of 24. Next, the playbook displays the resulting zone name.

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file dnszone-reverse-from-ip-copy.yml

Additional resources

- For more information on DNS zone, see Supported DNS zone types.
- You can see more sample Ansible playbooks for the ansible-freeipa ipadnszone module in the README-dnszone.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the ipadnszone variables.
- You can see sample Ansible playbooks for the **ipadnszone** module in the /usr/share/doc/ansible-freeipa/playbooks/dnszone directory.

CHAPTER 26. USING ANSIBLE TO MANAGE DNS LOCATIONS IN IDM

As Identity Management (IdM) administrator, you can manage IdM DNS locations using the **location** module available in the **ansible-freeipa** package. The chapter describes the following topics and procedures:

- DNS-based service discovery
- Deployment considerations for DNS locations
- DNS time to live (TTL)
- Using Ansible to ensure an IdM location is present
- Using Ansible to ensure an IdM location is absent

26.1. DNS-BASED SERVICE DISCOVERY

DNS-based service discovery is a process in which a client uses the DNS protocol to locate servers in a network that offer a specific service, such as **LDAP** or **Kerberos**. One typical type of operation is to allow clients to locate authentication servers within the closest network infrastructure, because they provide a higher throughput and lower network latency, lowering overall costs.

The major advantages of service discovery are:

- No need for clients to be explicitly configured with names of nearby servers.
- DNS servers are used as central providers of policy. Clients using the same DNS server have access to the same policy about service providers and their preferred order.

In an Identity Management (IdM) domain, DNS service records (SRV records) exist for **LDAP**, **Kerberos**, and other services. For example, the following command queries the DNS server for hosts providing a TCP-based **Kerberos** service in an IdM DNS domain:

Example 26.1. DNS location independent results

\$ dig -t SRV +short _kerberos._tcp.idm.example.com 0 100 88 idmserver-01.idm.example.com. 0 100 88 idmserver-02.idm.example.com.

The output contains the following information:

- **0** (priority): Priority of the target host. A lower value is preferred.
- **100** (weight). Specifies a relative weight for entries with the same priority. For further information, see RFC 2782, section 3.
- **88** (port number): Port number of the service.
- Canonical name of the host providing the service.

In the example, the two host names returned have the same priority and weight. In this case, the client uses a random entry from the result list.

When the client is, instead, configured to query a DNS server that is configured in a DNS location, the output differs. For IdM servers that are assigned to a location, tailored values are returned. In the example below, the client is configured to query a DNS server in the location **germany**:

Example 26.2. DNS location-based results

\$ dig -t SRV +short _kerberos._tcp.idm.example.com _kerberos._tcp.germany._locations.idm.example.com.
0 100 88 idmserver-01.idm.example.com.
50 100 88 idmserver-02.idm.example.com.

The IdM DNS server automatically returns a DNS alias (CNAME) pointing to a DNS location specific SRV record which prefers local servers. This CNAME record is shown in the first line of the output. In the example, the host <code>idmserver-01.idm.example.com</code> has the lowest priority value and is therefore preferred. The <code>idmserver-02.idm.example.com</code> has a higher priority and thus is used only as backup for cases when the preferred host is unavailable.

26.2. DEPLOYMENT CONSIDERATIONS FOR DNS LOCATIONS

Identity Management (IdM) can generate location-specific service (SRV) records when using the integrated DNS. Because each IdM DNS server generates location-specific SRV records, you have to install at least one IdM DNS server in each DNS location.

The client's affinity to a DNS location is only defined by the DNS records received by the client. For this reason, you can combine IdM DNS servers with non-IdM DNS consumer servers and recursors if the clients doing DNS service discovery resolve location-specific records from IdM DNS servers.

In the majority of deployments with mixed IdM and non-IdM DNS services, DNS recursors select the closest IdM DNS server automatically by using round-trip time metrics. Typically, this ensures that clients using non-IdM DNS servers are getting records for the nearest DNS location and thus use the optimal set of IdM servers.

26.3. DNS TIME TO LIVE (TTL)

Clients can cache DNS resource records for an amount of time that is set in the zone's configuration. Because of this caching, a client might not be able to receive the changes until the time to live (TTL) value expires. The default TTL value in Identity Management (IdM) is **1 day**.

If your client computers roam between sites, you should adapt the TTL value for your IdM DNS zone. Set the value to a lower value than the time clients need to roam between sites. This ensures that cached DNS entries on the client expire before they reconnect to another site and thus query the DNS server to refresh location-specific SRV records.

Additional resources

• For further information how to modify the default TTL of a DNS zone, see Configuration attributes of primary IdM DNS zones.

26.4. USING ANSIBLE TO ENSURE AN IDM LOCATION IS PRESENT

As a system administrator of Identity Management (IdM), you can configure IdM DNS locations to allow clients to locate authentication servers within the closest network infrastructure.

The following procedure describes how to use an Ansible playbook to ensure a DNS location is present in IdM. The example describes how to ensure that the **germany** DNS location is present in IdM. As a result, you can assign particular IdM servers to this location so that local IdM clients can use them to reduce server response time.

Prerequisites

- You know the IdM administrator password.
- You have installed the ansible-freeipa package on the Ansible control node.
- The example assumes that you have created and configured the ~/MyPlaybooks/ directory as a central location to store copies of sample playbooks.
- You understand the deployment considerations for DNS locations.

Procedure

1. Navigate to the ~/MyPlaybooks/ directory:

\$ cd ~/MyPlaybooks/

2. Make a copy of the **location-present.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/location/ directory:

\$ cp /usr/share/doc/ansible-freeipa/playbooks/location/location-present.yml location-present-copy.yml

- 3. Open the location-present-copy.yml Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipalocation** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the location.

This is the modified Ansible playbook file for the current example:

- name: location present example

hosts: ipaserver become: true

tasks:

- name: Ensure that the "germany" location is present ipalocation:

ipaadmin_password: Secret123

name: germany

- 5. Save the file.
- 6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory location-present-copy.yml

Additional resources

 To configure specific servers for the IdM locations that now exist in IdM, see Assigning an IdM server to a DNS location using the IdM Web UI or Assigning an IdM server to a DNS location using the IdM CLI.

26.5. USING ANSIBLE TO ENSURE AN IDM LOCATION IS ABSENT

As a system administrator of Identity Management (IdM), you can configure IdM DNS locations to allow clients to locate authentication servers within the closest network infrastructure.

The following procedure describes how to use an Ansible playbook to ensure that a DNS location is absent in IdM. The example describes how to ensure that the **germany** DNS location is absent in IdM. As a result, you cannot assign particular IdM servers to this location and local IdM clients cannot use them.

Prerequisites

- You know the IdM administrator password.
- No IdM server is assigned to the **germany** DNS location.
- You have installed the ansible-freeipa package on the Ansible control node.
- The example assumes that you have created and configured the ~/MyPlaybooks/ directory as a central location to store copies of sample playbooks.

Procedure

- 1. Navigate to the ~/MyPlaybooks/ directory:
 - \$ cd ~/MyPlaybooks/
- 2. Make a copy of the **location-absent.yml** file located in the /usr/share/doc/ansible-freeipa/playbooks/location/ directory:
 - \$ cp /usr/share/doc/ansible-freeipa/playbooks/location/location-absent.yml location-absent-copy.yml
- 3. Open the **location-absent-copy.yml** Ansible playbook file for editing.
- 4. Adapt the file by setting the following variables in the **ipalocation** task section:
 - Adapt the name of the task to correspond to your use case.
 - Set the **ipaadmin password** variable to the password of the IdM administrator.
 - Set the name variable to the name of the DNS location.
 - Make sure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

- name: location absent example

hosts: ipaserver become: true

tasks:

- name: Ensure that the "germany" location is absent

ipalocation:

ipaadmin_password: Secret123

name: germany state: absent

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

\$ ansible-playbook -v -i inventory location-absent-copy.yml

26.6. ADDITIONAL RESOURCES

- You can see more sample Ansible playbooks for the ansible-freeipa ipalocation module in the README-location.md file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the ipalocation variables.
- You can see sample Ansible playbooks for the ipalocation module in the /usr/share/doc/ansible-freeipa/playbooks/location directory.

CHAPTER 27. MANAGING DNS FORWARDING IN IDM

The following procedures describe how to configure DNS global forwarders and DNS forward zones in the Identity Management (IdM) Web UI, the IdM CLI, and using Ansible:

- Section 27.1, "The two roles of an IdM DNS server"
- Section 27.2, "DNS forward policies in IdM"
- Section 27.3, "Adding a global forwarder in the IdM Web UI"
- Section 27.4, "Adding a global forwarder in the CLI"
- Section 27.5, "Adding a DNS Forward Zone in the IdM Web UI"
- Section 27.6, "Adding a DNS Forward Zone in the CLI"
- Section 27.7, "Establishing a DNS Global Forwarder in IdM using Ansible"
- Section 27.8, "Ensuring the presence of a DNS global forwarder in IdM using Ansible"
- Section 27.9, "Ensuring the absence of a DNS global forwarder in IdM using Ansible"
- Section 27.10, "Ensuring DNS Global Forwarders are disabled in IdM using Ansible"
- Section 27.11, "Ensuring the presence of a DNS Forward Zone in IdM using Ansible"
- Section 27.12, "Ensuring a DNS Forward Zone has multiple forwarders in IdM using Ansible"
- Section 27.13, "Ensuring a DNS Forward Zone is disabled in IdM using Ansible"
- Section 27.14, "Ensuring the absence of a DNS Forward Zone in IdM using Ansible"

Additional resources

DNS forwarding

27.1. THE TWO ROLES OF AN IDM DNS SERVER

DNS forwarding affects how a DNS service answers DNS queries. By default, the Berkeley Internet Name Domain (BIND) service integrated with IdM acts as both an *authoritative* and a *recursive* DNS server:

Authoritative DNS server

When a DNS client queries a name belonging to a DNS zone for which the IdM server is authoritative, BIND replies with data contained in the configured zone. Authoritative data always takes precedence over any other data.

Recursive DNS server

When a DNS client queries a name for which the IdM server is not authoritative, BIND attempts to resolve the query using other DNS servers. If forwarders are not defined, BIND asks the root servers on the Internet and uses a recursive resolution algorithm to answer the DNS query.

In some cases, it is not desirable to let BIND contact other DNS servers directly and perform the recursion based on data available on the Internet. You can configure BIND to use another DNS server, a *forwarder*, to resolve the query.

When you configure BIND to use a forwarder, queries and answers are forwarded back and forth between the IdM server and the forwarder, and the IdM server acts as the DNS cache for non-authoritative data.

27.2. DNS FORWARD POLICIES IN IDM

IdM supports the **first** and **only** standard BIND forward policies, as well as the **none** IdM-specific forward policy.

Forward first (default)

The IdM BIND service forwards DNS queries to the configured forwarder. If a query fails because of a server error or timeout, BIND falls back to the recursive resolution using servers on the Internet. The **forward first** policy is the default policy, and it is suitable for optimizing DNS traffic.

Forward only

The IdM BIND service forwards DNS queries to the configured forwarder. If a query fails because of a server error or timeout, BIND returns an error to the client. The **forward only** policy is recommended for environments with split DNS configuration.

None (forwarding disabled)

DNS queries are not forwarded with the **none** forwarding policy. Disabling forwarding is only useful as a zone-specific override for global forwarding configuration. This option is the IdM equivalent of specifying an empty list of forwarders in BIND configuration.



NOTE

You cannot use forwarding to combine data in IdM with data from other DNS servers. You can only forward queries for specific subzones of the primary zone in IdM DNS.

By default, the BIND service does not forward queries to another server if the queried DNS name belongs to a zone for which the IdM server is authoritative. In such a situation, if the queried DNS name cannot be found in the IdM database, the **NXDOMAIN** answer is returned. Forwarding is not used.

Example 27.1. Example Scenario

The IdM server is authoritative for the **test.example**. DNS zone. BIND is configured to forward queries to the DNS server with the **192.0.2.254** IP address.

When a client sends a query for the **nonexistent.test.example.** DNS name, BIND detects that the IdM server is authoritative for the **test.example.** zone and does not forward the query to the **192.0.2.254.** server. As a result, the DNS client receives the **NXDomain** error message, informing the user that the queried domain does not exist.

27.3. ADDING A GLOBAL FORWARDER IN THE IDM WEB UI


This section describes how to add a global DNS forwarder in the Identity Management (IdM) Web UI.

Prerequisites


- You are logged in to the IdM WebUI as IdM administrator.
- You know the Internet Protocol (IP) address of the DNS server to forward queries to.

Procedure


1. In the IdM Web UI, select Network Services → DNS Global Configuration → DNS.




2. In the DNS Global Configuration section, click Add.



3. Specify the IP address of the DNS server that will receive forwarded DNS queries.




4. Select the Forward policy.




5. Click **Save** at the top of the window.

Verification steps

1. Select Network Services → DNS Global Configuration → DNS.



2. Verify that the global forwarder, with the forward policy you specified, is present and enabled in the IdM Web UI.



27.4. ADDING A GLOBAL FORWARDER IN THE CLI

This section describes how to add a global DNS forwarder from the command line interface (CLI).

Prerequisites

- You are logged in as IdM administrator.
- You know the Internet Protocol (IP) address of the DNS server to forward queries to.

Procedure

• Use the **ipa dnsconfig-mod** command to add a new global forwarder. Specify the IP address of the DNS forwarder with the **--forwarder** option.

[user@server ~]\$ **ipa dnsconfig-mod --forwarder=10.10.0.1** Server will check DNS forwarder(s).

This may take some time, please wait ...

Global forwarders: 10.10.0.1

IPA DNS servers: server.example.com

Verification steps

• Use the **dnsconfig-show** command to display global forwarders.

[user@server ~]\$ ipa dnsconfig-show

Global forwarders: 10.10.0.1

IPA DNS servers: server.example.com

27.5. ADDING A DNS FORWARD ZONE IN THE IDM WEB UI

This section describes how to add a DNS forward zone in the Identity Management (IdM) Web UI.



IMPORTANT

Do not use forward zones unless absolutely required. Forward zones are not a standard solution, and using them can lead to unexpected and problematic behavior. If you must use forward zones, limit their use to overriding a global forwarding configuration.


When creating a new DNS zone, Red Hat recommends to always use standard DNS delegation using nameserver (NS) records and to avoid forward zones. In most cases, using a global forwarder is sufficient, and forward zones are not necessary.

Prerequisites


- You are logged in to the IdM WebUI as IdM administrator.
- You know the Internet Protocol (IP) address of the DNS server to forward queries to.

Procedure


1. In the IdM Web UI, select **Network Services** → **DNS Forward Zones** → **DNS**.




2. In the DNS Forward Zones section, click Add.




3. In the **Add DNS forward zone** window, specify the forward zone name.



4. Click the **Add** button and specify the IP address of a DNS server to receive the forwarding request. You can specify multiple forwarders per forward zone.




5. Select the **Forward policy**.




6. Click **Add** at the bottom of the window to add the new forward zone.

Verification steps

1. In the IdM Web UI, select **Network Services** → **DNS Forward Zones** → **DNS**.



2. Verify that the forward zone you created, with the forwarders and forward policy you specified, is present and enabled in the IdM Web UI.



27.6. ADDING A DNS FORWARD ZONE IN THE CLI

This section describes how to add a DNS forward zone from the command line interface (CLI).



IMPORTANT

Do not use forward zones unless absolutely required. Forward zones are not a standard solution, and using them can lead to unexpected and problematic behavior. If you must use forward zones, limit their use to overriding a global forwarding configuration.

When creating a new DNS zone, Red Hat recommends to always use standard DNS delegation using nameserver (NS) records and to avoid forward zones. In most cases, using a global forwarder is sufficient, and forward zones are not necessary.

Prerequisites

- You are logged in as IdM administrator.
- You know the Internet Protocol (IP) address of the DNS server to forward queries to.

Procedure

• Use the **dnsforwardzone-add** command to add a new forward zone. Specify at least one forwarder with the **--forwarder** option if the forward policy is not **none**, and specify the forward policy with the **--forward-policy** option.

[user@server ~]\$ ipa dnsforwardzone-add forward.example.com. -- forwarder=10.10.0.14 --forwarder=10.10.1.15 --forward-policy=first

Zone name: forward.example.com. Zone forwarders: 10.10.0.14, 10.10.1.15

Forward policy: first

Verification steps

• Use the **dnsforwardzone-show** command to display the DNS forward zone you just created.

[user@server ~]\$ ipa dnsforwardzone-show forward.example.com.

Zone name: forward.example.com. Zone forwarders: 10.10.0.14, 10.10.1.15

Forward policy: first

27.7. ESTABLISHING A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to establish a DNS Global Forwarder in IdM.

In the example procedure below, the IdM administrator creates a DNS global forwarder to a DNS server with an Internet Protocol (IP) v4 address of **8.8.6.6** and IPv6 address of **2001:4860:4860::8800** on port **53**.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

- Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the **set-configuration.yml** Ansible playbook file. For example:
 - \$ cp set-configuration.yml establish-global-forwarder.yml
- 4. Open the **establish-global-forwarder.yml** file for editing.

- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to establish a global forwarder** in IdM DNS.
 - b. In the tasks section, change the name of the task to Create a DNS global forwarder to 8.8.6.6 and 2001:4860:4860:8800.
 - c. In the **forwarders** section of the **ipadnsconfig** portion:
 - i. Change the first **ip_address** value to the IPv4 address of the global forwarder: **8.8.6.6**.
 - ii. Change the second **ip_address** value to the IPv6 address of the global forwarder: **2001:4860:4860:8800**.
 - iii. Verify the **port** value is set to **53**.
 - d. Change the **forward_policy** to **first**.This the modified Ansible playbook file for the current example:

- name: Playbook to establish a global forwarder in IdM DNS

hosts: ipaserver become: true

tasks:

- name: Create a DNS global forwarder to 8.8.6.6 and 2001:4860:4860::8800 ipadnsconfig:

forwarders:

- ip address: 8.8.6.6

- ip address: 2001:4860:4860::8800

port: 53

forward_policy: first allow_sync_ptr: yes

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file establish-global-forwarder.yml

Additional resources

• You can see more sample Ansible playbooks for the **ansible-freeipa ipadnsconfig** module in the **README-dnsconfig.md** Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of **ipadnsconfig** variables.

27.8. ENSURING THE PRESENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure the presence of a DNS global forwarder in IdM. In the example procedure below, the IdM administrator ensures the presence of a DNS global forwarder to a DNS server with an Internet Protocol (IP) v4 address of **7.7.9.9** and IP v6 address of **2001:db8::1:0** on port **53**.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the forwarders-absent.yml Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-presence-of-a-global-forwarder.yml
- 4. Open the **ensure-presence-of-a-global-forwarder.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the name variable for the playbook to Playbook to ensure the presence of a global forwarder in IdM DNS.
 - b. In the tasks section, change the name of the task to Ensure the presence of a DNS global forwarder to 7.7.9.9 and 2001:db8::1:0 on port 53.
 - c. In the **forwarders** section of the **ipadnsconfig** portion:
 - i. Change the first ip_address value to the IPv4 address of the global forwarder: 7.7.9.9.
 - ii. Change the second **ip_address** value to the IPv6 address of the global forwarder: **2001:db8::1:0**.
 - iii. Verify the **port** value is set to **53**.
 - d. Change the **state** to **present**.

This the modified Ansible playbook file for the current example:

- name: Playbook to ensure the presence of a global forwarder in IdM DNS

hosts: ipaserver become: true

tasks:

- name: Ensure the presence of a DNS global forwarder to 7.7.9.9 and 2001:db8::1:0 on port 53

ipadnsconfig:

forwarders:

- ip_address: 7.7.9.9

- ip_address: 2001:db8::1:0

port: 53 state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-presence-of-a-global-forwarder.yml

Additional resources

 You can see more sample Ansible playbooks for the ansible-freeipa ipadnsconfig module in the README-dnsconfig.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of ipadnsconfig variables.

27.9. ENSURING THE ABSENCE OF A DNS GLOBAL FORWARDER IN IDM USING ANSIBLE

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure the absence of a DNS global forwarder in IdM. In the example procedure below, the IdM administrator ensures the absence of a DNS global forwarder to a DNS server with an Internet Protocol (IP) v4 address of **8.8.6.6** and IP v6 address of **2001:4860:4860:18800** on port **53**.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

- Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the **forwarders-absent.yml** Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-absence-of-a-global-forwarder.yml
- 4. Open the **ensure-absence-of-a-global-forwarder.yml** file for editing.
- 5. Adapt the file by setting the following variables:

- a. Change the name variable for the playbook to Playbook to ensure the absence of a global forwarder in IdM DNS.
- b. In the tasks section, change the name of the task to Ensure the absence of a DNS global forwarder to 8.8.6.6 and 2001:4860:4860:8800 on port 53.
- c. In the **forwarders** section of the **ipadnsconfig** portion:
 - i. Change the first **ip_address** value to the IPv4 address of the global forwarder: **8.8.6.6**.
 - ii. Change the second **ip_address** value to the IPv6 address of the global forwarder: **2001:4860:4860::8800**.
 - iii. Verify the **port** value is set to **53**.
- d. Verify the **state** is set to **absent**.This the modified Ansible playbook file for the current example:

- name: Playbook to ensure the absence of a global forwarder in IdM DNS

hosts: ipaserver become: true

tasks:

- name: Ensure the absence of a DNS global forwarder to 8.8.6.6 and

2001:4860:4860::8800 on port 53

ipadnsconfig: forwarders:

- ip address: 8.8.6.6

- ip address: 2001:4860:4860::8800

port: 53 state: absent

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-absence-of-a-global-forwarder.yml

Additional resources

 You can see more sample Ansible playbooks for the ansible-freeipa ipadnsconfig module in the README-dnsconfig.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of ipadnsconfig variables.

27.10. ENSURING DNS GLOBAL FORWARDERS ARE DISABLED IN IDM USING ANSIBLE

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure DNS Global Forwarders are disabled in IdM. In the example procedure below, the IdM administrator ensures that the forwarding policy for the global forwarder is set to **none**, which effectively disables the global forwarder.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig

2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Verify the contents of the **disable-global-forwarders.yml** Ansible playbook file which is already configured to disable all DNS global forwarders. For example:

\$ cat disable-global-forwarders.yml

- name: Playbook to disable global DNS forwarders

hosts: ipaserver become: true

tasks:

- name: Disable global forwarders.

ipadnsconfig:

forward_policy: none

4. Run the playbook:

\$ ansible-playbook -v -i inventory.file disable-global-forwarders.yml

Additional resources

• You can see more sample Ansible playbooks for the **ansible-freeipa ipadnsconfig** module in the **README-dnsconfig.md** Markdown file available in the /usr/share/doc/ansible-freeipa/directory. The file also contains the definitions of **ipadnsconfig** variables.

27.11. ENSURING THE PRESENCE OF A DNS FORWARD ZONE IN IDM USING ANSIBLE

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure the presence of a DNS Forward Zone in IdM. In the example procedure below, the IdM administrator ensures the presence of a DNS forward zone for **example.com** to a DNS server with an Internet Protocol (IP) address of **8.8.8.8**.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the forwarders-absent.yml Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-presence-forwardzone.yml
- 4. Open the **ensure-presence-forwardzone.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to ensure the presence of a dnsforwardzone in IdM DNS**.
 - b. In the tasks section, change the name of the task to Ensure presence of a dnsforwardzone for example.com to 8.8.8.8.
 - c. In the tasks section, change the ipadnsconfig heading to ipadnsforwardzone.
 - d. In the **ipadnsforwardzone** section:
 - i. Add the **ipaadmin_password** variable and set it to your IdM administrator password.
 - ii. Add the name variable and set it to example.com.
 - iii. In the forwarders section:
 - A. Remove the **ip_address** and **port** lines.
 - B. Add the IP address of the DNS server to receive forwarded requests by specifying it after a dash:

- 8.8.8.8

- iv. Add the **forwardpolicy** variable and set it to **first**.
- v. Add the **skip_overlap_check** variable and set it to **true**.
- vi. Change the **state** variable to **present**.

This the modified Ansible playbook file for the current example:

- name: Playbook to ensure the presence of a dnsforwardzone in IdM DNS

hosts: ipaserver become: true

tasks:

- name: Ensure the presence of a dnsforwardzone for example.com to 8.8.8.8

ipadnsforwardzone:

ipaadmin password: password01

name: example.com

forwarders: - 8.8.8.8

forwardpolicy: first skip overlap check: true

state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-presence-forwardzone.yml

Additional resources

You can see more sample Ansible playbooks for the ansible-freeipa ipadnsforwardzone
module in the README-dnsforwardzone.md Markdown file available in the
/usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of
ipadnsforwardzone variables.

27.12. ENSURING A DNS FORWARD ZONE HAS MULTIPLE FORWARDERS IN IDM USING ANSIBLE

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure a DNS Forward Zone in IdM has multiple forwarders. In the example procedure below, the IdM administrator ensures the DNS forward zone for **example.com** is forwarding to **8.8.8.8** and **4.4.4.4**.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- Open your inventory file and make sure that the IdM server that you want to configure is listed in the [ipaserver] section. For example, to instruct Ansible to configure server.idm.example.com, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the forwarders-absent.yml Ansible playbook file. For example:

\$ cp forwarders-absent.yml ensure-presence-multiple-forwarders.yml

- 4. Open the **ensure-presence-multiple-forwarders.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to ensure the presence of multiple forwarders in a dnsforwardzone in IdM DNS.**
 - b. In the tasks section, change the name of the task to Ensure presence of 8.8.8.8 and 4.4.4.4 forwarders in dnsforwardzone for example.com.
 - c. In the tasks section, change the ipadnsconfig heading to ipadnsforwardzone.
 - d. In the **ipadnsforwardzone** section:
 - i. Add the ipaadmin_password variable and set it to your IdM administrator password.
 - ii. Add the **name** variable and set it to **example.com**.
 - iii. In the **forwarders** section:
 - A. Remove the **ip_address** and **port** lines.
 - B. Add the IP address of the DNS servers you want to ensure are present, preceded by a dash:
 - 8.8.8.8 - 4.4.4.4
 - iv. Change the state variable to present.

This the modified Ansible playbook file for the current example:

```
    name: name: Playbook to ensure the presence of multiple forwarders in a dnsforwardzone in IdM DNS
hosts: ipaserver
```

become: true

tasks:

- name: Ensure presence of 8.8.8.8 and 4.4.4.4 forwarders in dnsforwardzone for example.com

ipadnsforwardzone:

ipaadmin_password: password01

name: example.com

forwarders:

- 8.8.8.8

- 4.4.4.4

state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-presence-multiple-forwarders.yml

Additional resources

You can see more sample Ansible playbooks for the ansible-freeipa ipadnsforwardzone
module in the README-dnsforwardzone.md Markdown file available in the
/usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of
ipadnsforwardzone variables.

27.13. ENSURING A DNS FORWARD ZONE IS DISABLED IN IDM USING ANSIBLE

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure a DNS Forward Zone is disabled in IdM. In the example procedure below, the IdM administrator ensures the DNS forward zone for **example.com** is disabled.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

- Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig
- 2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:
 - [ipaserver] server.idm.example.com
- 3. Make a copy of the forwarders-absent.yml Ansible playbook file. For example:
 - \$ cp forwarders-absent.yml ensure-disabled-forwardzone.yml
- 4. Open the **ensure-disabled-forwardzone.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the **name** variable for the playbook to **Playbook to ensure a dnsforwardzone is disabled in IdM DNS**.
 - b. In the **tasks** section, change the **name** of the task to **Ensure a dnsforwardzone for example.com is disabled**.

- c. In the tasks section, change the ipadnsconfig heading to ipadnsforwardzone.
- d. In the **ipadnsforwardzone** section:
 - i. Add the **ipaadmin_password** variable and set it to your IdM administrator password.
 - ii. Add the **name** variable and set it to **example.com**.
 - iii. Remove the entire forwarders section.
 - iv. Change the state variable to disabled.

This the modified Ansible playbook file for the current example:

- name: Playbook to ensure a dnsforwardzone is disabled in IdM DNS

hosts: ipaserver become: true

tasks:

- name: Ensure a dnsforwardzone for example.com is disabled ipadnsforwardzone:

ipaadmin password: password01

name: example.com state: disabled

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-disabled-forwardzone.yml

Additional resources

You can see more sample Ansible playbooks for the ansible-freeipa ipadnsforwardzone
module in the README-dnsforwardzone.md Markdown file available in the
/usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of
ipadnsforwardzone variables.

27.14. ENSURING THE ABSENCE OF A DNS FORWARD ZONE IN IDM USING ANSIBLE

This section describes how an Identity Management (IdM) administrator can use an Ansible playbook to ensure the absence of a DNS Forward Zone in IdM. In the example procedure below, the IdM administrator ensures the absence of a DNS forward zone for **example.com**.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsconfig directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsconfig

2. Open your inventory file and make sure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the forwarders-absent.yml Ansible playbook file. For example:

\$ cp forwarders-absent.yml ensure-absence-forwardzone.yml

- 4. Open the **ensure-absence-forwardzone.yml** file for editing.
- 5. Adapt the file by setting the following variables:
 - a. Change the name variable for the playbook to Playbook to ensure the absence of a dnsforwardzone in IdM DNS.
 - b. In the tasks section, change the name of the task to Ensure the absence of a dnsforwardzone for example.com.
 - c. In the **tasks** section, change the **ipadnsconfig** heading to **ipadnsforwardzone**.
 - d. In the **ipadnsforwardzone** section:
 - i. Add the **ipaadmin password** variable and set it to your IdM administrator password.
 - ii. Add the **name** variable and set it to **example.com**.
 - iii. Remove the entire forwarders section.
 - iv. Leave the state variable as absent.

This the modified Ansible playbook file for the current example:

- name: Playbook to ensure the absence of a dnsforwardzone in IdM DNS

hosts: ipaserver become: true

tasks:

- name: Ensure the absence of a dnsforwardzone for example.com ipadnsforwardzone:

ipaadmin password: password01

name: example.com

state: absent

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-absence-forwardzone.yml

Additional resources

You can see more sample Ansible playbooks for the ansible-freeipa ipadnsforwardzone
module in the README-dnsforwardzone.md Markdown file available in the
/usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of
ipadnsforwardzone variables.

CHAPTER 28. USING ANSIBLE TO MANAGE DNS RECORDS IN IDM

This chapter describes how to manage DNS records in Identity Management (IdM) using an Ansible playbook. As an IdM administrator, you can add, modify, and delete DNS records in IdM. The chapter contains the following sections:

- Ensuring the presence of A and AAAA DNS records in IdM using Ansible
- Ensuring the presence of A and PTR DNS records in IdM using Ansible
- Ensuring the presence of multiple DNS records in IdM using Ansible
- Ensuring the presence of multiple CNAME records in IdM using Ansible
- Ensuring the presence of an SRV record in IdM using Ansible

28.1. DNS RECORDS IN IDM

Identity Management (IdM) supports many different DNS record types. The following four are used most frequently:

Α

This is a basic map for a host name and an IPv4 address. The record name of an A record is a host name, such as **www**. The **IP Address** value of an A record is an IPv4 address, such as **192.0.2.1**. For more information about A records, see RFC 1035.

AAAA

This is a basic map for a host name and an IPv6 address. The record name of an AAAA record is a host name, such as **www**. The **IP Address** value is an IPv6 address, such as **2001:DB8::1111**. For more information about AAAA records, see RFC 3596.

SRV

Service (SRV) resource records map service names to the DNS name of the server that is providing that particular service. For example, this record type can map a service like an LDAP directory to the server which manages it.

The record name of an SRV record has the format _service._protocol, such as _ldap._tcp. The configuration options for SRV records include priority, weight, port number, and host name for the target service.

For more information about SRV records, see RFC 2782.

PTR

A pointer record (PTR) adds a reverse DNS record, which maps an IP address to a domain name.



NOTE

All reverse DNS lookups for IPv4 addresses use reverse entries that are defined in the **in-addr.arpa.** domain. The reverse address, in human-readable form, is the exact reverse of the regular IP address, with the **in-addr.arpa.** domain appended to it. For example, for the network address **192.0.2.0/24**, the reverse zone is **2.0.192.in-addr.arpa**.

The record name of a PTR must be in the standard format specified in RFC 1035, extended in RFC 2317, and RFC 3596. The host name value must be a canonical host name of the host for which you want to create the record.



NOTE

Reverse zones can also be configured for IPv6 addresses, with zones in the .ip6.arpa. domain. For more information about IPv6 reverse zones, see RFC 3596.

When adding DNS resource records, note that many of the records require different data. For example, a CNAME record requires a host name, while an A record requires an IP address. In the IdM Web UI, the fields in the form for adding a new record are updated automatically to reflect what data is required for the currently selected type of record.

28.2. COMMON IPA DNSRECORD-* OPTIONS

This section describes the options you can use when adding, modifying and deleting the most common DNS resource record types to Identity Management (IdM):

- A (IPv4)
- AAAA (IPv6)
- SRV
- PTR

In **Bash**, you can define multiple entries by listing the values in a comma-separated list inside curly braces, such as **--option={val1,val2,val3}**.

Table 28.1. General Record Options

Option	Description
ttl=number	Sets the time to live for the record.
structured	Parses the raw DNS records and returns them in a structured format.

Table 28.2. "A" record options

Option	Description	Examples
a- rec=ARECORD	Passes a single A record or a list of A records.	ipa dnsrecord-add idm.example.com host1a- rec=192.168.122.123
	Can create a wildcard A record with a given IP address.	ipa dnsrecord-add idm.example.com "*"a- rec=192.168.122.123 [a]

Option	Description	Examples
a-ip- address=strin g	Gives the IP address for the record. When creating a record, the option to specify the A record value is a-rec . However, when modifying an A record, the a-rec option is used to specify the current value for the A record. The new value is set with the a-ip-address option.	ipa dnsrecord-mod idm.example.coma-rec 192.168.122.123a-ip- address 192.168.122.124
[a] The example creates a wildcard A record with the IP address of 192.0.2.123.		

Table 28.3. "AAAA" record options

Option	Description	Example
aaaa- rec=AAAAREC ORD	Passes a single AAAA (IPv6) record or a list of AAAA records.	ipa dnsrecord-add idm.example.com www aaaa-rec 2001:db8::1231:5675
aaaa-ip- address=strin g	Gives the IPv6 address for the record. When creating a record, the option to specify the A record value is aaaa-rec. However, when modifying an A record, theaaaa-rec option is used to specify the current value for the A record. The new value is set with the-a-ip-address option.	ipa dnsrecord-mod idm.example.comaaaa-rec 2001:db8::1231:5675aaaa- ip-address 2001:db8::1231:5676

Table 28.4. "PTR" record options

Option	Description	Example
ptr- rec=PTRRECO RD		ipa dnsrecord-add 122.168.192.in-addr.arpa 4 ptr-rec server4.idm.example.com.
		\$ ipa dnsrecord-add 0.0.0.0.0.0.0.0.8.b.d.0.1.0.0.2.i p6.arpa. 1.1.1.0.0.0.0.0.0.0.0.0.0.0.0 ptr-rec server2.idm.example.com.
ptr- hostname=stri ng	Gives the host name for the record.	

Table 28.5. "SRV" Record Options

Option	Description	Example
rec=SRVRECORD Passes a single SRV record or a list of SRV records. In the examples on the right, _ldaptcp defines the service type and the connection protocol for the SRV record. TheSrV-reC option defines the priority, weight, port, and target values. The weight values of 51 and 49 in the examples add up to 100 and represent the probability, in percentages, that a particular record is used.	# ipa dnsrecord-add idm.example.com _ldaptcpsrv-rec="0 51 389 server1.idm.example.com."	
	# ipa dnsrecord-add server.idm.example.com _ldaptcp srv-rec="1 49 389 server2.idm.example.com."	
srv- priority=number	Sets the priority of the record. There can be multiple SRV records for a service type. The priority (0 - 65535) sets the rank of the record; the lower the number, the higher the priority. A service has to use the record with the highest priority first.	# ipa dnsrecord-mod server.idm.example.com _ldaptcp srv-rec="1 49 389 server2.idm.example.com."srv- priority=0
srv- weight=number	Sets the weight of the record. This helps determine the order of SRV records with the same priority. The set weights should add up to 100, representing the probability (in percentages) that a particular record is used.	# ipa dnsrecord-mod server.idm.example.com _ldaptcp srv-rec="0 49 389 server2.idm.example.com."srv- weight=60
srv- port=number	Gives the port for the service on the target host.	# ipa dnsrecord-mod server.idm.example.com _ldaptcp srv-rec="0 60 389 server2.idm.example.com."srv- port=636
srv- target=string	Gives the domain name of the target host. This can be a single period (.) if the service is not available in the domain.	

Additional resources

• For more information on how to use **ipa dnsrecord-add** and which DNS record types are supported by IdM, run the **ipa dnsrecord-add --help** command.

28.3. ENSURING THE PRESENCE OF A AND AAAA DNS RECORDS IN IDM USING ANSIBLE

This section shows how an Identity Management (IdM) administrator can use an Ansible playbook to ensure that A and AAAA records for a particular IdM host are present. In the example used in the procedure below, an IdM administrator ensures the presence of A and AAAA records for **host1** in the **idm.example.com** DNS zone.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.
- The idm.example.com zone exists and is managed by IdM DNS. For more information about adding a primary DNS zone in IdM DNS, see Using Ansible playbooks to manage IdM DNS zones .

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsrecord

2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **ensure-A-and-AAAA-records-are-present.yml** Ansible playbook file. For example:

\$ cp ensure-A-and-AAAA-records-are-present.yml ensure-A-and-AAAA-records-are-present-copy.yml

- 4. Open the ensure-A-and-AAAA-records-are-present-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsrecord** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **zone_name** variable to **idm.example.com**.
 - In the **records** variable, set the **name** variable to **host1**, and the **a_ip_address** variable to **192.168.122.123**.
 - In the **records** variable, set the **name** variable to **host1**, and the **aaaa_ip_address** variable to **::1**.

This is the modified Ansible playbook file for the current example:

- name: Ensure A and AAAA records are present

hosts: ipaserver become: true gather_facts: false

tasks:

Ensure A and AAAA records are present

- name: Ensure that 'host1' has A and AAAA records.

ipadnsrecord:

ipaadmin_password: Secret123

zone_name: idm.example.com

records:

- name: host1

a_ip_address: 192.168.122.123

- name: host1

aaaa_ip_address: ::1

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-A-and-AAAA-records-are-present-copy.yml

Additional resources

- For more information on A and AAAA records, see DNS records in IdM.
- You can see more sample Ansible playbooks for the **ansible-freeipa ipadnsrecord** module in the **README-dnsrecord.md** Markdown file available in the /usr/share/doc/ansible-freeipa/directory. The file also contains the definitions of the **ipadnsrecord** variables.
- You can see sample Ansible playbooks for the ipadnsrecord module in the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory.

28.4. ENSURING THE PRESENCE OF A AND PTR DNS RECORDS IN IDM USING ANSIBLE

This section shows how an Identity Management (IdM) administrator can use an Ansible playbook to ensure that an A record for a particular IdM host is present, with a corresponding PTR record. In the example used in the procedure below, an IdM administrator ensures the presence of A and PTR records for host1 with an IP address of 192.168.122.45 in the idm.example.com zone.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.
- The idm.example.com DNS zone exists and is managed by IdM DNS. For more information about adding a primary DNS zone in IdM DNS, see Using Ansible playbooks to manage IdM DNS zones.

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsrecord

2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **ensure-dnsrecord-with-reverse-is-present.yml** Ansible playbook file. For example:

\$ cp ensure-dnsrecord-with-reverse-is-present.yml ensure-dnsrecord-with-reverse-is-present-copy.yml

- 4. Open the ensure-dnsrecord-with-reverse-is-present-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsrecord** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **name** variable to **host1**.
 - Set the **zone_name** variable to **idm.example.com**.
 - Set the **ip_address** variable to **192.168.122.45**.
 - Set the create_reverse variable to yes.
 This is the modified Ansible playbook file for the current example:

- name: Ensure DNS Record is present.

hosts: ipaserver become: true gather_facts: false

tasks:

Ensure that dns record is present

- ipadnsrecord:

ipaadmin_password: Secret123

name: host1

zone_name: idm.example.com ip address: 192.168.122.45

create_reverse: yes
state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-dnsrecord-with-reverse-is-present-copy.yml

Additional resources

- For more information on A and PTR DNS records, see DNS records in IdM.
- You can see more sample Ansible playbooks for the ansible-freeipa ipadnsrecord module in the README-dnsrecord.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the ipadnsrecord variables.

• You can see sample Ansible playbooks for the **ipadnsrecord** module in the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory.

28.5. ENSURING THE PRESENCE OF MULTIPLE DNS RECORDS IN IDM USING ANSIBLE

This section shows how an Identity Management (IdM) administrator can use an Ansible playbook to ensure that multiple values are associated with a particular IdM DNS record. In the example used in the procedure below, an IdM administrator ensures the presence of multiple A records for **host1** in the **idm.example.com** DNS zone.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.
- The idm.example.com zone exists and is managed by IdM DNS. For more information about adding a primary DNS zone in IdM DNS, see Using Ansible playbooks to manage IdM DNS zones.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory:
 - \$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsrecord
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:
 - [ipaserver] server.idm.example.com
- 3. Make a copy of the ensure-presence-multiple-records.yml Ansible playbook file. For example:
 - \$ cp ensure-presence-multiple-records.yml ensure-presence-multiple-records-copy.yml
- 4. Open the ensure-presence-multiple-records-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsrecord** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - In the records section, set the name variable to host1.
 - In the **records** section, set the **zone name** variable to **idm.example.com**.
 - In the **records** section, set the **a_rec** variable to **192.168.122.112** and to **192.168.122.122**.
 - Define a second record in the **records** section:
 - Set the **name** variable to **host1**.

- Set the **zone_name** variable to **idm.example.com**.
- Set the aaaa rec variable to ::1.

This is the modified Ansible playbook file for the current example:

- name: Test multiple DNS Records are present.

hosts: ipaserver become: true gather_facts: false

tasks:

Ensure that multiple dns records are present

- ipadnsrecord:

ipaadmin_password: Secret123

records:

- name: host1

zone_name: idm.example.com a rec: 192.168.122.112

a_rec: 192.168.122.112

- name: host1

zone_name: idm.example.com

aaaa rec: ::1

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-presence-multiple-records-copy.yml

Additional resources

- For more information on A records in DNS, see DNS records in IdM.
- You can see more sample Ansible playbooks for the ansible-freeipa ipadnsrecord module in the README-dnsrecord.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the ipadnsrecord variables.
- You can see sample Ansible playbooks for the **ipadnsrecord** module in the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory.

28.6. ENSURING THE PRESENCE OF MULTIPLE CNAME RECORDS IN IDM USING ANSIBLE

A Canonical Name record (CNAME record) is a type of resource record in the Domain Name System (DNS) that maps one domain name, an alias, to another name, the canonical name.

You may find CNAME records useful when running multiple services from a single IP address: for example, an FTP service and a web service, each running on a different port.

This section shows how an Identity Management (IdM) administrator can use an Ansible playbook to ensure that multiple CNAME records are present in IdM DNS. In the example used in the procedure below, **host03** is both an HTTP server and an FTP server. The IdM administrator ensures the presence

of the www and ftp CNAME records for the host03 A record in the idm.example.com zone.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.
- The idm.example.com zone exists and is managed by IdM DNS. For more information about adding a primary DNS zone in IdM DNS, see Using Ansible playbooks to manage IdM DNS zones.
- The host03 A record exists in the idm.example.com zone.

Procedure

- 1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory:
 - $\$\ cd\ /usr/share/doc/ansible-freeipa/playbooks/dnsrecord$
- 2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

- 3. Make a copy of the **ensure-CNAME-record-is-present.yml** Ansible playbook file. For example:
 - $\$\ cp\ ensure-\text{CNAME-record-is-present.yml}\ ensure-\text{CNAME-record-is-present-copy.yml}$
- 4. Open the ensure-CNAME-record-is-present-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsrecord** task section:
 - (Optional) Adapt the description provided by the **name** of the play.
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **zone name** variable to **idm.example.com**.
 - In the **records** variable section, set the following variables and values:
 - Set the **name** variable to **www**.
 - Set the **cname hostname** variable to **host03**.
 - Set the **name** variable to **ftp**.
 - Set the **cname_hostname** variable to **host03**.

This is the modified Ansible playbook file for the current example:

- name: Ensure that 'www.idm.example.com' and 'ftp.idm.example.com' CNAME records

point to 'host03.idm.example.com'.

hosts: ipaserver become: true gather_facts: false

tasks:

- ipadnsrecord:

ipaadmin_password: Secret123 zone_name: idm.example.com

records: - name: www

cname_hostname: host03

- name: ftp

cname_hostname: host03

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-CNAME-record-is-present.yml

Additional resources

- You can see more sample Ansible playbooks for the ansible-freeipa ipadnsrecord module in the README-dnsrecord.md Markdown file available in the /usr/share/doc/ansible-freeipa/ directory. The file also contains the definitions of the ipadnsrecord variables.
- You can see sample Ansible playbooks for the **ipadnsrecord** module in the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory.

28.7. ENSURING THE PRESENCE OF AN SRV RECORD IN IDM USING ANSIBLE

A DNS service (SRV) record defines the hostname, port number, transport protocol, priority and weight of a service available in a domain. In Identity Management (IdM), you can use SRV records to locate IdM servers and replicas.

This section shows how an Identity Management (IdM) administrator can use an Ansible playbook to ensure that an SRV record is present in IdM DNS. In the example used in the procedure below, an IdM administrator ensures the presence of the **_kerberos._udp.idm.example.com** SRV record with the value of **10 50 88 idm.example.com** This sets the following values:

- It sets the priority of the service to 10.
- It sets the weight of the service to 50.
- It sets the port to be used by the service to 88.

Prerequisites

- You have installed the ansible-freeipa package on the Ansible controller. This is the host on which you execute the steps in the procedure.
- You know the IdM administrator password.

• The idm.example.com zone exists and is managed by IdM DNS. For more information about adding a primary DNS zone in IdM DNS, see Using Ansible playbooks to manage IdM DNS zones .

Procedure

1. Navigate to the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory:

\$ cd /usr/share/doc/ansible-freeipa/playbooks/dnsrecord

2. Open your inventory file and ensure that the IdM server that you want to configure is listed in the **[ipaserver]** section. For example, to instruct Ansible to configure **server.idm.example.com**, enter:

[ipaserver] server.idm.example.com

3. Make a copy of the **ensure-SRV-record-is-present.yml** Ansible playbook file. For example:

\$ cp ensure-SRV-record-is-present.yml ensure-SRV-record-is-present-copy.yml

- 4. Open the ensure-SRV-record-is-present-copy.yml file for editing.
- 5. Adapt the file by setting the following variables in the **ipadnsrecord** task section:
 - Set the **ipaadmin_password** variable to your IdM administrator password.
 - Set the **name** variable to **_kerberos._udp.idm.example.com**.
 - Set the **srv_rec** variable to '10 50 88 idm.example.com'.
 - Set the zone_name variable to idm.example.com.
 This the modified Ansible playbook file for the current example:

- name: Test multiple DNS Records are present.

hosts: ipaserver become: true gather_facts: false

tasks:

Ensure a SRV record is present

- ipadnsrecord:

ipaadmin_password: Secret123

name: _kerberos._udp.idm.example.com srv_rec: '10 50 88 idm.example.com' zone_name: idm.example.com

state: present

- 6. Save the file.
- 7. Run the playbook:

\$ ansible-playbook -v -i inventory.file ensure-SRV-record-is-present.yml

Additional resources

- For more information on SRV records, see DNS records in IdM.
- You can see more sample Ansible playbooks for the **ansible-freeipa ipadnsrecord** module in the **README-dnsrecord.md** Markdown file available in the /usr/share/doc/ansible-freeipa/directory. The file also contains the definitions of the **ipadnsrecord** variables.
- You can see sample Ansible playbooks for the **ipadnsrecord** module in the /usr/share/doc/ansible-freeipa/playbooks/dnsrecord directory.