



IST/Switch Table Reference Guide

V7.6.1
December 2013
XTRG1213

Table of Contents

Chapter 1

Introduction	9
Purpose of this Document	9
How this Manual is Organized	9
Related Documents	9
Revision Log	10

Chapter 2

Table Group Overview	12
Group Descriptions	12
ATM Group	12
Authorization Group	14
CMS Group	14
Currency Group	15
EMV Group	15
POS Group	15
Report Group	17
SAF Group	17
Settlement Group	17
Switch Group	17
Oasis Authentication Service Group	18

Chapter 3

ATM Tables	19
Table Descriptions	19
ATM	19
ATMAVAIL	27

ATM CASSETTE CONFIGURATION	28
ATM CASSETTE COUNTER	29
ATM CASSETTE LIST	30
ATM COUNTERS	31
ATMDESKEYS	32
ATM DISPENSE CONFIGURATION	34
ATM DISPENSE ITEM	35
ATM DISPENSE LIST(BILL TABLE)	35
ATM DEVICE STATE	36
ATMEJCAPTURE	39
ATM_EJOURNAL_LOG	40
ATM FIT	41
ATM FIT ENTRY	42
ATM FIT LIST	44
ATMGROUP	45
ATMKEYCHG	46
ATM_LOG	47
ATMLOG_CTRL	48
ATM_RKM_CERT	50
ATM_RKM_PK	52
ATMSDESC	53
ATMSTATUS	54
ATMSUPCARD	55
ATM TOTALS	56
DEV_SURCHARGE	57
INST_RKM_CERT	58
INST_RKM_CERT_REQ	59
INST_RKM_PK	60
MCPATMCFG	62
SURCHARGE_RATE	64

Chapter 4

Authorization Tables	65
Table Descriptions	65

IST_ACCOUNT	65
IST_ACCUM_AMOUNT	67
IST_ACCUM_COUNT	68
IST_BRANCH	69
IST_CARD	70
IST_CARDSEQ	71
IST_CARDTYPE	72
IST_CUSTOMER	74
ISTMAPDB	75
IST_ENTITY_REL	76
IST_ISS_ENTITY	78
IST_LIMIT_AMOUNT	79
IST_LIMIT_COUNT	80
IST_LOGHIST	81
IST_PIN	83
IST_PINHIST	84
IST_PIN_METHOD	85
IST_PIN_TYPE	85
IST_STATUS	86
IST_TXNCLASS	87
IST_TXNCLASS_DESC	88
IST_TXNDESC	88

Chapter 5

Currency Tables	89
Table Descriptions	89
ISTCURPNT	89
ISTCURR	90
ISTCURSPR	91

Chapter 6

CMS Tables	92
Table Descriptions	92
IST_CMS_ACT	92
IST_CMS_CARD	94

Chapter 7

EMV Tables	96
Table Descriptions	96
CAMKEYS	96
EMVSTIPCHK	103

Chapter 8

OAS Tables	106
Table Descriptions	106
OAS_AUDIT2	106
OAS_COUNTER	108
OAS_USER	108

Chapter 9

POS Tables	110
Table Descriptions	110
ACQ_ENTITY	110
ACQ_ENTITY_ADDRESS	120
ALLOWANCE	121
ALLW_CARD_SCHEME	121
ALLW_CURR	122
ALLW_LANG	122
ALLW_MCC	123

ALLW_POS_FORMAT	124
ALLW_FLOOR_LIM	125
ALT_MERCHANT_ID	126
CARD_SCHEME	127
COUNTRY	127
COUNTY	128
CURRENCY_CODE	129
ENTITY_LEVEL	129
INSTITUTION	130
LANGUAGE	131
MASTER_ADDRESS	131
GLOBAL_SEQ_CTRL	133
GLOBAL_VALUE_CTRL	133
MCC	134
MERCHANT_TYPE	134
POS_MSG_BRAND	135
POS_MSG_FORMAT	135
POS_OPEN_HOUR	136
POS_REFNUM	137
POS_SHC2POS_RC	138
POS_TERM_CAP_ADD	139
POS_TERM_CAP_AIR	143
POS_TERM_CAP_CHIP	144
POS_BATCH	146
POS_BATCH_ID	151
POS_TERM_CAP_LINE	152
POS_TERM_CAP_TRANS	153
POS_TERM_TYPE	156
POSLOG_ERR	162
POSLOG_EXTRACT_FILE	164
POSLOG_EXTRACT	165
POSLOG_XMF	166
POS_EXTRACT_TMP	167
POSLOG_500	175
PROCESS_BATCH	177

BATCH_STATUS	177
PROVINCE	178
TERMINAL	178
TERMINAL_BDK	181
POS_TERM_KEYS	182
POS_TKI_KEYS	184
POS_TKI_AUDIT	185

Chapter 10

Report Tables **186**

Table Descriptions	186
NETFEES	186
REPBINHDR	189
REPORT	190
REPORTS	191

Chapter 11

SAF Tables **192**

Table Descriptions	192
ISTREPLAYTAB	192
IST_SAFDB	194
IST_SAFHIST	195

Chapter 12

Settlement Table **196**

Table Descriptions	196
ISTACCUMU	196
STD500	200

Chapter 13

SHC Tables.....	203
Table Descriptions	203
AKB_KEYS	203
AUTHNUMBER.....	204
HOTRANGE	205
INST_BUSINESS_DAY.....	206
INST_PROFILE.....	210
ISS_PROFILE.....	213
ISTTRIG	215
LATERESPLOG	218
REVLOG.....	219
SHC600LOG.....	221
SHCBIN.....	232
SHCCARD	237
SHCCHIPLOG	238
SHCGENERICLOG.....	241
SHCEXTBINDB.....	244
SHCKEYS.....	245
SHCLOG_ADD.....	252
SHCLOG_CHEQUE	255
SHCLOG_IFD.....	258
SHCLOG.....	259
SHCLOG_VFRS	271
SHCMERCHANT	272
VISA_SPECIFIC_DATA.....	273
BINROUTE	274
Index.....	276



Introduction

Purpose of this Document

The IST/Switch product relies on the stored configuration values in the various system tables. Values may be entered through a GUI interface or through a cursor interface, depending on product version. This document provides descriptions of the database tables, including field names, field types, field sizes and field descriptions.

How this Manual is Organized

This manual is organized as a reference manual. Tables' descriptions are followed by field descriptions. Tables are organized alphabetically within their respective groups, but not all tables require configuration for certain product installations.

Individual products require configuration of the tables identified in their respective groups. Refer to the list of these groups in the first section.

Related Documents

Readers should refer to the following documents for information that supplements this manual:

IST Documents:

- *IST/Switch Administration Guide* - This manual provides a technical description of system installation, configuration and administration.
- *Debit & Credit Switch (DCS) Subsystem Guide* - This manual provides a technical description of the system architecture, server relationships and configuration forms. Note that the forms described in the *Debit & Credit Switch (DCS) Subsystem Guide* do not necessarily have a one to one relationship with the tables described in this manual.

Revision Log

Date	Effective W/ Version	Change
December 2013	7.6.1	Added the following tables: • “ATMLOG_CTRL” on page 48 • “ATMEJCAPTURE” on page 39 Updated the field description of FUNCTION_CODE in ATM_LOG table.
October 2013	7.6.1	Added “OAS Tables” on page 106 .
July 2013	7.6.1	Added the following tables: • “POS_TKI_KEYS” on page 184. • “POS_TKI_AUDIT” on page 185. Updated the following tables: • POS_TERM_KEYS with TKI_SUPPORT and TKI_STATE fields. • TERMINAL with SERIAL_NUMBER field.
May 2013	7.6.1	Added the following table: • “AKB_KEYS” on page 203.
November 2012	7.6.1	• Updated the FUNC_FLAG field on page 24. • Added RECYCLE_COUNT and PREV_RECYCLE_COUNT fields in ATMCASSETTECOUNTER Table
August 2012	7.6.1	Added the following table: • “ATM_LOG Table” on page 47.
July 2012	7.6.1	• Added MAX_COIN_DISPENSE field in ATM table on page 26. • Updated the FUNC_FLAG field on page 24.
April 2012	7.6.1	Updated the following table: • “POS_TERM_CAP_CHIP” on page 144.

Date	Effective W/ Version	Change
March 2012	7.6.1	Updated the following table: • “ATM Table” on page 19.
November 2011	7.6.1	Updated the following table: • “BINROUTE” on page 274. • “INST_PROFILE” on page 210. • “SHCEXTBINDB” on page 244.
November 2010	7.6.1	Added the following tables: • “ATM CASSETTE CONFIGURATION” on page 28. • “ATM CASSETTE COUNTER” on page 29. • “ATM CASSETTE LIST” on page 30. • “ATM COUNTERS” on page 31. • “ATMDESKEYS” on page 32. • “ATM DEVICE STATE ” on page 36. • “ATM DISPENSE CONFIGURATION” on page 34. • “ATM DISPENSE ITEM” on page 35. • “ATM DISPENSE LIST(BILL TABLE)” on page 35. • “ATM FIT” on page 41. • “ATM FIT ENTRY” on page 42. • “ATM FIT LIST” on page 44. • “ATM TOTALS” on page 56. Updated the following table: • “ATM” on page 19. Updated the list of tables names in section “ATM Group” on page 12.



Table Group Overview

Group Descriptions

The tables in IST/Switch are divided into groups by products. Some tables span several different products, while other tables are product-specific. The division of tables into groups is transparent to the end user who configures tables via a GUI or cursor-based interface. The product groups and their respective descriptions follow:

ATM Group

These tables facilitate customizing and maintaining an ATM (Automated Teller Machine) network.

- ATM
- ATMAVAIL
- ATMCASSETTECFG
- ATMCASSETTECOUNTER
- ATMCASSETTELIST
- ATMCOUNTERS
- ATMDESC
- ATMDESKEYS
- ATMDISPENSECFG
- ATMDISPENSEITEM
- ATMDISPENSELIST
- ATMDEVICESTATE
- ATM_EJOURNAL_LOG
- ATMFIT
- ATMFITENTRY

ATMFITLIST
ATMFITSELECT
ATMGROUP
ATMKEYCHG
ATM_RKM_CERT
ATM_RKM_PK
ATMSDESC
ATMSTATUS
ATMSUPCARD
ATMTOTALS
DEV_SURCHARGE
DEVICEKEY
INST_RKM_CERT
INST_RKM_CERT_REQ
INST_RKM_PK
MCPATMCFG
SURCHARGE_RATE

Authorization Group

These tables are used for authorizing transaction processing for cardholders. This independent module validates cardholder account information in order to approve transaction requests.

IST_ACCOUNT
 IST_ACCUM_AMOUNT
 IST_ACCUM_COUNT
 IST_BRANCH
 IST_CARD
 IST_CARDSEQ
 IST_CARDTYPE
 IST_CUSTOMER
 ISTMAPDB
 IST_ENTITY_REL
 IST_ISS-ENTITY
 IST_LIMIT_AMOUNT
 IST_LIMIT_COUNT
 IST_LOGHIST
 IST_PIN
 IST_PINHIST
 IST_PIN_METHOD
 IST_PIN_TYPE
 IST_STATUS
 IST_TXNCLASS
 IST_TXNCLASS_DESC
 IST_TXNDESC

CMS Group

The Card Management System facilitates financial institutions' issuance and maintenance of bank cards.

IST_CMS_ACT
 IST_CMS_CARD

Currency Group

Description to be filled in:

ISTCURPNT

ISTCURR

ISTCURSPR

EMV Group

The EMV Group is required when configuring a system to support chip-card transactions.

CAMKEYS

EMVSTIPCHK

POS Group

The POS Group enables configuration of a Point of Sale network.

ACQ_ENTITY

ACQ_ENTITY_ADDRESS

ALLOWANCE

ALLW_CARD_SCHEME

ALLW_CURR

ALLW_LANG

ALLW_MCC

ALLW_POS_FORMAT

ALLW_FLOOR_LIM

ALT_MERCHANT_ID

CARD_SCHEME

COUNTRY

COUNTY

CURRENCY_CODE

ENTITY_LEVEL

INSTITUTION

LANGUAGE

MASTER_ADDRESS
GLOBAL_SEQ_CTRL
GLOBAL_VALUE_CTRL
MCC
MERCHANT_TYPE
POS_MSG_BRAND
POS_MSG_FORMAT
POS_OPEN_HOUR
POS_REFNUM
POS_SHC2POS_RC
POS_TERM_CAP_ADD
POS_TERM_CAP_AIR
POS_TERM_CAP_CHIP
POS_BATCH
POS_BATCH_ID
POS_TERM_CAP_LINE
POS_TERM_CAP_TRANS
POS_TERM_TYPE
POSLOG_ERR
POSLOG_EXTRACT_FILE
POSLOG_EXTRACT
POSLOG_XMF
POS_EXTRACT_TMP
POSLOG_500
PROVINCE
TERMINAL
TERMINAL_BDK
POS_TERM_KEYS

Report Group

The Reports subsystem allows transaction reports to be generated from the various database tables in the Report Group.

NETFEES
 REPBINHDR
 REPORT
 REPORTS

SAF Group

Description about the group to be filled in.

ISTREPLAYTAB
 IST_SAFDB
 IST_SAFHIST

Settlement Group

The Settlement Group contains net debit and credit positions between issuers and acquirers. Settlement data for each transaction is stored and consolidated in a database which records the total financial activity and net settlement position for each institution.

ISTACCUMMU
 STD500

Switch Group

The Switch group of tables consists mainly of DCS tables which are used for transaction routing, logging, and processing among financial networks.

AUTHNUMBER
 HOTRANGE
 INST_BUSINESS_DAY
 INST_PROFILE
 ISS_PROFILE
 ISTTRIG
 LATERESPLOG
 REVLOG

SHC600LOG
SHCBIN
SHCCARD
SHCCHIPLOG
SHCGENERICLOG
SHCEXTBINDB
SHCKEYS
SHCLOG_ADD
SHCLOG_CHEQUE
SHCLOG_IFD
SHCLOG
SHCLOG_VFRS
VISA_SPECIFIC_DATA

Oasis Authentication Service Group

The Oasis Authentication Service group consists mainly of tables which are used to control user security for the GUI application for all IST products.

OAS_AUDIT2
OAS_COUNTER
OAS_USER

3

ATM Tables

Table Descriptions

ATM

ATM Table has the configuration for each Automatic Teller Machine.

ATM Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates the institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Indicates the group name to which the ATM belongs.
UNIT	NUMBER	3	Number of the configured ATM. Valid values are 001 to 999. Each ATMGROUP can handle 999 ATMs. Unit should be unique within the group. This number will be loaded to the ATM during the first load.
GOSERVICE	CHAR	1	Indicates if a "go in service" command is sent to the terminal during startup of the system. Possible values: Y and N (default).

ATM Table

Field Name	Type	Size	Description
MODEL	NUMBER		The manufacturer assigned model number of the ATM. Possible values are: 911: Diebold 911 emulation; two cassettes 912: Diebold 912 emulation; 2,3, or 4 cassettes Any 4 digit number for NCR & Triton
MAKE	CHAR	3	Indicates the manufacturer of the ATM. Possible values are: DBD: Diebold's TCS emulation NDC: NCR's NDC emulation TRN: Triton WND: Wincor NDC WDB: Wincor DBD
LOCAL_PIN	CHAR	1	Indicates if the ATM validates the PIN (Personal Identification Number). Possible values are: Y: To allow the ATM to validate the PIN N: Default. Do not allow the ATM to validate the PIN
ADD_TOTAL	CHAR	1	Indicates whether the terminal transaction processing will perform accumulation of transactions to ATMTOTALS table. Valid values are: Y: Default. Allow ATM to accumulate transaction totals N: Do not allow ATM to accumulate totals
TXN_ALLOW	CHAR	10	Indicates the types of transactions that are allowed to perform in the terminal. Possible values are Y and N for each transaction. Each slot is associated to a transaction as follows: Character 1: Withdrawal (WD) Character 2: Balance (BAL) Character 3: Deposit (DEP) Character 4: Transfer (TXF) Character 5: Payment (PAY)

ATM Table

Field Name	Type	Size	Description
MAXDISPENSE	NUMBER		Indicates the maximum number of bills to dispense on the whole. Any combination of bills from the supported cassettes will not exceed this value.
LOCATION	CHAR	25	Indicates the location of the ATM. The information in this field is used as the "Terminal Location" in the transaction. If "atm_acceptor_from_table" parameter is set as NO, this field is placed into "Acceptor Name" in the transaction request. The field may be used for informative purposes in reports.
GEO_LOC	CHAR	18	Indicates the geographic location of the terminal. The geographic location has the following structure: Country: ISO country code; 3 characters Province/State Code: 2 characters County Code: 3 characters Postal Code: 10 characters The field populates the "POS Geographic Location" in the transaction.
ACCEPTORNAME	CHAR	40	Indicates the acceptor name and location. The acceptor name has the following structure: ATM Location: 1-25 City Name: 26-38 Country Code: 39-40
H_LOCATION	CHAR	25	Informative field, not used in transaction processing. Its legacy used was to store the ATM location in non-english language.
LOGGING	CHAR	1	Indicates if the ATM system logs incoming/outgoing raw messages. Possible values are: Y - to log the messages N - Default; to avoid logging the messages If set as Y, the ATM System will save any message into ATMDUMP.DEBUG as received/sent to the terminal. WARNING: If set to 'N', raw messages from/to ATM will not be logged in IST/Switch.

ATM Table

Field Name	Type	Size	Description
TERMID	CHAR	8	Terminal Identification Number. The field is set in the transaction request message to identify the terminal.
TERM_COMP	CHAR	8	Field used only for Triton ATMs. Triton ATMs have 15 character terminal Id. The field is used to identify the terminal within the ATM system. The field is not placed in any internal IST/Switch field. International standards (VISA, MC) require only 8 characters.
WD_NO_RPT	NUMBER	1	Indicates whether the withdrawal transactions are allowed without receipt. Possible values are: 1/Y - allow withdrawal transactions without receipt 0/N - default; do not allow withdrawal transactions without receipt If set to Y, any withdrawal from an ATM is allowed even if there is any problem in the receipt printer.
TIME_OFFSET	NUMBER		Indicates the number of hours difference between the ATM and the IST/Switch locations. This field is useful when ATM is located in a different time zone from the server that runs the IST/Switch. Both positive and negative values are allowed.
MAC_REQUIRED	CHAR	1	Indicates if MAC is required or not. Valid values are: N - default; no MAC required Y/F - full MAC required S - selective MAC required (used only by NCR ATMs)

ATM Table

Field Name	Type	Size	Description
MAC_NCR_TXNREQ	CHAR	47	Indicates if selective MAC is required for NCR. Each character could be set as 1 or 0. 0 is the default value for all characters in the field.
MAC_NCR_TXNREPLY	CHAR	36	First character indicates if selective MAC is done for indicated messages (request, response, solicited status message, load, track fields and EMV).
MAC_NCR_SOLITSTAT	CHAR	11	Each character from the second position represents a field within the transaction request message.
MAC_NCR_OTHER	CHAR	4	Each character set as 1 indicates that the message field is considered to be part of the MAC calculation.
MAC_NCR_TRACK1	CHAR	6	
MAC_NCR_TRACK2	CHAR	6	
MAC_NCR_TRACK3	CHAR	11	
MAC_NCR_EMV	CHAR	5	

ATM Table

Field Name	Type	Size	Description
FUNC_FLAGS	CHAR	20	Sets processing configuration flags for the terminal. Possible values are Y and N. - Character 1 - Surcharge Confirmation; Possible values are Y/N. Default is Y. - Character 2 - Support of EMV/Chip card transactions; Possible values are Y/N. Default is N. - Character 3 - Not used. - Character 4 - Bunch Notes Acceptor allowed; Possible values are Y/N. Default is N, where, Y - BNA Supported A - Enhance BNA Supported. - Character 5 - VISA's remote terminal indicator; Possible values are Y/N. Default is N. - Character 6 - Disable Partial Reversal; Possible Values are Y/N. Default is N. - Character 7 - Minimum 4 Digit PIN; Possible Values Y/N. Default is N. - Character 8 - NDC Support 7 Cassettes; Possible values Y/N. Default is N. - Character 9 - EJ Supported; Possible values Y/N. Default is N. - Character 10 - Cheque Processing Flag; Possible Values are Y/N/B. Where, - N - No cheque processor (Default) - Y - Single Cheque processor available - B - Bunch cheque processor available.

ATM Table

Field Name	Type	Size	Description
			- Character 12 - Coin dispense supported. Possible values are Y/N. Default is N. Default 'N'. - Character 14 - Voice guidance flag. Possible values are Y/N. - Character 15 - Indicates if the ATM supports statement printing or not. Default is N. - Character 16 - Indicates if the ATM supports cash recycling or not. Default is N.
HDL_ACK	CHAR	1	Triton specific. Indicates whether or not the modem ACK is handled. Possible values are: N - default; do not handle ACK from modem Y - handle ACK from modem If modem is connected to the server through serial port, the flag has to be ON is a common communication configuration to handle modems with concentrator and converter hardware. If any hardware handles the modems with the dialup ATMs, it is possible that the modem ACK is not sent to the IST/Switch server.
PRIORITY_ROUTING	CHAR	32	Sets the VISA priority routing information. Possible values are VISA specific.
DISPENSE_TABLE_ID	NUMBER	8	ID of the dispenser table which should be used by the ATM.
CASSETTE_CFG_ID	NUMBER	8	ID of the cassette configuration used by the ATM.
FIT_LIST_ID	NUMBER	8	ID of the list of FITs used by the ATM. The FIT_LIST_ID is used to query the data from the ATMFIT table.
CURRENCY	NUMBER	3	Default Acquirer Currency of the ATM.

ATM Table

Field Name	Type	Size	Description
INTERNAL_UNIT	NUMBER	8	Unique Number to identify ATM (Generated by the GUI).
MANUFACTURER	VARCHAR	25	Name of the manufacturer. Used by GUI.
EMULATION	VARCHAR	25	Name of emulation. Used by GUI.
MAX_COIN_DISPENSE	NUMBER	8	Indicates the maximum number of coins to dispense on the whole.

ATMAVAIL

The atmavail table records the data on the availability of each ATM unit. When the ATM changes its state from off-line to on-line, the information for the Begin Date and Begin Time fields is assigned. When the ATM changes its state from on-line to off-line (command 'go out of service' is received or the ATM is out of order), the End Date and the End Time fields are assigned (again, only in the shared memory). When the begin and end pairs of fields are assigned, a new record is inserted into the table.

ATMAVAIL Table

Field Name	Type	Size	Description
GROUP_NAME	VARCHAR2	10	Defines an ATM group name.
UNIT	NUMBER		The unit number of the ATM that is being configured. Maximum three digits. Unit must match the name of the ATM. For example, if your ATM is named atm0409, then Unit is 409.
BEGIN_DATE	DATE		This field stores the actual date of settlement of the transaction, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 15.
BEGIN_TIME	NUMBER		Defines the time of the ATM unit transition from the off-line state to the online state.
END_DATE	DATE		This field stores the actual date of settlement of the transaction, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 15.
END_TIME	NUMBER		This field displays the time at which the key change ended. The time format is HHMMSS, where HH represents the hour, MM represents the minute, and SS represents the second.
FAULT	NUMBER		Records the status number that describes the fault that generated the online to off-line state transition. The status numbers are described by the atmsdesc table.
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.

ATM CASSETTE CONFIGURATION

This table contains the ATM cassette configuration. Each record in this table is the configuration for a single cassette. All records for a given ATM are associated by the CASSETTE_CFG_ID on the ATM table.

ATMCASSETTECFG Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
CASSETTE_CFG_ID	NUMBER	8	Cassette Configuration ID (used to link a group of cassettes to ATM).
CASSETTE_NBR	NUMBER	8	Cassette number within group of cassettes.
ITEM_TYPE	NUMBER	8	Type of item in the cassette. This is used to represent the media type of the item that cassette holds (cash, tickets, coins etc).
DENOMINATION_ID	CHAR	1	ID of the denomination.
DENOMINATION	NUMBER/ AMOUNT	26,8	Value of the item in the cassette.
CURRENCY	NUMBER	3	Currency code of the item in cassette.
MAXDISPENSE	NUMBER	8	Maximum number of items which can be dispense from the cassette at one time.

ATM CASSETTE COUNTER

This table contains totals information by cassette number. Each ATM has one record for each cassette configured, in this table. The counters are updated during transaction processing to reflect the most current totals.

ATMCASSETTECOUNTER Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Group name to which the ATM belongs.
UNIT	NUMBER	3	Unit Number of the ATM (LUNO).
CASSETTE_NBR	NUMBER	8	Number of the cassette.
ITEMS_REJECTED	NUMBER	10	Number of bills rejected.
CASH_INC	MONEY		Amount of money added to cassette.
CASH_DEC	MONEY		Amount of money removed from the cassette.
CASH_OUT	MONEY		Amount of money dispensed from the cassette.
CASH_CUR_BAL	MONEY		Current balance to money in the cassette.
CASH_START_BAL	MONEY		Starting balance of cassette.
CASH_PREV_BAL	MONEY		Previous balance of cassette before the reset.
RESET_TIME	DATE TIME		Date, time when the cassette was reset.
RECYCLE_COUNT	NUMBER	10	Number of notes recycled.
PREV_RECYCLE_COUNT	NUMBER	10	Value previous to reset, number of notes recycled.

ATM CASSETTE LIST

This table is used only by the GUI to configure display of possible values for entry on the GUI field.

ATMCASSETTELIST Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Group to which the ATM belongs.
CASSETTE_CFG_ID	NUMBER	8	Cassette configuration ID (used to link a group of cassettes to ATM).
DESCRIPTION	VARCHAR2	100	Description of the cassette List ID.
NBR_OF_CASSETTES	NUMBER	3	Number of cassettes in list.
CASSETTE_CFG_TYPE	VARCHAR	50	Type of items in cassettes.

ATM COUNTERS

This table contains counters pertaining to the ATM, other than transaction totals.

ATMCOUNTERS Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Group name to which the ATM belongs.
UNIT	NUMBER	3	Unit Number of the ATM (LUNO).
CARDS_RETAIN	NUMBER	10	Number of cards retained.
FILM_RETAIN	NUMBER	10	Film retained at the ATM.
AFTER_HOUR_DEP	NUMBER	10	Number of after hour deposits.
RESET_TIME	DATE TIME		Date, time when the ATM was reset.

ATMDESKEYS

This table is used to store the terminal master key, pin encryption key and MAC key. There is one record for each terminal.

ATMDESKEYS Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Group name to which the ATM belongs.
UNIT	NUMBER	3	Unit Number of the ATM (LUNO).
TMK1	VARCHAR2	74	Terminal Master Key 1.
TMK2	VARCHAR2	74	Terminal Master Key 2.
TMKLEN	NUMBER	2	Length of Terminal Master Key. Possible Values: 16 32 (Default) 48
TMK1_CHK_DIGITS	VARCHAR2	16	Check digits for Terminal Master Key 1.
TMK2_CHK_DIGITS	VARCHAR2	16	Check digits for Terminal Master Key 2.
TPK1	VARCHAR2	74	Terminal PIN Key 1.
TPK2	VARCHAR2	74	Terminal PIN Key 2.
TPKLEN	NUMBER	2	Length of Terminal PIN Key. Possible Values: 16 32 (Default) 48

ATMDESKEYS Table

Field Name	Type	Size	Description
TPK1_CHK_DIGITS	VARCHAR2	16	Check digits for Terminal PIN Key 1.
TPK2_CHK_DIGITS	VARCHAR2	16	Check digits for Terminal PIN Key 2.
TAK1	VARCHAR2	74	Terminal MAC Key 1.
TAK2	VARCHAR2	74	Terminal MAC Key 2.
TAKLEN	NUMBER	2	Length of Terminal MAC Key. Possible Values: 16 32 (Default) 48
TAK1_CHK_DIGITS	VARCHAR2	16	Check digits for Terminal MAC Key 1.
TAK2_CHK_DIGITS	VARCHAR2	16	Check digits for Terminal MAC Key 2.
TMK	NUMBER	1	Current TMK in use. Possible Values: 1 or 2
TPK	NUMBER	1	Current TPK in use. Possible Values: 1 or 2
TAK	NUMBER	1	Current TAK in use. Possible Values: 1 or 2
TPK_TXN_THRES	NUMBER	10	Threshold after which TPK should be exchanged, 0 indicates no dynamic exchange.
TPK_TXN_COUNT	NUMBER	10	Current count of TPK use.
TPK_CHANGE_HOUR	NUMBER	6	Number of hours after which to perform TPK exchange, 0 indicate no dynamic exchange.
TPK_DATE_TIME	DATE TIME		Date and time the TPK was last exchanged.

ATMDESKEYS Table

Field Name	Type	Size	Description
TAK_TXN_THRES	NUMBER	10	Threshold after which TAK should be exchanged, 0 indicates no dynamic exchange.
TAK_TXN_COUNT	NUMBER	10	Current count of TAK use.
TAK_CHANGE_HOUR	NUMBER	6	Number of hours after which to perform TAK exchange, 0 indicate no dynamic exchange.
TAK_DATE_TIME	DATE TIME		Date and time the TAK was last exchanged.

ATM DISPENSE CONFIGURATION

Defines the different amounts which can be dispensed.

ATMDISPENSECFG Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
DISPENSE_TABLE_ID	NUMBER	8	ID of the Dispense table.
AMOUNT	NUMBER/ AMOUNT	26.8	Value to be dispensed.
ITEMTYPE	NUMBER	8	Type of the item.
CURRENCY	NUMBER	3	Currency code of the items.
DISPENSE_CFG_ID	NUMBER	10	ID for this dispense amount (unique/generated by GUI).

ATM DISPENSE ITEM

This table defines the list of cassettes and number of item to dispense from a cassette for the DISPENSE_CFG_ID.

ATMDISPENSEITEM Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
DISPENSE_CFG_ID	NUMBER	8	ID of the Dispense Value.
CASSETTE_NBR	NUMBER	8	Number of the cassette.
UNITS_TO_DISPENSE	NUMBER	8	Number of the units to dispense.

ATM DISPENSE LIST(BILL TABLE)

This table defines a list of dispense tables for a given institution groupname, cassette_cfg_id. This table is used only by the GUI.

ATMDISPENSELIST Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Group name to which the ATM belongs.
CASSETTE_CFG_ID	NUMER	8	Cassette Configuration ID (link a cassettes configuration which this dispense table is based on).
DISPENSE_TABLE_ID	NUMBER	8	ID of the Dispense Table cfg (unique/generated by GUI).
DESCRIPTION	VARCHAR2	100	Description of the Dispense table.

ATM DEVICE STATE

The data in this table represents the current state of the ATM. Any transient data that needs to be maintained for transaction processing at the ATM is saved here. This record is created along with the ATM record with default values.

NOTE: The fields **TPDU**, **STATETABLENAME** and **STATETABLEVER** should be provided by the user on the GUI.

ATMDEVICESTATE Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Group name to which the ATM belongs.
UNIT	NUMBER	3	Number of the configured ATM. Valid values are 001 to 999. Each ATMGROUP can handle 999 ATMs Unit should be unique within the group. This number will be loaded to the ATM during the first load.
FLAG1	NUMBER	10	Flags for saving state. Each bit represents a Boolean value that can be queried, set or unset.
FLAG2	NUMBER	10	Future use.
FLAG3	NUMBER	10	Future use.
STATUS1	NUMBER	10	Status is an internal number that represents a fault on the ATM.
STATUS2	NUMBER	10	ATM server maintains 5 status values.
STATUS3	NUMBER	10	
STATUS4	NUMBER	10	
STATUS5	NUMBER	10	

ATMDEVICESTATE Table

Field Name	Type	Size	Description
DEVICE_FITNESS	NUMBER	10	Flags for holding the fitness of each device.
CASSETTE_FITNESS	NUMBER	10	Flags for holding the fitness of each of the dispenser cassettes. Each bit represents a single cassette.
CONFIGID	NUMBER	10	Configuration ID.
LAST_CMDTYPE	NUMBER	10	Last command sent to the ATM.
LAST_TXNTYPE	NUMBER	10	Type of transaction last performed.
OAR_SCREEN	NUMBER	10	Screen number updated by the OAR server.
LASTMSG_TIME	NUMBER	10	Timestamp of the last message from the ATM.
TRACE	NUMBER	10	Current running trace number for the device.
TPDU	VARCHAR	8	Transport Protocol Data Unit.
EMV_IDENTIFIER	VARCHAR	6	EMV identifier, indicating which type of EMV application is running on the ATM.
LANGUAGE	NUMBER	10	Language offset used in the state table on the ATM.
PCODE	NUMBER	10	Processing code from the last message.
RESPCODE	NUMBER	10	Response code from the last message.
ACCT_NUM	VARCHAR2	32	Account Number used for OAR transactions.
ACCT_NUM2	VARCHAR2	32	Account number used for OAR transactions.
TVN	VARCHAR2	32	Terminal Verification number.
LUNO	VARCHAR2	10	Logical Unit Number.
CAP_DATE	NUMBER	8	Business date of the ATM.
MSG_COORD_NUM	CHAR	1	Message Coordination Number.

ATMDEVICESTATE Table

Field Name	Type	Size	Description
OAR_LINE	NUMBER	10	Data added by the OAR server.
MODEL_SPECIFIC	VARCHAR2	50	Any model specific data goes in here. For example: Triton uses it to save the transaction code.
NODE	VARCHAR2	30	Node name.
STATETABLENAME	VARCHAR2	64	Name of the state table used by the ATM.
STATETABLEVER	NUMBER	8	Version number of the State table.
FAULT	NUMBER	8	Current fault value for monitor.
SEVERITY	NUMBER	8	Current severity value Used by monitor.
AVAILDATE	DATE		Date ATM last became available.
AVAILTIME	NUMBER	8	Time ATM last became available.

ATMEJCAPTURE

ATMEJCAPTURE Table

Field Name	Type	Size	Description
INSTITUTIONID	VARCHAR2	10	Indicates the institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Indicates the group name to which the ATM belongs.
UNIT	NUMBER		Indicates the number of configured ATM.
RECORDDATE	DATE		Indicates the date when the EJ Data is logged into database.
RECORDTIME	NUMBER		Indicates the date when the EJ Time is logged into database.
SEQNOSTART	NUMBER		Stores the record (message) number from where the download is started.
SEQNOLAST	NUMBER		Stores the record (message) number where the download is completed.
RECORDTYPE	NUMBER		Currently set to zero.
EXTRACTFLAG	NUMBER		Currently set to zero.
RECORD	VARCHAR2	2048	Indicates the EJ data that stored in database.
SHCLOG_ID	VARCHAR2	20	Unique message identifier of the switch.

ATM_EJOURNAL_LOG

This table is used to display the log information of the Electronic Journal process.

ATM_EJOURNAL_LOG Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates the institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Indicates the group name to which the ATM belongs.
UNIT	NUMBER		Indicates the number of the configured ATM.
STARTINGDATE	DATE		Indicates the date when the EJ download started.
STARTINGTIME	NUMBER		Indicates the time when the EJ download started.
STARTINGSEQUENCE	NUMBER		Stores the record (message) number from where the download is started.
ENDSEQUENCE	NUMBER		Stores the record (message) number where the download is completed.
FILENAME	VARCHAR2	256	Indicates the file name where the EJ was stored.

ATM FIT

This table along with ATMFITENTRY contains information that comprises the Financial Institution Table (FIT) data for an ATM. Multiple terminals can share the same FIT data. Information from this table is loaded to the terminal during fit download.

ATM FIT Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
FIT_LIST_ID	NUMBER	8	ID that represents a list of FITs.
FIT_ENTRY_ID	VARCHAR2	10	ID of the fit entry.
FIT	VARCHAR2	10	BIN Value to download. Example: 45321.
INDIRECT_STATE	NUMBER	1	Indirect state flow number which should be used for this FIT. Valid values: 0 to 7 0 is default.

ATM FIT ENTRY

This table along with ATMFIT contains information that comprises the Financial Institution Table (FIT) data for an ATM. Multiple terminals can share the same FIT data. Information from this table is loaded to the terminal during fit download.

ATMFITENTRY Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
FIT_ENTRY_ID	VARCHAR2	10	ID of the fit entry.
INSTOFFSET	NUMBER	2	Offset of the BIN on the card. Valid values: 0 to 79 0 is default.
PANLEN	NUMBER	2	Length of PAN Data on card. Valid values: 0 to 19 18 is default.
PANVALOFFSET	NUMBER	2	Offset of the PAN validation data. Valid values: 0 to 79 0 is default.
PANVALLEN	NUMBER	2	Length of the PAN validation data. Valid values: 0 to 19 18 is default.
PINLEN	NUMBER	2	Minimum allowed PIN length. Valid values: 4 to 12 12 is default.

ATMFITENTRY Table

Field Name	Type	Size	Description
PANPAD	CHAR	1	Pad character used to pad the PAN when less than 16. F is default.
PINOFFSET	NUMBER	2	Offset of the expiry date on the card from the field separator. Valid values: 0 to 37 0 is default.
DEC_TABLE	CHAR	16	Decimalization table. "0123456789012345" is default.
PINMETHOD	CHAR	1	PIN block verification method Valid Values: V - Visa Verification Method (Default) D - DES IBM 3624 Verification Method.
PINBLOCKTYPE	CHAR	1	Pin block format type. Valid Values: A - ANSI Format (default) P - PINP PIN Pad Format
EXPIRYOFFSET	NUMBER	2	Offset of the expiry date on the card from the field separator.. Valid values: 0 to 37 0 is default.

ATMFITENTRY Table

Field Name	Type	Size	Description
VERIFY_PIN_LOCAL	CHAR	1	Indicates if the PIN must be verified locally at the ATM when the device has the capability: Valid values: Y N (Default)
LANG_CODE_OFFSET	NUMBER	2	Offset of the language code value from the field separator. Valid values: 0 to 79 0 is default.
PIN_WAIT_OK	CHAR	1	If ATM should wait for customer to press OK after entering PIN. Valid values: Y N (Default)

ATM FIT LIST

This table is used only by the GUI to configure display of possible values for entry on the GUI field.

ATMFITLIST Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
GROUP	VARCHAR2	10	Group to which the ATM belongs.
FIT_LIST_ID	NUMBER	8	ID represents a list of FITs configured in the ATMFIT table.
DESCRIPTION	VARCHAR2	100	Description of the FIT.

ATMGROUP

ATMGROUP table defines a set of related ATMs. The ATMGROUP concept was introduced in order to allow the ATM System to handle more than thousand ATMs. An ATM group should have up to 999 ATMs on it.

ATMGROUP Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates the institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Identifies the ATM group. Group names are defined by the administrator/customer. The name should be meaningful to the administrator/customer.
GOSERVICE	CHAR	1	Indicates if a "go in service" command is sent to the terminals in the group during startup of the system. Possible values are Y and N (default).
NET_NAME	CHAR	10	Identifies the network (set of groups) to which this group belongs. The ATM Monitor uses it in order to arrange ATM groups. The network name should be meaningful to the administrator/customer.
KPE_TXN_THRESHOLD MAC_TXN_THRESHOLD	NUMBER		Maximum number of transactions to process with the same key. The key (MAC, KPE) will be exchanged if maximum number of transactions is reached. Possible values are any positive number and the default value is 0. At key exchange process, this value will take over any value from the ATM table.
FUNC_FLAGS	CHAR	20	Sets processing configuration flags for the group of ATMs. Possible values are Y and N. Character 1: Surcharge confirmation, default N. All other characters are reserved for future use.
GROUP_NUM	NUMBER		Indicates the assigned number to the ATM group. The number is generated and assigned by the ATM system and cannot be modified by the administrator/customer.

ATMKEYCHG

This table logs key exchanges done at each ATM.

ATMKEYCHG Table

Field Name	Type	Size	Description
UNIT	NUMBER		Indicates the number of the configured ATM.
GROUP_NAME	VARCHAR2	10	Indicates the group name to which the ATM belongs.
START_DATE	DATE		Indicates the date when the key change process for KPE started
START_TIME	NUMBER		Indicates the time when the key change process for KPE started
END_DATE	DATE		Indicates the date when the key change process for KPE finish
END_TIME	NUMBER		Indicates the time when the key change process for KPE finish
STATUS	NUMBER		Indicates the current status of the key exchange process: Possible values: 0 = In progress; 1 = Successfully Finished
O_COMMENT	CHAR	10	Indicates the description of the key change status. E.g. created. Valid values: START CHG = Starting KPE change process START MAC = Starting MAC key change process FIN CHG = Finished KPE change process FIN MAC = Finished MAC key change process
MAC_DATE	DATE		Indicates the date when the key change process for MAC key finish
MAC_TIME	NUMBER		Indicates the time when the key change process for MAC key finish
INSTITUTION_ID	VARCHAR2	10	Indicates the institution to which the ATM belongs.

ATM_LOG

ATM_LOG Table

Field Name	Type	Size	Description
SHCLOG_ID	CHAR	20	Unique message identifier of the switch.
INSTITUTION_ID	VARCHAR2	10	Indicates the institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Indicates the group name to which the ATM belongs.
UNIT NUMBER	NUMBER	3	Unit number of the ATM.
FUNCTION_CODE	NUMBER	3	Type of logged message. Possible values are: ATM Device Status Message - 1521 Totals Inquiry Request - 572 Totals Reset Request - 573 Add to Cassette - 583 Subtract from Cassette - 584 Reset Cassette - 585 Cassette totals inquiry - 586
LOGGED_TIME	DATE		This field contains the time the log was created.
LOG_DATA	VARCHAR2	4000	Data in XML format for the above function codes.

ATMLOG_CTRL

ATMLOG_CTRL

Field Name	Type	Size	Description
SHCLOG_ID	CHAR	20	Unique message identifier of the switch.
PROCESSOR_BUSDAY	DATE		Indicates the date when the transaction is logged into database.
SEQ_TRACE_NO	NUMBER		Indicates the sequence number of the current entry inserted.
STATUS	CHAR	1	Indicates the status of transaction processing. Possible values are: • Blank -, indicates that the transaction is yet to be processed. • C - indicates that the transaction is processed. • X - indicates that the entry is related to EOD, also indicates change of processor_busday.
SEQUENCE_NUM	NUMBER		Currently set to zero.
SRCID	CHAR	6	Indicates the source that has inserted the record. Possible values are: • ATMEJC - indicates that the transaction is from ATM EJ capture table. • ATMLOG - indicates that the transaction is from ATM_LOG table. • EOD - indicates the EOD where processor_busday is changed to next date.
TABLE_NAME	CHAR	32	Contains the table name from which data can be extracted and processed. Possible values are: • ATMEJCAPTURE - this table contains information related to ATM EJ messages from ATM. • ATM_LOG - this table contains information related to ATM device status messages, ATM supervisory and ATM settlement message information. • ATMCTRL - indicates the EOD where processor_busday is changed to next date.

ATMLOG_CTRL

Field Name	Type	Size	Description
CREATE_DATE	DATE		Indicates the date when the transaction logged in the database.
LASTUPD_DATE	DATE		Indicates the date when the transaction status ID updated in the database.
RETRY_IND	NUMBER		Currently set to zero.

ATM_RKM_CERT

The atm_rkm_cert table is used to store the Certificate information for Diebold ATMs. Every Diebold ATM should have at least two certificates:

- Active Primary Verification/Signature
- Active Primary Encipher/Decipher

Diebold recommends to have a secondary set of keys as a standard procedure.

The records in this table are inserted by the atmrmcmd during the Remote Key Transport Command.

ATM_RKM_CERT

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
GROUP_NAME	VARCHAR2	10	Defines and ATM group name.
UNIT	NUMBER		The unit number of the ATM that is being configured. Maximum three digits. Unit must match the name of the ATM. For example, if your ATM is named atm0409, then Unit is 409.
KEY_VERSION	NUMBER		Indicates the INST_RKM__PK key version assigned in the GEN_RSA command for internal institutions. For external institutions, this number should be 0.
CERT_VERSION	NUMBER		Indicates the internal index assigned to the table.
AUTH_DATE	DATE		Indicates the date when the certificate was authenticated.
AUTH_TIME	NUMBER		Indicates the time when the certificate was authenticated.
ATM_ID	VARCHAR2	10	Indicates the ATM identification number. It is a combination of the group number and the ATM number.
CERTIFICATE	VARCHAR2	2500	Stores certificate data.

ATM_RKM_CERT

Field Name	Type	Size	Description
CERT_LEVEL	NUMBER		Indicates if the Certificate is Primary or Secondary.
CERT_TYPE	CHAR	1	Indicates if it is a Verification/ Signature (V), or Encipher/ Decipher (E) certificate.
VALID_FROM_DATE	DATE		Indicates the initial date for the certificate.
VALID_FROM_TIME	NUMBER		Indicates the initial time for the certificate.
VALID_TO_DATE	DATE		Indicates the expiry date for the certificate.
VALID_TO_TIME	NUMBER		Indicates the expiry time for the certificate.

ATM_RKM_PK

The atm_rkm_pk c table is used to store the Encrypted Pin Pad (EPP) Public Key information from NCR ATMs.

The records in this table are inserted by the atmrmcmd during the Authentication.

ATM_RKM_PK

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
GROUP_NAME	VARCHAR2	10	Defines an ATM group name.
UNIT	NUMBER		The unit number of the ATM that is being configured. Maximum three digits. Unit must match the name of the ATM. For example, if your ATM is named atm0409, then Unit is 409.
KEY_VERSION	NUMBER		Indicates the INST_RKM__PK key version assigned in the GEN_RSA command for internal institutions. For external institutions, this number should be 0.
AUTH_DATE	DATE		Indicates the date of the EPP public key authentication.
AUTH_TIME	INUMBER		Indicates the time of the EPP public key authentication.
EPP_SERIAL_NUM	VARCHAR2	10	Indicates the serial number of the ATM EPP.
EPP_PUBLIC_KEY	VARCHAR2	650	Indicates the Public Key of the ATM EPP.
EPP_PK_SIGNATURE	VARCHAR2	512	Indicates the signature of the EPP Public Key.
EXT_PK_INSTID	VARCHAR2	10	Indicates the identifier of the institution that signed the EPP public key. This is a key field to relate the EPP information with the institution RMK public key information.
EXT_PK_VERSION	NUMBER		Indicates the system internal key index of the institution that signed the EPP public key. This is a key field to relate the EPP information with the institution RMK public key information.

ATMSDESC

Indicates the ATM Status description.

ATMSDESC Table

Field Name	Type	Size	Description
STATUS	NUMBER		Internal status number.
SEVERITY	CHAR	10	Indicates the severity of the status
DESCRIPTION	CHAR	40	Indicates the brief status description
INSTITUTION_ID	VARCHAR2	10	Indicates the institution to which the ATM belongs.

ATMSTATUS

This table logs the status reported by the terminal. Every status reported by the terminal generates a record in this table.

ATMSTATUS Table

Field Name	Type	Size	Description
UNIT	NUMBER		Indicates the number of the configured ATM.
GROUP_NAME	VARCHAR2	10	Indicates the group name to which the ATM belongs.
STATUS_DATE	DATE		Indicates the date when the status was report by the ATM
STATUS_TIME	NUMBER		Indicates the time when the status was report by the ATM
STATUS	NUMBER		Indicates the ID of the reported status
SDESC	CHAR	40	Indicates hte description of the reported status
INSTITUTION_ID	VARCHAR2	10	Indicates the institution to which the ATM belongs.

ATMSUPCARD

This table stores the supervisor cards and additional parameters to use during supervisor transactions.

ATMSUPCARD Table

Field Name	Type	Size	Description
PAN	CHAR	19	Valid supervisor card used to allow administrative transactions at the ATM. The supervisor PAN is validated for any supervisor transaction performed at the ATM
O_COMMENT	CHAR	30	Comment for the supervisor card
INSTITUTION_ID	VARCHAR2	10	Indicates the institution to which the ATM belongs.
MAXPINFAILS	NUMBER		Indicates the maximum number of PIN fails per day for this supervisor card
CURRPINFAILS	NUMBER		Indicates the current number of PIN attempts for this supervisor card
PINFALDATE	DATE		Indicates the last date when the supervisor typed a failed PIN. It is used to reset the PIN fails every date.
PINFALHOUR	NUMBER		Last hour when supervisor typed a failed PIN.

ATM TOTALS

This table holds transaction totals. Transaction totals can be maintained by currency code, transaction type.

ATMTOTALS Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Group name to which the ATM belongs.
UNIT	NUMBER	3	Unit Number of the ATM (LUNO).
TYPE	VARCHAR	6	Type of the transaction in totals record, Default possible values are: 1 Withdrawals 2 Deposits 3 Transfer 4 Balance/enquiry 5 Payment (loan/Bill)
CURRENCY	NUMBER	10	Currency of the transactions.
COUNT	NUMBER	10	Number of transactions.
AMOUNT	MONEY		Total amount of transactions.
RESET_TIME	DATE TIME		Date, time when totals record was reset
PREV_COUNT	NUMBER	10	Previous number of transaction (Before last reset).
PREV_AMOUNT	MONEY		Previous total amount of transaction (Before last reset).

DEV_SURCHARGE

The table configures the surcharge for a group of ATMs.

DEV_SURCHARGE Table

Field Name	Type	Size	Description
GROUP_NAME	VARCHAR2	10	Indicates the group name to which the ATM belongs.
PAN_LOW	CHAR	19	Indicates the lower PAN (or part of the PAN) of the range to which this surcharge configuration will be applied
PAN_HI	CHAR	19	Indicates the higher PAN (or part of the PAN) of the range to which this surcharge configuration will be applied
FLAG	CHAR	1	Indicates the type of surcharge to apply for the range. Possible values: F = Will apply the configured flat fee (see bellow field) as the surcharge P = A percentage of the amount will be calculated. N = No surcharge will be applied.
FLAT_FEE	NUMBER	26,8	Indicates the flat surcharge to apply if "surcharge type" is set to "F"
PERCENT_RATE_ID	NUMBER	8	Forms part of the key to the SURCHARGE_RATE table.
INSTITUTION_ID	VARCHAR2	10	Indicates the institution to which the ATM belongs.

INST_RKM_CERT

The inst_rkm_cert table is used to store the certificate information for institutions. The information is generated through PKCS#7 files delivered by the Certificate Authority.

INST_RKM_CERT Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
KEY_VERSION	NUMBER		Indicates the index of the public key associated with the certificate. For internal institutions, the public key is generated; for external institutions, the public key is delivered within the PKCS#7 file.
CERT_VERSION	NUMBER		Indicates the internal index assigned to the certificate.
CREATION_DATE	DATE		Indicates the date of the creation of the key in case of internal institutions. Indicates the date when the public key was loaded into the IST/Switch system.in case of external institutions.
CREATION_TIME	NUMBER		Indicates the time of the creation of the key in case of internal institutions. Indicates the time when the public key was loaded into the IST/Switch system.in case of external institutions.
CERT_STATUS	NUMBER		Indicates the status of the certificate. Valid values: 1 indicates active status; 0 indicates inactive status.
CERT_LEVEL	NUMBER		Indicates the level of the certificate. Valid values: 1 indicates primary; 0 indicates secondary.
CERT_TYPE	CHAR	1	Indicates the type of the certificate. Valid values: V indicates Verification/Signature certificate; E indicates Encipher/Decipher (E) certificate.
CERTIFICATE	VARCHAR2	2500	Indicates Certificate data (PKCS#7 format).
VALID_FROM_DATE	DATE		Indicates the initial date of the certificate.
VALID_FROM_TIME	NUMBER		Indicates the initial time of the certificate.

INST_RKM_CERT Table

Field Name	Type	Size	Description
VALID_TO_DATE	DATE		Indicates the expiry date of the certificate.
VALID_TO_TIME	NUMBER		Indicates the expiry time of the certificate.
REQ_VERSION	NUMBER		Indicates the Version Index to the INST_RKM_CER_REQ record, if the record is from an internal institution.

INST_RKM_CERT_REQ

The inst_rkm_cert_req table stores certificate request information for institutions. The request is generated through the atmrmcmd based on the public key and Institution data. The request is stored in the database.

INST_RKM_CERT_REQ Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
KEY_VERSION	NUMBER		Indicates the index of the public key associated with the certificate. For internal institutions, the public key is generated; for external institutions, the public key is delivered within the PKCS#7 file.
REQ_VERSION	NUMBER		Indicates the Version Internal index assigned to the certificate request.
CERTIFICATE_REQ	VARCHAR2	2500	Indicates the Certificate request data (PKCS#10 format).
CREATION_DATE	DATE		Indicates the date of the creation of the key in case of internal institutions. Indicates the date when the public key was loaded into the IST/Switch system in case of external institutions.
CREATION_TIME	NUMBER		Indicates the time of the creation of the key in case of internal institutions. Indicates the time when the public key was loaded into the IST/Switch system in case of external institutions.

INST_RKM_PK

The inst_rkm_rk table stores the public key information of an institution. Each institution may have its own public key information.

INST_RKM_PK Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates the identifier of the institution to which the ATM belongs. This institution can be “internal” or “external”. Internal institutions are those internal to IST/Switch and configured to process transactions. External institutions are, for example, NCR and Diebold, and they send their public key for the validation process.
KEY_VERSION	NUMBER		Indicates the key index of the internal system. Whenever an RSA key pair is requested from the atmrmcmd, a new key version is created. The last version is considered the “current” version and will be used for all the RKM processing.
CREATION_DATE	DATE		Indicates the date of the creation of the key in case of internal institutions. Indicates the date when the public key was loaded into the IST/Switch system. in case of external institutions.
CREATION_TIME	NUMBER		Indicates the time of the creation of the key in case of internal institutions. Indicates the time when the public key was loaded into the IST/Switch system. in case of external institutions.
PUBLIC_KEY	VARCHAR2	650	Indicates the public key component of the RSA pair generated with the atmrmcmd.
SECRET_KEY	VARCHAR2	2650	Indicates the secret key component of the RSA pair generated with the atmrmcmd. This field is encrypted with the HSM LMK.

INST_RKM_PK Table

Field Name	Type	Size	Description
EXT_PK_INSTID	VARCHAR2	10	Indicates the identifier of the institution that signed the public key. As part of the process, the system internal institutions should send the public key to be signed by external institutions.
EXT_PK_VERSION	NUMBER		Indicates the key version of the external institution which signed the internal public key.
EXT_PK_SIGNATURE	VARCHAR2	512	Indicates the signature of the internal public key generated by the external institution with the external public key.

MCPATMCFG

The mcpatmcfg table is used by the interface that handles the Triton Dial-up ATMs. To add a new Dialup ATM, information related to the ATM has to be inserted in this table.

MCPATMCFG Table

Field Name	Type	Size	Description
PGMVER	CHAR	10	Program version of the Triton ATM.
TBLVER	CHAR	10	Table version of the Triton ATM.
FRMVER	CHAR	10	Firmware version of the triton ATM.
HRTINT	NUMBER		Indicates the heartbeat interval -number of minutes within which the ATM must remain idle, without generating any transactions, before it a configuration download request. After the configured number of minutes will request a new KPE.
PROCOD	NUMBER		
TXNTYP	NUMBER		
TXNCNT	NUMBER		Indicates the current number of transactions. The number of transactions is incremented each transaction request regardless of whether or not it was successful. If the value of Download Txn Interval is set (not zero) and the value of TXNCNT is greater than, or equal to, the value of Download Txn Interval, the ATM will perform a download procedure. After this, the value of this field is reset to (0).
STO001	CHAR	40	Text Message
STO002	CHAR	40	Text Message
STO003	CHAR	40	Text Message
STO004	CHAR	40	Text Message
MAR001	CHAR	40	Text Message
MAR002	CHAR	40	Text Message
MAR003	CHAR	40	Text Message
MAR004	CHAR	40	Text Message
WEL001	CHAR	30	Text Message
WEL002	CHAR	30	Text Message
WEL003	CHAR	30	Text Message
EXI001	CHAR	30	Text Message
EXI002	CHAR	30	Text Message

MCPATMCFG Table

Field Name	Type	Size	Description
EXI003	CHAR	30	Text Message
PRI001	CHAR	40	Text Message
PRI002	CHAR	40	Text Message
PRI003	CHAR	40	Text Message
PRI004	CHAR	40	Text Message
ROWFLD	NUMBER		
UNIT	NUMBER		The unit number of the ATM that is being configured. Maximum length is 4. The unit number must match the name of the ATM. For example, if your ATM name is 409, then Unit is 409.
GROUP_NAME	VARCHAR2	10	Defines and ATM group name.
INSTITUTION_ID	VARCHAR2	10	Text Message

SURCHARGE_RATE

This table is used to set the percentage of the surcharge applied to the transaction. If Flat/Percentage field in the dev_surcharge table is set to Percentage, an entry in the surcharge_rate table will be set to the needed percentage.

SURCHARGE_RATE Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Institution to which the ATM belongs.
GROUP_NAME	VARCHAR2	10	Indicates the group name to which the ATM belongs.
PERCENTAGE_RATE_ID	NUMBER	12	Percentage rate surcharge entry to use
AMOUNT_LOW	NUMBER	26,8	Indicates the lower amount to apply for the surcharge. If the cardholder's balance is less than this value, this value will be used as surcharge
AMOUNT_HI	NUMBER	26,8	Indicates the higher amount to apply for the surcharge. If the cardholder's balance is greater than this value, this value will be used as surcharge
PERCENTAGE	NUMBER	26,8	Value used to calculate the surcharge as a percentage of the transaction amount

4

Authorization Tables

Table Descriptions

IST_ACCOUNT

The istaccount table defines the authorization parameters of the financial accounts of the bank . It derives attributes specific to account entity. The information is related to card, child of account group and customer and so on.

IST_ACCOUNT Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
ENTITY_ID	VARCHAR2	32	Indicates the financial account number.
LEDGER_BALANCE	NUMBER	26, 8	Indicates the available and uncleared balance.
AVAILABLE_BALANCE	NUMBER	26, 8	Indicates the available account balance.
PREAUTH_AMOUNT	NUMBER	26, 8	Indicates the amount held for pre-authorized transaction.
ADVANCE_LINE	NUMBER	26, 8	Indicates the advance overdraft limit applied to the account.

IST_ACCOUNT Table

Field Name	Type	Size	Description
ADVANCE_LINE_USED	NUMBER	26, 8	Indicates the advance overdraft used.
NET_ACTIVITY	NUMBER	26, 8	Indicates the net result of all day transactions.
CURRENCY_CODE	NUMBER		Indicates the Numeric ISO currency code.
LAST_ACTIVITY_DATE	DATE		Indicates the date of last activity against the account. Format: MM/DD/YYYY.
LAST_ACTIVITY_TIME	NUMBER		Indicates the time of last activity against the account.
LAST_UPDATE_DATE	DATE		Indicates the date on which the account was last updated. Format: MM/DD/YYYY.
LAST_UPDATE_TIME	NUMBER		Indicates the time when the account was last updated.

IST_ACCUM_AMOUNT

The istaccumamount table is for accumulating the amount base on entity type and entity id.

IST_ACCUM_AMOUNT Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
ENTITY_TYPE	VARCHAR2	10	Indicates the code used to identify the entity level within the entity hierarchy (e.g., agent, chain, merchant, corporate merchant)
ENTITY_ID	VARCHAR2	32	Indicates the internal ID assigned to an entity. When an only a part of the institution uses this entry, this field indicates the part. When whole institution uses this entry, a "*" should be used.
LIMIT_ID	VARCHAR2	32	The limit_id from the ist_limit_amount table.
AMOUNT_USED	NUMBER	26, 8	Indicates the amount used.
START_DATE	DATE		Indicates the start date of current accumulation entry.
LAST_DATE	DATE		Indicates the date of the last accumulation.
LAST_TIME	NUMBER		Indicates the time of the last accumulation.

IST_ACCUM_COUNT

This table is for counting the transaction times base on entity type and entity id.

IST_ACCUM_COUNT Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
ENTITY_TYPE	VARCHAR2	10	Indicates the code used to identify the entity level within the entity hierarchy (e.g., agent, chain, merchant, corporate merchant).
ENTITY_ID	VARCHAR2	32	Indicates the internal ID assigned to an entity. When an only a part of the institution uses this entry, this field indicates the part. When whole institution uses this entry, a "*" should be used.
LIMIT_ID	VARCHAR2	32	The limit_id from the ist_limit_amount table .
COUNT_USED	NUMBER		Indicates the numbers of transactions that have been used.
START_DATE	DATE		Indicates the start date of the current accumulation entry
LAST_DATE	DATE		Indicates the date of the last accumulation.
LAST_TIME	NUMBER		Indicates the time of the last accumulation.

IST_BRANCH

The istbranch table defines the branch name and id under the institution identifier.

IST_BRANCH Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates unique identifier.
BRANCH_ID	VARCHAR2	10	Indicates the ID of the branch where the account was opened.
BRANCH_NAME	VARCHAR2	30	Indicates the name of the branch where the account was opened.

IST_CARD

The istcard table contains card parameters as well as accumulated amounts and counts. The use of other tables in the authorization process may be determined by certain indicators in this table. The istcard table passes the following information to the other authorization tables: PAN, card type, transaction class, card status, primary/secondary account, and the card base. The bank is responsible for configuring the card authorization details such as the PVV, TPVV, and the card accumulators.

IST_CARD Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates unique identifier.
ENTITY_ID	VARCHAR2	19	Indicates the card number that includes the following information: BIN Number Customer Base Number Sequence Number Check Digit
EXPIRYDATE	DATE		Indicates the date on which the card expires. Format is: MM/DD/YYYY.
OLD_EXPIRYDATE	DATE		Indicates the expiry date of the renewed card, if applicable.
LAST_ACTIVITY_DATE	DATE		Indicates the date of last activity against the account. Format: MM/DD/YYYY.
LAST_ACTIVITY_TIME	NUMBER		Indicates the time of last activity against the account.
LANGUAGE_CODE	VARCHAR2	3	Indicates the ISO language code. Valid values: 1: English 2: Other.
SEQ_NO	NUMBER		Indicates the sequence number of the current card issued.
CONSENT_DATE	DATE		Indicates the date on which the application for the card is approved.

IST_CARDSEQ

The istcardseq table contains the card sequence number of issued cards.

IST_CARDSEQ Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
ENTITY_ID	VARCHAR2	10	Indicates the card number.
SEQUENCE	VARCHAR2	4	Indicates the sequence number of the current card issued.
ADDON	VARCHAR2	4	Indicates the add-on sequence number of the current card issued.

IST_CARDTYPE

The IST_CARDTYPE table defines card types of a financial institution (e.g. Visa Gold Card). The authorization process receives card type information from the istcard table. From the istcardtype table, the authorization process passes a transaction class value to the isttxnclass table. The business is responsible for setting card limits and fees.

IST_CARDTYPE Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
ENTITY_ID	VARCHAR2	32	Indicates the type of card. Values are defined by the user.
DESCRIPTION	VARCHAR2	20	Describes the card type.
CARD_RENEWAL_FEE	NUMBER	26, 8	Indicates the fee to renew the card.
CARD_RPLCMNT_FEE	NUMBER	26, 8	Indicates the fee to replace the card.
EMERGENCY_ISSUE_FEE	NUMBER	26, 8	Indicates the fee to issue an emergency card.
DEFAULT_PKVI	CHAR	1	Defines the default PKV key index.
DEFAULT_LANG_CODE	VARCHAR2	3	Defines the default language code.
ICC_INDICATOR	CHAR	1	Indicates whether International Citicard (ICC) access is allowed. Valid values: 0: No ICC access or usage; 1: ICC access.
ICC_CARD_PREFIX	VARCHAR2	10	Indicates the card prefix(BIN) that should be used with new cards that have ICC access.
CARD_PREFIX	VARCHAR2	10	Indicates the card prefix(BIN) that should be used with new cards that do not have ICC access.
CARD_LIFE	CHAR	2	Indicates the period (in months) before card expires.

IST_CARDTYPE Table

Field Name	Type	Size	Description
CARD_RENEWAL_IND	CHAR	1	Indicates the card renewal indicator. Valid values: 0: Automatic renewal, 1: Manual renewal.
CARD_CATEGORY	CHAR	1	Indicates the category of the card. Valid values: 0 through 9. Values are defined by the user.
SERVICE_CODE	CHAR	3	Indicates the service code, which determines the restrictions for local and international transactions using the card. Any cards restricted to local transactions will be denied for international transactions. Normally, this field is set to '20' (that is, international usage is allowed).

IST_CUSTOMER

The istcustomer table defines the non-financial information of a parent or primary customer. It also defines the restrictions and limits of the customer accounts and its supplementary accounts. Customer base (identification) numbers are updated in this table.

IST_CUSTOMER Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
ENTITY_ID	VARCHAR2	10	Indicates the Customer Base Number/ Customer Identification Number.
CUSTOMER_TYPE	CHAR	1	Indicates the type of customer. Valid values are: 0: Client; 1: Staff.
OPEN_DATE	DATE		Indicates the date on which the customer account was opened. Format is MM/DD/YYYY.
CARD_SEQNO	NUMBER		Indicates the sequence number of the current card issued.
ID_NUMBER	VARCHAR2	20	Indicates the Identification number of the document that the user presented.
ID_TYPE	VARCHAR2	2	Indicates the Customer Identification Document Type.

ISTMAPDB

IST/Foundation uses this table to set up conditions for accessing various accounts in the data base. This table is also used to access transaction description messages and promotional messages.

ISTMAPDB Table

Field Name	Type	Size	Description
EKEY	CHAR	32	Key used as part of the condition used to access accounts in the data base. Examples of values: ATM.TXNDESC.MSG ATM.PROMO.MSG ISTAUTH.OAR.QUERY
OWNER	CHAR	32	Not currently used.
CODE	CHAR	10	A six-digit processing code. The values in this field may include a language code.
STATUS	CHAR	10	Records the status of the ATM unit: 0: the ATM is off-line, 1: the ATM is online, 2: the ATM has outstanding warnings
SEQUENCE	CHAR	10	Sequence number of a primary card for this customer base number. Zero fill
TEXT1	VARCHAR2	255	Text associated with the fields currently in use, or part of a Select statement.
TEXT2	VARCHAR2	255	Text associated with the fields currently in use, or part of a Select statement.
TEXT3	VARCHAR2	255	Not currently used.
TEXT4	VARCHAR2	255	Not currently used.
TEXT5	VARCHAR2	255	Not currently used.

IST_ENTITY_REL

The istentityrel table describes the relationship between the different entities.

IST_ENTITY_REL Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
ENTITY_TYPE	VARCHAR2	10	Indicates the entity type. Valid values: CARD - card ACCT - account CUST - customer CDTP - card type ACTP - account type
ENTITY_ID	VARCHAR2	32	Indicates the internal ID assigned to an entity. When an only a part of the institution uses this entry, this field indicates the part. When whole institution uses this entry, a "*" should be used.
REL_TYPE	VARCHAR2	10	Indicates the entity type of the related entity. Valid values:- CARD - card ACCT - account CUST - customer CDTP - card type ACTP - account type LMTAMT - Amount Limit LMTCNT - Frequency Limit

IST_ENTITY_REL Table

Field Name	Type	Size	Description
REL_ID	VARCHAR2	32	Indicates the entity ID of the related entity. If the REL_ID is related to the ACCOUNT TYPE entity (rel_type is "ACTP"), the REL_ID can have the following values: 04 - for Checking account 05 - for Savings account
REL_INDICATOR	CHAR	1	Refers to the Relationship Indicator Valid values are: P - Parent R -Related
REL_SUBTYPE	VARCHAR2	30	Indicates the subtype(s) of the related entity. . 1. For ACCOUNT entity (entity_type is "ACCT"), the rel_subtype is primary/secondary indicator for related account entity. Use "PRIMARY" for primary and "SECONDARY" for secondary. 2. txn types for related attribute entities of limit. Valid values are: "PURCHASE", "CASH", "TC", "TSFUSD", "TSFBASECURR", "DEPOSIT" and "TSFMULTICURR". If there are multiple subtypes for one entity, use the symbol ' ' for conjunction them. For example: "PURCHASE CASH" means: the limit for purchase or cash withdraw;

IST_ISS_ENTITY

The istissentity table contains the information related to the issuing entity.

IST_ISS_ENTITY Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
ENTITY_TYPE	VARCHAR2	10	Indciates the entity type. Valid values :- CARD - card ACCT - account CUST - customer CDTP - card type ACTP - account type
ENTITY_ID	VARCHAR2	32	Indicates the entity ID. Card number (entity_id field from ist_card) Account number (entity_id field from ist_account) Customer number (entity_id field from ist_customer) Card type ID Account type ID
DESCRIPTION	VARCHAR2	35	Indicates the description of each entity..
STATUS	VARCHAR2	2	Indicates the "Status" of Card/Account/Customer/CardType/AcctType.
TXNCLASS	VARCHAR2	10	Indicates the class of transactions that the card can be used for. Valid values are defined by the user in the isttxnclass table.
ADDRESS_ID	NUMBER	12	Indicates the reference ID associated to master_address(UDM) table.
REGION	VARCHAR2	10	Indicates the region in which the customer opened the account. Values are defined by the user
BRANCH_ID	VARCHAR2	10	Indicates the ID of the branch where the customer opened the account.

IST_LIMIT_AMOUNT

The istlimitamount table contents the limit of transaction amount.

IST_LIMIT_AMOUNT Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
LIMIT_ID	VARCHAR2	32	REL_ID in the ist_entity_rel table. It is unique across all limit tables, which needs some method to manage relationship.
LIMIT_AMOUNT	NUMBER	26, 8	Indicates the amount limit.
LIMIT_LEVEL	VARCHAR2	10	The entity_type of the limitation against. Example: If the limit_level is card, each card will have its own accumulation record towards the limit. If the limit_level is card type, the whole card type will have a accumulation record towards the limit, this means once the limit is reached, none of the cards that belong to the card type will be able to do transaction.
INTERVAL	VARCHAR2	20	Indicates the the interval of limitation. Valid Values: • M • D
CURRENCY_CODE	NUMBER		Indicates the Numeric ISO currency code..
START_DATE	DATE		Indicates the start date of the current accumulation entry.

IST_LIMIT_COUNT

The istlimitcount table contains the limit of transaction frequency.

IST_LIMIT_COUNT Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
LIMIT_ID	VARCHAR2	32	The REL_ID in the ist_entity_rel table. It is unique across all limit tables, which needs some method to manage relationship.
LIMIT_COUNT	NUMBER		Indicates the transaction frequency limit.
LIMIT_LEVEL	VARCHAR2	10	The entity_type of the limitation against. Example: If the limit_level is card, each card will have its own accumulation record towards the limit. If the limit_level is card type, the whole card type will have a accumulation record towards the limit, this means once the limit is reached, none of the cards that belong to the card type will be able to do transaction.
INTERVAL	VARCHAR2	20	Indicates the interval of limitaion. Valid Values: • M • D
CURRENCY_CODE	NUMBER		Indicates the Numeric ISO currency code.
START_DATE	DATE		Indicates the start date of the current accumulation entry.

IST_LOGHIST

The istloghist table contains the financial transaction history of accounts.

IST_LOGHIST Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates the unique institution identifier.
PAN	VARCHAR2	19	Indicates the card number defined in the ist_card table
ACCOUNT_ID	VARCHAR2	32	Indicates the account number defined in the ist_account table
MSGTYPE	NUMBER		Indicates the message type of the transaction
TRACE	NUMBER		Indicates the trace number of the transaction.
PCODE	NUMBER		Indicates the processing code of the transaction.
RESPCODE	NUMBER		Indicates the response code of the transaction.
ACQ_CURRENCY_CODE	NUMBER		Indicates the acquirer currency code.
CR_DR_IND	CHAR	1	Credit or Debit Indicator.
AMOUNT	NUMBER	26, 8	Indicates the transaction amount.
CH_AMOUNT	NUMBER	26, 8	Indicates the card holder amount.
NEW_BALANCE	NUMBER	26, 8	Indicates the new balance after the current transaction.
TXN_DATE	DATE		Indicates the date of transaction in the format MMDDYYYY.
TXN_TIME	NUMBER		Indicates the time of transaction in the format HHMMSS.
SETTLEMENT_DATE	DATE		Indicates the date of settlement.
AUTHNUM	VARCHAR2	10	Indicates the authorization number of the transaction to support the search for the original preauthorization confirmation message when a pre-authorization completion message comes in.

IST_LOGHIST Table

Field Name	Type	Size	Description
TXN_SRC	VARCHAR2	10	Indicates activity concerning personal identification number. Valid values are 0= Issued; 1= PIN; Assignment; 2= PIN Maintenance; 3= Update; 9= Delete.
ACQUIRER	VARCHAR2	10	Indicates the internal acquirer bin..
ISSUER	VARCHAR2	10	Indicates the internal user bin.
TERMID	VARCHAR2	8	Indicates the terminal ID where the transaction was initiated and transacted.
STORE_ID	VARCHAR2	4	Indicates the store ID.

IST_PIN

The istpin table contains the data for PIN verification.

IST_PIN Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
ENTITY_ID	VARCHAR2	19	Indicates the card number.
PIN_METHOD	CHAR	1	Indicates the pin encrypted method. Valid values are: V -Visa PVV D- IBM DES
PIN_TYPE	CHAR	1	Indicates the type of personal identification number. Valid values are: A - ATM PIN T - Telephone PIN
PIN_DATA	VARCHAR2	12	Indicates the PIN data.
OLD_PIN_DATA	VARCHAR2	12	Indicates the old PINdata.
PKVI	CHAR	1	Indicates the PIN Verification Key Index.
OLD_PKVI	CHAR	1	Indicates the old PIN Verification Key Index.
RETRY_COUNT	NUMBER		Indicates the number of times the PIN has been retried.

IST_PINHIST

This table contains a history of pin creations and updates.

IST_PINHIST Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
PAN	VARCHAR2	19	Indicates the card number defined in the ist_card table.
TXN_DATE	DATE		Indicates the date of transaction.in the format MMDDYYYY..
TXN_TIME	NUMBER		Indicates the time of Transaction in the format HHMMSS.
PIN_METHOD	CHAR	1	Indicates the PIN encrypted method.
PIN_TYPE	CHAR	1	Indicates the type of the PIN. Valid values are: A - ATM PIN T- Telephone PIN.
PIN_ACTIVITY	CHAR	1	Indicates activity concerning personal identification number. Valid values are 0= Issued; 1= PIN Assignment; 2= PIN Maintenance; 3= Update; 9= Delete.
TERMINID	VARCHAR2	8	Indicates the terminal ID where the transaction was initiated and transacted.
TXNSRC	VARCHAR2	10	Indicates the transaction source.
ACQUIRER	VARCHAR2	10	Indicates the the internal acquirer bin..
CLERK_ID	NUMBER		Indicates the ID of the clerk.
SUPERVISOR	NUMBER		Indicates the ID of the supervisor who is handling the PIN assignment.
DEVICE_TYPE	CHAR	1	Indicates where the PIN activity was initiated. Valid values are 0=ATM; 1=Branch.

IST_PIN_METHOD

The istpinmethod contains the description of PIN encryption methods that are used in ist_pin table.

IST_PIN_METHOD Table

Field Name	Type	Size	Description
PIN_METHOD	CHAR	1	Indicates the PIN method code.
NAME	VARCHAR2	10	Indicates the PIN method name. For example, PVVand DES.
DESCRIPTION	VARCHAR2		Indicates the PIN method description.. For example, Visa PVV, IBM Pin-offset DES.

IST_PIN_TYPE

The istpintype table contains the description of the PIN type that is used in the ist_pin table.

IST_PIN_TYPE Table

Field Name	Type	Size	Description
PIN_TYPE	CHAR	1	Indicates the PIN type code.
NAME	VARCHAR2	10	Indicates the PIN type name. For example, ATM-PIN, TEL-PIN.
DESCRIPTION	VARCHAR2	30	Indicates the PIN type description.

IST_STATUS

This table defines the relationship between the host status code and the IST/Switch internal status code. Some often used values are shown in the Status field in the istcard table earlier in this chapter.

IST_STATUS Table

Field Name	Type	Size	Description
ENTITY_TYPE	VARCHAR2	10	Indicates the code used to identify the entity level within the entity hierarchy (e.g., agent, chain, merchant, corporate merchant).
STATUS	VARCHAR2	2	Indicates the host status code. Values are defined by the user
NAME	VARCHAR2	10	Indicates the short name of the account.
NO_CR_DR	CHAR	1	Indicates when the record is used. Valid values: 0: default 1: for CR transactions 2: for DR transactions 3: for non-financial transactions
IST_RESPCODE	NUMBER		Indicates the internal response code.
DESCRIPTION	VARCHAR2	30	Indicates the description of each entity.

IST_TXNCLASS

This table is used to link a processing code to a transaction class.

IST_TXNCLASS Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Bank Institution Number
TXNCLASS	VARCHAR2	10	Indicates the class of transactions that the card can be used for. Valid values are defined by the user in the isttxn class table.
ALLOWED_PCODE	NUMBER		A six-digit processing code. First two digits describe a specific transaction Second two digits describe account types affected for debits and inquiries and the 'from' account for transfers. 'Last two digits describe account types affected for credits and the 'to' account for transfers. The same processing code is used in all messages related to the transaction. The field corresponds to ISO bitmap 3.

IST_TXNCLASS_DESC

This table is used to link a processing code to a transaction class. This table contains the description of transaction class code that is used in the ist_txnclass table.

IST_TXNCLASS_DESC Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier
TXNCLASS	VARCHAR2	10	Indicates the class of transactions that the card can be used for. Valid values are defined by the user in the isttxnclass table.
NAME	VARCHAR2	10	Indicates the name of the transaction class.
DESCRIPTION	VARCHAR2	30	Indicates the description of the transaction class.

IST_TXNDESC

The isttxndesc table contains the description of the transaction by processing code.

IST_TXNDESC Table

Field Name	Type	Size	Description
INSTITUTION_ID	CHAR	10	Unique institution identifier.
PCODE	NUMBER		Indicates the processing code. This value is defined internally.
DESCRIPTION	CHAR	20	Description of the processing code.
SHORTDESC	CHAR	6	Short description of the processing code
HOST_TXN_CODE	CHAR	4	Indicates the Host Transaction Code.

5

Currency Tables

Table Descriptions

ISTCURPNT

This table indicates the precise decimal point position for each currency.

ISTCURPNT Table

Field Name	Type	Size	Description
CURRENCY	NUMBER		Numeric ISO Currency Code.
CURRENCY_NAME	CHAR	25	Description of ISO Currency.
O_DECIMAL	NUMBER		Decimal position.
EU_DECIMAL	NUMBER		Europay-specific decimal position.

ISTCURR

ISTCURR Table

Field Name	Type	Size	Description
BIN	CHAR	10	Bank Institution Number.
CURRENCY	NUMBER		Numeric ISO Currency Code.
INSTRUMENT	CHAR	1	Indicates whether notes or traveller's checks are used in the transaction. Valid values: 0: Notes 1: Travellers checks 2: USD notes, non-staff 9: USD notes, staff.
A_DESC	CHAR	25	Other Language Description.
E_DESC	CHAR	25	English Description.
A_STRCODE	CHAR	8	Text Message.
E_STRCODE	CHAR	8	Text Message.
WASH_RATE	NUMBER	26,8	The Wash rate is used in cross currency conversion where the currency exchange has already used one of the Sell or Buy rates as the first leg of the conversion. Usually this rate allows an equal 1:1 exchange and falls between the Buy and Sell rates in value. The Wash rate is also used at the positive authorization of staff currency conversion. This is also referred to as the Bank Rate.
SELL_RATE	NUMBER	26,8	The Sell rate is used to convert POS purchase amounts in base currency to a foreign account currency in order to determine the amount to debit the account.
BUY_RATE	NUMBER	26,8	The Buy rate is used to convert a foreign dispensed currency or a purchase amount at a foreign POS to a local currency (base currency) equivalent.
VALUE_DATE	DATE		This field stores the actual date of settlement of the transaction, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 15.
HOST_CURRENCY_CODE	CHAR	5	Currency code in host formatter corresponding to an ISO currency code.
MULT_DIV	CHAR	1	Text Message.

ISTCURSPR

This table is used to define the exchange rate spreads from the main exchange rates for different card types and currency codes. The table holds adjustment values as percentages (e.g. a value of 100 will use the full buy/sell rate whereas a value of 50 uses 50% of the buy/sell rate).

ISTCURSPR Table

Field Name	Type	Size	Description
BIN	CHAR	10	Bank Institution Number.
CARDTYPE	CHAR	4	Four-digit card type code.
CURRENCY	NUMBER		Numeric ISO Currency Code.
SELL_SPREAD	NUMBER	26,8	Positive/Negative spread relative to the sell rate (%).
BUY_SPREAD	NUMBER	26,8	Positive/Negative spread relative to the buy rate (%).



CMS Tables

Table Descriptions

IST_CMS_ACT

To record activities completed by the Card Management System. This table is filled in automatically by the CMS.

IST_CMS_ACT Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
PAN	VARCHAR2	19	Personal Account Number
PAN_REPL	VARCHAR2	19	Card number to be replaced
REGION	VARCHAR2	10	Region division where the card was issued.
BRANCH	VARCHAR2	10	Branch Id where the transaction was acquired.
CARDTYPE	VARCHAR2	10	Four-digit card type code.

IST_CMS_ACT Table

Field Name	Type	Size	Description
CMS_FUNC	VARCHAR2	2	Function completed on the card. Zero fill 01 = Add 02 = Delete 03 = Modify 05 = Lost/hot 06 = Renewal 11 = Convert 12 = Issue in renewal 50 = Re-issue
STATUS	VARCHAR2	2	The export status of the record.
CMS_MODE	NUMBER		Mode of operation (updated by system)
TX_DATE	DATE		The date of activity occurred
TX_TIME	NUMBER		The time of activity occurred (hhmmss)
ACT_COUNT	NUMBER		Activity count describes the number of times this record has been exported to the activity file. Zero fill
ACT_DATE	DATE		The date the record was (last) written to the activity file
ACT_TIME	NUMBER		The time this record was (last) written to the activity file (hhmmss)
PM_STATUS	NUMBER		The status of PIN mailer printing
PM_DATE	DATE		The date the PIN Mailer was (last) printed
PM_TIME	NUMBER		The time the PIN Mailer was (last) printed
SEQ_NO	VARCHAR2	4	The nth card issued by CMS
REPL_REASON	VARCHAR2	40	Reason for card replacement, where applicable

IST_CMS_CARD

To record card related information which is required for card management but not for authorization.

IST_CMS_CARD Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
ENTITY_ID	VARCHAR2	19	Indicates an internal ID assigned to an entity.
EXPIRYDATE	DATE		Date when the card will expire
OLD_EXPIRYDATE	DATE		Previous card expiry date
EMBOSSNAME	VARCHAR2	35	Name that appears in the plastic
MAGSTRIPNAME	VARCHAR2	35	The name contained in the cards magnetic stripe
CARDINDICATOR	CHAR	1	Indicates whether the card is primary or supplementary. 0 = primary 1 = supplementary
ISSUEDATE	DATE		Card issuance date
EMERGENCY_REISSUE	CHAR	1	Indicates whether an emergency issue occurred. 0 = Normal Issue; 1 = Emergency Issue
ISSUANCEFEE	CHAR	1	Indicates whether issuance fee will be charged. 0 = No fee; 1 = Charge fee

IST_CMS_CARD Table

Field Name	Type	Size	Description
SEND_TO_BRANCH	CHAR	1	Determines whether the card is held at the branch for customer: Y: to send the card at the branch; N: not to send the card to the branch.
BLOCK_CODE	CHAR	1	Displays the block code for the card: ' ' - Normal F - Fraud L - Lost S - Stolen N - No renew Q - Writeoff T - Terminated
PRODUCTION_IND	CHAR	1	Production status of the card. 0 = Normal 1 = New Issue 2 = Renewal



EMV Tables

Table Descriptions

CAMKEYS

Master Keys and configuration for EMV Application Cryptogram processing and Issuer Script Mac Generation.

CAMKEYS Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique Institution Identifier.
BIN	CHAR	10	Indicates the internal Bank Institution Number
USERBINID	CHAR	10	Indicates the User Bank Institution Number
KEY_INDEX	NUMBER		Indicates the index of the master derivation keys
CRYPTOGRAM	CHAR	74	Indicates the Master Key for Authentication Cryptograms (used in ARQC verification and ARPC generation)

CAMKEYS Table

Field Name	Type	Size	Description
MKSMI	CHAR	74	Indicates the master key for secure messaging integrity (used in the generation of the MAC for issuer scripts)
IVAC	CHAR	32	Indicates the Initialization vector for EMV 2000 Application Cryptogram session key derivation
IVSMI	CHAR	32	Indicates the Initialization vector for EMV2000 Secure Messaging for Integrity session key derivation
BFACTOR	NUMBER		Indicates the branch factor for EMV2000 session key derivation
TREEHEIGHT	NUMBER		Indicates the tree height for EMV2000 session key derivation
ONBEHALF_APP	CHAR	8	Used to set the ARPC response code for MCHIP4 and CSU for CCD for cryptogram processing on behalf of the issuer when the transaction is approved. Char 1: Approve "Y" or "N" Used to set CSU Byte 2 Bit 8 Used to set ARPC Response code Byte 2 Bit 5 Char2: Force Online "Y" or "N" Used to set CSU Byte 2 Bit 4 Used to set ARPC Response code Byte 2 Bit 3 Char3: Offline Counter "N", "R", "A", "U" Used to set CSU Byte 2 bit 1 and 2 Used to set ARPC Response code Byte 2 bit 1 and 2 Where "N" = Do not update counters "R" = Reset Counters to Zero "A" = Add transaction to Counters "U" = Set counters to upper offline limit

CAMKEYS Table

Field Name	Type	Size	Description
ONBEHALF_DEC	CHAR	8	Used to set the ARPC response code for MCHIP4 and CSU for CCD for cryptogram processing on behalf of the issuer when the transaction is declined. Char 1: Approve "Y" or "N" Used to set CSU Byte 2 Bit 8 Used to set ARPC Response code Byte 2 Bit 5 Char2: Force Online "Y" or "N" Used to set CSU Byte 2 Bit 4 Used to set ARPC Response code Byte 2 Bit 3 Char3: Offline Counter "N", "R", "A", "U" Used to set CSU Byte 2 bit 1 and 2 Used to set ARPC Response code Byte 2 bit 1 and 2 Where "N" = Do not update counters "R" = Reset Counters to Zero "A" = Add transaction to Counters "U" = Set counters to upper offline limit

CAMKEYS Table

Field Name	Type	Size	Description
ONBEHALF_REF	CHAR	8	Used to set the ARPC response code for MCHIP4 and CSU for CCD for cryptogram processing on behalf of the issuer when the transaction is referred Char 1: Approve "Y" or "N" Used to set CSU Byte 2 Bit 8 Used to set ARPC Response code Byte 2 Bit 5 Char2: Force Online "Y" or "N" Used to set CSU Byte 2 Bit 4 Used to set ARPC Response code Byte 2 Bit 3 Char3: Offline Counter "N", "R", "A", "U" Used to set CSU Byte 2 bit 1 and 2 Used to set ARPC Response code Byte 2 bit 1 and 2 Where "N" = Do not update counters "R" = Reset Counters to Zero "A" = Add transaction to Counters "U" = Set counters to upper offline limit

CAMKEYS Table

Field Name	Type	Size	Description
STIP_APP	CHAR	8	Used to set the ARPC response code for MCHIP4 and CSU for CCD for cryptogram processing in stand in for the issuer when the transaction is approved. Char 1: Approve "Y" or "N" Used to set CSU Byte 2 Bit 8 Used to set ARPC Response code Byte 2 Bit 5 Char2: Force Online "Y" or "N" Used to set CSU Byte 2 Bit 4 Used to set ARPC Response code Byte 2 Bit 3 Char3: Offline Counter "N", "R", "A", "U" Used to set CSU Byte 2 bit 1 and 2 Used to set ARPC Response code Byte 2 bit 1 and 2 Where "N" = Do not update counters "R" = Reset Counters to Zero "A" = Add transaction to Counters "U" = Set counters to upper offline limit

CAMKEYS Table

Field Name	Type	Size	Description
STIP_DEC	CHAR	8	Used to set the ARPC response code for MCHIP4 and CSU for CCD for cryptogram processing in stand in for the issuer when the transaction is Declined Char 1: Approve "Y" or "N" Used to set CSU Byte 2 Bit 8 Used to set ARPC Response code Byte 2 Bit 5 Char2: Force Online "Y" or "N" Used to set CSU Byte 2 Bit 4 Used to set ARPC Response code Byte 2 Bit 3 Char3: Offline Counter "N", "R", "A", "U" Used to set CSU Byte 2 bit 1 and 2 Used to set ARPC Response code Byte 2 bit 1 and 2 Where "N"= Do not update counters "R" = Reset Counters to Zero "A" = Add transaction to Counters "U" = Set counters to upper offline limit

CAMKEYS Table

Field Name	Type	Size	Description
STIP_REF	CHAR	8	Used to set the ARPC response code for MCHIP4 and CSU for CCD for cryptogram processing in stand in for the issuer when the transaction is referred Char 1: Approve - "Y" or "N" Used to set CSU Byte 2 Bit 8. Used to set ARPC Response code Byte 2 Bit 5 Char2: Force Online "Y" or "N" Used to set CSU Byte 2 Bit 4 Used to set ARPC Response code Byte 2 Bit 3 Char3: Offline Counter "N", "R", "A", "U" Used to set CSU Byte 2 bit 1 and 2 Used to set ARPC Response code Byte 2 bit 1 and 2 Where "N" = Do not update counters "R" = Reset Counters to Zero "A" = Add transaction to Counters "U" = Set counters to upper offline limit

EMVSTIPCHK

This table stores the conditions verified by the IST/Switch during stand-in processing of chip-card transactions. IST/Switch provides a default callback function. However, you are responsible for writing your own callback function if you want to change the default stand-in conditions. In this case, note that you are also responsible for ensuring the consistency between this table and the callback function.

EMVSTIPCHK Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier.
USERBINID	CHAR	10	Internal Bank Institution Number.
BIN	CHAR	10	Bank Institution Number
CHECK_CLASS	NUMBER		Condition class. Valid values: 1 positive authorization, 2 negative authorization, 3 positive or negative authorization
CHECK_STRING	CHAR	32	32-bit condition mask used to select the conditions verified during negative or positive authorization. When the n-th bit is 1, IST/Switch checks the n-th condition in the callback function. Otherwise, IST/Switch skips to the next condition.
ACTION_STRING	CHAR	32	32-bit action mask used to select the action taken when a certain condition is satisfied. Set to 1 (decline transaction) or 0 (approve transaction).
ISSUER_RESP	CHAR	64	Response codes to be set when IST/Switch declines a transaction because a condition is satisfied.
CALLBACK	CHAR	30	Name of the callback function used to check the conditions under positive, negative, or both classes. Default callback for VSDC is emv_chkcb_default Default callback for MCHIP is emv_chkcb_mchip
DESCRIPTION	CHAR	32	User comments
COND1	CHAR	48	Description of the condition check1.

EMVSTIPCHK Table <Variable> (Continued)

Field Name	Type	Size	Description
COND2	CHAR	48	Description of the condition check2.
COND3	CHAR	48	Description of the condition check3.
COND4	CHAR	48	Description of the condition check4.
COND5	CHAR	48	Description of the condition check5.
COND6	CHAR	48	Description of the condition check6.
COND7	CHAR	48	Description of the condition check7.
COND8	CHAR	48	Description of the condition check8.
COND9	CHAR	48	Description of the condition check9.
COND10	CHAR	48	Description of the condition check10.
COND11	CHAR	48	Description of the condition check11.
COND12	CHAR	48	Description of the condition check12.
COND13	CHAR	48	Description of the condition check13.
COND14	CHAR	48	Description of the condition check14.
COND15	CHAR	48	Description of the condition check15.
COND16	CHAR	48	Description of the condition check16.
COND17	CHAR	48	Description of the condition check17.
COND18	CHAR	48	Description of the condition check18.
COND19	CHAR	48	Description of the condition check19.
COND20	CHAR	48	Description of the condition check20.

EMVSTIPCHK Table <Variable> (Continued)

Field Name	Type	Size	Description
COND21	CHAR	48	Description of the condition check21.
COND22	CHAR	48	Description of the condition check22.
COND23	CHAR	48	Description of the condition check23.
COND24	CHAR	48	Description of the condition check24.
COND25	CHAR	48	Description of the condition check25.
COND26	CHAR	48	Description of the condition check26.
COND27	CHAR	48	Description of the condition check27.
COND28	CHAR	48	Description of the condition check28.
COND29	CHAR	48	Description of the condition check29.
COND30	CHAR	48	Description of the condition check30.
COND31	CHAR	48	Description of the condition check31.
COND32	CHAR	48	Description of the condition check32.



OAS Tables

Table Descriptions

OAS_AUDIT2

When enabled, login attempts are logged in the OAS_AUDIT2 table in the entitlement database and can be viewed using the User Authentication Audit form.

OAS_AUDIT2 Table

Field Name	Type	Size	Description
CLIENT_ID	NUMBER	25	Client identification/numeric ID of the user. The unique user ID corresponding to the user who performed the action. (zero if not applicable).
DATE	DATETIME		Indicates the timestamp of the activity.

OAS_AUDIT2 Table

Field Name	Type	Size	Description
ACTIVITY	VARCHAR	25	Indicates the user activity.
REASON	VARCHAR	25	Indicates the reason for the outcome of the operation and reason for failure.
PARAMS	VARCHAR	100	The encoded input and output parameters to the operation.

OAS_COUNTER

The OAS_COUNTER is a table with a single row and a single column. It contains the counter with the first available client ID to be used for new users in OAS_USER.

OAS_COUNTER Table

Field Name	Type	Size	Description
CLIENT_ID	DECIMAL	25	Client identification/numeric ID of the user.

OAS_USER

OAS_USER Table

Field Name	Type	Size	Description
CLIENT_ID	DECIMAL	25	An unique identifier.
STATUS	CHAR	1	Status of the account. Values: L - locked T - Terminated Space - Normal
USER_ID	VARCHAR	12	User ID .
PASSWORD	VARCHAR	48	Hash of the current password, base64-encoded.
PWD_STATUS	CHAR	1	Values: I - initial (expired) Space - Normal
PWD_CHANGE_DATE	DATE		Date and time of the last successful password change.
PWD_CHANGE_TIME	INTEGER		

OAS_USER Table

Field Name	Type	Size	Description
PWD_CNT	INTEGER		Number of times the current password has been used for authentication.
PWD_RETRIES	INTEGER		Number of consecutive failed authentication attempts with the password.
PWD_FAIL_DATE	DATE		Date and time of the last failed authentication attempt.
PWD_FAIL_TIME	INTEGER		
PWD_SUCC_DATE	DATE		Date and time of the last successful authentication attempt.
PWD_SUCC_TIME	INTEGER		
PWD_LIFE	INTEGER		Number of days the password stays valid (null to use the server's default).
PWD_MAX_CNT	INTEGER		Maximum number of authentications for which the password is valid (null to use the server's default).
PWD_MAX_RETRIES	INTEGER		Maximum failed authentication attempts before the account is locked.



POS Tables

Table Descriptions

ACQ_ENTITY

The Acq_Entity table stores information on entities (e.g merchant, store) within an institution.

ACQ_ENTITY Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates an internal ID assigned to an institution. It represents the highest level of the client within the system. e.g. ABC Bank, CLIENT
ENTITY_ID	VARCHAR	30	Indicates the Internal ID assigned to an entity.
ENTITY_LEVEL_IND	NUMBER	2	Indicates the numeric value representing the level of an entity in the entity hierarchy.
ENTITY_NAME	VARCHAR	50	Indicates the legal business name of the entity (e.g., merchant).

ACQ_ENTITY Table

Field Name	Type	Size	Description
ENTITY_DBA_NAME	VARCHAR	50	The "Doing Business As" name for this entity. This is the name by which the entity is known to its clients. Value is send to networks in DE 43.
ENTITY_ABA_NR	VARCHAR	9	The ABA (American Bank Association) number identifies a merchant to a direct debit switch.
SETTL_PLAN_ID	NUMBER	12	Indicates the ID of the settlement plan to be used for an entity.
ENTITY_STATUS	CHAR	1	A code used to indicate the status of an entity. Sample values: A (active), N (not active).
PARENT_ENTITY_ID	VARCHAR	30	Indicates the ID of the parent entity. NULL, if the entity doesn't have parent entity
ALLW_ID	NUMBER	12	Identifies a set of different allowances. Reference to allowance table. Default: NULL.
EXTERNAL_ENTITY_ID	VARCHAR	30	An optional ID assigned to the entity, to uniquely identify the entity system wide.
CAL_ACTIVITY_ID	VARCHAR	15	The Calendar Activity ID that is applicable to the entity. Default for IST/Switch, POS Subsystem: NULL
CREATION_DATE	DATE		Indicates the date the entity record was created.
EXP_START_DATE	DATE		Indicates the date when the first transaction is expected to be received.
ACTUAL_START_DATE	DATE		Date when the first transaction for this entity (e. g. merchant) can be actually received and processed.
TERMINATION_DATE	DATE		Indicates the date when no more transactions can be accepted from entity.
ALW_NON_QUAL_UPGRD	CHAR	1	Indicates whether an upgrade is allowed (i.e., credit amount to pay to an entity). Used only for non-qualification calculations.

ACQ_ENTITY Table

Field Name	Type	Size	Description
NON_QUAL_IND	CHAR	1	Non Qualification Indicator (Y/N). Indicates whether the non-qualification calculation should be performed when incoming transactions contain a MAS code other than the one expected for this entity (merchant).
ALW_RECLASS_UPGRD	CHAR	1	Y/N flag indicating whether the merchant is allowed to receive an upgrade resulting from reclassified transactions: Y = reclass upgrade allowed.
ON_HOLD_IND	CHAR	1	Indicates whether or not payments should be suspended for this entity: Y = Payments suspended.
ON_HOLD_SETTL_PLAN	NUMBER	12	Identifies the settlement plan to be used for the entities marked "OnHold".
HOT_MERCHANT_FLAG	CHAR	1	An indicator used to specify whether not the entity is a Hot merchant. Y = entity is a hot merchant.
TAX_EXEMPT_IND	CHAR	1	An indicator used to determine whether or not the entity is exempted from paying taxes.
RSRV_FUND_STATUS	CHAR	1	Indicates the status of the reserve fund collection. Sample values: blank (no reserve needed) R (reserve needed) F (reserve fund fulfilled)
RSRV_TO_BE_MET	NUMBER	26,8	The maximum amount of funds to be held in reserve for the entity. It is used only when the reserve fund status indicates that split payment is in effect.
RSRV_PERCENTAGE	NUMBER	26,8	Percentage of the transaction amount that is to be directed to the reserve fund account of the entity. It is used only when the reserve fund status indicates that split payment is in effect.

ACQ_ENTITY Table

Field Name	Type	Size	Description
COMPANY_TYPE	VARCHAR	3	Indicates the company type. Sample values: 100 = Sole Proprietorship / Individual; 101 = Partnership; 200 = Corporation; 2 01 = Limited Liability Company; 300 = Medical; 301 = Legal; 400 = Association; 401 = Estate; 402 = Trust Company; 500 = Discontinued; 800 = International Organization; 901 = Government, Federal; 902 = Government, State/Province; 903 = Government, Local.
VAT_REG_NR	VARCHAR	20	Indicates the value added tax registration number.
SETTL_AGT_NR	VARCHAR	4	Indicates the settlement agent number.
TZ_DIFF	CHAR	3	Indicates the time zone difference.
PROCESSING_TYPE	VARCHAR	5	Information field indicating how the entity transmits its processing file to the processor. sample Values: Facts, CDC, NDC, Offsite (OFSTE), SPS.
BILLING_TYPE	CHAR	2	Information field used to indicate how the entity is billed. Sample values: DB (Discount Plan Bundled), DP (Discount Plan), DR (Discount Rates).
TAX_ID	VARCHAR	20	Indicates the federal tax ID.

ACQ_ENTITY Table

Field Name	Type	Size	Description
RECLASS_IND	CHAR	1	A report indicator determining whether reclasses are combined with the fees or reported separately: S (Separate) = reclasses reported separately from fees; C (Combined) = reclasses reported combined with fees.
LAST_TRANS_CL_DATE	DATE		Indicates the date when the last activity transaction was processed for the entity.
AUTH_BY_LOC_IND	CHAR	1	An information field used to indicate whether or not authorizations are sent to MAS by location level, or by default corporate level. Y = location level.
DAYS_TO_HOLD	NUMBER	3	Indicate the number of days to delay a payment for an 'on hold' acquiring entity.
PFOLIOSALE_ACQ_BIN	VARCHAR	6	Indicates the BIN of the acquirer purchasing the merchant portfolio.
MERCH_REF_NBR	VARCHAR	20	Indicates the merchant reference number.
TIN_TYPE	CHAR	1	Identifies the Taxpayer ID Number as a Social Security Number or Employee Identification Number.
OOB_DATE	DATE		Date the merchant ceased to engage in any Visa business at the merchant location.
OWNERSHIP_CHG_DATE	DATE		Indicates the date the ownership of the business changed.
INFO_REFUSAL_IND	CHAR	1	Indicates that the merchant refused to provide its Taxpayer ID number to the Acquirer.
MPS_ID	NUMBER	12	Indicates the merchant profile service ID.

ACQ_ENTITY Table

Field Name	Type	Size	Description
BUSINESS_OWNERTYPE	NUMBER	2	Code indicating the type of the business owner. Sample values: 0 = Unknown; 1 = No applicable classification (not female or handicapped); 2 = Female; 3 = Physically handicapped female; 4 = Physically handicapped male; 11 = Veteran Indicator (Gender not Classified); 12 = Veteran Indicator, Female; 13 = Veteran Indicator, Male; 21 = Physically handicapped Veteran (Gender not classified); 22 = Physically handicapped veteran Female; 23 = Physically handicapped veteran Male; 81 = Veteran era specified (gender not classified), Vietnam.
OTHER_TYPE1	CHAR	1	Disadvantaged small business or certification type. Valid values: Y = SBA-certified small disadvantaged business; 0 = Unknown; 1 = Not certified as small disadvantage business; 2 = SBA-certified small business; 4 = Other government- or agency-recognized certification (such as Minority Supplier Development Council); 5 = Self certified small business; 6 = Dual certification as small business (e.g., by SBA and also recognized by other agency, or government); 7 = Dual certification as small disadvantage business (e.g., by SBA and also recognized by Other agency, or government); 8 = Dual certification as small business (e.g., Self certified and also recognized by other agency, or government); A = Dual certification as small business (e.g. Self certified and SBA); B = Self-certified small disadvantage business; C = SBA-certified as Historically Under utilized Business Zone.

ACQ_ENTITY Table

Field Name	Type	Size	Description
OTHER_TYPE2	NUMBER	2	Indicates the racial or ethnic type of the owner. Valid values: 00 = Unknown; 01 = Not Minority Owned; 11 = African American; 12 = Asian Pacific American; 13 = Subcontinent Asian American; 14 = Hispanic American; 15 = Native American Indian; 16 = Native Hawaiian; 17 = Native Alaskan; 18 = Caucasian; 19 = Other.
ALT_TAX_ID	VARCHAR	15	Indicates the merchant's tax identification number for the alternate tax amount.
DUN_NBR	VARCHAR	30	A number assigned by DUN & Bradstreet (D&B) that identifies the Merchant on D&B's database.
MERCH_DNN_ID	NUMBER	3	Indicates the unique 3-digit merchant DNN prefix for Discover.
MERCH_DNN_PREFIX	NUMBER	2	Indicates the unique 2 Digit Merchant DNN prefix in Discover.
DNN_INVOICE_NBR	VARCHAR	8	Indicates the DNN Invoice Number (Discover)
INVOICE_BATCH	NUMBER	3	This field contains an American Express assigned three-digit code that specifies processing options applicable to this batch.
INVOICE_SUB_CD	NUMBER	2	This field contains an unique American Express assigned code that specifies Additional Amex controls and processing requirements.
PC_ID	CHAR	6	Process control ID (PCID) - a unique identifier assigned by the American Express to merchants, locations, and third party processors.
CAP_NBR	VARCHAR	10	Indicates the Amex Chain Affiliated Property Number.

ACQ_ENTITY Table

Field Name	Type	Size	Description
ESTABLISH_ALPHA_ID	VARCHAR	4	Indicates the Diners Establishment Alpha ID.
RECAP_REF_NBR	VARCHAR	8	Indicates the diners recap reference number.
CHARACTER_SET_IND	VARCHAR	3	Indicates the character set indicator.
LOC_LANG_MERCHDESC	VARCHAR	96	Indicates the description of merchant in local language.
MERCH_VOL_IND	CHAR	2	The number of basis points by which the Interchange Reimbursement Fee is reduced. All US acquired purchase and credit transactions must contain one of the following values: Space = not used; 01-99 = the number of basis points by which the Interchange Reimbursement Fee will be reduced. For Non-US purchases and credits, as well as all cash transactions, the Edit Package will pad this field with spaces. VIC will edit Merchant Name and Merchant Volume Indicator against the eligibility table.
RISK_ID_IND	CHAR	1	Represents the first part of the field "Special Condition Indicators" and indicate the merchant risk level, whether is zero floor-limit required and what are the terminal capabilities. Valid values (BASEII): space = RIS indicator is not required for the merchant; 1 = Zero floor-limit required; 2 = Terminal capable of reading and transmitting the full, unaltered contents of the magnetic stripe; 3 = Zero floor-limit and terminal capable of reading and transmitting the full, unaltered contents of the magnetic stripe. Other values can be added as applicable.

ACQ_ENTITY Table

Field Name	Type	Size	Description
PRESTIGIOUS_PR_IND	CHAR	1	Represents the second part of the field “Special Condition Indicators” and indicates whether the merchant belongs to the prestigious property category and therefore qualifies for a special Floor Limits and treatment. Valid values (BASE II): Space = None of the specified conditions are present; B = Hotel qualifying for a special Floor Limit of \$1000 and permitted to use Status Check Procedure; D = Hotel permitted to use Status Check Procedure with a Floor Limit of \$500 (lowest level of chargeback protection); F = Facsimile Draft provided; H = Visa Lodging Services, Hotel qualifies for the special floor limit (international only); L = Visa Lodging Services Merchant; S = Hotel or Restaurant merchant qualifies for a special Floor limit of \$1500 and has the highest level of chargeback protection; 8 = Quasi cash/Online gambling transaction. Other values can be added as applicable.
PROGRAM_REGISTR_ID	VARCHAR	6	Program Registration ID or Promotion Code. Monitors and tracks a participant's activity in special promotion programs. It provides members the ability to calculate and track value-added cardholder services and promotions, including rebate calculations, point programs, and transaction processing differentiation. Sample values: Warehouse Club Programs, Service Industries, Supermarket, etc.
IATA_CD	VARCHAR	3	A three-digit IATA code used in processing Extended Payment tickets.
TRAVEL_AGENCY_CD	VARCHAR	8	Indicates the code identifying the travel agency.
TRAVEL_AGENCY_NAME	VARCHAR	25	Indicates the name of the travel agency.
MERCH_VERIFI_VALUE	VARCHAR	10	Indicates the merchant verification value.
OIL_CO_BRAND_NAME	VARCHAR	9	The code indicating the brand name of the merchant oil company.

ACQ_ENTITY Table

Field Name	Type	Size	Description
DEFAULT_MCC	VARCHAR	5	Indicates the default MCC.
LANGUAGE_CODE	VARCHAR	3	The ISO language code used to define multi-language displays of reports and screens.
COMPANY_ID	VARCHAR	30	Indicates the company identifier of the entity.
ACCT_PPLAN_ID	VARCHAR	25	Unique identifier for the account posting plan.
DEF_POSTING_ENTITY	VARCHAR	25	Default posting entity to be used if the posting entity id in settlement plan is null.
SETUP_STAGE	CHAR	1	Indicates the setup stage where the user left the Merchant Setup Screen.
SETUP_COMPLETE_IND	CHAR	1	Indicates the setup complete indicator.

ACQ_ENTITY_ADDRESS

This associative table stores the address IDs associated with an acquiring entity.

ACQ_ENTITY_ADDRESS Table

Field Name	Type	Size	Description
ADDRESS_ROLE	VARCHAR	20	A value assigned by the system to an address role. This must be a value from the address role list maintained in the field value control table (GLOBAL_VALUE_CTRL).
EFFECTIVE_DATE	DATE		Indicates the effective date of the rate.
ADDRESS_ID	NUMBER	12	A system-assigned value given to an address record.
ENTITY_ID	VARCHAR	30	An Internal ID assigned to an entity.
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.

ALLOWANCE

This table groups together a set of allowance properties that can be assigned to an entity (e.g., merchant).

ALLOWANCE Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
ALLW_ID	NUMBER	12	A number assigned to an allowance record.
DESCRIPTION	VARCHAR	50	Indicates the description of the allowance.

ALLW_CARD_SCHEME

This table specifies the card schemes allowed for an entity using the associated allowance profile (controlled by allowance ID).

ALLW_CARD_SCHEME Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
ALLOWANCE ID	NUMBER	12	Indicates the number assigned to an allowance record.
CARD SCHEME	CHAR	2	A code used to identify a card scheme. Valid Values: 03 (Amex), 04 (Visa), 05 (MasterCard), 06 (Europay), 07 (Diners Club), 08 (Discover), 09 (JCB).

ALLW_CURR

This table specifies the allowed currencies for an entity using the associated allowance profile (controlled by allowance ID). For merchants for example, these are the currencies for acquiring transactions.

ALLW_CURR Table

Field Name	Type	Size	Description
INSTITUTION ID	VARCHAR	10	An internal ID assigned to an institution.
ALLOWANCE ID	NUMBER	12	A number assigned to an allowance record.
CURRENCY ROLE	VARCHAR	20	A system- assigned value given to a currency role (e.g. a base currency role).
CURRENCY CODE	CHAR	3	Indicates the ISO 8583 currency code.
CURRENCY NAME	CHAR		Indicates the description of currency code.

ALLW_LANG

This table specifies the language codes allowed for an entity using the associated allowance profile (controlled by allowance ID).

ALLW_LANG Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
ALLOWANCE ID	NUMBER	12	A number assigned to an allowance record.
LANGUAGE_CODE	VARCHAR	3	The ISO language code associated to this allowance record.
LANGUAGE_STATUS	CHAR	1	Indicates the language status. Valid values are P= Primary; S= Secondary.

ALLW_MCC

This table specifies the Merchant Category Codes allowed for an entity using the associated allowance profile (controlled by allowance ID).

ALLW_MCC Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
ALLW_ID	NUMBER	12	A number assigned to an allowance record.
CARD_SCHEME	CHAR	2	A code used to identify a card scheme. Values: 03 (Amex), 04 (Visa), 05 (MasterCard), 06 (Europay), 07 (Diners Club), 08 (Discover), 09 (JCB).
MCC	VARCHAR	5	A code used to identify the type of business a merchant conducts.
USAGE	VARCHAR	15	Usage. Possible values: CLEARING, MAS, CRD etc.

ALLW_POS_FORMAT

This table specifies the POS formats allowed for an entity using the associated allowance profile (controlled by allowance ID).

ALLW_POS_FORMAT Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
ALLOWANCE_ID	NUMBER	12	A number assigned to an allowance record.
CARD_SCHEME	CHAR	2	A code used to identify a card scheme. Values: 03 (Amex), 04 (Visa), 05 (MasterCard), 06 (Europay), 07 (Diners Club), 08 (Discover), 09 (JCB).
POS_FORMAT	VARCHAR	8	Indicates the sequential ID of the POS message format.

ALLW_FLOOR_LIM

The table holds information about allowed floor limits of a terminal. These values are used for download to device and for use by device. Please note, that these values are not used for evaluation of message by IST/Switch subsystems.

ALLW_FLOOR_LIMTable

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
ALLW_ID	NUMBER	12	A number assigned to an allowance record.
ACQ_INST_ID	VARCHAR2	10	Indicates the acquirer.
PRE_COM_LIM	NUMBER	3	For a non-IC transaction, the value to which a terminal shall seek the acquirer's approval before completing the transaction i.e. the terminal is not permitted to complete the transaction locally. For an IC transaction, the value may be used in a random selection for on-line authorization or the terminal and issuer action codes specify the actions to be taken when the transaction amount is greater than or equal to this value. Resets the terminal floor limit if the terminal supports this function. Units are in the largest denomination of the default currency
POST_COM_LIM	NUMBER	3	For a non-IC transaction, the value which a terminal shall not complete the transaction locally, having attempted but failed to contact the acquirer. For an IC transaction, this value may be used. Units are in the largest denomination of the default currency.

ALT_MERCHANT_ID

This table maps internal merchant IDs to card association-recognized merchant IDs.

ALT_MERCHANT_ID Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
ENTITY_ID	VARCHAR	30	Internal ID assigned to an entity
CARD_SCHEME	CHAR	2	A code used to identify a card scheme. Values: 03 (Amex), 04 (Visa), 05 (MasterCard), 06 (Europay), 07 (Diners Club), 08 (Discover), 09 (JCB).
CS_MERCHANT_ID	VARCHAR	30	Card scheme merchant ID.
CLEARING_FLAG	CHAR	1	This indicates merchant is doing clearing through card association or directly.
PROP_LICENCE_FLAG	CHAR	1	JCB, Diners Proprietary License Flag.
TIER_IND	VARCHAR	3	Indicates the tier indicator.
CS_TIER_MERCH_ID	NUMBER	6	Tiered Merchant Identifier.

CARD_SCHEME

This table specifies a list of valid card schemes supported by the system (e.g. Visa, MasterCard, Europay, JCB, AMEX, Discover and other private label cards).

CARD_SCHEME Table

Field Name	Type	Size	Description
CARD_SCHEME	CHAR	2	A code used to identify a card scheme. Values: 03 (Amex), 04 (Visa), 05 (MasterCard), 06 (Europay), 07 (Diners Club), 08 (Discover), 09 (JCB).
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
CARD_SCHEME_NAME	VARCHAR	50	Name of the card scheme. (E. g. Visa, MasterCard, Amex)

COUNTRY

This table stores countries recognized by either ISO or card associations and mainly used as a reference table.

COUNTRY Table

Field Name	Type	Size	Description
CNTRY_CODE	CHAR	3	ISO 8583 standard 3-digit code identifying a country.
CNTRY_NAME	VARCHAR	50	The name of the country.
CNTRY_CODE_ALPHA2	CHAR	2	A 2-character alpha code assigned to a country.
CNTRY_CODE_ALPHA3	CHAR	3	A 3-character alpha code assigned to a country.
CURR_CODE	CHAR	3	An ISO code identifying a currency. (E.g. 124 for Canadian Dollar).

COUNTRY Table

Field Name	Type	Size	Description
CURR_PATTERN	VARCHAR	12	Currency pattern for storage and display purposes, e.g. #,##0.000.
DATE_PATTERN	VARCHAR	20	Indicates the date pattern.
ECONOMIC_AREA_IND	VARCHAR	4	Indicates the economic area indicator.

COUNTY

This table stores counties within a province or state for reference purposes.

COUNTY Table

Field Name	Type	Size	Description
PROV_STATE_NUM_CD	NUMBER	2	Numerical code assigned by Visa to identify a province or state.
COUNTY_CD	NUMBER	4	A three-digit ISO (3166) code identifying a country.
COUNTY	VARCHAR	25	Full name of the county.
COUNTY_ABBREV	CHAR	5	Abbreviation used for the county.

CURRENCY_CODE

This table stores a list of ISO 8583 currency codes.

CURRENCY_CODE Table

Field Name	Type	Size	Description
CURR_CODE	CHAR	3	An ISO code identifying a currency. (E.g. 124 for Canadian Dollar).
CURR_NAME	VARCHAR	50	Name of the currency (e.g. Canadian Dollar, British Pound, etc).
CURR_CODE_ALPHA2	CHAR	2	The 3-character (alpha) currency code (E.g. CAN for Canadian Dollar).
CURR_CODE_ALPHA3	CHAR	3	The 3-character (alpha) currency code (E.g. CAN for Canadian Dollar).
CURR_EXPONENT	CHAR	1	A number indicating the decimal point location in the currency amount.

ENTITY_LEVEL

This table stores the entity levels used when assigning as Acquiring Entity to a level in the hierarchy. Each level can be described by a name using the Entity Type column.

ENTITY_LEVEL Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
ENTITY_LEVEL_IND	NUMBER	2	Numeric value representing the level of an entity in the entity hierarchy
ENTITY_TYPE	VARCHAR	20	A code used to identify the entity level within the entity hierarchy (e.g., agent, chain, merchant, corporate merchant)

INSTITUTION

An institution is an entity, which is identified by an internally- assigned, unique ID within the system. Institutions are classified by type (inst_ type column) such as main_ inst, member, card_ association, etc. This table is part of the institution setup.

INSTITUTION Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
INST_TYPE	VARCHAR	20	Identifies the type of this institution (e.g. MAIN_INST, CARD_ASSOC, MEMBER etc.).
INST_NAME	VARCHAR	40	The name of the institution associated with the INSTITUTION_ID.
INST_FYEAR_ST_DT	CHAR	4	A value defining the fiscal year of an institution (format MMDD).
LANGUAGE_CODE	VARCHAR	3	The ISO language code used to define multi-language displays of reports and screens. Default: English.
SECONDARY_LANGUAGE_CODE	VARCHAR	3	The ISO language code used to define multi-language displays of reports and screens.
INST_CURR_CODE	CHAR	3	To determine the currency in which the GL entries are maintained in MAS.

LANGUAGE

This table stores the ISO language codes used in the system.

LANGUAGE Table

Field Name	Type	Size	Description
LANGUAGE_CODE	VARCHAR	3	The ISO language code used to define multi-language displays of reports and screens. Default: English.
LANGUAGE_DESC	VARCHAR	20	Indicates the description of the language

MASTER_ADDRESS

The Master_Address table contains details on all addresses stored in the system. Each address has a unique system-assigned ID used to associate the address with an entity (e.g., institution, merchant, etc.) through an associative table (e.g., INST_ADDRESS).

MASTER_ADDRESS Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
ADDRESS_ID	NUMBER	12	A system-assigned value given to an address record. Reference to acq_entity_address.
ADDRESS1	VARCHAR	50	The first row of information in the address.
ADDRESS2	VARCHAR	50	The second row of information in the address.
CITY	VARCHAR	50	Indicates the city name.
PROV_STATE_ABBREV	CHAR	3	An alphabetic code identifying the province (state) of the address.
PROV_STATE_NUM_CD	NUMBER	2	Numerical code assigned by Visa to identify a province or state.

MASTER_ADDRESS Table

Field Name	Type	Size	Description
PROVINCE_STATE	VARCHAR	50	Full name of the province or state.
COUNTY_CD	NUMBER	4	County code. Required in USA for some card associations.
COUNTY	VARCHAR	25	Full name of the county of the address.
POSTAL_CD_ZIP	VARCHAR	20	Postal or Zip code corresponding to the address.
GEOCODE	VARCHAR	16	Special code for addressing needed by the Vertex tax system
CNTRY_CODE	CHAR	3	ISO 8583 standard 3-digit code identifying a country
COUNTRY	VARCHAR	50	Name of the country.
PHONE1	VARCHAR	30	The main telephone number at this address.
PHONE2	VARCHAR	30	The secondary telephone number at this address.
FAX	VARCHAR	30	The fax number used to send and receive facsimile messages.
EMAIL_ADDRESS	VARCHAR	100	E-mail address of an entity/contact person.
URL	VARCHAR	100	Internet address associated with this address ID.
ADDRESS3	VARCHAR	50	The third row of information in the address.
ADDRESS4	VARCHAR	50	The fourth row of information in the address.

GLOBAL_SEQ_CTRL

The Global Sequence Control Form contains sequence numbers for tables devoid of institution IDs.

GLOBAL_SEQ_CTRL Table

Field Name	Type	Size	Description
SEQ_NAME	VARCHAR	37	Name of the sequence
LAST_SEQ_NBR	NUMBER	15	Last value used for this sequential number.
MAX_SEQ_NBR	NUMBER	15	Maximum number allowed for the sequential number.
SEQ_BLOCK_SIZE	NUMBER	15	Value used for improving performance by UDM_UTIL package. UDM_UTIL will update the sequence number plus the size when getNextSeq() is called for the first time. Each time after that, the database is not accessed by getNextSeq() to call the seq_block_size. So, getNextSeq() will have better performance because it does not access database each time.

GLOBAL_VALUE_CTRL

The Global Value Control table includes the fields described below.

GLOBAL_SEQ_CTRL Table

Field Name	Type	Size	Description
FIELD_NAME	VARCHAR	37	Name of the column in database tables.
FIELD_VALUE	VARCHAR	20	Predefined values for associated column.
FIELD_VALUE_DESC	VARCHAR	200	Description of the field value

MCC

Merchant Category Code table contains information for classifying merchants.

MCC Table

Field Name	Type	Size	Description
CARD_SCHEME	CHAR	2	A code used to identify a card scheme. Sample values: 03 (Amex), 04 (Visa), 05 (MasterCard), 06 (Europay), 07 (Diners Club), 08 (Discover), 09 (JCB).
MCC	VARCHAR	5	A code used to identify the type of business a merchant conducts
MERCHANT_TYPE	VARCHAR	4	A code used to categorize a merchant based on the type of business conducted. This type is implied through the MCC.
DESCRIPTION	VARCHAR	100	Description of the category code.

MERCHANT_TYPE

This table stores the valid merchant types defined by a card association.

MERCHANT_TYPE Table

Field Name	Type	Size	Description
CARD_SCHEME	CHAR	2	A code used to identify a card scheme. Sample values: 03 (Amex), 04 (Visa), 05 (MasterCard), 06 (Europay), 07 (Diners Club), 08 (Discover), 09 (JCB).
MERCHANT_TYPE	VARCHAR	4	A code used to categorize a merchant based on the type of business conducted. This type is implied through the MCC.
DESCRIPTION	VARCHAR	50	Description of the merchant type.

POS_MSG_BRAND

This is an internal table that should be maintained by eFunds Corporation.

POS_MSG_BRAND Table

Field Name	Type	Size	Description
POS_MESSAGE_BRAND	NUMBER	4	Indicates the Message Brand (Key field). Please use const. above 200 for custom brand.
MESSAGE_BRAND	VARCHAR	20	Indicates the VISA_2ND, HYPERCOM, VERIFONE, ECHO, ISO_8583,ISO_8583_ECHO. (This will be set in UA description file.)
MESSAGE_VERSION	VARCHAR2	20	Indicates the 5_3, 5_4, 5_6, 5_8, 6_1, 3_332, 0 (This will be used in UA description file.)

POS_MSG_FORMAT

This table stores information for a terminal.

POS_MSG_FORMAT Table

Field Name	Type	Size	Description
POS_FORMAT	VARCHAR2	8	Indicates the Index.
POS_MSG_BRAND	NUMBER	4	Indicates the message brand e.g., Visa 5.8, Visa 6.1, Hypercom 3.32.
FORMAT	CHAR	32	Indicates the Map of message formats. Define as required.
BLOCK	CHAR	32	Indicates the Map for blocking of the message format (for V2DC).

POS_MSG_FORMAT Table

Field Name	Type	Size	Description
LOG	CHAR	32	Indicates the Map for logging of the message format.
TRACE	CHAR	32	Indicates the Map for tracing of the message format
DESCRIPTION	VARCHAR2	50	Indicates the description of the message format.

POS_OPEN_HOUR

This table stores the terminal open hours for a merchant.

POS_OPEN_HOUR Table

Field Name	Type	Size	Description
HOUR_ID	NUMBER	4	Indicates an automatically generated sequence.
IX	CHAR	1	Indicates the Day. Valid values are:0-Sunday ... 6-Saturday.
OPENHR	NUMBER	4	Indicates the time that terminal opens per Hour ID.HHMM,OpenHr =0, CloseHr=2359 means open 24 hours.
CLOSEHR	NUMBER	4	Indicates the time that terminal closes per Hour ID. HHMM.

POS_REFNUM

This table allows record insertion or flag updates for existing records. The fields PAN, INFO, and FLAGS are used in other proprietary transaction sets to facilitate reversals.

POS_REFNUM Table

Field Name	Type	Size	Description
TERM_RECORD_SEQ	NUMBER	15	Indicates the terminal record sequence.
TERMINID	VARCHAR2	8	Indicates the terminal ID.
REFNUM	CHAR	12	Indicates the reference number.
ORIGMSG	NUMBER		Indicates the original message type.
PAN	CHAR	22	Indicates the Personal Account Number used in APACS format where reversal is required.
FLAGS	NUMBER		Indicates the Flags used in APACS format where reversal is required. Set by GUI or site-specific application.
INFO	CHAR	2	Indicates additional information.

POS_SHC2POS_RC

The table is used for Visa 2nd authorization messages.

POS_SHC2POS_RC Table

Field Name	Type	Size	Description
SHC_RESPONSE	NUMBER	4	Indicates the SHC generated response (<1000) or TMAP generated response >1000.
POS_MSG_BRAND	NUMBER	4	Indicates the key to POS_MSG_BRAND.
LANGUAGE_CODE	VARCHAR2	3	Language indicator (also in Visa 2nd authorization message).
CARD_SCHEME	CHAR	2	Indicates the optional card scheme.
DISPLAY_LENGTH	NUMBER	4	Indicates the optional display length.
POS_RESPONSE	CHAR	4	Indicates the POS response.
RESPONSE_TEXT	VARCHAR2	255	Indicates the response text.

POS_TERM_CAP_ADD

The POS Term Cap Addenda Table is an extension of the POS_TERM_CAP_TRANS table for industry specific data.

POS_TERM_CAP_ADD Table

Field Name	Type	Size	Description
POS_BATCH_IDX_A	CHAR	16	Indicates the Reference to POS_BATCH.
POS_TRANS_IDX_A	CHAR	16	Indicates the Reference to POS_TERM_CAP_TRANS.
POS_ADD_VERSION	CHAR	5	Indicates the Terminal Capture Addendum Version.
INDUSTRY_DATA_IND	NUMBER	2	Indicates the Industry Data Indicator.
COMM_CRD_DATA_IND	CHAR	1	Indicates the Commercial Card Data Indicator.
REQ_PAYMENT_SRV	NUMBER	2	Indicates the Requested Payment Service.
PRODUCT_CD	CHAR	6	Indicates the product code.
TRANSACTION_ID	CHAR	15	Indicates the transaction code.
VALID_CD	CHAR	4	Indicates the Valid Code.
REQ_ACI	CHAR	1	Indicates the Requested Authorization Characteristics Indicator.
RESP_ACI	CHAR	1	Indicates the Response Authorization Characteristics Indicator.
START_DATE	DATE		Indicates the start date.
END_DATE	DATE		Indicates the end date.
DAY_RATE	NUMBER	26,8	Indicates the day rate.
NO_SHOW_IND	CHAR	1	Indicates No Show Indicator.
EXTRA_CHARGES	CHAR	6	Indicates the extra charges.
MARKET_SPEC_REQ	CHAR	1	Indicates the Market Data Identifier request

POS_TERM_CAP_ADD Table

Field Name	Type	Size	Description
MARKET_SPEC_RESP	CHAR	1	Indicates the Market Data Identifier response.
FIRST_AUTH_AMT	NUMBER	26,8	Indicates the First Authorization Amount.
DURATION	NUMBER	2	Indicates the duration.
PURCH_ID	CHAR	25	Indicates the purchase ID.
PREST_PROP_IND	CHAR	1	Indicates the Prestigious Property Indicator.
COMM_CARD_REQ_IND	CHAR	1	Indicates the Commercial Card Request Indicator.
COMM_CARD_RESP_IND	CHAR	1	Indicates the Commercial Card Response Indicator.
SALES_TAX_FLAG	CHAR	1	Indicates the Sales Tax Flag.
SALES_TAX	NUMBER	26,8	Indicates the Sales Tax.
PURCH_ORDER_NR	CHAR	17	Indicates the Purchase Order Number.
FLEET_TYPE	CHAR	1	Indicates the Fleet Type.
FLEET_ID_NR	CHAR	17	Indicates the Fleet ID Number.
FLEET_RESTR	CHAR	1	Indicates the Fleet Restriction.
CH_AUTH_ENTITY	CHAR	1	Indicates the Cardholder Authentication Entity.
DISCOUNT_AMT	NUMBER	26,8	Indicates the Discount Amount.
FREIGHT_AMT	NUMBER	26,8	Indicates the Freight Amount.
DUTY_AMT	NUMBER	26,8	Indicates the Duty Amount.
DEST_ZIP_CD	CHAR	20	Indicates the Destination Zip Code.
INVOICE_NR	CHAR	6	Indicates the Invoice Number.

POS_TERM_CAP_ADD Table

Field Name	Type	Size	Description
CUST_REFERENCE_ID	CHAR	17	Indicates the Customer Reference ID.
CUST_VAT_REG_NR	CHAR	13	Indicates the Customer VAT Registration Number.
DEST_COUNTRY_CD	CHAR	3	Indicates the Destination Country Code.
LOCAL_TAX_INCLUDED	CHAR	1	Indicates the Local Tax Included.
LOCAL_TAX_AMT	NUMBER	26,8	Indicates the Local Tax Amount.
MUL_CL_SEQ_CNT	NUMBER	2	Indicates the Multiple Clearing Sequence Count.
MUL_CL_SEQ_NR	NUMBER	2	Indicates the Multiple Clearing Sequence Number.
NAT_TAX_AMT	NUMBER	26,8	Indicates the National Tax Amount.
NAT_TAX_INCL_FLAG	CHAR	1	Indicates the National Tax Included Flag.
ORI_CITY_AIRPRT_CD	CHAR	3	Indicates the Originating City Airport Code.
OTHER_TAX_AMT	NUMBER	26,8	Indicates the Other Tax Amount.
PASS_NAME	CHAR	20	Indicates the Passenger Name.
PURCH_ORDER_DATE	DATE		Indicates the Purchase Order Date.
RENTAL_RET_CITY	CHAR	18	Indicates the Rental Return City.
RENTAL_RET_LOC_ID	CHAR	10	Indicates the Rental Return Location ID.
RENTAL_RET_STATE	CHAR	3	Indicates the Rental Return State.
RENTER_NAME	CHAR	20	Indicates the Renter Name.
RESTR_TICKET_IND	CHAR	1	Indicates the Restricted Ticket Indicator.
SHIP_POST_CD	CHAR	10	Indicates the Ship postal code.

POS_TERM_CAP_ADD Table

Field Name	Type	Size	Description
SUMM_COMM_CD	CHAR	4	Indicates the Summary Commodity Code.
TAX_AMT	NUMBER	26,8	Indicates the Tax Amount.
TAX_RATE	NUMBER	4	Indicates the Tax Rate.
TICKET_NR	CHAR	13	Indicates the Ticket Number.
TOTAL_AUTH_AMT	NUMBER	26,8	Indicates the Total Authorization Amount.
TRIP_LEG_1_INFO	CHAR	7	Indicates the Trip Leg 1 Information.
TRIP_LEG_2_INFO	CHAR	7	Indicates the Trip Leg 2 Information.
TRIP_LEG_3_INFO	CHAR	7	Indicates the Trip Leg 3 Information.
TRIP_LEG_4_INFO	CHAR	7	Indicates the Trip Leg 4 Information.
REL_PARTICIPANT	CHAR	1	Indicates the Relationship Participant.

POS_TERM_CAP_AIR

The POS_TERM_CAP_AIR Table is an extension of the POS_BATCH log file for airline travel record details.

POS_TERM_CAP_AIR Table

Field Name	Type	Size	Description
POS_BATCH_IDX_M	CHAR	16	Indicates the Reference to POS_BATCH
POS_TRANS_IDX_M	CHAR	16	Indicates the Reference to POS_TERM_CAP_TRANS.
POS_LINE_IDX_M	CHAR	16	Indicates the Timestamp of line generated by UA.
ITEM_SEQUENCE_NR_M	NUMBER	3	Indicates the Item Sequence Number.
POS_LINE_VERSION_M	CHAR	5	Indicates the version (2.0).
COUPON_NR	NUMBER	1	Indicates the Coupon number.
CARRIER_CD	CHAR	2	Indicates the Carrier code.
FLIGHT_NR	CHAR	5	Indicates the Flight number.
SRV_CLASS	CHAR	2	Indicates the Service class.
ORI_CITY_AIRPRT_CD_M	CHAR	5	Indicates the Origination City/Airport Code.
STOP_OVER_CD	CHAR	1	Indicates the Stop over code.
DEST_CITY_CD	CHAR	5	Indicates the Destination City/ Airport code.
FARE_BASIS_CD	CHAR	8	Indicates the Fare Basis Code.
DEPT_DATE	CHAR	6	Indicates the Departure date.
DEPT_TIME	NUMBER	4	Indicates the Departure time.
ARRIV_TIME	NUMBER	4	Indicates the Arrival time.

POS_TERM_CAP_CHIP

The POS_TERM_CAP_CHIP Table is an extension of the POS_TERM_CAP_TRANS table and includes EMV related data.

POS_TERM_CAP_CHIP Table

Field Name	Type	Size	Description
POS_BATCH_IDX_C	CHAR	16	Indicates the Reference to POS_TERM_CAP_TRANS.
POS_TRANS_IDX_C	CHAR	16	Internal ID of POS_TERM_CAP_CHIP record.
POS_CHIP_VERSION	CHAR	5	2.0.
TERM_TXN_DATE	DATE		Indicates the Transaction Date.
DERI_KEY_IDX	CHAR	2	Indicates the Derivation Key Index.
CRYPTO_VERSION	CHAR	2	Indicates the Cryptogram Version Number.
CRYPTO_TXN_TYPE	NUMBER	2	Indicates the Transaction type.
TERM_COUNTRY_CODE	NUMBER	3	Indicates the ISO Country code.
CRYPTO_AMOUNT	CHAR	12	Indicates the Cryptogram amount.
TERM_CAP_PROFILE	CHAR	6	Indicates the Terminal Capture Profile.
TVR	CHAR	10	Indicates the Terminal Verification Results.
UNPREDICTABLE_NUM	CHAR	8	Indicates the Unpredictable number.
TERM_SER_NUM	CHAR	8	Indicates the Interface device Serial Number.
CVR	CHAR	8	Indicates the Card Verification Results.
CRYPTOGRAM	CHAR	16	Indicates the Response Cryptogram.
APP_TXN_COUNTER	CHAR	4	Indicates the Application Transaction Counter.

POS_TERM_CAP_CHIP Table

Field Name	Type	Size	Description
APP_ICHG_PROFILE	CHAR	4	Indicates the Application Interchange Profile.
ISSUER_SCRIPT_RES	CHAR	40	Indicates the Issuer Script.
CHIP_COND_CD	NUMBER	1	Indicates the Chip Condition Code.
CARD_SEQ_NR	NUMBER	3	Indicates the Card Sequence Number.
TERM_TYPE	NUMBER		Indicates the environment of the terminal, its communications capability, and its operational control.
CRYPTO_CURR_CODE	NUMBER		Indicates the currency code of the transaction.
NEG_FILE_VERSION	NUMBER		Indicates the version number assigned by the payment system for the application.
CCARD_CRYPT_TRACE	NUMBER		Indicates the type of cryptogram.
CRYPTO_CB_AMOUNT	NUMBER	26, 8	Indicates the secondary amount associated with the transaction representing a cashback amount.
ISSUER_DISCRE_DATA	CHAR	32	
ISSUER_APP_DATA	CHAR	64	Contains proprietary application data for transmission to the issuer in an online transaction.

POS_BATCH

The POS_BATCH table is the main logging file table for batch of transactions.

POS_BATCH Table

Field Name	Type	Size	Description
POS_BATCH_IDX	CHAR	16	Unique internal identification of Pos_Batch record.
INSTITUTION_ID	VARCHAR2	10	Indicates the institution of terminal, or special institution if without DB(default BIN).
ENTITY_ID	VARCHAR2	30	Indicates an internal ID assigned to an entity.
TERM_RECORD_SEQ	NUMBER	15	Indicates the Terminal Record Sequence or store (4) if without DB.
TERMINID	CHAR	8	Indicates the terminal ID. (4-8)
BATCH_ID	NUMBER		Indicates the batch number/
ORIG_BATCH_ID	NUMBER		Indicates the original internal batch number. Batch_nr – orig_tbatch_nr =retry.
TBATCH_ID	CHAR	8	Indicates the batch number from terminal.
CAPTURE_TYPE	CHAR	1	Indicates the capture type. Valid values: H – host capture (shclog*) T –Terminal capture (post_term_cap*) P - Pure Host Capture

POS_BATCH Table

Field Name	Type	Size	Description
CLOSE_FLAG	CHAR	1	Indicates the flag status. Valid values: S – Suspended O – open C – closed, totals matched; P – pending closure (initial 0500 received and totals mismatched); U – closed, mismatched totals, 320 totals match; Visa 2nd Good batch; N – closed, mismatched totals, 320 totals mismatch; L – lost 320 upload; R – Visa 2nd rejected batch; D – Visa 2nd duplicate batch. M - Mismatched Totals (OLTP)
EXTRACT_FLAG	CHAR	1	N – not ready for extract – initial value P – pending extract R – to be re-extracted –when error solved, set by GUI D – done – after extract – set by extract process S – suspended extract – set by GUI (from E or other reason); E – error during extract – skip this for the rest of generating BASEIIA.
OPEN_DATE	DATE		Open date set by Switch date – when the first message came.
OPEN_TIME	NUMBER	6	Open time set by Switch date – when first message came.
CLOSE_DATE	DATE		Open date set to 19900101, if open. Set by Switch date. – when was closed.
CLOSE_TIME	NUMBER	6	Close time set by Switch date. – when was closed.
DBC_NUM_DB	NUMBER		Indicates the Debit Card Number of Debits.
DBC_AMT_DB	NUMBER	26,8	Indicates the Debit Card Amount of Debits.
DBC_NUM_CR	NUMBER		Indicates the Debit Card Number of Credits.
DBC_AMT_CR	NUMBER	26,8	Indicates the Debit Card Amount of Credits.

POS_BATCH Table

Field Name	Type	Size	Description
DBC_NUM_ADJ	NUMBER		Indicates the Debit Card Number of Adjustments.
DBC_AMT_ADJ	NUMBER	26,8	Indicates the Debit Card Amount of Adjustments.
DBC_AMT_NET	NUMBER	26,8	Indicates the Fields not ending "g" are accumulated from 0[1234]xx messages.
DBC_NUM_DBG	NUMBER		Indicates the Debit Card Number of Debits from 0500 message.
DBC_AMT_DBG	NUMBER	26,8	Indicates the Debit Card Amount of Debits from 0500 message.
DBC_NUM_CRG	NUMBER		Indicates the Debit Card Number of Credits from 0500 message.
DBC_AMT_CRG	NUMBER	26,8	Indicates the Debit Card Amount of Credits from 0500 message.
DBC_NUM_ADJG	NUMBER		Indicates the Debit Card Number of Adjustments from 0500 message.
DBC_AMT_ADJG	NUMBER	26,8	Indicates the Debit Card Amount of Adjustments from 0500 message.
DBC_AMT_NETG	NUMBER	26,8	Indicates the Debit Card Amount Net from 0500 message.
CRC_NUM_DB	NUMBER		Indicates the Credit Card Number of Debits accumulated from 0[1234]xx messages.
CRC_AMT_DB	NUMBER	26,8	Indicates the Credit Card Amount of Debits accumulated from 0[1234]xx messages.
CRC_NUM_CR	NUMBER		Indicates the Credit Card Number of Credits accumulated from 0[1234]xx messages.
CRC_AMT_CR	NUMBER	26,8	Indicates the Credit Card Amount of Credits accumulated from 0[1234]xx messages.
CRC_NUM_ADJ	NUMBER		Indicates the Credit Card Number of Adjustments accumulated from 0[1234]xx messages.
CRC_AMT_ADJ	NUMBER	26,8	Indicates the Credit Card Amount of Adjustments accumulated from 0[1234]xx messages.
CRC_AMT_NET	NUMBER	26,8	Indicates the Credit Card Amount Net accumulated from 0[1234]xx messages.
CRC_NUM_DBG	NUMBER		Indicates the Credit Card Number of Debits from 0500 message.

POS_BATCH Table

Field Name	Type	Size	Description
CRC_AMT_DBG	NUMBER	26,8	Indicates the Credit Card Amount of Debits from 0500 message.
CRC_NUM_CRG	NUMBER		Indicates the Credit Card Number of Credits from 0500 message.
CRC_AMT_CRG	NUMBER	26,8	Indicates the Credit Card Amount of Credits from 0500 message.
CRC_NUM_ADJG	NUMBER		Indicates the Credit Card Number of Adjustments from 0500 message.
CRC_AMT_ADJG	NUMBER	26,8	Indicates the Credit Card Amount of Adjustments from 0500 messages.
CRC_AMT_NETG	NUMBER	26,8	Indicates the Credit Card Amount Net from 0500 message
CASHBACK_AMTG	NUMBER	26,8	Indicates the Cashback amount from 0500 message.
HASH_AMTG	NUMBER	26,8	Indicates the Hash amount from 0500 message.
DEPOSIT_AMTG	NUMBER	26,8	Indicates the Deposit amount from 0500 message.
DEPOSIT_SIGN	CHAR	2	Indicates the Deposit Sign.
RECORD_CNT	NUMBER	9	Indicates the Record count.
ACQUIRER	CHAR	10	Indicates the Acquirer of Visa 2 nd .
AGENT_NR	NUMBER	6	Indicates the Agent Number.
CHAIN_NR	NUMBER	6	Indicates the Chain Number.
TERM_ID_NR	CHAR	8	Indicates the Visa 2nd terminal number in terminal table.
BLOCK_IND	CHAR	1	Indicates the Block indicator.
CURRENCY_CODE	CHAR	3	Indicates the currency code.
ADDRESS_ID	NUMBER	12	Indicates the Address identification.
MER_LOC_NR	CHAR	5	Indicates the Merchant Location Number.

POS_BATCH Table

Field Name	Type	Size	Description
TRAV_AGENCY_NAME	VARCHAR2	25	Indicates the Travel Agency Name.
TRAV_AGENCY_CD	VARCHAR2	8	Indicates the Travel Agency Code.
TRANS_CNT	NUMBER	4	Indicates the Transaction Count.
MERCH_ENTITY_ID	VARCHAR	30	Indicates the merchant entity identification.

POS_BATCH_ID

The view POS_BATCH_ID is used for easier processing of Electronic draft capture. It depends on POS_BATCH and POS_TERM_KEYS table.

POS_BATCH_ID Table

Field Name	Type	Size	Description
TERM_RECORD_SEQ	NUMBER	26,8	Indicates the terminal record sequence.
TERMINID	CHAR	8	Indicates the terminal ID.
BATCH_ID	NUMBER	38	Indicates an internal batch ID.
ORIG_BATCH_ID	NUMBER	38	Indicates the original batch ID.
TBATCH_ID	CHAR	8	Indicates the terminal batch ID.
CLOSE_FLAG	CHAR	1	Indicates the close flag.
CAPTURE_TYPE	CHAR	1	Indicates the capture type.
POS_BATCH_IDX	CHAR	16	Indicates the unique identifier of record of POS_BATCH table.

POS_TERM_CAP_LINE

The POS_TERM_CAP_LINE table is an extension of the POS_TERM_CAP_TRANS TABLE for storing purchasing card line-item information.

POS_TERM_CAP_LINE Table

Field Name	Type	Size	Description
POS_BATCH_IDX_L	CHAR	16	Indicates the Reference to POS_BATCH.
POS_TRANS_IDX_L	CHAR	16	Indicates the Reference to POS_TERM_CAP_LINE.
POS_LINE_IDX_L	CHAR	16	Indicates the Timestamp of line generated by UA.
ITEM_SEQUENCE_NR_L	NUMBER	3	Indicates the Item Sequence Number.
POS_LINE_VERSION_L	CHAR	5	Indicates the Version.
ADD_ITEM	CHAR	1	Indicates the add item.
ITEM_COMMODITY_CD	CHAR	12	Indicates the Item Commodity Code.
ITEM_DESCRIPTION	CHAR	26	Indicates the Item Description.
LINE_ITEM_AMT	CHAR	12	Indicates the Line Item Amount (total).
LINE_ITEM_DISC_AMT	CHAR	12	Indicates the Line Item Discount Amount.
UNIT_COST	CHAR	12	Indicates the Unit Cost.
UNIT_OF_MEASURE	CHAR	12	Indicates the Unit Of Measure.
VAT_AMT	CHAR	12	Indicates the VAT Amount.
VAT_RATE	NUMBER	4	Indicates the VAT Rate.
QUANTITY	CHAR	12	Indicates the Quantity.
PRODUCT_CD	CHAR	12	Indicates the Product Code.

POS_TERM_CAP_TRANS

The POS_TERM_CAP_TRANS Table stores information related to uploaded individual transaction requests.

POS_TERM_CAP_TRANS Table

Field Name	Type	Size	Description
POS_BATCH_IDX_T	CHAR	16	Indicates the Reference to POS_BATCH.
POS_TRANS_IDX_T	CHAR	16	Indicates the unique internal ID of POS_TERM_CAP_TRANS record.
POS_TRANS_VERSION	CHAR	5	Indicates the Terminal Capture Transaction Version 2.0.
TERMID	CHAR	8	Indicates the Terminal ID.
BATCH_ID	NUMBER		Indicates the Batch ID.
MSGTYPE	NUMBER		Indicates the Message Type.
PAN	VARCHAR2	22	Indicates the Personal Account Number.
PCODE	NUMBER		Indicates the Processing Code.
AMOUNT	NUMBER	26,8	Indicates the Authorized Amount.
SETTLEMENT_AMT	NUMBER	26,8	Indicates the Settlement Amount.
TRAN_DATE	DATE		Indicates the Local Transaction Date.
TRAN_TIME	NUMBER		Indicates the Local Transaction Time.
TRACE	NUMBER		Indicates the Trace Number.
LOCAL_TIME	NUMBER		Indicates the Local Time.
LOCAL_DATE	DATE		Indicates the Local Date.
EXPIRY_DATE	CHAR	4	Indicates the Expiry Date.
SETTLEMENT_DATE	DATE		Indicates the Settlement Date.

POS_TERM_CAP_TRANS Table

Field Name	Type	Size	Description
CAP_DATE	DATE		Indicates the Capture.Date.
MCC	NUMBER		Indicates the Merchant Category Code.
SHIFT_NUMBER	NUMBER		Indicates the Shift Number.
ACQUIRER	CHAR	10	Indicates the Acquirer.
REFNUM	CHAR	12	Indicates the Reference Number.
AUTHNUM	CHAR	6	Indicates the Authorization Number.
RESPCODE	NUMBER		Indicates the Response Code.
TERMLOC	CHAR	25	Indicates the Terminal Location.
STOREID	NUMBER		Indicates the Store ID.
ACCEPTORNAME	CHAR	40	Indicates the Acceptor Name.
ACQ_CURRENCY_CODE	NUMBER		Indicates the Acquirer Currency Code.
POS_ENTRY_CODE	NUMBER		Indicates the POS Entry Code.
POS_CONDITION_CODE	NUMBER		Indicates the POS Condition Code.
POS_PIN_CAP_CODE	CHAR	1	Indicates the POS Pin Capture Code.
POS_CAP_CODE	NUMBER		Indicates the POS Capture Code.
DEVICE_CAP	NUMBER		Indicates the Device Capture.
DEVICE_DEVCAP	NUMBER		Indicates the Device Devcap (bitmap of flags).
CASH_BACK	NUMBER	26,8	Indicates the Cashback Amount.
ORIG_MSG	NUMBER		Indicates the Original Message Type.

POS_TERM_CAP_TRANS Table

Field Name	Type	Size	Description
ORIG_TRACE	NUMBER		Indicates the Original Trace Number.
ORIG_DATE	DATE		Indicates the Original Date of Transaction.
ORIG_TIME	NUMBER		Indicates the Original Time of Transaction.
TERMINAL_TRACE	NUMBER		Indicates the Terminal Trace.
AVS_RESULTCODE	CHAR	1	Indicates the AVS Result Code.
CARD_SCHEME	CHAR	2	Indicates the code used to identify a card scheme. Sample values: 03 (Amex), 04 (Visa), 05 (Master-Card), 06 (Europay), 07 (Diners Club), 08 (Discover), 09 (JCB).
NETW_ID_CD	CHAR	1	Indicates the Network ID Code.
TIP_AMT	NUMBER	26,8	Indicates the Tip Amount.
LINE_ITEM_CNT	NUMBER	3	Indicates the Line Count. If filled, records exist in POS_TERM_CAP_AIR.
LINE_ITEM_CNT_M	NUMBER	3	Indicates the Line Item Count.
REIMB_ATTR	CHAR	1	Indicates the Reimbursement Attribute.
FORMATTER_DEVCAP	NUMBER		Indicates the Formatter DEVCAP.
POS_COND_X	CHAR	1	Indicates the POS Condition Code Extension.
EXT_DATE	CHAR	16	Indicates the Extended Data.
SHC_DEVCAP	NUMBER		Indicates the SHC DEVCAP.
MASK_PAN	VARCHAR2	22	Refers to the PAN where several mid-digits are masked. This field is used to protect the PAN when it is displayed in the GUI..

POS_TERM_TYPE

This table stores information on POS terminal types.

POS_TERM_TYPE Table

Field Name	Type	Size	Description
POS_TERM_TYPE	VARCHAR	20	Type of the POS terminal; Used for referential integrity; Sequence – if adding new, add 1 to the max. Maximum is stored in global_seq_ctrl table in the column LAST_SEQ_NBR with SEQ_NAME = 'POS_TERMINAL_TYPE' Internal value
POS_TERM_MAKE	VARCHAR	10	Manufacturer of the device. Valid values are: Hypercom, Omron, and Verifone; Default NULL
POS_TERM_MODEL	VARCHAR	10	Model number of the device
CARD_INPUT_CAPAB	CHAR	1	Card data input capability. Valid values are: 0 – unknown (default), 1 - Manual, no terminal, 2 - Magnetic stripe reader, 3 - Bar code, 4 - OCR, 5 - ICC reader only, 6 - Key entry, 7 - Magnetic stripe reader and key entry, 8 - ICC, magnetic stripe reader, and key entry, 9 - ICC and magnetic stripe reader, A – Card Present & Magnetic Stripe Unreliable, B – Image MICR and Magnetic Stripe C – MICR and Magnetic stripe Reader, D – No terminal, E - Contactless magnetic stripe, F - Contactless chip

POS_TERM_TYPE Table

Field Name	Type	Size	Description
CH_AUTH_CAPAB	CHAR		Cardholder authentication capability. Valid values are: 0 - no electronic authentication, or unknown (default) 1 - PIN capture capability 2 - electronic signature 3 - biometrics 4 - biographic 5 - electronic authentication inoperative 6 - other (default) 7 - Password With Digital Certification 8 - Password Without Digital Certification 9 - PIN Verified by device 'A' - PIN pad Inoperative
CARD_CAP_CAPAB	CHAR		Card Capture Capability. It can be: 0 - None, or unknown (default) 1 - Capture 2 - Credit 3 - Debit
OPER_ENV	CHAR		Operating Environment. Valid values are: 0 - No terminal used or unknown, 1 - On premises of card acceptor, attended (default), 2 - On premises of card acceptor, unattended, 3 - Off premises of card acceptor, attended, 4 - Off premises of card acceptor, unattended, 5 - On premises of cardholder, unattended, 6 - Internet originated, delivery mode unknown or unspecified, 7 - Internet originated, electronic delivery of product, 8 - Internet originated, physical delivery of product 9 - No terminal

POS_TERM_TYPE Table

Field Name	Type	Size	Description
CVV_ELIGIBLE	CHAR		CVV eligible. Valid values: 1 - Yes 0 - No, unknown (default)
CARD_UPDATE	CHAR		Indicates the ability of the terminal to update the card. Valid values are: 0 – unknown (default), 1 - none, 2 - magnetic stripe write, 3 - ICC (ISO 8583-93)
TERMINAL_OUTPUT	CHAR		Indicates the ability of the terminal to print/display messages 0 - Unknown, 1 - None, 2 - Printing, 3 - Display, 4 - Printing and display (default)
PIN_CAPTURE	CHAR		PIN capture capability. Valid values are: 0 - no pin capture capability, 4 - C - number of digits able to capture. e.g. 4 = 4 digits, 5 = 5 digits, 6, 7, 8, 9 = 9 digits, A=10 digits, B=11 digits, C=12 digits.
CAT_LEVEL	CHAR	2	Indicates whether the cardholder activated the terminal and the level of CAT security 0 Not a CAT transaction (default) CAT level 1 – automated dispensing with PIN CAT level 2 – Self Service terminal CAT level 3 – Limited amount terminal CAT level 4 – In-Flight Commerce CAT level 6 – Electronic Commerce CAT level 7 – Transponder Transaction

POS_TERM_TYPE Table

Field Name	Type	Size	Description
KEYS_LOAD_TYPE	CHAR		This field contains the status of the current key load for this terminal: C - Load new keys to terminal when terminal is closed, R - Randomly send new keys to terminal when terminal is closed, S - Static until sign on message is requested A - DUKPT TDES D: DUKPT N: No T: TKR Note: Application will decide DUKPT by presence of DUKPT fields in the message.
SRVRSTR_CD	CHAR		Describes the terminal's abilities when accepting transactions. The code is used when building an interchange message and in determining the requirements of the transaction. Values depend on the terminal type. Valid values are: 0 – unknown (default) 1 - Use default transaction code, 2 - Need transaction amount, 3 - Both 1 and 2 are true
COND_CD	CHAR	2	Condition code – transaction 1 – Unspecified (default) 2 - Unattended 4 - Cardholder Operated 16 - Can do Debit 32 - Can do Credit 64 - Can Read Card 128 - Electronic Cash Register 256 - Dialterm
SENDS_BATCH_NR	CHAR		'Y' if terminal sends batch number, or 'N' if POS subsystem creates batch_nr
REVERSAL_IND	CHAR		If terminal sends reversal after disconnect, set to Y If terminal does not send reversal, set to N (POS OVM will send reversal)

POS_TERM_TYPE Table

Field Name	Type	Size	Description
DEVICE_TYPE	NUMBER(2)		0 Administrative terminal 1 POS terminal (default) 2 ATM 3 Home terminal 4 ECR 5 Dial terminal 6 In store Processor 7 Main Frame 8 Travelers check machine 9 Fuel machine 1 Scrip machine 11 Coupon machine 12 Ticket machine 13 Point-of-banking terminal 14 - 16 reserved

POS_TERM_TYPE Table

Field Name	Type	Size	Description
SENDS_320_TWICE	CHAR		Host capture batch records (320) after disconnect Y – if batch is sent from the beginning after disconnect, N – if batch records are sent only from disconnect (default)
SERVER_MBOX	VARCHAR	32	Default server mailbox Default server mailbox NULL
CAPABILITIES	Varchar	20	Capabilities of terminal: Byte 1: Partial Approval Support Byte 2: Partial reversal Support Byte 3: Commercial Card Support Values for Partial Approval Support are: “P” – Partial Approval “B” – Prepaid Card Balance Values for Partial Reversal Support and Commercial Card Support: “Y” – Yes, supported “N” – No, not supported Default: NULL – behaviour is application dependent.

POSLOG_ERR

The POSLOG_ERR table is used for logging information about error during

- parsing of the message (format error),
- identification of terminal, merchant or card scheme,
- processing of messages in POS subsystem (e.g. system error, IST/Switch time-out).

POSLOG_ERR Table

Field Name	Type	Size	Description
LOGDATE	DATE		Indicates the system date.
LOGTIME	CHAR	10	Indicates the system time.
SESSION_ID	CHAR	16	Indicates the session ID.
PORT_ID	NUMBER	4	Indicates the Port name/MT COM mbox.
LOGGED_BY	VARCHAR	32	Indicates the Entity which logged record (e.g., OVM mbox name, fmt mbox name).
ERROR_TYPE	NUMBER	4	Error type: Less than 500 - as SHC response codes defined in file shcerror.h; 30- Format error, Over 500 - POS subsystem defined internal error numbers
INSTITUTION_ID	VARCHAR2	10	Indicates the unique institution identifier.
ENTITY_ID	CHAR	30	Indicates the terminal owner Id.
TERM_RECORD_SEQ	NUMBER	15	Indicates the Terminal Record Sequence. If known, internal terminal ID.
TERMINID	CHAR	8	Indicates the Terminal number (ID).
POS_MESSAGE_BRAND	NUMBER	4	Indicates the POS Message brand.
MSGTYPE	NUMBER	4	Indicates the Message Type 100, 200... V2 DC: Header=2, Parameter=3, detail=4 or 320 or 330, line=5, airline=6, trailer=7, response=8.

POSLOG_ERR Table

Field Name	Type	Size	Description
TRACE	NUMBER		Indicates the Trace number from the message.
TBATCH_NR	CHAR	6	Indicates the Batch number from the message
RECORD_NR	NUMBER	4	Indicates the Number of the record within a batch.
FIELD_NAME	VARCHAR	50	Indicates the Name of the field, path.
FIELD_OFFSET	NUMBER	5	Indicates the offset of the field.
FIELD_NUMBER	NUMBER	4	Indicates the number of the field
FIELD_DATA	VARCHAR	128	Indicates the Data which caused the error.

POSLOG_EXTRACT_FILE

The POSLOG_EXTRACT_FILE table stores information about each cut of the extracted file.

POS_EXTRACT_FILE Table

Field Name	Type	Size	Description
DATE_TO	DATE		All the non-extracted batches closed on or before this date will be extracted.
CUT_NR	NUMBER		Indicates the cut number.
FILE_NAME	CHAR	120	Indicates the file name.
TIME_TO	NUMBER		All non-extracted batches closed on or before this time and date_to will be extracted.
GOOD_BATCHES	NUMBER		Indicates the good batches.
EXTRACT_TIME	NUMBER		Indicates the extract time.
EXTRACT_DATE	DATE		Indicates the extract date.
DATE_FROM	DATE		Indicates the date from.
TIME_FROM	NUMBER		Indicates the time from.
INSTITUTION_ID	VARCHAR2	10	Indicates the Institution of terminal, or special institution if without DB (default BIN).
OWNER_ENTITY_ID	CHAR	30	Indicates the Owner entity identification (reference to acq_entity).
FILE_STATUS	CHAR	1	Indicates the file status.

POSLOG_EXTRACT

The POSLOG_EXTRACT table stores info about each extract run and it's parameters.

POSLOG_EXTRACT Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates the Institution of terminal, or special institution if without Default BIN.
OWNER_ENTITY_ID	CHAR	30	Indicates the Owner entity identification (reference to acq_entity).
TERM_RECORD_SEQ	NUMBER	26,8	Indicates the Terminal Record Sequence or store (4) if without DB.
TERM_NR	CHAR	16	Indicates the Terminal ID (4-8).
BATCH_NR	CHAR	8	Indicates the batch number.
CLOSE_DATE	DATE		Set to 19900101, if open. Set by Switch date. – when was closed.
CLOSE_TIME	NUMBER		Set by Switch date. – when was closed.
CUT_NR	NUMBER	2	Indicates the cut number.
EXTRACT_DATE	DATE		Indicates the extract date.
EXTRACT_TIME	NUMBER		Indicates the extract time.
STATUS	CHAR	1	Indicates the status. Valid values are: D: Done; E: Error during extract.
FILE_NAME	CHAR	120	Indicates the file name.

POSLOG_XMF

The POSLOG_XMF Table stores incoming and outgoing external message in raw format.

POSLOG_XMF Table

Field Name	Type	Size	Description
SESSION_ID	NUMBER		Indicates the Session ID.
DIRECTION	CHAR	1	Indicates the direction.
LOGDATE	DATE		Displays the date when the message was generated in the format MM/DD/YYYY.
LOGTIME	CHAR	10	Displays the time when the message was generated in the format HHMMSS.
LEN	NUMBER		Indicates the length.
MESSAGE	VARCHAR	282	Text message.

POS_EXTRACT_TMP

The POS_EXTRACT_TMP table holds data of transactions being extracted by POS_EXTRACT process for a short period of time.

POS_EXTRACT_TMP Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates the Institution ID
ENTITY_ID	VARCHAR2	30	Indicates the entity ID.
TERM_RECORD_SEQ	NUMBER	15	Indicates the Terminal record sequence.
TBATCH_ID	CHAR	8	Indicates the Terminal batch ID.
CAPTURE_TYPE	CHAR	1	Indicates the capture type.
EXTRACT_FLAG	CHAR	1	Indicates the extract flag.
SETTLEMENT_TIME	NUMBER	6	Indicates the settlement time.
CLOSE_DATE	DATE		Indicates the closed date.
CLOSE_TIME	NUMBER	6	Indicates the closed time.
HASH_AMTG	NUMBER	26,8	Indicates the hash amount.
AGENT_NR	NUMBER	6	Indicates the agent number.
CHAIN_NR	NUMBER	6	Indicates the Chain number.
TERM_ID_NR	CHAR	8	Indicates the terminal ID number.
CURRENCY_CODE	CHAR	3	Indicates the currency code.
ADDRESS_ID	NUMBER	12	Indicates the Address ID.
POS_BATCH_IDX	CHAR	16	Indicates the unique ID of POS_BATCH record.

POS_EXTRACT_TMP Table

Field Name	Type	Size	Description
POS_TRANS_IDX	CHAR	16	Indicates the unique ID of POS_TERM_CAP_TRANS record.
POS_TRANS_VERSION	CHAR	5	Indicates the Version of the record.
TERMID	CHAR	8	Indicates the terminal ID.
BATCH_ID	NUMBER		Indicates the internal batch ID.
MSGTYPE	NUMBER		Indicates the Message Type.
PAN	VARCHAR2	22	Indicates the Account Number.
PCODE	NUMBER		Indicates the processing code.
AMOUNT	NUMBER	26,8	Indicates the amount.
SETTLEMENT_AMT	NUMBER	26,8	Indicates the settlement amount.
TRAN_DATE	DATE		Indicates the local transaction date.
TRAN_TIME	NUMBER		Indicates the local transaction time.
TRACE	NUMBER		Indicates the trace number.
LOCAL_TIME	NUMBER		Indicates the local time.
LOCAL_DATE	DATE		Indicates the local date.
EXPIRY_DATE	CHAR	4	Indicates the expiry date.
SETTLEMENT_DATE	DATE		Indicates the settlement date.
CAP_DATE	DATE		Indicates the Capture Date.
MCC	NUMBER		Indicates the Reference Number.
SHIFT_NUMBER	NUMBER		Indicates the shift number.

POS_EXTRACT_TMP Table

Field Name	Type	Size	Description
ACQUIRER	CHAR	10	Indicates the Acquirer.
REFNUM	CHAR	12	Indicates the Reference Number.
AUTHNUM	CHAR	6	Indicates the Authorization Number.
RESPCODE	NUMBER		Indicates the response code.
TERMLOC	CHAR	25	Indicates the terminal location.
STOREID	NUMBER		Indicates the store ID.
ACCEPTORNAME	CHAR	40	Indicates the acceptor name.
ACQ_CURRENCY_CODE	NUMBER		Indicates the acquirer currency code.
POS_ENTRY_CODE	NUMBER		Indicates the POS entry code.
POS_CONDITION_CODE	NUMBER		Indicates the POS condition code.
POS_PIN_CAP_CODE	CHAR	1	Indicates the POS Pin Capture Code.
POS_CAP_CODE	NUMBER		Indicates the POS Capture Code.
DEVICE_CAP	NUMBER		Indicates the Device Capture.
DEVICE_DEVCAP	NUMBER		Indicates the Device Devcap (bitmap of flags).
CASH_BACK	NUMBER	26,8	Indicates the Cashback Amount.
ORIG_MSG	NUMBER		Indicates the Original Message Type.
ORIG_TRACE	NUMBER		Indicates the Original Trace Number.
ORIG_DATE	DATE		Indicates the Date of Original Transaction.
ORIG_TIME	NUMBER		Indicates the time of Original Transaction.

POS_EXTRACT_TMP Table

Field Name	Type	Size	Description
TERMINAL_TRACE	NUMBER		Indicates the terminal trace number.
AVS_RESULTCODE	CHAR	1	Indicates the AVS result code.
CARD_SCHEME	CHAR	2	Indicates the code used to identify a card scheme.
NETW_ID_CD	CHAR	1	Indicates the Network ID Code.
TIP_AMT	NUMBER	26,8	Indicates the tip amount.
LINE_IMEM_CNT	NUMBER	3	Indicates the Line Count of POS_TERM_CAP for this transaction.
LINE_ITEM_CNT_M	NUMBER	3	Indicates the POS_TERM_CAP_AIR record for this transaction.
REIMB_ATTR	CHAR	1	Indicates the Reimbursement Attribute.
FORMATTER_DEVCAP	NUMBER		Indicates the Formatter capabilities
POS_COND_X	CHAR	1	Indicates the POS Condition Code .
EXT_DATA	CHAR	16	Indicates the Extract Data.
SHC_DEVCAP	NUMBER		Indicates the SHC capabilities.
ACQ_COUNTRY	NUMBER		Indicats the acquirer country code.
ISSUER_DATA	CHAR	128	Indicates the Issuer data.
CARD_SEQNO	NUMBER		Indicates the card sequence number.
CHIP_INDEX	CHAR	20	Indicates the reference to shclog record.
POS_ADD_VERSION	CHAR	5	Indicates the version of POS_TERM_CAP_ADD record.
INDUSTRY_DATA_IND	NUMBER	2	Indicates the Industry Data Indicator.
COMM_CRD_DATA_IND	CHAR	1	Indicates the Commercial Card Data Indicator.

POS_EXTRACT_TMP Table

Field Name	Type	Size	Description
REQ_PAYMENT_SRV	NUMBER	2	Indicates the Requested Payment Service.
PRODUCT_CD	CHAR	6	Indicates the Product Code.
TRANSACTION_ID	CHAR	15	Indicates the Transaction ID.
VALID_CD	CHAR	4	Indicates the Valid Code.
REQ_ACI	CHAR	1	Indicates the Requested Authorization Characteristics Indicator.
RESP_ACI	CHAR	1	Indicates the Response Authorization Characteristics Indicator.
START_DATE	DATE		Indicates the start date.
END_DATE	DATE		Indicates the end date.
DAY_RATE	NUMBER	26,8	Indicates the day rate.
NO_SHOW_IND	CHAR	1	Indicates the No show indicator.
EXTRA_CHARGES	CHAR	6	Indicates the extra charges.
MARKET_SPEC_REQ	CHAR	1	Indicates the Market Data Identifier request.
MARKET_SPEC_RESP	CHAR	1	Indicates the SP Market Data Identifier response.
FIRST_AUTH_AMT	NUMBER	26,8	Indicates the First Authorization Amount.
DURATION	NUMBER	2	Indicates the duration.
PURCH_ID	CHAR	25	Indicates the purchase ID.
PREST_PROP_IND	CHAR	1	Indicates the Prestigious Property Indicator.
COMM_CARD_REQ_IND	CHAR	1	Indicates the Commercial Card Request Indicator.
COMM_CARD_RESP_IND	CHAR	1	Indicates the Commercial Card Response Indicator.

POS_EXTRACT_TMP Table

Field Name	Type	Size	Description
SALES_TAX_FLAG	CHAR	1	Indicates the sales tax flag.
SALES_TAX	NUMBER	26,8	Indicates the sales tax.
PURCH_ORDER_NR	CHAR	17	Indicates the purchase order number.
FLEET_TYPE	CHAR	1	Indicates the fleet type.
FLEET_ID_NR	CHAR	17	Indicates the Fleet ID Number.
FLEET_RESTR	CHAR	1	Indicates the Fleet Restriction.
CH_AUTH_ENTITY	CHAR	1	Indicates the Cardholder Authentication Entity.
DISCOUNT_AMT	NUMBER	26,8	Indicates the Discount Amount.
FREIGHT_AMT	NUMBER	26,8	Indicates the Freight Amount.
DUTY_AMT	NUMBER	26,8	Indicates the Duty Amount.
DEST_ZIP_CD	CHAR	20	Indicates the Destination Zip Code.
INVOICE_NR	CHAR	6	Indicates the Invoice Number.
CUST_REFERENCE_ID	CHAR	17	Indicates the Customer Reference ID.
CUST_VAT_REG_NR	CHAR	13	Indicates the Customer VAT Registration Number.
DEST_COUNTRY_CD	CHAR	3	Indicates the Destination Country Code.
LOCAL_TAX_INCLUDED	CHAR	1	Indicates the Local Tax Included.
LOCAL_TAX_AMT	NUMBER	26,8	Indicates the Local Tax Amount.
MUL_CL_SEQ_CNT	NUMBER	2	Indicates the Multiple Clearing Sequence Count.
MUL_CL_SEQ_NR	NUMBER	2	Indicates the Multiple Clearing Sequence Number.

POS_EXTRACT_TMP Table

Field Name	Type	Size	Description
NAT_TAX_AMT	NUMBER	26,8	Indicates the National Tax Amount.
NAT_TAX_INCL_FLAG	CHAR	1	Indicates the National Tax Included Flag.
ORI_CITY_AIRPRT_CD	CHAR	3	Indicates the Originating City Airport Code.
OTHER_TAX_AMT	NUMBER	26,8	Indicates the Other Tax Amount.
PASS_NAME	CHAR	20	Indicates the Passenger Name.
PURCH_ORDER_DATE	DATE		Indicates the Purchase Order Date.
RENTAL_RET_CITY	CHAR	18	Indicates the Rental Return City.
RENTAL_RET_LOC_ID	CHAR	10	Indicates the Rental Return Location ID.
RENTAL_RET_STATE	CHAR	3	Indicates the Rental Return State.
RENTER_NAME	CHAR	20	Indicates the Renter Name.
RESTR_TICKET_IND	CHAR	1	Indicates the Restricted Ticket Indicator.
SHIP_POST_CD	CHAR	10	Indicates the Ship postal code.
SUMM_COMM_CD	CHAR	4	Indicates the Summary Commodity Code.
TAX_AMT	NUMBER	26,8	Indicates the Tax Amount.
TAX_RATE	NUMBER	4	Indicates the Tax Rate.
TICKET_NR	CHAR	13	Indicates the Ticket Number.
TOTAL_AUTH_AMT	NUMBER	26,8	Indicates the Total Authorization Amount.
TRIP_LEG_1_INFO	CHAR	7	Indicates the Trip Leg 1 Information.
TRIP_LEG_2_INFO	CHAR	7	Indicates the Trip Leg 2 Information.

POS_EXTRACT_TMP Table

Field Name	Type	Size	Description
TRIP_LEG_3_INFO	CHAR	7	Indicates the Trip Leg 3 Information.
TRIP_LEG_4_INFO	CHAR	7	Indicates the Trip Leg 4 Information.
REL_PARTICIPANT	CHAR	1	Indicates the Relationship Participant.
FLIPPED_MSGTYPE	NUMBER		Indicates the flipped message type.
ORIGFLIPPEDMSG	NUMBER		Indicates the original flipped message type.
TXNDEST	CHAR	10	Indicates the Transaction Destination.
ALTERNATEACQUIRER	CHAR	10	Indicates the alternate acquirer.
F_ID	CHAR	11	Indicates the forwarding institution/BIN ID.
MVV	CHAR	10	Indicates the Merchant Verification Value .
TRAV_AGENCY_NAME	CHAR	25	Indicates the Travel Agency Name.
TRAV_AGENCY_CD	CHAR	8	Indicates the Travel Agency Code.
SERVICE_CODE	CHAR	4	Indicates the Service Code.
ACQUIRER_DATA	VARCHAR2	128	Indicates the acquirer data.
REVCODE	NUMBER		Indicates the revcode.
AUTH_DEVCAP	NUMBER		Indicates the auth_devcap.

POSLOG_500

Table POSLOG_500 is used for logging of every reconciliation message (message type 500) entering POS subsystem.

POSLOG_500 Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates an institutionID.
ENTITY_ID	VARCHAR2	30	Indicates an entity ID.
TERM_REC_SEQ	NUMBER	16	Indicates the terminal record sequence.
TERMID	CHAR	8	Indicates the terminal ID.
LOCAL_DATE	DATE		Indicates the local date.
LOCAL_TIME	NUMBER		Indicates the local time.
PCODE	NUMBER		Indicates the processing code.
TRACE	NUMBER		Indicates the trace number.
BATCH_ID	NUMBER		Indicates the internal batch ID.
ORIG_BATCH_ID	NUMBER		Indicates the original internal batch ID.
RESPCODE	NUMBER	4	Indicates the response code.
REASON_CODE	NUMBER	4	Indicates the reason code.
NETCODE	NUMBER	3	Indicates the network code.
REFNUM	CHAR	12	Indicates the reference number.
TBATCH_NR	CHAR	6	Indicates the terminal batch number.
DBC_NUM_DB	NUMBER	10	Indicates the Debit Card Number of Debits.
DBC_AMT_DB	NUMBER	26,8	Indicates the Debit Card Amount of Debits.

POSLOG_500 Table

Field Name	Type	Size	Description
DBC_NUM_CR	NUMBER	10	Indicates the Debit Card Number of Credits.
DBC_AMT_CR	NUMBER	26,8	Indicates the Debit Card Amount of Credits.
CRC_NUM_DB	NUMBER	10	Indicates the Credit Card Number of Debits.
CRC_AMT_DB	NUMBER	26,8	Indicates the Credit Card Amount of Debits.
CRC_NUM_CR	NUMBER	10	Indicates the Credit Card Number of Credits.
CRC_AMT_CR	NUMBER	26,8	Indicates the Credit Card Amount of Credits.
ATH_NUM_DB	NUMBER	10	Indicates the count of authorization.
SETTLEMENT_AMT	NUMBER	26,8	Indicates the settlement amount.
TRANSF_NUM	NUMBER	10	Indicate the count of transfers.
TRANSF_NUM_REV	NUMBER	10	Indicates the count of reversed transfers.
INQUIRY_NUM	NUMBER	10	Indicates the count of inquiries.
PAY_NUM	NUMBER	10	Indicates the count of payments
PAY_NUM_REV	NUMBER	10	Indicates the count of reversed payments.

PROCESS_BATCH

This table holds the data of batches to be extracted by pos_extract process.

PROCESS_BATCH Table

Field Name	Type	Size	Description
PROCESS_NR	NUMBER		Indicates the process number.
BATCH_IDX	CHAR	16	Indicates the batch index.
CAPTURE_TYPE	CHAR	1	Indicates the type of capture.
GROUP_NR	NUMBER		Indicates the group number.

BATCH_STATUS

This table the holds the status of the batches, processed by ext_format process.

BATCH_STATUS Table

Field Name	Type	Size	Description
BATCH_IDX	CHAR	16	Indicates the batch index.
FORMAT	VARCHAR2	16	Indicates the format.
STATUS	CHAR		Indicates the batch status.

PROVINCE

This table stores all provinces, states, or other geographical regions of a country.

PROVINCE Table

Field Name	Type	Size	Description
CNTRY_CODE	CHAR	3	Indicates the ISO 8583 standard 3- digit code identifying a country.
PROV_STATE_ABBREV	CHAR	3	Indicates an alphabetic code assigned to a province (state).
PROV_STATE_NUM_CD	NUMBER	2	Indicates a numerical code assigned by Visa to identify a province or state
PROVINCE_STATE	VARCHAR	50	Indicates a full name of the province or state

TERMINAL

This table keeps information about terminal range belonging to one merchant.

TERMINAL Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution
TERM_RECORD_SEQ	NUMBER	16	Indicates the sequential number of the terminal record. Internal value. This is unique number for group of terminals. It is used for ref. integrity, sequence – if adding new, add 1 to the maximum. Maximum is stored in global_seq_ctrl table in the column LAST_SEQ_NBR with SEQ_NAME = 'term_record_seq'
TERMINAL_ID_LOW	CHAR	8	Low range of terminal IDs
TERMINAL_ID_HIGH	CHAR	8	High range of terminal IDs

TERMINAL Table

Field Name	Type	Size	Description
ALLW_ID	NUMBER	12	A number assigned to an allowance record. Internal value
BAR_ACCESS	CHAR	1	Y/N indicator of the request processing. Values: Y (requests refused), N (normal processing - default)
HOUR_ID	NUMBER		Reference to the table POS_OPEN_HOUR, where open hours are stored; Default 0 – open 24 hours /7 days a week
ACTUAL_START_DATE	DATE		Date when the first transaction for this entity (e.g. merchant) can be actually received and processed.
TERMINATION_DATE	DATE		Date when no more transactions can be accepted from terminal. Default - NULL
TERMINAL_ID_NR	NUMBER	8	Terminal ID number (V number). Default NULL. Please note: This is not DE 41
POS_TERMINAL_TYPE	VARCHAR	20	Type of the POS terminal. Reference to POS_TERM_TYPE table
POS_MSG_BRAND	NUMBER	4	POS Message Brand Index. Reference to POS_MSG_BRAND table
OWNER_ENTITY_ID	VARCHAR	30	Internal ID assigned to an entity Owner entity identification (reference to acq_entity); usually Merchant id
DEFAULT_CURR_CD	CHAR	3	Indicates the default currency code

TERMINAL Table

Field Name	Type	Size	Description
CPS_ELIGIBLE	CHAR	1	Indicates the CPS eligible: Y- yes, N – no (default). Note 1: If terminal does not send CPS and CPS_ELIGIBLE set to: 'Y'=Yes, POS subsystem will mark transaction as CPS and send to SHC/network as CPS eligible. 'N'=No, POS will mark transaction as not CPS eligible. " " (space), POS subsystem will not mark it and outgoing network (e.g. Visa Basel) can mark it as CPS depending on network processing logic. Note 2: If terminal sends CPS, it is always CPS transaction. (TC 57 03 will be created for CPS and for all chip trans.)).
DEFAULT_MCC	VARCHAR	5	Indicates the default MCC.
SERIAL_NUMBER	VARCHAR2	30	Indicates the serial Number of a particular terminal.

TERMINAL_BDK

This table stores information of base derivation key.

TERMINAL_BDK Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates the multi institution support.
KEY_SET_ID	VARCHAR	9	Indicates the key set identifier.
DUKPT_BDK_NOW	VARCHAR	48	Indicates the duplicate base derivation key.
BDK_LEN	NUMBER	34	Indicates the length of Base Derived Key (32 for single DES: 32, 33 or 48 for TDES).
CHK_DIGIT	VARCHAR	16	Indicates the Check Digit.

POS_TERM_KEYS

The terminal keys table is used to maintain security keys.

POS_TERM_KEYS Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates the system supplied Institution ID in drop-down menu.
OWNER_ENTITY_ID	VARCHAR	30	Indicates the terminal owner entity ID.
TERM_RECORD_SEQ	NUMBER	15	Indicates the Terminal record sequence.
TERMINID	CHAR	8	Indicates the Terminal ID.
TMFK	CHAR	74	Indicates the field entry for terminal master keys and is manually edited. This field does not appear on all sites.
TMFK_LEN	NUMBER	2	Indicates the TMFK length.
INLOAD	CHAR	1	Indicates the Loading Keys now.
COM_KEY_NOW	CHAR	74	Indicates the 16-digit cryptogram for the current COM or KPE key.
COM_KEY_LEN	NUMBER	2	Indicates the Length of Communication Key.
COM_LOAD_DATE	DATE		Indicates the date on which the current keys were loaded. The date format is MM/DD/YYYY.
COM_LOAD_TIME	NUMBER	6	Indicates the time at which the current keys were loaded. The time format is HHMMSS.
COM_OFF_KEY_NOW	CHAR	74	Indicates the current 16-digit cryptogram for the offline COM or KPE key or current key for Terminal Key Register.
COM_OFF_LOAD_DATE	DATE		Indicates the date on which the COM offline keys were loaded. The date format is MM/DD/YYYY.
COM_OFF_LOAD_TIME	NUMBER	6	Indicates the Last time when updating Communication Offline Key.

POS_TERM_KEYS Table

Field Name	Type	Size	Description
MAC_KEY_NOW	CHAR	74	Indicates the Current Message Authentication Key.
MAC_KEY_LEN	NUMBER	2	Indicates the length of MAC Key.
MAC_LOAD_DATE	DATE		Indicates the date when the MAC was last updated.
MAC_LOAD_TIME	NUMBER	6	Indicates the time when the MAC was last updated.
MAC_OFF_KEY_NOW	CHAR	74	Indicates the Last Key Register POS MAC or current key for Terminal Key Register.
MAC_OFF_LOAD_DATE	DATE		Indicates the date when MAC Offline Key was last updated.
MAC_OFF_LOAD_TIME	NUMBER	6	Indicates the time when MAC Offline Key was last updated.
KME_KEY_NOW	CHAR	74	Indicates the current 16-digit cryptogram for the Message Encryption Key.
KME_KEY_LEN	NUMBER	2	Indicates the length of Message Encryption Key.
KME_LOAD_DATE	DATE		Indicates the date when the Message Encryption Key.was last updated.
KME_LOAD_TIME	NUMBER	6	Indicates the time when the Message Encryption Key.was last updated.
KME_OFF_KEY_NOW	CHAR	74	Indicates the Current KME Offline key or current key for Terminal Key Register.
KME_OFF_LOAD_DATE	DATE		Indicates the date when the KME offline key was last updated.
KME_OFF_LOAD_TIME	NUMBER	6	Indicates the time when the KME offline key was last updated.
KSN_DESCRIPTOR	CHAR	3	Indicates the Key Serial Number Descriptor.
DUKPT_BDK_NOW	CHAR	32	Indicates the Base Derived Key from Derived Unique Key Per Transaction (DUKPT) PIN Block format.

POS_TERM_KEYS Table

Field Name	Type	Size	Description
BKD_LEN	NUMBER	2	Indicates the Length of Base Derived Key.
TKI_SUPPORT	VARCHAR2	10	Indicates whether the flag supports POS TMK or not. - If the flag is 'Y' then it is ready to support POS TMK - If the flag is 'N' or 'NULL' then the terminal is not supporting POS TMK
TKI_STATE	NUMBER		Indicates whether the TMK key is cativated or not. - If the status is 'Y' then the TMK key is activated and ready to use. - If the key is 'N' TMK key is not activated, need to activate the key before using it.

POS_TKI_KEYS

POS_TKI_KEYS Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
SECRET_KEY	NUMBER		Indicates the version of the key for a particular Institution ID.
PUBLIC_KEY	VARCHAR2	540	Public Key of the RSA Pair which is shared with Terminal during public key download.
SECRET_KEY	VARCHAR2	2048	Secret Key of the RSA Pair used to encrypt the terminal serial number coming in the TMK Download request message.

POS_TKI_AUDIT

POS_TKI_AUDIT Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	An internal ID assigned to an institution.
TERMINAL_ID	VARCHAR2	8	Indicates the terminal ID.
LOGGED_DATE	DATE		Date of logging the transaction.
LOGGED_TIME	NUMBER		Time of logging the transaction.
FUNCTION_CODE	NUMBER		
RAWDATA	VARCHAR2	2000	Contains the XML data contains the transaction details.

10

Report Tables

Table Descriptions

NETFEES

This table stores the network fees involved for a network transaction. It is used for generating reports on the fees charged to the issuing institutions by the acquiring institutions.

NETFEES Table

Field Name	Type	Size	Description
ISSUER	CHAR	10	Indicates the name of the issuer of the card to which network fees apply.
ACQUIRER	CHAR	10	Indicates the name of the acquiring institution.
DEVICETYPE	CHAR	1	Indicates the type of device that has to be monitored: ATM or POS. Valid values: A = ATM; P = POS.
TXNTYPE	CHAR	1	Indicates the transaction type code. Valid values: W= withdrawal; D= deposit; B= balance; T= transfer; P=payment; L= loan; C= credit card; S= POS; K= cheque; *= other.

NETFEES Table

Field Name	Type	Size	Description
SETTLE_WITH	CHAR	1	Indicates whom you want to settle with: issuer or agent. Valid values: I= issuer; A= agent.
PICKUP_DR	NUMBER	26,8	Indicates the fee incurred if card is picked up.
APP_DR	NUMBER	26,8	Indicates the fee for approving a transaction
ISSDENY_DR	NUMBER	26,8	Indicates the fee charged for each transaction denied by the issuer.
NETFAIL_DR	NUMBER	26,8	Indicates the flat fee charged for each incomplete credit transaction due to network failure.
APP_PCT	NUMBER	26,8	Indicates the percentage of approve fee base on transaction amount.
ISSDENY_PCT	NUMBER	26,8	Indicates the percentage of transaction amount for each transaction denied by issuer.
NETFAIL_PCT	NUMBER	26,8	Indicates the percentage of transaction amount for each incomplete transaction due to network failure.
BIN1	CHAR	10	Indicates the BIN of the acquirer.
BIN1_APP_CR	NUMBER	26,8	Indicates the fee charged for approved transactions summarized by BIN1.
BIN1_ISSDENY_CR	NUMBER	26,8	Indicates the fee charged for issuer denied transactions summarized by BIN1.
BIN1_NETFAIL_CR	NUMBER	26,8	Indicates the fee charged for incomplete credit transactions due to network failure summarized by BIN1.
BIN2	CHAR	10	Indicates the BIN of the acquirer.
BIN2_APP_CR	NUMBER	26,8	Indicates the fee charged for approved transactions summarized by BIN2.
BIN2_ISSDENY_CR	NUMBER	26,8	Indicates the fee charged for issuer denied transactions summarized by BIN2.
BIN2_NETFAIL_CR	NUMBER	26,8	Indicates the fee charged for incomplete credit transactions due to network failure summarized by BIN2.

NETFEES Table

Field Name	Type	Size	Description
BIN3	CHAR	10	Indicates the BIN of the acquirer.
BIN3_APP_CR	NUMBER	26,8	Indicates the fee charged for approved transactions summarized by BIN3..
BIN3_ISSDENY_CR	NUMBER	26,8	Indicates the fee charged for issuer denied transactions summarized by BIN3.
BIN3_NETFAIL_CR	NUMBER	26,8	Indicates the fee charged for incomplete credit transactions due to network failure summarized by BIN3.
BIN4	CHAR	10	Indicates the BIN of the acquirer.
BIN4_APP_CR	NUMBER	26,8	Indicates the fee charged for approved transactions summarized by BIN4.
BIN4_ISSDENY_CR	NUMBER	26,8	Indicates the fee charged for issuer denied transactions summarized by BIN4.
BIN4_NETFAIL_CR	NUMBER	26,8	Indicates the fee charged for incomplete credit transactions due to network failure summarized by BIN4.
BIN5	CHAR	10	Indicates the BIN of the acquirer.
BIN5_APP_CR	NUMBER	26,8	Indicates the fee charged for approved transactions summarized by BIN5.
BIN5_ISSDENY_CR	NUMBER	26,8	Indicates the fee charged for issuer denied transactions summarized by BIN5.
BIN5_NETFAIL_CR	NUMBER	26,8	Indicates the fee charged for incomplete credit transactions due to network failure summarized by BIN5.
BIN6	CHAR	10	Indicates the BIN of the acquirer.
BIN6_APP_CR	NUMBER	26,8	Indicates the fee charged for approved transactions summarized by BIN26.
BIN6_ISSDENY_CR	NUMBER	26,8	Indicates the fee charged for issuer denied transactions summarized by BIN6.
BIN6_NETFAIL_CR	NUMBER	26,8	Indicates the fee charged for incomplete credit transactions due to network failure summarized by BIN6.
BIN7	CHAR	10	Indicates the BIN of the acquirer.

NETFEES Table

Field Name	Type	Size	Description
BIN7_APP_CR	NUMBER	26,8	Indicates the fee charged for approved transactions summarized by BIN7.
BIN7_ISSDENY_CR	NUMBER	26,8	Indicates the fee charged for issuer denied transactions summarized by BIN7.
BIN7_NETFAIL_CR	NUMBER	26,8	Indicates the fee charged for incomplete credit transactions due to network failure summarized by BIN7.
O_ROWID	NUMBER		Reserved.

REPBINHDR

REPBINHDR Table

Field Name	Type	Size	Description
BIN	CHAR	10	Indicates the BIN of the institution for which the heading is used.
HEADING1	CHAR	40	Indicates the first line of the institution's heading information in this field.
HEADING2	CHAR	40	Indicates the second line of the institution's heading information in this field.
O_ROWID	NUMBER		

REPORT

The report table displays information about the report. For each report generated, a record is created in the report table. The information is for display purposes only and should not be edited.

REPORT Table

Field Name	Type	Size	Description
REPNUMBER	NUMBER		Indicates the report number. This field displays the numeric code that identifies the report that is being generated. The value in this field should not exceed 6 digits in length.
REPDESC	CHAR	40	Indicates the report description. This field displays a brief description of the report that is being generated.
REPTYPE	CHAR	1	Indicates the report type. This field displays how frequently the report is generated. Valid type: D: Daily; M: Monthly; N: On request.
REPPROGRAM	CHAR	20	Indicates the report program name. This field displays the name of the program that is used to generate the report.
REPMEDIA	CHAR	1	Indicates the report output media. This field displays the medium or device to which the report will be sent. Valid values: P: Printer; S: Screen; F: File.
REPRUNDATE	DATE		This field stores the actual date of settlement of the transaction, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 15.
QRYFROMDATE	DATE		This field stores the actual date of settlement of the transaction, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 15.
QRYTODATE	DATE		This field stores the actual date of settlement of the transaction, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 15.
REPRUNTIME	NUMBER		This field stores the actual time of settlement of the transaction, in the format HHMMSS. The field corresponds to ISO bitmap 15.

REPORT Table

Field Name	Type	Size	Description
REPSEQNO	NUMBER		Indicates the response sequence number. This field specifies the number of times that the report has been generated. Each time this report is generated, the value in this field increments by one.
REPPAGELEN	NUMBER		Indicates the report page length. This field specifies the page length, in the number of lines of text down the page. Range: 10 to 200.
REPCOLUMNLEN	NUMBER		Indicates the report column length. This field displays the page width, in the number of characters across the page. Range: 10 to 200.

REPORTS

REPORTS Table

Field Name	Type	Size	Description
REPORTID	CHAR	10	Report ID.
DESC	CHAR	20	Short report description
DESC_LONG	CHAR	40	Long report description
TMPL	CHAR	40	Report template file name
GUIFLAG	CHAR	1	Flag indicates whether GUI should show the report. Y - Yes N - No



SAF Tables

Table Descriptions

ISTREPLAYTAB

This table contains the replay configuration for each BIN.

ISTREPLAYTAB

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique Institution Identifier.
USERBINID	CHAR	10	User Bank Institution Number.
NETWORKID	CHAR	10	The Network ID encoded on the magnetic stripe, usually the first 4-10 digits padded with spaces. When the switch processes a transaction, IST/Founda-tion first looks at this table based on the Network ID. It uniquely identifies a financial institution. The shcextbin table directs a range of BINs to an owner shcbin record. DCS checks the shcextbin table before checking the shcbin table.
RINTERVAL	NUMBER		Interval to wait before resending an unacknowledged message.

ISTREPLAYTAB

Field Name	Type	Size	Description
FINTERVAL	NUMBER		Fast Interval, in seconds, between sending different messages to the destination node.
SINTERVAL	NUMBER		Slow Interval, in seconds, between sending different messages to the destination node.
NPERCENT	NUMBER		The percentage at which the mode changes to normal mode.
FPERCENT	NUMBER		The percentage at which the mode changes to forward mode.
MAXOUT	NUMBER		Number of new requests sent at the next interval.
FULLFILESIZE	NUMBER		Maximum level of utilization of SAF file.
REPLACE_RESPONSES	CHAR	1	Enter 'Y' for sending the next request as soon as a response is received, 'N' otherwise.
ENABLE_PROC_REQ	CHAR	1	Enter 'Y' for enabling system messages. Note that if this parameter is set to 'N', istreplay is not able to send messages to DCS; consequently, the replay mode cannot be changed even if the correct parameters are configured.
VERIFY_RESPONSE	CHAR	1	Enter 'Y' for verifying the response code and setting the SAF mode, 'N' otherwise.

IST_SAFDB

This table contains all the pending messages that need to be sent to the host.

IST_SAFDB Table

Field Name	Type	Size	Description
DESTINATION	VARCHAR2	21	The string composed with institution_id.userbin_id.
SEQ_NO	NUMBER		Sequence number generated by the system automatically.
SAF_DATE	DATE		Date when the SAF record was created.
SEND_TIME	NUMBER		Current time of record being sent.
STATUS	CHAR		Status of record (e.g., pending, done, skip).
ROUTE	VARCHAR2	60	Destination of routing.
FORMAILBOX	VARCHAR2	60	Mailbox name for notification.
REPLAY	CHAR		Flag of replay.
RESPCODE	NUMBER		Response code.
SAFCUTOFFDATE	DATE		SAF cutoff date.
SAFCUTOFFTIME	NUMBER		SAF cutoff time.
EVENTID	NUMBER		Event ID (Not used).
RAW_LEN	NUMBER		Length of raw message.
RAW_MSG	LONG RAW		The message of raw message.
MTI	CHAR		The message type classifier.

IST_SAFHIST

This table contains the transaction history, which is processed by using the SAF module.

IST_SAFHIST Table

Field Name	Type	Size	Description
DESTINATION	VARCHAR2	21	String composed with institution_id.userbin_id.
SEQ_NO	NUMBER		Sequence number generated by the system automatically.
SAF_DATE	DATE		Date of SAF record created.
SEND_TIME	NUMBER		Current time of record being sent.
STATUS	CHAR		Status of record (e.g., pending, done, skip).
ROUTE	VARCHAR2	60	Destination of routing.
FORMAILBOX	VARCHAR2	60	Mailbox name for notification.
REPLAY	CHAR		The flag of replay.
RESPCODE	NUMBER		The response code.
SAFCUTOFFDATE	DATE		The SAF cutoff date.
SAFCUTOFFTIME	NUMBER		The SAF cutoff time.
EVENTID	NUMBER		Event ID (Not used).
RAW_LEN	NUMBER		The length of raw message.
RAW_MSG	LONG RAW		Content of raw message.
MTI	CHAR		Message type classifier.

12

Settlement Table

Table Descriptions

ISTACCUMU

This table is used by the ist accumulator to accumulate the transaction totals which can be used for reconciliation and balancing.

ISTACCUMU Table

Field Name	Type	Size	Description
TXNSRC	VARCHAR2	10	The Institution ID of the institution where the transaction originated. For any transactions that involves issuer and acquirer, this is the acquiring institution or non-issuing institution. For financial/authorization / reversal messages, it's the acquiring institution.
ACQUIRER	CHAR	10	Indicates the acquiring BIN for the transactions
ACQ_ENTITY_ID	VARCHAR2	30	Indicates the Acquiring Entity ID who acquired the transactions

ISTACCUMU Table

Field Name	Type	Size	Description
TXNDEST	VARCHAR2	10	Indicates the Institution ID of the institution where the issuer is. For any transactions that involves issuer and acquirer, this is the issuing institution or non-acquiring institution. For financial/authorization / reversal messages, it's the issuing institution.
ISSUER	CHAR	10	Indicates the Issuer BIN for the transactions
ISS_ENTITY_ID	VARCHAR2	30	Indicates the Issuer Entity ID who received the transactions
ACQ_CUR_CODE	NUMBER		Indicates the ISO standard currency code of the acquiring currency
ISS_CUR_CODE	NUMBER		Indicates the ISO standard currency code of the issuing currency
ACCUMU_GROUP	NUMBER		Indicates the Accumulation group code: Valid values: 1 = Credit 2 = Reversal Credit 3 = Debit 4 = Reversal Debit 5 = Transfer 6 = Transfer Reversal 7 = Inquiries 8 = Authorization only 9 = Charge back Credit 10 = Charge back Debit;
CARD_PRODUCT	CHAR	10	Indicates the product type of the card. It is mentioned as "UNKNOWN" if the product type is not defined
DEVICE_TYPE	NUMBER		Indicates the type of device which acquired the transaction. Valid values: 1 = ATM 2 = POS 3 = Other
ACQ_BUS_DATE	DATE		Indicates the Acquirer Business Day
ISS_BUS_DATE	DATE		Indicates the Issuer Business Day

ISTACCUMU Table

Field Name	Type	Size	Description
MAIN_BUS_DATE	DATE		Indicates the Processor/Switch Business Day
NUM_TXN	NUMBER		Indicates the number of transaction which have been accumulated in this record.
PRO_PRNCPL_AMT	NUMBER	26, 8	Indicates the amount accumulated in processor currency
PRO_SRCHGR_AMT	NUMBER	26, 8	Currently not in use
PRO_FEE_AMT	NUMBER	26, 8	Currently not in use
PRO_DISCNT_AMT	NUMBER	26, 8	Currently not in use
ACQ_PRNCPL_AMT	NUMBER	26, 8	Indicates the amount accumulated in acquirer currency
ACQ_SRCHGR_AMT	NUMBER	26, 8	Currently not in use
ACQ_FEE_AMT	NUMBER	26, 8	Currently not in use
ACQ_DISCNT_AMT	NUMBER	26, 8	Currently not in use
ISS_PRNCPL_AMT	NUMBER	26, 8	Indicates the amount accumulated in issuer currency
ISS_SRCHGR_AMT	NUMBER	26, 8	Currently not in use
ISS_FEE_AMT	NUMBER	26, 8	Currently not in use
ISS_DISCNT_AMT	NUMBER	26, 8	Currently not in use
ACQ_RECON_FLAG	CHAR	1	Indicates whether the record has been reconciled by the acquirer. Value is "Y"
ACQ_RECON_DATE	DATE		Indicates the date record reconciled with the acquirer
ACQ_RECON_TIME	NUMBER		Time record was reconciled with the acquirer
ISS_RECON_FLAG	CHAR	1	Indicates whether the record has been reconciled by the issuer. Value is "Y"

ISTACCUMU Table

Field Name	Type	Size	Description
ISS_RECON_DATE	DATE		Indicates the date record, reconciled with the issuer
ISS_RECON_TIME	NUMBER		Indicates the time record, reconciled with the issuer
LAST_TXN_TIME	NUMBER		Indicates the last time of the updated record.

STD500

STD500 Table

Field Name	Type	Size	Description
MSGTYPE	NUMBER		ISO 8583 message type identifier that defines the class of transaction. Typical message type identifiers: 0110: Authorization request response 0130: Authorization advice response 0210: Financial request response 0230: Financial advice response 0410: Reversal Request Transaction 0430: Reversal advice response 6xxx: Late message. The value xxx depends on the type of message that was late. For example, 6110 identifies a 0110 as a late response. 7xxx: Preauthorization 8xxx: Service Request 9xxx: Device Response. A 9000 indicates a positive response while a 9001 indicates a negative response.
TRACE	NUMBER		A system trace number assigned to the transaction by the acquirer. The value in this field is set for the life of the transaction and remains unique for a particular terminal/acquirer within a day. For on-us transactions, the first three digits indicate the message type, and the last four indicate the transaction number.
TRANDATE	DATE		Indicates the transmission date of the transaction in GMT time. The format of the date is CCYYMMDD.
TRANTIME	NUMBER		Message transmission time.
FLAGS	NUMBER		
SETTLEMENT_DATE	DATE		This field stores the actual date of settlement of the transaction, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 15.
FORWARD_INST	CHAR	10	Text Message
ISSUER	CHAR	10	This field stores the BIN that identifies the issuing institution of this transaction. IST/Foundation uses this field to determine transaction routing.

STD500 Table

Field Name	Type	Size	Description
ACQUIRER	CHAR	10	This field stores the BIN that identifies the acquiring institution of this transaction. IST/Foundation uses this field to determine transaction routing.
SETTLEMENT_AGENT	CHAR	10	Text Message
CURRENCY_CODE	NUMBER		Identifies the ISO standard currency code assigned to the network. The switch maintains the concept of a base currency that is used for all conversions: IST/Foundation automatically performs currency conversion between the acquirer and the issuer based on the currency code.
ADVICE_REASON	NUMBER		
RESPCODE	NUMBER		
SERIAL_NUMBER	NUMBER		
NETWORK_DATA	CHAR	30	This value is used to identify the transaction type processed by this BIN. Valid values:03 - Amex04 - Visa04:2 VISA ATM04:4 Plus ATM.05 - MasterCard06 - Europay07 - Diners08 - Discover09 - JCBNOTE: Users who receive this upgrade will need to repopulate their external BIN tables to update to the new values that are stored in this field.
NUM_CREDIT	NUMBER		
NUM_CREDIT_REV	NUMBER		
NUM_DEBIT	NUMBER		
NUM_DEBIT_REV	NUMBER		
NUM_TRANSFER	NUMBER		
NUM_TRANSFER_REV	NUMBER		
NUM_INQUIRY	NUMBER		

STD500 Table

Field Name	Type	Size	Description
NUM_AUTH	NUMBER		This is the authorization code provided by the issuer when a transaction is approved.
NUM_AUTH_REV	NUMBER		
FEE_CR_PROCESSING	NUMBER	26,8	
FEE_CR_TRANSACTION	NUMBER	26,8	
FEE_DB_PROCESSING	NUMBER	26,8	
FEE_DB_TRANSACTION	NUMBER	26,8	
AMT_CREDIT	NUMBER	26,8	
AMT_CREDIT_REV	NUMBER	26,8	
AMT_DEBIT	NUMBER	26,8	
AMT_DEBIT_REV	NUMBER	26,8	
AMT_AUTH	NUMBER	26,8	
AMT_AUTH_REV	NUMBER	26,8	
AMT_NETSET	NUMBER	26,8	
O_ROWID	NUMBER		

13

SHC Tables

Table Descriptions

AKB_KEYS

Store the Keys that are used during exchange of keys from Network to IST/Switch. This is required only when keys are required to be imported from an external end point into IST/Switch. Atalla AKB requires a different key block for each type of key to be imported.

AKB_KEYS Table

Field Name	Type	Size	Description
KEY_ID	VARCHAR2	74	Key ID
KEY_TYPE	VARCHAR2	1	Type of key needs to be used. Possible Values are: • P - PIN key • M - MAC key
KEY_BLOCK	VARCHAR2	74	Atalla Key Block

AUTHNUMBER

Stores the next authnumber to be used when shc authorize transaction. Normally it's used for ISO8583- 87 field 38.

AUTHNUMBER Table

Field Name	Type	Size	Description
AUTHNUM	NUMBER		This is the authorization code provided by the issuer when a transaction is approved. Normally it's used in ISO8583- 87 field 38
AUTHDATE	DATE		This is the local date when the last authnumber is used

HOTRANGE

Defines the a range of cards to be hot. Transactions of hot cards will be denied. Whether this table will be used to check the transaction depends on the configuration in shcbin form.

HOTRANGE Table

Field Name	Type	Size	Description
PAN_LOW	CHAR	19	Defines the lowest PAN in the card range. If the range is less than 19 digits, DCS pads the entered PAN with leading zeros to obtain a normalized PAN of 19 digits.
PAN_HI	CHAR	19	Defines the highest pan in the card range. If the PAN is less than 19 digits, DCS pads the entered PAN with leading zeros to obtain a normalized PAN of 19 digits.
STATUS	NUMBER		This value will be used as response code in shcmsg when a pan is found to be within a hotrange. It should be a denied response code (none-0)
CARDALERT	CHAR	1	Alert system if hot card is detected. Transactions involving hot cards are recorded into debug for the application that applying hotrange checking. Default = N

INST_BUSINESS_DAY

The institution business day table is used to define the start and end times of the business which are necessary for calculating reconciliation totals. It also stores the current business days of a given institution.

INST_BUSINESS_DAY Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Indicates the institution to which the ATM belongs.
ENTITY_ID	VARCHAR2	30	When only part of the institution uses this entry, this field indicates the part. When whole institution uses this entry, a "*" should be used.
INSTITUTION_TYPE	CHAR	10	Select from values Acquirer, Issuer, Both, Switch. Acquirer: This institution acts as acquirer in IST/Switch system Issuer: This institution acts as issuer in IST/Switch system. Both: This institution acts as both acquirer and issuer in IST/Switch system Switch: This institution acts as switch in IST/Switch system. This is usually applied to processor.
ATM_BUS_DAY	DATE		This field stores the actual business date of the ATM transaction, in the format MM/DD/YYYY. The value can be used as capture date or settlement date depending on the requirement.
POS_BUS_DAY	DATE		This field stores the actual business date of the POS transaction, in the format MM/DD/YYYY. The value can be used as capture date or settlement date depending on the requirement.
OTHER_BUS_DAY	DATE		This field stores the actual business date of the transactions other than ATM and POS, in the format MM/DD/YYYY. The value can be used as capture date or settlement date depending on the requirement.

INST_BUSINESS_DAY Table

Field Name	Type	Size	Description
ATM_FCUTOVER_TIME	NUMBER		Time by which IST/Switch will force ATM cutover, if not sent by the institution. For main institution, this is the time that main institution should cutover itself. For member institution, this is the time that the main institution should cutover this member if the member hasn't cutvoer itself by this time. The member cutover itself by sending a cutover message to switch.
POS_FCUTOVER_TIME	NUMBER		Time by which IST/Switch forces POS cutover, if not sent by the institution. For main institution, this is the time that main institution should cutover itself. For member institution, this is the time that the main institution should cutover this member if the member hasn't cutover itself by this time. The member cutover itself by sending a cutover message to switch.
OTHER_FCUTOVER_TM	NUMBER		Time by which IST/Switch will force other devices to cutover, if not sent by the institution. For main institution, this is the time that main institution should cutover itself. For member institution, this is the time that the main institution should cutover this member if the member hasn't cutover itself by this time. The member cutover itself by sending a cutover message to switch.
ATM_A_RECON_DAY	DATE		This field stores the actual date for which the reconciliation has been done when the member acting as acquirer for ATM transactions, in the format MM/DD/YYYY.
POS_A_RECON_DAY	DATE		This field stores the actual date for which the reconciliation has been done when the member acting as acquirer for POS transactions, in the format MM/DD/YYYY.
OTHER_A_RECON_DAY	DATE		This field stores the actual date for which the reconciliation has been done when the member acting as acquirer for other transactions, in the format MM/DD/YYYY.
ATM_A_RECON_TIME	NUMBER		Time when ATM reconciliation messages will be sent. For main institution, this field is not used.If the member institution is issuer only, this field is not used.Otherwise, this field is the time that main institution should send acquirer reconciliation message to this member. The acquirer reconciliation messages sent to members contain the amounts of transactions that the member acts as an acquirer.

INST_BUSINESS_DAY Table

Field Name	Type	Size	Description
POS_A_RECON_TIME	NUMBER		Time when POS reconciliation messages will be sent to member. For main institution, this field is not used.If the member institution is issuer only, this field is not used.Otherwise, this field is the time that main institution should send acquirer reconciliation message to this member. The acquirer reconciliation messages sent to members contain the amounts of transactions that the member acts as an acquirer.
OTHER_A_RECON_TIME	NUMBER		Time when other devices' reconciliation messages will be sent. For main institution, this field is not used.If the member institution is issuer only, this field is not used.Otherwise, this field is the time that main institution should send acquirer reconciliation message to this member. The acquirer reconciliation messages sent to members contain the amounts of transactions that the member acts as an acquirer.
ATM_I_RECON_DAY	DATE		This field stores the actual date for which the reconciliation has been done when the member acting as issuer for ATM transactions, in the format MM/DD/YYYY.
POS_I_RECON_DAY	DATE		This field stores the actual date for which the reconciliation has been done when the member acting as issuer for POS transactions, in the format MM/DD/YYYY.
OTHER_I_RECON_DAY	DATE		This field stores the actual date for which the reconciliation has been done when the member acting as issuer for other transactions, in the format MM/DD/YYYY.
ATM_I_RECON_TIME	NUMBER		If ATM reconciliation message is not received by that time, IST/Switch will force sending a reconciliation message.message.For main institution, this field is not used.If the member institution is acquirer only, this field is not used.Otherwise, this field is the time that main institution should send issuer reconciliation message to this member. The issuer reconciliation messages sent to members contain the amounts of transactions that the member acts as an issuer.

INST_BUSINESS_DAY Table

Field Name	Type	Size	Description
POS_I_RECON_TIME	NUMBER		Time when POS reconciliation messages will be sent to member..For main institution, this field is not used.If the member institution is acquirer only, this field is not used.Otherwise, this field is the time that main institution should send issuer reconciliation message to this member. The issuer reconciliation messages sent to members contain the amounts of transactions that the member acts as an issuer.
OTHER_I_RECON_TIME	NUMBER		Time when other devices' reconciliation messages will be sent to member.For main institution, this field is not used.If the member institution is acquirer only, this field is not used.Otherwise, this field is the time that main institution should send issuer reconciliation message to this member. The issuer reconciliation messages sent to members contain the amounts of transactions that the member acts as an issuer.
CONFIG	CHAR	40	This is for configuration. Each character represents a configuration value. The meaning of each character should be described in GUI form that configure this table. Direct access to this field is not recommended.

INST_PROFILE

This table stores institution IDs. An institution is an entity which is identified by an internally-assigned, unique ID within the system. Institutions are classified by type (inst_type column) such as main_inst, issuer, acquirer, etc. This table stores information outside of our switch for each institution. For example, a institution's member ids in MasterCard network or Visa network. It can be used to lookup these member ids from institution/bin or lookup bin from these member ids.

INST_PROFILE Table

Field Name	Type	Size	Description
TXNSRC	VARCHAR2	10	The institution ID of the institution where the transaction originated. For any transactions that involves issuer and acquirer, this is the acquiring institution or non-issuing institution. For financial/authorization / reversal messages, it is the acquiring institution. For messages sent from issuer to other party (e.g., issuer fee), this is the receiving institution. For messages not related to PAN, it may just be the institution that originates the messages.
TXNDEST	VARCHAR2	10	The institution ID of the institution where the issuer is. For any transactions that involves issuer and acquirer, this is the issuing institution or non-acquiring institution. For financial/authorization / reversal messages, it is the issuing institution. For messages sent from acquirer to other party (e.g., acquirer fee), this is the receiving institution. For messages not related to PAN, it may just be the institution that receives the messages.
ISS_ENTITY_ID	CHAR	30	Further defines part of the TxnDest institution that can be used with this record.

INST_PROFILE Table

Field Name	Type	Size	Description
MSGTYPE	CHAR	40	ISO 8583 message type identifier that defines the class of transaction. Typical message type identifiers: 0110: Authorization request response 0130: Authorization advice response 0210: Financial request response 0230: Financial advice response 0410: Reversal Request Transaction 0430: Reversal advice response 6xxx: Late message. The value xxx depends on the type of message that was late. For example, 6110 identifies a 0110 as a late response. 7xxx: Preauthorization 8xxx: Service Request 9xxx: Device Response. A 9000 indicates a positive response while a 9001 indicates a negative response. Regular expression can be used in this field. For example: "0100I0200", ".1.." etc.
EXTERNALID	CHAR	11	The ID that is needed but is not a part of the ISO8583 messages. For example, visa's station ID.
EXT_ID_DESC	CHAR	20	Description of External Id.
MEMBER_ID	CHAR	11	Stores Acquirer ID value. DCS uses this to check for duplicate transactions via the Europay rule inconjunction with the Forwarding ID value. Generally it's the member id of a institution assigned by external network (Visa, MasterCard, Europay etc.). This id may be used in field 32, 99, 100 in external ISO messages. MasterCard may use this value in field 2 in 8xx messages.
F_ID	CHAR	11	Stores Forwarding ID values. DCS uses this in conjunction with Acquirer ID to check for duplicate transactions via the Europay rule. This id may be used in field 33 in external ISO messages
INST_ID	CHAR	10	Internal ID assigned to an institution. The INST_ID field and the USERBIN_ID field together identifies a bin. The INST_ID field is the institution ID part of the bin.
USERBIN_ID	CHAR	10	BIN identifier for multiinstitutions. The INST_ID field and the USERBIN_ID field together identifies a bin. The USERBIN_ID field is the user bin ID part of the bin.

INST_PROFILE Table

Field Name	Type	Size	Description
KEYPARAM	VARCHAR	10	This ID point to the shckeys table to indicate which shckeys entry to use. The shckeys entry stores the Zone key for PIN block encryption.
INIT_STATUS	CHAR	1	The initial status. 'D' indicates that inst_profile is down when system startup. 'U' indicates that inst_profile is up when system startup.
ID	INT		An unique ID to identify the inst_profile entry.

ISS_PROFILE

This table stores the information that indicate how to find the issuer bin. Only transactions that have issuer involved should use this table.

ISS_PROFILE Table

Field Name	Type	Size	Description
TXNSRC	VARCHAR2	10	The Institution ID of the institution where the transaction originated. For any transactions that involves issuer and acquirer, this is the acquiring institution or non-issuing institution. For financial/authorization / reversal messages, it's the acquiring institution. For messages sent from issuer to other party (e.g. issuer fee), this is the receiving institution. For messages not related to PAN, it may just be the institution that originates the messages.
TXNDEST	VARCHAR2	10	The Institution ID of the institution where the issuer is. For any transactions that involves issuer and acquirer, this is the issuing institution or non-acquiring institution. For financial/authorization / reversal messages, it's the issuing institution. For messages sent from acquirer to other party (e.g. acquirer fee), this is the receiving institution. For messages not related to PAN, it may just be the institution that receives the messages.
ISS_ENTITY_ID	CHAR	60	This further defines part of the txnDest institution that can be used with this record. If there is no entity id as input to lookup this record. The eneity id defined will become the entity id of the message. This is issuer entity id. This field can contain regular expression.
CARDPRODUCT	CHAR	60	Refers to different card brand and different services/products. Normally it reflects different logos on the card. For example: VISA, MASTERCARD, CIRRUS, MAESTRO, INTERLINK, PLUS, CIBC... This field can contain regular expression.

ISS_PROFILE Table

Field Name	Type	Size	Description
MSGTYPE	CHAR	40	ISO 8583 message type identifier that defines the class of transaction. Typical message type identifiers: 0110: Authorization request response 0130: Authorization advice response 0210: Financial request response 0230: Financial advice response 0410: Reversal Request Transaction 0430: Reversal advice response 6xxx: Late message. The value xxx depends on the type of message that was late. For example, 6110 identifies a 0110 as a late response. 7xxx: Preauthorization 8xxx: Service Request 9xxx: Device Response. A 9000 indicates a positive response while a 9001 indicates a negative response. This field can contain regular expression.
DEVICETYPE	CHAR	3	The device type, e.g. POS, ATM, OTHER. Other device types can also be defined but may not be recognized by core products. This field can contain regular expression.
PCODE	CHAR	80	A six-digit processing code. First two digits describe a specific transaction Second two digits describe account types affected for debits and inquiries and the ifromî account for transfers. ñ Last two digits describe account types affected for credits and the itoî account for transfers. The same processing code is used in all messages related to the transaction. The field corresponds to ISO bitmap 3. This field can contain regular expression.
HASPIN	CHAR	1	Has PIN or not (e.g., Y, N).
ISS_INST_ID	CHAR	10	Issuer's Unique Institution ID. Identifies the issuer bin.
ISS_USERBIN_ID	CHAR	10	Identifies the issuer bin.
PRIORITY	NUMBER		Priority of this entry (1-99), the lower the integer, the higher the priority.

ISTTRIG

This table contains the thresholds for the dynamic triggers.

ISTTRIG Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique Institution Identifier.
TRIGID	CHAR	20	Indicates the Unique trigger identifier For Switch the first 10 characters are the Userbinid and the next 3 are "NET" "Userbinid" "NET"
TRIGGER_1	NUMBER		Indicates the threshold for trigger 1
COUNTER_1	NUMBER		Currently not in use
TRIGGER_2	NUMBER		Indicates the threshold for trigger 2
COUNTER_2	NUMBER		Currently not in use
TRIGGER_3	NUMBER		Indicates the threshold for trigger 3
COUNTER_3	NUMBER		Currently not in use
TRIGGER_4	NUMBER		Indicates the threshold for trigger 4
COUNTER_4	NUMBER		Currently not in use
TRIGGER_5	NUMBER		Indicates the threshold for trigger 5
COUNTER_5	NUMBER		Currently not in use
TRIGGER_6	NUMBER		Indicates the threshold for trigger 6
COUNTER_6	NUMBER		Currently not in use
TRIGGER_7	NUMBER		Indicates the threshold for trigger 7
COUNTER_7	NUMBER		Currently not in use

ISTTRIG Table

Field Name	Type	Size	Description
TRIGGER_8	NUMBER		Indicates the threshold for trigger 8
COUNTER_8	NUMBER		Currently not in use
TRIGGER_9	NUMBER		Indicates the threshold for trigger 9
COUNTER_9	NUMBER		Currently not in use
TRIGGER_10	NUMBER		Indicates the threshold for trigger 10
COUNTER_10	NUMBER		Currently not in use
TRIGGER_11	NUMBER		Indicates the threshold for trigger 11
COUNTER_11	NUMBER		Currently not in use
TRIGGER_12	NUMBER		Indicates the threshold for trigger 12
COUNTER_12	NUMBER		Currently not in use
TRIGGER_13	NUMBER		Indicates the threshold for trigger 13
COUNTER_13	NUMBER		Currently not in use
TRIGGER_14	NUMBER		Indicates the threshold for trigger 14
COUNTER_14	NUMBER		Currently not in use
TRIGGER_15	NUMBER		Indicates the threshold for trigger 15
COUNTER_15	NUMBER		Currently not in use
TRIGGER_16	NUMBER		Indicates the threshold for trigger 16
COUNTER_16	NUMBER		Currently not in use
TRIGGER_17	NUMBER		Indicates the threshold for trigger 17

ISTTRIG Table

Field Name	Type	Size	Description
COUNTER_17	NUMBER		Currently not in use
TRIGGER_18	NUMBER		Indicates the threshold for trigger 18
COUNTER_18	NUMBER		Currently not in use
TRIGGER_19	NUMBER		Indicates the threshold for trigger 19
COUNTER_19	NUMBER		Currently not in use
TRIGGER_20	NUMBER		Indicates the threshold for trigger 20
COUNTER_20	NUMBER		Currently not in use

LATERESPLOG

This table stores the late reversal responses that are generated.

LATERESPLOG Table

Field Name	Type	Size	Description
PAN	CHAR	19	Permanent Account Number of the cardholder.
PCODE	INT		Processing code of the transaction.
TRACE	INT		Trace number of the transaction.
TERMID	CHAR	8	Terminal ID where the transaction was initiated and transacted.
LOCAL_TIME	INT		Local_time in HHMMSS
LOCAL_DATE	DATE TIME		Local_date in YYYYMMDD
TRANDATE	DATE TIME		GMT Transaction Date in YYYYMMDD
TRANTIME	INT		GMT Transaction time in HHMMSS
RESPCODE	INT		Response code
ACQUIRER	CHAR	10	Acquirer BIN's internal ID
ISSUER	CHAR	10	Issuer BIN's internal ID

REVLOG

This table stores the reversal generated when the message times out.

REVLOG Table

Field Name	Type	Size	Description
PAN	CHAR	19	Permanent Account Number of the cardholder.
PCODE	INT		Processing code of the transaction.
TRACE	INT		Trace number of the transaction.
LOCAL_TIME	INT		Local_time in HHMMSS
LOCAL_DATE	DATETIME		Local_date in YYYYMMDD
CAP_DATE	DATETIME		Local capture date in YYYYMMDD
TERMID	CHAR	8	Terminal ID where the transaction was initiated and transacted.
TERMLOC	CHAR	25	Terminal Location
ACQUIRER	CHAR	10	Acquirer Bin internal ID
ISSUER	CHAR	10	Issuer Bin internal ID
TXNSRC	CHAR	10	The institution ID from where the txn come from
TXNDEST	CHAR	10	The institution ID to where the txn goes
ALTERNATEACQUIRER	CHAR	10	Not Used
ENTITYID	CHAR	30	Acquirer entity ID
ISSENTITYID	CHAR	30	Issuer entity ID
MEMBER_ID	CHAR	11	Member ID of the bank in external network
F_ID	CHAR	11	Member ID the forwarding institution in external network.

REVLOG Table

Field Name	Type	Size	Description
FILLER1	CHAR	50	Filler1 for customization use
FILLER2	CHAR	50	Filler2 for customization use
FILLER3	CHAR	50	Filler3 for customization use
FILLER4	CHAR	50	Filler4 for customization use
CARDPRODUCT	CHAR	10	Card Product. E.g. VISA, PLUS
SEGDATA	BLOB		Segment data. No sensitive information allowed in this field
SEGSIZE	INT		Size of segment data.
DEVICE_DEVCAP	INT		Various flags
DEVICE_CAP	INT		Various flags
FORMATTER_DEVCAP	INT		Various flags
SHC_DEVCAP	INT		Various flags
AUTH_DEVCAP	INT		Various flags
POS_CONDITION_CODE	SMALL INT		POS Condition Code
POS_PIN_CAP_CODE	CHAR	1	POS Pin Capability code
POS_CAP_CODE	SMALL INT		POS Capability code
MERCHANT_TYPE	SMALL INT		Merchant Type
ISS_CURRENCY_CODE	SMALL INT		Issuer Currency Code
SHCLOG_ID	CHAR	20	Shclog_ID, matches chip_index in shclog

SHC600LOG

This table logs the 06xx messages. This is a logging table intended for viewing data only.

SHC600LOG Table

Field Name	Type	Size	Description
MSGTYPE	NUMBER		ISO 8583 message type identifier that defines the class of transaction. Typical message type identifiers: 0110: Authorization request response 0130: Authorization advice response 0210: Financial request response 0230: Financial advice response 0410: Reversal Request Transaction 0430: Reversal advice response 6xxx: Late message. The value xxx depends on the type of message that was late. For example, 6110 identifies a 0110 as a late response. 7xxx: Preauthorization 8xxx: Service Request 9xxx: Device Response. A 9000 indicates a positive response while a 9001 indicates a negative response.
PAN	CHAR	19	Personal Account Number
MASK_PAN	CHAR	19	Refers to the PAN where several mid-digits are masked. This field is used to protect the PAN when it is displayed in the GUI.
PCODE	NUMBER		A six-digit processing code. First two digits describe a specific transaction Second two digits describe account types affected for debits and inquiries and the ifromî account for transfers. ñ Last two digits describe account types affected for credits and the îtoî account for transfers. The same processing code is used in all messages related to the transaction. The field corresponds to ISO bitmap 3.
TXNTYPE	NUMBER		Indicates the internal bit flag value such as deposits, withdrawals etc.
AMOUNT	NUMBER	26,8	Indicates the amount invoved in this transaction in currency indicated in acq_currency_code.

SHC600LOG Table

Field Name	Type	Size	Description
AVAL_BALANCE	NUMBER	26,8	This field stores the available balance or the new transaction amount in the currency of the acquirer. If the transaction is partially reversed, this field stores the actual dispensed amount. Otherwise, this field displays the available balance from the issuing institution or host. In a case where the host returns both ledger and available balance, this field stores the available balance. The field corresponds to ISO bitmap 54 (Additional Amount).
AMOUNT_EQUIV	NUMBER	26,8	Indicates the converted amount, if there has been currency conversion.
CASH_BACK	NUMBER	26,8	This field stores the ledger balance if the issuing institution returns both the ledger and available balance in the response. A cashback transaction is a cash amount withdrawn from a credit card in addition to the actual purchase. The cash back amount is stored in the base currency of the switch. A cashback is processed as a purchase, not a cash advance.
ISS_CONV_RATE	NUMBER	26,8	The iss_conv_rate field contains the conversion rate DCS uses when converting between the issuer's preferred currency and the base currency of the switch. DCS uses the issuer's shcbin record to obtain the ISO Currency Code. It uses this code to obtain the conversion rate from the currency database to set the value of iss_conv_rate.
ISS_CURRENCY_CODE	NUMBER		Currency code associated with the issuer or account amount.
ISS_CONV_DATE	DATE		Indicates the date of the issuer currency
ACQ_CONV_RATE	NUMBER	26,8	Contains the rate DCS uses when converting between the acquirer's preferred currency and the base currency of the switch. DCS sets the acq_conv_rate using the currency database. DCS uses the acquirer's ISO Currency Code in the shcbin table as an index into the currency database to retrieve the acq_conv_rate.
ACQ_CURRENCY_CODE	NUMBER		Indicates the currency code of the amount

SHC600LOG Table

Field Name	Type	Size	Description
ACQ_CONV_DATE	DATE		This field stores the actual date of settlement of the transaction, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 15.
TRA_AMOUNT	NUMBER	26,8	Indicates the transfer amount in tra_currency_code
TRA_CONV_RATE	NUMBER	26,8	Indicates the rate used if the currency conversion happens
TRA_CURRENCY_CODE	NUMBER		Indicates the currency code of the transaction amount
TRA_CONV_DATE	DATE		Indicates the date of the conversion to convert the transferee amount
FEE	NUMBER	26,8	Indicates the fee amount.
NEW_FEE	NUMBER	26,8	Indicates if there is any change in the fee.
NEW_AMOUNT	NUMBER	26,8	Indicates the changed amount.
NEW_SETL_AMOUNT	NUMBER	26,8	Indicates the changed settlement amount.
SETTLEMENT_FEE	NUMBER	26,8	Indicates the fee charged for settlement
SETTLEMENT_RATE	NUMBER	26,8	Indicates the conversion rate used to convert the amount into settlement currency
SETTLEMENT_CODE	NUMBER		Indicates the settlement currency code.
SETTLEMENT_AMOUNT	NUMBER	26,8	Indicates the amount in settlement currency
TRANDATE	DATE		Indicates the message transmission date.
TRANTIME	NUMBER		Message transmission time.
TRACE	NUMBER		The trace number used for transaction tracing.

SHC600LOG Table

Field Name	Type	Size	Description
LOCAL_TIME	NUMBER		This field stores the local time of the terminal where the transaction occurred, using a 24 hour clock in the format HHMMSS, where HH represents hour, MM represents minutes, and SS represents seconds. If the field is not set, DCS sets the Local Time field to the local time when the transaction enters the DCS node. The field corresponds to ISO bitmap 12.
LOCAL_DATE	DATE		This field stores the local date of the transaction, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 12.
SETTLEMENT_DATE	DATE		This field stores the actual date of settlement of the transaction, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 15.
CAP_DATE	DATE		This field stores the local date of the transaction captured, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 17.
POS_ENTRY_CODE	NUMBER		Identifies how a transaction is entered. e.g. magnetic strip, manual entry etc.
POS_CONDITION_CODE	NUMBER		Identifies the condition as how the transaction is entered. e.g. customer present, card present etc.
POS_PIN_CAP_CODE	CHAR	1	This code describes the method used to capture the card data and the PIN capability of the terminal.
POS_CAP_CODE	NUMBER		This parameter maps the transaction code with the POS capability code. The point-of-sale capability code describes the capability of the acquiring terminal for electronically reading the account number and expiry date from the card.
LIFE_CYCLE	NUMBER		This field is used (1) to indicate that the Authorization Request is a 'preauthorization' Request, and (2) to indicate the specific amount of time, in seconds, for which the preauthorization will remain valid (i.e. the period of time for which the Issuer or its agent will 'guarantee' or 'hold' funds).
ACQUIRER	CHAR	10	This field stores the BIN that identifies the acquiring bin of the transaction.
ISSUER	CHAR	10	This field stores the BIN that identifies the issuing bin of the transaction.

SHC600LOG Table

Field Name	Type	Size	Description
TRANSFEE	CHAR	10	This field stores the BIN that identifies the issuing transferee of this transaction. IST/Foundation uses this field to determine transaction routing.
ORIGINATOR	CHAR	10	String used to identify the switch. (For internal use only.) The value of 1010101010 indicate switch originated.
MEMBER_ID	CHAR	11	Stores Acquirer ID value. DCS uses this to check for duplicate transactions via the Europay rule in conjunction with the Forwarding ID value. Generally it's the member id of a institution assigned by external network (Visa, MasterCard, Europay etc.). This id may be used in field 32, 99, 100 in external ISO messages. MasterCard may use this value in field 2 in 8xx messages.
F_ID	CHAR	11	Stores Forwarding ID values. DCS uses this in conjunction with Acquirer ID to check for duplicate transactions via the Europay rule. This id may be used in field 33 in external ISO messages
TXNSRC	VARCHAR2	10	The Institution ID of the institution where the transaction originated. For any transactions that involves issuer and acquirer, this is the acquiring institution or non-issuing institution. For financial/authorization / reversal messages, it's the acquiring institution. For messages sent from issuer to other party (e.g. issuer fee), this is the receiving institution. For messages not related to PAN, it may just be the institution that originates the messages.
TXNDEST	VARCHAR2	10	The Institution ID of the institution where the issuer is. For any transactions that involves issuer and acquirer, this is the issuing institution or non-acquiring institution. For financial/authorization / reversal messages, it's the issuing institution. For messages sent from acquirer to other party (e.g. acquirer fee), this is the receiving institution. For messages not related to PAN, it may just be the institution that receives the messages.
ALTERNATEACQUIRER	CHAR	10	Reserved

SHC600LOG Table

Field Name	Type	Size	Description
ENTITYID	VARCHAR2	30	Any entity within acquiring domain to indicate more detailed information about where the transaction comes from. For example, merchant name, store name, BASEI, SMS etc. When switch is acquirer, its meaning should match the definition of acquiring entity in UDM. Note that separate acquiring BINS are required for SMS and Basel to differentiate between key encryption/decryption information.
ISS_ENTITYID	VARCHAR2	30	This further defines part of the txnDest institution that can be used with this record. If there is no entity id as input to lookup this record. The eneity id defines here will become the entity id of the message. This is issuer entity id. This field can contain regular expression.
DEVICE_CAP	NUMBER		Logs the device capability field in shcmsg.
TXN_START_TIME	NUMBER		Start time of the transaction for statistical purposes. Set when shc logs the response.
TXN_END_TIME	NUMBER		End time of the transaction for statistical purposes. Set when shc logs the response.
RESPCODE	NUMBER		This field stores the response code that determines the disposition of the transaction. The Response field corresponds to ISO bitmap 39.
REASON_CODE	NUMBER		Value in this field is based on the application. Reason codes are mapped to response codes. For a list of reason codes, see Appendix B.
REVCODE	NUMBER		Identifies the type of or reason for the reversal.
SHCERROR	NUMBER		This is a code indicating the disposition of an internal process. It also indicates the IST/Switch respond to a transaction message.

SHC600LOG Table

Field Name	Type	Size	Description
SAF	NUMBER		This field indicates whether the transaction was processed by IST/Foundation standin processing. A zero (0) in this field indicates that the transaction was authorized or denied by the host system. Any other value indicates that IST/Foundation performed standin authorization. The flag is set whenever an issuer communication link is down.
ORIGMSG	NUMBER		For reversal transactions, this field holds the original message type. This allows successive transaction messages to be logically linked.
ORIGTRACE	NUMBER		For reversal transactions, this field holds the original trace number. This allows successive transaction messages to be logically linked.
ORIGDATE	DATE		Reserved
ORIGTIME	NUMBER		Reserved
ACQ_COUNTRY	NUMBER		This code identifies the country of the acquiring institution, that is, the financial organization responsible for the merchant or ATM.
TRACK2	CHAR	79	Reserved
TRACK3	CHAR	104	Reserved
REFNUM	CHAR	12	This field stores the reference number assigned by the acquirer. This field may be omitted for some transactions, depending on the acquirer's specifications. The field corresponds to ISO bitmap 37.
AUTHNUM	CHAR	6	This is the authorization code provided by the issuer when a transaction is approved.
TERMID	CHAR	8	This field identifies the terminal from which the message came. The field corresponds to ISO bitmap 41.

SHC600LOG Table

Field Name	Type	Size	Description
ACCEPTORNAME	CHAR	40	This field stores the acceptor name and location. This field is required for most transactions and is stored in a format ready for printing. The field corresponds to ISO bitmap 43.
TERMLOC	CHAR	25	Code that identifies the card acceptor defining the point-of-service in both local and interchange environments.
ADDRRESPONSE	CHAR	25	Additional Response. User defined buffer. Internal use only. For example: in the case of open account relationship (OAR) transactions initiated at ATM terminals, the Additional Resp field contains the file name of the OAR screen template. The field corresponds to ISO bitmap 44.
ACCTNUM	CHAR	42	This field stores to and from accounts used for a transaction. This information is not always present. When present, the account numbers are formatted as from-account to-account, where the character acts as a separator. The numbers are optional and, if present, correspond to the TO and FROM account types in the Processing Code field of the transaction message. The field maps to ISO bitmap numbers 102 and 103.
BRANCH	NUMBER		Branch Id where the transaction was acquired.
SERIAL_1	NUMBER		(For internal use only.)
SERIAL_2	NUMBER		(For internal use only.)
STOREID	NUMBER		Indicates the Store ID.
LANE	NUMBER		Identifies the lane number of a store. (Used by POS.) DCS initializes the field lane from the merchant database records.
TERMINAL_TRACE	NUMBER		This is a number used to sequence a transaction from a terminal.
CHECKER_ID	NUMBER		User defined. (Used by POS.) Typically, the checker_id identifies the cashier at the point of sale.

SHC600LOG Table

Field Name	Type	Size	Description
SUPERVISOR	NUMBER		User defined. (Used by POS.)
SHIFT_NUMBER	NUMBER		User defined. (Used by POS.)
BATCH_ID	NUMBER		Reserved
DEVICE_DEVCAP	NUMBER		Indicator for recurrent payment support is set if both shcmmsg. device_devcap & SH_DEVICE_POSCOND_Recurrent are True.
SHC_DEVCAP	NUMBER		Used by programmers to set up flags
FORMATTER_DEVCAP	NUMBER		Used by programmers to set up flags
AUTH_DEVCAP	NUMBER		Used by programmers to set up flags
FILLER1	CHAR	50	Text Message
FILLER2	CHAR	50	Text Message
FILLER3	CHAR	50	Text Message
FILLER4	CHAR	50	Text Message
ISSUER_DATA	CHAR	128	Stores agent/formatter specific data which may be necessary for reporting to an issuerhost. Information from an inbound request is stored in the acquirer_data field, while information from an inbound response is stored in the issuer_data field.
ACQUIRER_DATA	CHAR	128	This field is used as an acquirer_data field, to store agent/formatter specific data which may be necessary for reporting or passing to an acquirer host.
NEW_AMOUNT_EQUIV	NUMBER	26,8	This field contains the actual amount dispensed in the issuer's currency in the event of a partial reversal.
ACQ_AVAL_BALANCE	NUMBER	26,8	Available balance in acquirer's currency.
ACQ_LEDGER_BALANCE	NUMBER	26,8	Ledger balance in acquirer's currency.

SHC600LOG Table

Field Name	Type	Size	Description
SETL_AVAL_BALANCE	NUMBER	26,8	Available balance in settlement currency.
SETL_LEDGER_BALANCE	NUMBER	26,8	Ledger balance in settlement currency.
AVAL_BALANCE_TYPE	NUMBER		This field contains the amount type of the aval_balance field. If it is empty, aval_balance is the available balance. Otherwise, aval_balance is the other balance specified in the following balance type table.
LEDGER_BALANCE_TYPE	NUMBER		This field contains the amount type of the ledger_balance field. If it is empty, ledger_balance is the ledger balance. Otherwise, ledger_balance is other balance specified in the following balance type table.
NEW_SETL_FEE	NUMBER	26,8	Amount of the fee applied to the transaction in the settlement currency.
TXN_AMOUNT	NUMBER	26,8	Reserved
TXN_NEW_AMOUNT	NUMBER	26,8	Reserved
TXN_CURRENCY_CODE	NUMBER		Reserved
TXN_CONV_RATE	NUMBER	26,8	Reserved
TXN_CONV_DATE	DATE		Reserved
CH_AMOUNT	NUMBER	26,8	This field identifies the transaction amount in the cardholder's billing currency.
CH_NEW_AMOUNT	NUMBER	26,8	When the actual transaction amount differs from the authorized amount, New CH Amount may be used to store the real transaction amount in the currency of the cardholder's account. For example, a Visa cardholder withdraws \$100 from an ATM. The transaction is approved, but the ATM only has \$50 in its cash drawer. The ATM sends a partial reversal to the Visa network which converts the outstanding \$50 to the currency of the cardholder's account and sends the amount to the issuer. If the issuer is using IST/Switch, the switch stores the amount in the currency of the cardholder's account into the ch_new_amount field in the shcmsh structure.

SHC600LOG Table

Field Name	Type	Size	Description
CH_CURRENCY_CODE	NUMBER		This field identifies the ISO currency code of the cardholder's billing currency.
CH_CONV_RATE	NUMBER	26,8	This field identifies the wash rate of the ch_currency_code with respect to the issuer currency.
CH_CONV_DATE	DATE		Reserved
LEDGER_BALANCE	NUMBER	26,8	Reserved
ADM_MSG_BUF	VARCHAR2	255	Text Message

SHCBIN

The shcbn table defines the working parameters for acquiring and issuing institutions connected to IST/Switch. The shcbn, shcauth and shcsaf forms provide the interface to this database. The shcbn table need to be filled before any acquirer and issuer profiles are first defined. The shcbn form automatically initializes the shcauth and shcsaf forms for the institution.

NOTE:

The system can distinguish between BINs that have one or more leading zeroes. For example, BINs 0445566 and 00445566 are processed as two different BINs. BIN IDs are space-padded.

SHCBIN Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique institution identifier. This is the institution id part of the bin.
USERBINID	CHAR	10	User bank instituion number. This field identifies a user bin. Default is #.networkid.
NETWORKID	CHAR	10	The networkid is the internal id of the bin, it must be unique. This is usually a sequential number.
DESCRIPTION	CHAR	30	User comments
CARDNAME	CHAR	10	Stores a card name, not exceeding 10 characters in length. This field is used by several utilities when control over a group of cards is required, especially when the switch is supporting several issuers who issue the same type of cards. The Card Name must exist in the Card Type table. A Card Name field left blank automatically displays a value of iNoneî.
NETWORK	CHAR	10	The network value equals to another bin's user bin id within the same institution. the other bin's configuration will be used, the configuration in this bin entry will be discarded.

SHCBIN Table

Field Name	Type	Size	Description
PINPARM	CHAR	10	Stores the 1-10 digit Network ID of the record that controls PIN verification padded with spaces. Similar to the Parameter Network ID field, this field allows several institutions to share a PIN Verification record. All pinverparm parameter information is shared.
MAILBOX	CHAR	30	The name of the mailbox to where the transaction will be sent if a message is sent to the bin.
PORT	CHAR	30	The name of the port to where the transaction will be sent if a message is sent to the bin.
BINTYPE	NUMBER		Defines the default issuer for transaction processing. A default issuer is used to route cards with no matching issuer shcbin record to an external network such as CIRRUS, PLUS, EUROPAY or INTERAC. The external network identifies the issuer and routes the transaction to the appropriate issuer host.
TIMEOUT	NUMBER		Indicates how many seconds an acquirer waits for a response before timing out the transaction. The Time Out Value is the time interval that DCS is given to respond to a transaction request. If the transaction message must be routed to an external issuer or an internal IST/Switch authorization module for authorization, DCS creates an event to time the response message.
NETMGR	CHAR	40	Defines the mailbox name of the Network Manager that DCS uses to send 0800 Network Management Requests. Currently the network manager strings include ShcNetworkManager and euroNetworkManager for Europay BINs. Do not change these values.
USEKEYS	CHAR	1	Indicates whether the key is used to encrypt PIN block when sending another party through this bin.
TXN_SET	CHAR	20	Defines the allowed transaction types, It must be inputted from GUI
SAFTYPE	CHAR	1	How to do stand-in. either Positive standin, negative standin or just deny transactiion when issuer is not available.

SHCBIN Table

Field Name	Type	Size	Description
SAFFILE	CHAR	1	Identifies whether the use of saf files are allowed. Values: Yes or No
SAFINTER	CHAR	1	Indicates what should be done On timeout. (R)=repeat txn (S)=mark down (N)=do nothing
SAFAMOUNT	NUMBER	26,8	Indicates the daily limit in negative authorization
SAFLIMIT	NUMBER		Indicates the maximum number of daily withdrawals for negative authrization
REFRESH	NUMBER		Indicates when to refresh daily limits (HHMM)
POSMailBOX	CHAR	30	Indicates the mail box name of the authorization module.
AUTHFLAG	CHAR	4	Indicates the type of authorization shc should use. 'FULL' perform all the configured verification, 'PREA' perform preauth, 'PASS' pass through message, no verification, 'MPAS'reserved
AUTHSERVER	CHAR	30	Indicates the mailbox of pre-authorization server
TXNAMOUNT	NUMBER	26,8	Indicates the maaximum amount per txn while in Store and Forward
ISS_MINAMOUNT	NUMBER	26,8	Indicates the minimum transaction amount, as acquirer
ACQ_MINAMOUNT	NUMBER	26,8	Indicates the minimum transaction amount, as issuer
FLOOR_1	NUMBER	26,8	Indicates the floor amount 1 for customization use
FLOOR_2	NUMBER	26,8	Indicates the floor amount 1 for customization use
FLOOR_3	NUMBER	26,8	Indicates the floor amount 1 for customization use
NPINTRY	NUMBER		Indicates the number of pin retry allowed
DEF_FROM_ACCT	NUMBER		Indicates the default from account

SHCBIN Table

Field Name	Type	Size	Description
DEF_TO_ACCT	NUMBER		Indicates the default to account
DEBIT_CREDIT	CHAR	1	Indicates whether the bin process debit or credit transaction.
CHECKEXP	CHAR	1	Indicates the check expiry date.
CHECKPIN	CHAR	1	Indicates wheather check pin is in shc
CHECKHOT	CHAR	1	Indicates whether the check is hot card or not. Valid values are: I = Individual cards R = Range of cards B = Both I & R N = No checking
CHECKSCODE	CHAR	1	Indicates whether or not the check service code is in tracks of shc
CHECKCVV	CHAR	1	Check Card Verification Value indicates if the switch must verify the Card Verification Value (CVV). Valid values:Y or 1: check CVV1,2: check CVV2 B: check both CVV1 and CVV2. N: disable checking.
CVVDATE	NUMBER		Date after which IST/Foundation checks the CVV on the card. Format is YYMM.
CHECKMOD10	CHAR	1	Indicates whether to check the check digit
CARDALERT	CHAR	1	Alert system if hot card is detected. Transactions involving hot or warm cards are recorded into IST/Foundation system log facility.Default = N
CUTOFF	NUMBER		Reserved
SEND500	CHAR	1	Reserved
CUTOVERTYPE	CHAR	1	Reserved
CCSTLMT	CHAR	1	Indicates hether or not to use MAC/KME

SHCBIN Table

Field Name	Type	Size	Description
CURRENCY_CODE	NUMBER		Identifies the ISO standard currency code assigned to the bin. The switch maintains the concept of a base currency that is used for all conversions: IST/Foundation automatically performs currency conversion between the acquirer and the issuer based on the currency code.
COUNTRY_CODE	NUMBER	3	Identifies the ISO standard numeric country code assigned to the network. This value is included in most online messages and is required during the settlement process. If an incoming transaction does not contain a valid acquirer country code, DCS uses the acquirer country code from this field acquirer's shcbin record.
BANKNAME	CHAR	22	Stores the name of the institution, not exceeding 22 characters in length, in this field. Sometimes, this field is used as a general acceptor name. The shccmd utility displays this field in its header information during command execution.
ECHOTEST	CHAR	1	Whether or not perform echo test for this bin. Valid values are: N = never D = only when down A = always
BINRANGE	CHAR	1	Reserved
BIN_CFG	CHAR	32	Each character in this field stands for a configuration. Please refer to shcbincfg form and shccam form description for more information
CAMMAILBOX	CHAR	30	Indicates the name of the mailbox to be used for the Card Authentication Module. This option allows the use of different Card Authentication Modules during chip-card processing.

SHCCARD

The shccard table stores information about individual cards. The information can be used while making decisions during transaction edit and standin

SHCCARD Table

Field Name	Type	Size	Description
PAN	CHAR	19	Personal Account Number
MASK_PAN	CHAR	19	The PAN with several mid-digits masked. This field is used to protect the PAN when it is displayed in the GUI.
CREATED	DATE		Indicates the date when this record was created. This is optional.
STATUS	NUMBER		If the value of this field is not 0, this value will be used as the response code of the transactions that happened to this card.
SAFDATE	NUMBER		Indicates the dates for which the SAFamounts should be applied.
SAFNUM	NUMBER		Indicates the number of SAF transactions.
SAFAMOUNT	NUMBER	26,8	Indicates the amount of all the SAF transactions.
FAILEDPIINS	NUMBER		Indicates the number of PIN tries that failed.
CARDALERT	CHAR	1	Indicates whether or not a warning message should appear in debug file when denying the transactions of this card. Valid values are: Y - Yes N- No Note: The debug level also determines whether or not the warning message can appear in debug files.
LASTTXNTIME	NUMBER		Indicates the time of the last transaction.
LASTTXNAMT	NUMBER	26,8	Indicates the amount of the last transaction.

SHCCARD Table

Field Name	Type	Size	Description
LASTTXNTERMID	CHAR	8	Indicates the terminal ID of the last transaction.
LASTTXNACQUIRER	CHAR	10	Indicates the acquirer of the last transaction..
LASTTXNAUTHNUM	CHAR	6	Indicates the authorization number of the last transaction.
LASTTXNRESPCODE	NUMBER		Indicates the response code of the last transaction.

SHCCHIPLOG

SHCCHIPLOG Table

Field Name	Type	Size	Description
CHIP_INDEX	CHAR	20	
TERM_TXN_DATE	DATE		
CVV_RES_CODE	CHAR	1	
CARD_AUTH_RES_CODE	CHAR	1	
TERM_TYPE	NUMBER		Indicates the terminal type, as defined by EMV/NCR manuals.
TERM_ENTRY_CAP	NUMBER		
CHIP_COND_CODE	NUMBER		
CCPS_TXN_IND	NUMBER		
CARD_AUTH_REL_IND	NUMBER		
MSG_REASON_CODE	NUMBER		
DERI_KEY_IDX	NUMBER		

SHCCHIPLOG Table

Field Name	Type	Size	Description
CRYPTO_VERSION	NUMBER		Indicates the Cryptogram Version Number.
CRYPTO_TXN_TYPE	NUMBER		Indicates the Transaction type..
TERM_COUNTRY_CODE	NUMBER		
CRYPTO_CURR_CODE	NUMBER		
NEG_FILE_VERSION	NUMBER		
CCARD_PA_TRACE	NUMBER		
CCARD_PURCH_TRACE	NUMBER		
CCARD_CRYPT_TRACE	NUMBER		
MCARD_BATCH_TRACE	NUMBER		
MCARD_TXN_TRACE	NUMBER		
CRYPTO_AMOUNT	NUMBER	26,8	Indicates the Cryptogram amount.
CRYPTO_CB_AMOUNT			
SRV_RESTRICT_CODE	CHAR	3	
TERM_CAP_PROFILE	CHAR	6	
TVR	CHAR	10	
UNPREDICTABLE_NUM	CHAR	8	
TERM_SER_NUM	CHAR	8	
CVR	CHAR	6	
ISSUER_DISCRE_DATA	CHAR	32	

SHCCHIPLOG Table

Field Name	Type	Size	Description
CRYPTOGRAM	CHAR	16	Indicates the Response Cryptogram.
APP_TXN_COUNTER	CHAR	4	
APP_ICHG_PROFILE	CHAR	4	
ARPC_CRYPTOGRAM	CHAR	16	
ARPC_RESPCODE	CHAR	2	
ISSUER_SCRIPT_RES	CHAR	40	
CCARD_SCH_CRYPTO	CHAR	16	
ISSUER_APP_DATA	CHAR	64	
BITMAP	NUMBER		
TVR_CVR_STATUS	CHAR		
ISSUER_AUTH_DATA	CHAR	32	

SHCGENERICLOG

The shcgenericlog table stores the segments in the message. No update is done to this table. Only insert is allowed. The log_id field is linked to the chip_index field in the shclog table.

SHCGENERICLOG Table

Field Name	Type	Size	Description
LOG_ID	CHAR	20	This field has to match the chip_index field in the shclog table.
MSGTYPE	NUMBER		Indicates the message type of the message.
REQRESP	CHAR	1	Indicates the request response of the message. Valid values are: Q - Request P - Response
SWITCH_DATE	DATE		Indicates the settlement date, by default. If the settlement_date is empty, it is filled the switch business day defined in inst_business_day table.
FIELD1	VARCHAR2	512	Indicates the information that is logged in segment1.
FIELD2	VARCHAR2	512	Indicates the information that is logged in segment2.
FIELD3	VARCHAR2	512	Indicates the information that is logged in segment3.
FIELD4	VARCHAR2	512	Indicates the information that is logged in segment4.
FIELD5	VARCHAR2	512	Indicates the information that is logged in segment5.
FIELD6	VARCHAR2	512	Indicates the information that is logged in segment6.
FIELD7	VARCHAR2	512	Indicates the information that is logged in segment7.
FIELD8	VARCHAR2	512	Indicates the information that is logged in segment8.
FIELD9	VARCHAR2	512	Indicates the information that is logged in segment9.
FIELD10	VARCHAR2	512	Indicates the information that is logged in segment10.

SHCGENERICLOG Table

Field Name	Type	Size	Description
FIELD11	VARCHAR2	512	Indicates the information that is logged in segment11.
FIELD12	VARCHAR2	512	Indicates the information that is logged in segment12.
FIELD13	VARCHAR2	512	Indicates the information that is logged in segment13.
FIELD14	VARCHAR2	512	Indicates the information that is logged in segment14.
FIELD15	VARCHAR2	512	Indicates the information that is logged in segment15.
FIELD16	VARCHAR2	512	Indicates the information that is logged in segment16.
FIELD17	VARCHAR2	512	Indicates the information that is logged in segment17.
FIELD18	VARCHAR2	512	Indicates the information that is logged in segment18.
FIELD19	VARCHAR2	512	Indicates the information that is logged in segment19.
FIELD20	VARCHAR2	512	Indicates the information that is logged in segment20.
FIELD21	VARCHAR2	512	Indicates the information that is logged in segment21.
FIELD22	VARCHAR2	512	Indicates the information that is logged in segment22.
FIELD23	VARCHAR2	512	Indicates the information that is logged in segment23.
FIELD24	VARCHAR2	512	Indicates the information that is logged in segment24.
FIELD25	VARCHAR2	512	Indicates the information that is logged in segment25.
FIELD26	VARCHAR2	512	Indicates the information that is logged in segment26.
FIELD27	VARCHAR2	512	Indicates the information that is logged in segment27.
FIELD28	VARCHAR2	512	Indicates the information that is logged in segment28.
FIELD29	VARCHAR2	512	Indicates the information that is logged in segment29.

SHCGENERICLOG Table

Field Name	Type	Size	Description
FIELD30	VARCHAR2	512	Indicates the information that is logged in segment30.
FIELD31	VARCHAR2	512	Indicates the information that is logged in segment31.
FIELD32	VARCHAR2	512	Indicates the information that is logged in segment32.
FIELD33	VARCHAR2	512	Indicates the information that is logged in segment33.
FIELD34	VARCHAR2	512	Indicates the information that is logged in segment34.
FIELD35	VARCHAR2	512	Indicates the information that is logged in segment35.
FIELD36	VARCHAR2	512	Indicates the information that is logged in segment36.
FIELD37	VARCHAR2	512	Indicates the information that is logged in segment37.
FIELD38	VARCHAR2	512	Indicates the information that is logged in segment38.
FIELD39	VARCHAR2	512	Indicates the information that is logged in segment39.
FIELD40	VARCHAR2	512	Indicates the information that is logged in segment40.

SHCEXTBINDB

The shcextbindb table defines all the PAN ranges that the IST/Switch can recognize. A PAN range may appear multiple times if they belong to multiple card brands.

SHCEXTBINDB Table

Field Name	Type	Size	Description
LOWBIN	CHAR	15	Defines the numerically smallest entry of a specific BIN range.
HIGHBIN	CHAR	15	Defines the numerically largest BIN of a specific BIN range.
STATUS	CHAR	1	Indicates whether this record should be used or not. Valid values: A - Record should be used.
DESCRIPTION	CHAR	50	An optional description of this entry.
DESTINATION	VARCHAR2	10	Card issuer institution ID. The institution ID may be a network institution ID or a member institution ID.
ENTITY_ID	VARCHAR2	30	Defines the entity_id of this PAN range within the institution. User can leave it empty or '*' if no entity_id for this PAN.
CARDPRODUCT	CHAR	10	Refers to different card brand and different services/products. Normally it reflects different logos on the card. For example: VISA, MASTERCARD, CIRRUS, MAESTRO, INTERLINK, PLUS, CIBC, etc.
NETWORK_DATA	CHAR	10	This field stores information specific for this PAN range. Different destinations may use it differently.
FILE_NAME	CHAR	20	This is an optional field that indicates the name of the file from where the record originated.

SHCEXTBINDB Table

Field Name	Type	Size	Description
FILE_VERSION	CHAR	10	This is an optional field that indicates the version of the file from where the record originated.
FILE_DATE	DATE		This is an optional field that indicates the date of the file from where the record originated.
COUNTRY_CODE	NUMBER	3	Identifies the ISO standard numeric country code. This is the country code of the card issuer. Default value is 0.

SHCKEYS

SHCKEYS Table

Field Name	Type	Size	Description
INSTITUTION_ID	VARCHAR2	10	Unique Institution Identifier.
USERBINID	CHAR	10	User bank institution number. Default is #.networkid..
BIN	CHAR	10	Bank Institution Number
KEYTYPES	CHAR	1	Text Message
KEK	CHAR	74	Stores the value of the encrypted key.
KEKCHK	CHAR	4	Stores check digits.
ACQPINIDX	NUMBER		Acquirer PIN Index indicates the field containing the active KPE. Values are 0, 1 or 2.
ACQPIN1	CHAR	74	Stores the cryptogram of the specified Key type (encrypted under the HMK), either eKM.1 (KPE), eKM.3 (KMAC) or eKM.2 (KME).

SHCKEYS Table

Field Name	Type	Size	Description
ACQPIN1CHK	CHAR	4	Acquirer PIN 1 Count flag set by the acquirer AIL depending on the Key Type, using the current KEK_counter.
ACQPIN2	CHAR	74	Stores the cryptogram of the specified Key type (encrypted under the HMK), either eKM.1 (KPE), eKM.3 (KMAC) or eKM.2 (KME).
ACQPIN2CHK	CHAR	4	Acquirer PIN 2 Count flag set by the acquirer AIL depending on the Key Type, using the current KEK_counter.
ISSPINIDX	NUMBER		
ISSPIN1	CHAR	74	
ISSPIN1CHK	CHAR	4	Text Message
ISSPIN2	CHAR	74	Issuer PIN 2. Issuer database's PIN counter value.
ISSPIN2CHK	CHAR	4	Text Message
ACQMACIDX	NUMBER		Acquirer Message Authentication Index. Acquirer changes index value depending on key type.
ACQMAC1	CHAR	74	Acquirer Message Authentication Key 1 stores the first cryptogram of the specified Key type (encrypted under the HMK), either eKM.1 (KPE), eKM.3 (KMAC) or eKM.2 (KME).
ACQMAC1CHK	CHAR	4	Text Message
ACQMAC2	CHAR	74	Acquirer Message Authentication Key 2 stores the first cryptogram of the specified Key type (encrypted under the HMK), either eKM.1 (KPE), eKM.3 (KMAC) or eKM.2 (KME).
ACQMAC2CHK	CHAR	4	Text Message
ISSMACIDX	NUMBER		Issuer Message Authentication Index. Issuer changes index value depending on key type.

SHCKEYS Table

Field Name	Type	Size	Description
ISSMAC1	CHAR	74	Issuer Message Authentication Key 1 stores the KMAC cryptogram.
ISSMAC1CHK	CHAR	4	Issuer MAC 1 Count stores the counter value with the Key used at the Issuer when the MAC Key is being used.
ISSMAC2	CHAR	74	Issuer Message Authentication Key 2 stores the KMAC cryptogram.
ISSMAC2CHK	CHAR	4	Text Message
FLAGS	CHAR	5	Text Message
O_ROWID	NUMBER		
ACQBIN	CHAR	10	Acquirer BIN
ISSBIN	CHAR	10	Issuer BIN
ACQKEK	CHAR	74	Acquirer Key Exchange Key
ACQKEKCHK	CHAR	4	Text Message
ACQPIN3	CHAR	74	Stores the cryptogram of the specified Key type (encrypted under the HMK), either eKM.1 (KPE), eKM.3 (KMAC) or eKM.2 (KME).
ACQPIN3CHK	CHAR	4	Text Message
ACQMAC3	CHAR	74	Acquirer Message Authentication Key 3 stores the first cryptogram of the specified Key type (encrypted under the HMK), either eKM.1 (KPE), eKM.3 (KMAC) or eKM.2 (KME).
ACQMAC3CHK	CHAR	4	Text Message
ISSPIN3	CHAR	74	Issuer PIN 3. Issuer database's PIN counter value.
ISSPIN3CHK	CHAR	4	Text Message
ISSMAC3	CHAR	74	

SHCKEYS Table

Field Name	Type	Size	Description
ISSMAC3CHK	CHAR	4	Text Message
ACQKMEIDX	NUMBER		Acquirer Message Encryption Key Index stores the active key index.
ACQKME1	CHAR	74	Acquirer Message Encryption Key 1 stores the first cryptogram of the specified Key type (encrypted under the HMK), either eKM.1 (KPE), eKM.3 (KMAC) or eKM.2 (KME).
ACQKME1CHK	CHAR	4	Text Message
ACQKME2	CHAR	74	Acquirer Message Encryption Key 2 stores the first cryptogram of the specified Key type (encrypted under the HMK), either eKM.1 (KPE), eKM.3 (KMAC) or eKM.2 (KME).
ACQKME2CHK	CHAR	4	Text Message
ACQKME3	CHAR	74	Acquirer Message Encryption Key 3 stores the first cryptogram of the specified Key type (encrypted under the HMK), either eKM.1 (KPE), eKM.3 (KMAC) or eKM.2 (KME).
ACQKME3CHK	CHAR	4	Text Message
ISSKMEIDX	NUMBER		Issuer Message Encryption Key Index stores the active key index.
ISSKME1	CHAR	74	Text Message
ISSKME1CHK	CHAR	4	Text Message
ISSKME2	CHAR	74	Text Message
ISSKME2CHK	CHAR	4	Text Message
ISSKME3	CHAR	74	Text Message
ISSKME3CHK	CHAR	4	Text Message
ACQKEKSTAT	CHAR	1	Text Message

SHCKEYS Table

Field Name	Type	Size	Description
ACQPIN1STAT	CHAR	1	Text Message
ACQMAC1STAT	CHAR	1	Text Message
ACQKME1STAT	CHAR	1	Text Message
ACQPIN2STAT	CHAR	1	Text Message
ACQMAC2STAT	CHAR	1	Text Message
ACQKME2STAT	CHAR	1	Text Message
ACQPIN3STAT	CHAR	1	Text Message
ACQMAC3STAT	CHAR	1	Text Message
ACQKME3STAT	CHAR	1	Text Message
ISSKEKSTAT	CHAR	1	Text Message
ISSPIN1STAT	CHAR	1	Text Message
ISSMAC1STAT	CHAR	1	Text Message
ISSKME1STAT	CHAR	1	Text Message
ISSPIN2STAT	CHAR	1	Text Message
ISSMAC2STAT	CHAR	1	Text Message
ISSKME2STAT	CHAR	1	Text Message
ISSPIN3STAT	CHAR	1	Text Message
ISSMAC3STAT	CHAR	1	Text Message
ISSKME3STAT	CHAR	1	Text Message

SHCKEYS Table

Field Name	Type	Size	Description
ACQKEKCNT	CHAR	20	Text Message
ACQPIN1CNT	CHAR	20	Acquirer PIN 1 Count flag set by the acquirer AIL depending on the Key Type, using the current KEK_counter.
ACQPIN2CNT	CHAR	20	Acquirer PIN 2 Count flag set by the acquirer AIL depending on the Key Type, using the current KEK_counter.
ACQPIN3CNT	CHAR	20	Acquirer PIN 3 Count flag set by the acquirer AIL depending on the Key Type, using the current KEK_counter.
ACQMAC1CNT	CHAR	20	Text Message
ACQMAC2CNT	CHAR	20	Acquirer Message Authentication Key 2 Count.
ACQMAC3CNT	CHAR	20	Acquirer Message Authentication Key 3 Count.
ACQKME1CNT	CHAR	20	Acquirer Message Encryption Key 1 Count. Acquirer sets the field depending on the Key Type using the current KEK_counter.
ACQKME2CNT	CHAR	20	Acquirer Message Encryption Key 2 Count. Acquirer sets the field depending on the Key Type using the current KEK_counter.
ACQKME3CNT	CHAR	20	Acquirer Message Encryption Key 3 Count. Acquirer sets the field depending on the Key Type using the current KEK_counter.
ISSKEKCNT	CHAR	20	Text Message
ISSPIN1CNT	CHAR	20	Text Message
ISSPIN2CNT	CHAR	20	Text Message
ISSPIN3CNT	CHAR	20	Text Message
ISSMAC1CNT	CHAR	20	Issuer MAC 1 Count stores the counter value with the Key used at the Issuer when the MAC Key is being used.

SHCKEYS Table

Field Name	Type	Size	Description
ISSMAC2CNT	CHAR	20	Issuer MAC 2 Count stores the counter value with the Key used at the Issuer when the MAC Key is being used.
ISSMAC3CNT	CHAR	20	Issuer MAC 3 Count stores the counter value with the Key used at the Issuer when the MAC Key is being used.
ISSKME1CNT	CHAR	20	Text Message
ISSKME2CNT	CHAR	20	Text Message
ISSKME3CNT	CHAR	20	Text Message
DEF_CLASS	CHAR	1	Text Message
DEF_INDEX	CHAR	1	Text Message
VAL_NEW	CHAR	1	Text Message
VAL_SEQ	CHAR	1	Text Message
VAL_CHK	CHAR	1	Text Message
UPD_TBL	CHAR	1	Text Message
KEK_LEN	NUMBER		
ISSKPE_LEN	NUMBER		
ISSKME_LEN	NUMBER		
ISSMAC_LEN	NUMBER		
ACQKPE_LEN	NUMBER		
ACQKME_LEN	NUMBER		
ACQMAC_LEN	NUMBER		

SHCLOG_ADD

Shclog_add table contains industry specific data of an OLTP transaction.

SHCLOG_ADD Table

Field Name	Type	Size	Description
SHCLOG_IDX	CHAR	20	An internal ID; reference to shclog.chip_index
INDUSTRY_DATA_IND	NUMBER	2	Indicates the Industry data indicator. Valid Values are: 0 - Unknown, Unsure 1 - Airline 1, 2 - Airline 2, 3 - Hotel Preferred 4 - Hotel Normal 5 - Auto Preferred 6 - Auto Normal 7 - Direct Marketing 8 - Fuel 9 - MOTO 10 - Retail 11 - Medical (Visa) 12 - Limited Amount Terminal
COMM_CRD_DATA_IND	CHAR	1	Indicates the commercial card data present
REQ_PAYMENT_SRV	NUMBER	2	Indicates the requested payment service
PRODUCT_CD	CHAR	6	Indicates the product code
VALID_CD	CHAR	4	Indicates the validation code
REQ_ACI	CHAR	1	Indicates the requested ACI
RESP_ACI	CHAR	1	Indicates the response ACI
START_DATE	DATE		Indicates the start date

SHCLOG_ADD Table

Field Name	Type	Size	Description
END_DATE	DATE		Indicates the end date
DAY_RATE	NUMBER	26,8	Indicates the day rate
NO_SHOW_IND	CHAR	1	Indicates the no show indicator
EXTRA_CHARGES	CHAR	6	Indicates the extra charges
MARKET_SPEC_REQ	CHAR	1	Indicates the market specific data request
MARKET_SPEC_RESP	CHAR	1	Indicates the market specific data response
FIRST_AUTH_AMT	NUMBER	26,8	Indicates the first authorization amount
DURATION	NUMBER	2	Indicates the duration
PURCH_ID	CHAR	25	Indicates the purchase identifier
PREST_PROP_IND	CHAR	1	Indicates the prestigious property indicator
COMM_CARD_REQ_IND	CHAR	1	Indicates the Level II Commercial card request indicator. Valid values are: 0 - No Request. 1 - Request Card Type (in request).
COMM_CARD_RESP_IND	CHAR	1	Indicates the Level II Commercial card response indicator. Valid values are: B - Bussines card R - Corporate S - Purchasing 0 - Non commercial " " - Invalid request indicator received (in response)
SALES_TAX_FLAG	CHAR	1	Indicates the sales tax flag
SALES_TAX	NUMBER	26,8	Indicates the sales tax.
PURCH_ORDER_NR	CHAR	17	Indicates the purchase order number.

SHCLOG_ADD Table

Field Name	Type	Size	Description
FLEET_TYPE	CHAR	1	Indicates the Fleet type. Valid values are: Driver ID - bit 1 on Odometer - bit 2 on Vehicle ID - bit 3 on
FLEET_ID_NR	CHAR	17	Indicates the Fleet fueling card. Identification number - some of Driver ID, Vehicle ID, other ID number.
FLEET_RESTR	CHAR	1	Indicates the Fleet card - product restriction. Valid values are: 0 - fuel card only 1 - unrestricted card
CH_AUTH_ENTITY	CHAR	1	Indicates the cardholder authentication entity
REIMBURSEMENT_ATTR	CHAR	1	Indicates the reimbursement attribute
DISCOUNT_AMT	NUMBER	26,8	Indicates the discount amount
FREIGHT_AMT	NUMBER	26,8	Indicates the freight amount
DUTY_AMT	NUMBER	26,8	Indicates the duty amount
DEST_ZIP_CD	CHAR	20	Indicates the destination ZIP/postal code

SHCLOG_CHEQUE

The Shclog_cheque contain cheques related data of OLTP transaction. Sensitive data are currently not supported by IST/Switch acquiring interfaces.

SHCLOG_CHEQUE Table

Field Name	Type	Size	Description
SHCLOG_IDX	CHAR	20	Indicates an internal ID; reference to shclog.chip_index.
CHECK_TYPE	NUMBER	2	Indicates the cheque type. Valid values are: 1 - Personal/Business 2 - Payroll 3 - Government 4 - Travelers check 5 - Money order 6 - Cashiers check 7 - Counter check 8 - Two party check 9 - Personal only 10 - Business only 11 - Appraisal 12 - Mail order 13 - Mail order personal
VERIF_METHOD	NUMBER	2	Indicates the verification method. Valid values are: 1 - Telecredit 2 - Telecheck 3 - TeleCheck 4 - JBS 7 - Bank card 8 - Telecredit 9 - Full MICR Number

SHCLOG_CHEQUE Table

Field Name	Type	Size	Description
ENTRY_TYPE	NUMBER	2	Indicates the entry type: 1 - Keyed MICR (Account number) 2 - Keyed MICR NPC (check number, ABA, account number.) 3 - Keyed full MICR (MICR 50 + check seq.) 4 - Keyed partial MICR (account + check seq.) 5 - Driver license with raw MICR data (raw MICR + drivers. license + state code) 6 - Drivers license (drivers. license + state) 7 - Drivers license Equifax (drivers license + birth date) 8 - Short MICR (MICR 26) 9 - MICR read (check number, ABA, account number) 10 - Account number (account nr. + check nr. optional) 11 - Raw MICR 12 to 14 - Reserved
MICR_LENGTH	NUMBER	2	Indicates the MICR length.
ROUTING_NR	NUMBER	9	Indicates the routing number.
CHECK_NR	NUMBER	18	Indicates the cheque sequence number.
MICR_NR	CHAR	50	Indicates the MICR data including type. Valid values are: C- Check reader A - Manual account number R - Manual route number

SHCLOG_CHEQUE Table

Field Name	Type	Size	Description
ID_TYPE	NUMBER	2	Indicates the ID type: 0 - Unknown 1 - US Driver's License 2 - Canadian Driver's License 3 - Mexican Driver's License 4 - US Identification 5 - Canadian Identification 6 - Mexican Identification 7 - Military Identification 8 - Law Enforcement ID 9 - US Gov
DRIVER_LIC_NR	CHAR	32	Indicates the driver license number (not supported currently).
EXPIR_DATE	NUMBER	8	Indicates the expiration date.
BIRTH_DATE	DATE		Indicates the birth date (not supported currently).
NAME	CHAR	35	Indicates the name (not supported currently).
ADDR1	CHAR	29	Indicates the address.
ADDR2	CHAR	29	Indicates the address.
CITY	CHAR	20	Indicates the city.
STATE_CD	CHAR	2	Indicates the state code.
ZIP_CD	CHAR	9	Indicates the zip code.
COUNTRY_CD	CHAR	2	Indicates the country code.
PHONE	CHAR	20	Indicates the phone number.
BANK_CD	CHAR	2	Indicates the bank code.

SHCLOG_IFD

The shclog_ifd table stores IFD message specific information that is not able to be logged into shclog table, such as ifd_data_1, ifd_data_2, etc. The two tables are linked by shclog_idx.

SHCLOG_IFD Table

Field Name	Type	Size	Description
SHCLOG_IDX	CHAR	20	The index field linking this table to the shclog table.
IFD_DATA_1	VARCHAR2	255	IFD data part I, comes from DE48 in IFD transactions
IFD_DATA_2	VARCHAR2	255	IFD data part II, come from DE125 in IFD transactions

SHCLOG

IST/Foundation maintains a log of all transactions processed by the switch in the Transaction Log table - shclog. You can use this information to generate reports. Also, since the trace number in shclog is the same as the trace number in a debug file, you can use this information to reference specific transactions in the debug file. The information in shclog is for display purposes and should not be edited. The shclog database provides several methods of access to retrieve transaction records. Transaction records in shclog are retrieved using one of the following index keys: Local Date, PAN, Trace, Local Time, Acquirer, Terminal Id Settlement Date, Trace Capture Date Reference Number, PAN The shclog form consists of three screens (or pages) of transaction fields. All three pages are described in this chapter.

SHCLOG Table

Field Name	Type	Size	Description
MSGTYPE	NUMBER		ISO 8583 message type identifier that defines the class of transaction. Typical message type identifiers: 0110: Authorization request response 0130: Authorization advice response 0210: Financial request response 0230: Financial advice response 0410: Reversal Request Transaction 0430: Reversal advice response 6xxx: Late message. The value xxx depends on the type of message that was late. For example, 6110 identifies a 0110 as a late response. 7xxx: Preauthorization 8xxx: Service Request 9xxx: Device Response. A 9000 indicates a positive response while a 9001 indicates a negative response.
FLIPPED_MSGTYPE	NUMBER		Flipped message type is the message type sent to networks (Visa, MasterCard, Europay) in the request. If this message type is same as the message type received from shc, the flipped message type can be just the message type received from shc (recommended) or 0. Formatter/agents should fill this field when receiving responses from networks.
PAN	CHAR	19	Text Message. Personal Account Number
MASK_PAN	CHAR	19	The PAN with several mid-digits masked. This field is used to protect the PAN when it is displayed in the GUI.

SHCLOG Table

Field Name	Type	Size	Description
PCODE	NUMBER		A six-digit processing code. First two digits describe a specific transaction Second two digits describe account types affected for debits and inquiries and the from account for transfers. Last two digits describe account types affected for credits and the to account for transfers. The same processing code is used in all messages related to the transaction. The field corresponds to ISO bitmap 3.
TXNTYPE	NUMBER		This field is used to store the transaction type identified by the first two digits of the pcode. Valid values are: 0x0001 - Withdraw 0x0002 - Deposit 0x0004 - Transfer 0x0008 - Balance Inquiry 0x0010 - Bill Payment 0x0020 - Reserved 0x0040 - Purchase 0x0080 - Reserved 0x0100 - Reserved 0x0200 - Reserved 0x0400 - Reserved 0x0800 - Reserved 0x1000 - Reserved 0x2000 - Authenticate These flags may appear along with another flag also; but this condition is quite rare.
AMOUNT	NUMBER	26,8	Indicates the amount of the transaction in acquirer currency
AVAL_BALANCE	NUMBER	26,8	This field stores the available balance or the new transaction amount in the currency of the acquirer. If the transaction is partially reversed, this field stores the actual dispensed amount. Otherwise, this field displays the available balance from the issuing institution or host. In a case where the host returns both ledger and available balance, this field stores the available balance. The field corresponds to ISO bitmap 54 (Additional Amount).

SHCLOG Table

Field Name	Type	Size	Description
AMOUNT_EQUIV	NUMBER	26,8	This field stores the converted amount in issuer currency if shc is required to do conversion for this transaction.
CASH_BACK	NUMBER	26,8	This field stores the cash back amount in acquirer currency. A cashback transaction is a cash amount withdrawn from a credit card in addition to the actual purchase. The cash back amount is stored in the base currency of the switch. A cashback is processed as a purchase, not a cash advance.
ISS_CONV_RATE	NUMBER	26,8	The iss_conv_rate field contains the conversion rate DCS uses when converting between the issuer's preferred currency and the base currency of the issuer institution. DCS uses the issuer's shcbin record to obtain the ISO Currency Code. It uses this code to obtain the conversion rate from the currency database to set the value of iss_conv_rate.
ISS_CURRENCY_CODE	NUMBER		Currency code associated with the issuer or account amount.
ISS_CONV_DATE	DATE		Effective date of issuer conversion rate.
ACQ_CONV_RATE	NUMBER	26,8	Contains the rate DCS uses when converting between the acquirer's preferred currency and the base currency of the issuer institution. DCS sets the acq_conv_rate using the currency database. DCS uses the acquirer's ISO Currency Code in the shcbin table as an index into the currency database to retrieve the acq_conv_rate.
ACQ_CURRENCY_CODE	NUMBER		Currency code associated with the acquirer amount.
ACQ_CONV_DATE	DATE		Effective date of transfer conversion rate.
TRA_AMOUNT	NUMBER	26,8	This field stores the transaction amount in the currency of the transferee logged in Transferee Currency Code.
TRA_CONV_RATE	NUMBER	26,8	Rate used to convert settlement amount to transferee amount for interbank transfer transactions.
TRA_CURRENCY_CODE	NUMBER		Currency code of the credit account for interbank transfer transactions.

SHCLOG Table

Field Name	Type	Size	Description
TRA_CONV_DATE	DATE		Effective date of transferee conversion date.
FEE	NUMBER	26,8	Indicates the fee amount that is incurred for this transaction. Different networks may use this filed in a different way.
NEW_FEE	NUMBER	26,8	Indicates the adjusted amount of fee that is incurred for this transaction. Different networks may use this filed in a different way.
NEW_AMOUNT	NUMBER	26,8	Indicates the adjusted amount in acquirer currency.
NEW_SETL_AMOUNT	NUMBER	26,8	Indicates the adjusted amount in settlement currency.
SETTLEMENT_FEE	NUMBER	26,8	Amount of the fee applied to the transaction in the settlement currency.
SETTLEMENT_RATE	NUMBER	26,8	Rate used to convert acquired amount to settlement amount. The field corresponds to ISO bitmap 9.
SETTLEMENT_CODE	NUMBER		Currency code associated with the settlement amount.
SETTLEMENT_AMOUNT	NUMBER	26,8	Amount of the transaction in the settlement currency.
TRANDATE	DATE		Indicates the message transmission date in the format MM/DD/YYYY. The field corresponds to ISO bitmap 7.
TRANTIME	NUMBER		Indicates the message transmission time in the format HHMMSS. The field corresponds to ISO bitmap 7.
TRACE	NUMBER		A system trace number assigned to the transaction by the acquirer. The value in this field is set for the life of the transaction and remains unique for a particular terminal/acquirer within a day.
LOCAL_TIME	NUMBER		This field stores the local time of the terminal where the transaction occurred, using a 24 hour clock in the format HHMMSS, where HH represents hour, MM represents minutes, and SS represents seconds. If the field is not set, DCS sets the Local Time field to the local time when the transaction enters the DCS node. The field corresponds to ISO bitmap 12.

SHCLOG Table

Field Name	Type	Size	Description
LOCAL_DATE	DATE		This field stores the local date at the terminal where the transaction occurred in the format MM/DD/YYYY, where MM represents the month, DD represents the day, and YYYY represents the year. If the field is not set, DCS sets the Local Date field to the local date when the transaction enters the DCS node. The field corresponds to ISO bitmap 13.
SETTLEMENT_DATE	DATE		This field stores the actual date of settlement of the transaction, in the format MM/DD/YYYY. The field corresponds to ISO bitmap 15.
CAP_DATE	DATE		This field contains the capture date of the terminal. This date may be different from the settlement date if the terminal is closed at a different time of day than the cutover of settlement dates. If the transaction is acquired by an ATM, this date is set by the ATM Server; otherwise, the Capture Date defaults to the transaction settlement date. The Capture Date field corresponds to ISO bitmap 17.
POS_ENTRY_CODE	NUMBER		Maps the transaction code with the POS entry code. This code describes the method used to capture the card data, and the PIN capability of the terminal.
POS_CONDITION_CODE	NUMBER		This parameter maps the transaction code with the POS condition code. This code identifies the condition under which the transaction occurred at the point of service.
POS_PIN_CAP_CODE	CHAR	1	This code indicates the maximum number of PIN characters that can be accepted by the Point of Service device.
POS_CAP_CODE	NUMBER		This parameter maps the transaction code with the POS capability code. The point-of-sale capability code describes the capability of the acquiring terminal for electronically reading the account number and expiry date from the card.
LIFE_CYCLE	NUMBER		This field is used (1) to indicate that the Authorization Request is a preauthorization Request, and (2) to indicate the specific amount of time, in seconds, for which the preauthorization will remain valid (i.e. the period of time for which the Issuer or its agent will guarantee or hold funds).

SHCLOG Table

Field Name	Type	Size	Description
ACQUIRER	CHAR	10	This field stores the BIN that identifies the acquiring institution of this transaction. IST/ Foundation uses this field to determine transaction routing.
ISSUER	CHAR	10	This field stores the BIN that identifies the issuing institution of this transaction. IST/ Foundation uses this field to determine transaction routing.
TRANSFEREE	CHAR	10	This field stores the BIN that identifies the issuing transferee of this transaction. IST/ Foundation uses this field to determine transaction routing.
ORIGINATOR	CHAR	10	BIN used to identify the switch. (For internal use only.) The value of the special BIN is 1010101010.
MEMBER_ID	CHAR	11	Stores Acquirer ID value. DCS uses this to check for duplicate transactions via the Europay rule inconjunction with the Forwarding ID value. Generally it's the member id of a institution assigned by external network (Visa, MasterCard, Europay etc.). This id may be used in field 32, 99, 100 in external ISO messages. MasterCard may use this value in field 2 in 8xx messages.
F_ID	CHAR	11	Stores Forwarding ID values. DCS uses this in conjunction with Acquirer ID to check for duplicate transactions via the Europay rule. This id may be used in field 33 in external ISO messages
TXNSRC	CHAR	10	The institution id of the institution where the transaction originated. For financial/ authorization/reversal messages, it's the acquiring institution. For messages not related to PAN, it may just be the institution that originates the transaction.
TXNDEST	CHAR	10	The institution id of the institution where the transaction is sent to. For financial/ authorization/reversal messages, it's the issuing institution. For messages not related to PAN, it may just be the institution that receives the transaction.
ALTERNATEACQUIRER	CHAR	10	BIN number of alternate acquirer.

SHCLOG Table

Field Name	Type	Size	Description
ENTITYID	CHAR	30	Any entity within acquiring domain to indicate more detailed information about where the transaction comes from. For example, merchant name, store name, BASEI, SMS etc. When switch is acquirer, its meaning should match the definition of acquiring entity in UDM. Note that separate acquiring BINS are required for SMS and Basel to differentiate between key encryption/decryption information.
ISS_ENTITYID	VARCHAR2	30	Any entity within the issuing domain to indicate more detailed information about where the transaction originated from. For example, branch id, sub network name, BASEI, SMS, etc.
CARDPRODUCT	CHAR	10	Refers to different card brand and different services/products. Normally it reflects different logos on the card. For example: VISA, MASTERCARD, CIRRUS, MAESTRO, INTERLINK, PLUS, CIBC...
MVV	CHAR	10	The Merchant Verification Value (MVV) in field 62.20 is carried in V.I.P. and Base II transactions to identify merchants that participate in the U.S. Select Merchant Fee (SMF) programs. The value is assigned by Visa and will be unique to the merchant. Only acquirers and issuers in the U.S. region will be affected Positions 82-91 in Draft data, TCR - 5 Payment Service Data, carry the MVV. Field 62.0 - CPS Fields Bitmap is a bitmap field that specifies which subfields are present. Bit 4 in byte 3 must be 1 to indicate that subfield 62.20 is present.
INVOICE_NUMBER	CHAR	6	Invoice Number
TRANS_ID	CHAR	15	Holds the value of the Transaction Identifier. DE62.2 will be used to link original authorization and financial requests to subsequent messages.
FPI	CHAR	3	Holds the value of the Fee Program Indicator for Visa. DE63.19 will contain the FRI. value that corresponds to the fee program assessed on the US or interregional purchase or credit voucher transaction.
TXN_START_TIME	NUMBER		Start time of the transaction for statistical purposes. Set when shc receives the request.

SHCLOG Table

Field Name	Type	Size	Description
TXN_END_TIME	NUMBER		End time of the transaction for statistical purposes. Set when shc logs the response.
DEVICE_CAP	NUMBER		Logs the device capability field in shcmsg.
RESPCODE	NUMBER		This field stores the response code that determines the disposition of the transaction. The Response field corresponds to ISO bitmap 39.
REASON_CODE	NUMBER		Value in this field is based on the application. Reason codes are mapped to response codes. For a list of reason codes, see Appendix B.
REVCODE	NUMBER		Identifies the type of or reason for the reversal.
SHCERROR	NUMBER		This is a code indicating the disposition of an internal process. It also indicates the IST/Switch respond to a transaction message.
SAF	NUMBER		This field indicates whether the transaction was processed by IST/Foundation standin processing. A zero (0) in this field indicates that the transaction was authorized or denied by the host system. Any other value indicates that IST/Foundation performed standin authorization. The flag is set whenever an issuer communication link is down.
ORIGMSG	NUMBER		For reversal transactions, this field holds the original message type. This allows successive transaction messages to be logically linked.
ORIGFLIPPEDMSG	NUMBER		Set as the original message type for inbound responses when the message type in the request to the network is flipped.
ORIGTRACE	NUMBER		For reversal transactions, this field holds the original trace number. This allows successive transaction messages to be logically linked.
ORIGDATE	DATE		For reversal transactions, this field holds the original local date. This allows successive transaction messages to be logically linked.
ORIGTIME	NUMBER		For reversal transactions, this field holds the original local time. This allows successive transaction messages to be logically linked.

SHCLOG Table

Field Name	Type	Size	Description
MERCHANT_TYPE	NUMBER		Merchant Type. Code used to categorize a merchant based on the type of business conducted. This type is implied through the MCC
ACQ_COUNTRY	NUMBER		This code identifies the country of the acquiring institution, that is, the financial organization responsible for the merchant or ATM.
REFNUM	CHAR	12	This field stores the reference number assigned by the acquirer. This field may be omitted for some transactions, depending on the acquirer's specifications. The field corresponds to ISO bitmap 37.
AUTHNUM	CHAR	6	This is the authorization code provided by the issuer when a transaction is approved.
TERMID	CHAR	8	This field identifies the terminal from which the message came. The field corresponds to ISO bitmap 41.
ACCEPTORNAME	CHAR	40	This field stores the acceptor name and location. This field is required for most transactions and is stored in a format ready for printing. The field corresponds to ISO bitmap 43.
TERMLOC	CHAR	25	Code that identifies the card acceptor defining the point-of-service in both local and interchange environments. The field corresponds to ISO bitmap 42.
ADDRESPONSE	CHAR	25	Additional Response. User defined buffer. Internal use only. For example: in the case of open account relationship (OAR) transactions initiated at ATM terminals, the Additional Resp field contains the file name of the OAR screen template. The field corresponds to ISO bitmap 44.
ACCTNUM	CHAR	42	This field stores to and from accounts used for a transaction. This information is not always present. When present, the account numbers are formatted as from-accountto-account, where the Ì character acts as a separator. The numbers are optional and, if present, correspond to the TO and FROM account types in the Processing Code field of the transaction message. The field maps to ISO bitmap numbers 102 and 103.
BRANCH	NUMBER		Branch Id where the transaction was acquired.

SHCLOG Table

Field Name	Type	Size	Description
SERIAL_1	NUMBER		(For internal use only.)
SERIAL_2	NUMBER		(For internal use only.)
STOREID	NUMBER		Store where the transaction was processed. (Used by POS.) DCS initializes the field storeid from the merchant database records.
LANE	NUMBER		Identifies the lane number of a store. (Used by POS.) DCS initializes the field lane from the merchant database records.
TERMINAL_TRACE	NUMBER		This is a number used to sequence a transaction from a terminal.
CHECKER_ID	NUMBER		User defined. (Used by POS.) Typically, the checker_id identifies the cashier at the point of sale.
SUPERVISOR	NUMBER		User defined. (Used by POS.)
SHIFT_NUMBER	NUMBER		User defined. (Used by POS.)
BATCH_ID	NUMBER		Used to group transactions. (Used by POS.) DCS uses the batch_id field when processing electronic draft capture (EDC) transactions and transactions which are stored by the terminal manager in the termtot table.
DEVICE_DEVCAP	NUMBER		Indicator for recurrent payment support is set if both shcmmsg. device_devcap & SH_DEVICE_POSCOND_Recurrent are True.
SHC_DEVCAP	NUMBER		Used by programmers to set up flags
FORMATTER_DEVCAP	NUMBER		Used by programmers to set up flags
AUTH_DEVCAP	NUMBER		Used by programmers to set up flags
FILLER1	CHAR	50	Text Message
FILLER2	CHAR	50	Text Message
FILLER3	CHAR	50	Text Message

SHCLOG Table

Field Name	Type	Size	Description
FILLER4	CHAR	50	Text Message
ISSUER_DATA	CHAR	128	Stores agent/formatter specific data that comes from inbound response. This data may be necessary for processing that happens later. For example, settlement, clearing and so on.
ACQUIRER_DATA	CHAR	128	Stores agent/formatter specific data that comes from inbound response. This data may be necessary for processing that happens later. For example, settlement, clearing and so on.
NEW_AMOUNT_EQUIV	NUMBER	26,8	This field contains the actual amount dispensed in the issuer's currency in the event of a partial reversal.
ACQ_AVAL_BALANCE	NUMBER	26,8	Available balance in acquirer's currency.
ACQ_LEDGER_BALANCE	NUMBER	26,8	Ledger balance in acquirer's currency.
SETL_AVAL_BALANCE	NUMBER	26,8	Available balance in settlement currency.
SETL_LEDGER_BALANCE	NUMBER	26,8	Ledger balance in settlement currency.
AVAL_BALANCE_TYPE	NUMBER		This field contains the amount type of the aval_balance field. If it is empty, aval_balance is the available balance. Otherwise, aval_balance is the other balance specified in the following balance type table.
LEDGER_BALANCE_TYPE	NUMBER		This field contains the amount type of the ledger_balance field. If it is empty, ledger_balance is the ledger balance. Otherwise, ledger_balance is other balance specified in the following balance type table.
NEW_SETL_FEE	NUMBER	26,8	Amount of the fee applied to the transaction in the settlement currency.
TXN_AMOUNT	NUMBER	26,8	This field is used during customization.
TXN_NEW_AMOUNT	NUMBER	26,8	This field is used during customization.
TXN_CURRENCY_CODE	NUMBER		This field contains the ISO currency code of the original transaction in the device.

SHCLOG Table

Field Name	Type	Size	Description
TXN_CONV_RATE	NUMBER	26,8	Rate used to convert settlement amount to amount in txn_amount.
TXN_CONV_DATE	DATE		Effective date of txn_conv_rate.
CH_AMOUNT	NUMBER	26,8	This field identifies the transaction amount in the cardholder's billing currency.
CH_NEW_AMOUNT	NUMBER	26,8	When the actual transaction amount differs from the authorized amount, New CH Amount may be used to store the real transaction amount in the currency of the cardholder's account. For example, a Visa cardholder withdraws \$100 from an ATM. The transaction is approved, but the ATM only has \$50 in its cash drawer. The ATM sends a partial reversal to the Visa network which converts the outstanding \$50 to the currency of the cardholder's account and sends the amount to the issuer. If the issuer is using IST/Switch, the switch stores the amount in the currency of the cardholder's account into the ch_new_amount field in the shcmsg structure.
CH_CURRENCY_CODE	NUMBER		This field identifies the ISO currency code of the cardholder's billing currency.
CH_CONV_RATE	NUMBER	26,8	This field identifies the wash rate of the ch_currency_code with respect to the issuer currency.
CH_CONV_DATE	DATE		Effective date of cardholder currency conversion date.
LEDGER_BALANCE	NUMBER	26,8	Indicates the ledger balance in issuer/cardholder currency.
SLOT_NUM	NUMBER		This field is for internal use.
DEVICE_FEE	NUMBER	26,8	Indicates the fee that is incurred due the usage of the device.
SHC_DATA_BUFFER	CHAR	254	This field is casted to shc_data structure to store additional information
CARD_SEQNO	NUMBER		Card sequential number. Identifies the card used when multiple cards are associated with a single account.
ALPHARESPONSECODE	CHAR	3	Indicates the unchanged response code from the issuer.
CHIP_TYPE	CHAR	1	Processing type, early or full.

SHCLOG Table

Field Name	Type	Size	Description
CHIP_INDEX	CHAR	20	Index into the shcchiplog table.
PROCESSOR_BUSDAY	DATE		Indicates the date of the transaction at processor system
SEQ_TRACE_NO	NUMBER		This field is reserved for internal use.

SHCLOG_VFRS

This table stores Fraud Reporting System (FRS) message specific information that can not be logged in the shclog table. This table is linked to the shclog table by field shclog_idx.

SHCLOG_VFRS Table

Field Name	Type	Size	Description
SHCLOG_IDX	CHAR	20	The index field linking shclog_vfrs table to the shclog table.
EXPR_DATE	SMALLINT		The card expiry date.
FRAUD_INFO	VARCHAR2	256	Fraud Information.
POS_GEO_LOC	CHAR	19	The geographical location of the POS.
NETCODE	NUMBER		The network code.
RCVG_INST_ID	CHAR	10	The identification of the receiving institution.
ADDTL_TRACE_DATA	CHAR	24	Additional Trace Data. Acquirer or issuer can use information in this field to track the transaction they submitted
SUPPORT_INFO	VARCHAR2	255	Supporting information. It logs the data from the original fraud transaction

SHCMERCHANT

The SHCMERCHANT table is used to store information about blocked terminals/merchants details received from Fraud Navigator. Based on this stored information, IST Switch will block transactions to these terminal/merchants.

SHCMERCHANT Table

Field name	Type	Size	Description
INSTITUTION	VARCHAR2	10	Unique Institution ID
ACQ_ENTITYID	VARCHAR2	30	Any entity within acquiring domain to indicate more detailed information about where the transaction comes from. For example merchant name.
ACCEPTOR_ID	CHAR	25	Card Acceptor ID
TERMINAL_ID	CHAR	8	Terminal ID . The terminal which is used to block the transactions.
RESPCODE	NUMBER		Stores the response code that determines the disposition of the transaction. This field corresponds to ISO bitmap 39.
TRANDATE	DATE		Used to store the transaction date.
TRANTIME	NUMBER		Used to store the transaction time in HHMMSS.
DUARTION	NUMBER		Used to specify the blocking interval or time of a merchant/terminal.

VISA_SPECIFIC_DATA

This table is created to store pin_block and track data, which are not log in shclog due to security reason, from preauth transaction, so that they can be retrieved in preauth completion transaction.

VISA_SPECIFIC_DATA Table

Field Name	Type	Size	Description
PAN	CHAR	19	Personal Account Number.
REFNUM	CHAR	12	This field stores the reference number assigned by the acquirer. This field may be omitted for some transactions, depending on the acquirer's specifications. The field corresponds to ISO bitmap 37.
PINBLOCK	CHAR	16	Personal Identification Number(PIN) Data, corresponding to ISO field DE52. For visa transactions, it must be encrypted and formatted as a block of 16 hexadecimal digits.
TRACK	CHAR	79	This field is used in original authorization and financial requests, and preauth completion transactions
LOCAL_DATE	DATE		This field stores the actual date of settlement of the transaction, in the format MM/DD/YYYY.
TID	CHAR	15	It is a Visa-generated identifier , unique for each original authorization and financial request. The identifier links original messages to subsequent messages. In visa transactions, it is stored in DE62.2

BINROUTE

Switch(shc) will use the mailbox and port configured in binroute table to decide the routing instead of using mailbox and port configured in shcbin table. Shc after deciding to which shcbin the message will be sent, then will try to find a suitable binroute for that bin from binroute table in the shared memory.

BINROUTE Table

Field Name	Type	Size	Description
INSTITUTION ID	VARCHAR	10	Indicates the institution to which the ATM belongs.
USERBIN ID	CHAR	10	Identifies a shcbin record in shcbin table with institutionID. In GUI, user should choose the institutionID and userbinID from a dropdown list of bins.
NODE	VARCHAR	30	Indicates connection of the node.
MAILBOX	VARCHAR	30	Indicates the mailbox name of the node.
PORT	VARCHAR	31	Indicates the port name of that node.
CFG	VARCHAR	31	Indicates other configuration flags, for future use. The configuration flags are usually a flag that has a value like 'Y', 'N' etc. This is similar to the bincfg in shcbin table.
INIT_STATUS	CHAR	1	Indicates the initial status. This determines if the binroute should be brought up on startup or wait for an initiated sign-on (from a given direction). Valid values are U for up and D for down. This only works for local node. Initially, all the binroute that are on remote node are down. Once the newly brought up node is ready for processing, it will exchange the binroute status with other nodes, then the remote binroute status will be updated.

BINROUTE Table

Field Name	Type	Size	Description
ECHO	CHAR	1	Sends echo for the route. Valid values: D - When the connection is down U - When the connection is up A - Echos always N - Never sends echo C - Echos when binroute is down and port is up.
GROUPTYPE	CHAR	1	Indicates how to choose the ports. Valid values is R which means round robin. If the site is not running distributed Switch but wants to support round robin to the networks. This could be defined at the binroute as well.
PRIORITY	INT		Indicates the priority of the binroute. In general, the lower priority binroute is the backup binroute. The priority is a number. The bigger number stands for lower priority. if a connection has a lesser priority it is only used if the primary connection is down. When more than one binroute have same priority, the local binroutes will be considered higher priority.
MISC	VARCHAR	39	Indicates miscellaneous information for future use.
INST_PROFILE_ID	INT		This ID is used to link the binroute entry with inst_profile entry.
BASE_PORT_NAME	VARCHAR	30	Indicates whether the singleton control is required for the binroute entry. If base_port_name is filled, shcecho will use singleton control for the binroute entry. The key to the singleton is " echol "+" base_port_name ". For example, if the base_port_name is " VisaRoute ", the singleton key is " echolVisaroute ". When an shcecho tries to create echo messages for key " echolVisaroute ", shcecho will try to get a lock for this key for a period of time. If lock is acquired, the shcecho will create echo messages for the binroute entry. If not, shcecho will skip the entry. The field in ist_singleton that stores the keys are task_keys.
BLRNODE	VARCHAR	30	Indicates the balancer node that BIN route is associated. This marks all routes associated with one balancer node when the balancer node is down (crashed or shutdown).

Index

A

A_DESC	90
A_STRCODE	90
ACCEPTORNAME	21, 154, 169, 228, 267
ACCOUNT_ID	81
ACCT_NUM	37
ACCT_NUM2	37
ACCT_PPLAN_ID	119
ACCTNUM	228, 267
ACCUMU_GROUP	197
ACQ_AVAL_BALANCE	229, 269
ACQ_BUS_DATE	197
ACQ_CONV_DATE	223, 261
ACQ_CONV_RATE	222, 261
ACQ_COUNTRY	170, 227, 267
ACQ_CUR_CODE	197
ACQ_CURRENCY_CODE .	81, 154, 169, 222, 261
ACQ_DISCNT_AMT	198
ACQ_ENTITY	110
ACQ_ENTITY_ADDRESS	120
ACQ_ENTITY_ID	196
ACQ_FEE_AMT	198
ACQ_INST_ID	125
ACQ_LEDGER_BALANCE	229, 269
ACQ_MINAMOUNT	234
ACQ_PRNCPL_AMT	198
ACQ_RECON_DATE	198
ACQ_RECON_FLAG	198
ACQ_RECON_TIME	198
ACQ_SRCHGR_AMT	198

ACQBIN	247
ACQKEK	247
ACQKEKCHK	247
ACQKEKCNT	250
ACQKEKSTAT	248
ACQKME_LEN	251
ACQKME1	248
ACQKME1CHK	248
ACQKME1CNT	250
ACQKME1STAT	249
ACQKME2	248
ACQKME2CHK	248
ACQKME2CNT	250
ACQKME2STAT	249
ACQKME3	248
ACQKME3CHK	248
ACQKME3CNT	250
ACQKME3STAT	249
ACQKMEIDX	248
ACQKPE_LEN	251
ACQMAC_LEN	251
ACQMAC1	246
ACQMAC1CHK	246
ACQMAC1CNT	250
ACQMAC1STAT	249
ACQMAC2	246
ACQMAC2CHK	246
ACQMAC2CNT	250
ACQMAC2STAT	249
ACQMAC3	247
ACQMAC3CHK	247
ACQMAC3CNT	250

ACQMAC3STAT	249	ADDTL_TRACE_DATA	271
ACQMACIDX	246	ADM_MSG_BUF	231
ACQPIN1	245	ADVANCE_LINE	65
ACQPIN1CNT	246, 250	ADVANCE_LINE_USED	66
ACQPIN1STAT	249	ADVICE_REASON	201
ACQPIN2	246	AFTER_HOUR_DEP	31
ACQPIN2CNT	246, 250	AGENT_NR	149, 167
ACQPIN2STAT	249	ALLOWANCE	121
ACQPIN3	247	ALLW_CARD_SCHEME	121
ACQPIN3CHK	247	ALLW_CURR	121
ACQPIN3CNT	250	ALLW_FLOOR_LIM	125
ACQPIN3STAT	249	ALLW_ID	111, 121, 122, 123, 125, 179
ACQPINIDX	245	allw_id	122, 124
ACQUIRER	82, 84, 149, 154, 169, 186, 196, 201, 224, 264	ALLW_LANG	122
ACQUIRER_DATA	174, 229, 269	ALLW_MCC	123
ACT_COUNT	93	ALLW_POS_FORMAT	124
ACT_DATE	93	ALPHARESPONSECODE	270
ACT_TIME	93	ALT_MERCHANT_ID	126
ACTION_STRING	103	ALT_TAX_ID	116
ACTIVITY	107	ALTERNATEACQUIRER	174, 225, 264
ACTUAL_START_DATE	111, 179	ALW_NON_QUAL_UPGRD	111
ADD_ITEM	152	ALW_RECLASS_UPGRD	112
ADD_TOTAL	20	AMOUNT	34, 56, 81, 153, 168, 221, 260
ADDON	71	AMOUNT_EQUIV	222, 261
ADDR1	257	AMOUNT_HI	64
ADDR2	257	AMOUNT_LOW	64
ADDRESPONSE	228, 267	AMOUNT_USED	67
ADDRESS_ID	78, 120, 131, 149, 167	AMT_AUTH	202
ADDRESS_ROLE	120	AMT_AUTH_REV	202
ADDRESS1	131	AMT_CREDIT	202
ADDRESS2	131	AMT_CREDIT_REV	202
ADDRESS3	132	AMT_DEBIT	202
ADDRESS4	132	AMT_DEBIT_REV	202
		AMT_NETSET	202

APP_DR	187
APP_ICHG_PROFILE	145, 240
APP_PCT	187
APP_TXN_COUNTER	144, 240
ARPC_CRYPTOGAM	240
ARPC_RESPCODE	240
ARRIV_TIME	143
ATH_NUM_DB	176
ATM_A_RECON_DAY	207
ATM_A_RECON_TIME	207
ATM_BUS_DAY	206
ATM_FCUTOVER_TIME	207
ATM_I_RECON_DAY	208
ATM_I_RECON_TIME	208
ATM_ID	50
ATMEJCAPTURE	39
ATMLOG_CTRL	47
AUTH_BY_LOC_IND	114
AUTH_DATE	50, 52
AUTH_DEVCAP	174, 229, 268
AUTH_TIME	50, 52
AUTHDATE	204
AUTHFLAG	234
AUTHNUM	81, 154, 169, 204, 227, 267
AUTHSERVER	234
AVAILABLE_BALANCE	65
AVAILDATE	38
AVAILTIME	38
AVAL_BALANCE	222, 260
AVAL_BALANCE_TYPE	230, 269
AVS_RESULTCODE	155, 170

B

BANK_CD	257
BANKNAME	236
BAR_ACCESS	179
BASE_PORT_NAME	275
BATCH_ID	146, 151, 153, 168, 175, 229, 268
BATCH_IDX	177
BATCH_NR	165
BATCH_STATUS	177
BDK_LEN	181, 184
BEGIN_DATE	27
BEGIN_TIME	27
BFACTOR	97
BILLING_TYPE	113
BIN	87, 88, 90, 91, 96, 103, 189, 245
BIN_CFG	236
BIN1	187
BIN1_APP_CR	187
BIN1_ISSDENY_CR	187
BIN1_NETFAIL_CR	187
BIN2	187
BIN2_APP_CR	187
BIN2_ISSDENY_CR	187
BIN2_NETFAIL_CR	187
BIN3	188
BIN3_APP_CR	188
BIN3_ISSDENY_CR	188
BIN3_NETFAIL_CR	188
BIN4	188
BIN4_APP_CR	188
BIN4_ISSDENY_CR	188
BIN4_NETFAIL_CR	188

BIN5	188
BIN5_APP_CR	188
BIN5_ISSDENY_CR	188
BIN5_NETFAIL_CR	188
BIN6	188
BIN6_APP_CR	188
BIN6_ISSDENY_CR	188
BIN6_NETFAIL_CR	188
BIN7	188
BIN7_APP_CR	189
BIN7_ISSDENY_CR	189
BIN7_NETFAIL_CR	189
BINRANGE	236
BINTYPE	233
BIRTH_DATE	257
BITMAP	240
BLOCK	135
BLOCK_CODE	95
BLOCK_IND	149
BLRNODE	275
BRANCH	92, 228, 267
BRANCH_ID	69, 78
BRANCH_NAME	69
BUSINESS_OWNERTYPE	115
BUY_RATE	90
BUY_SPREAD	91

C

CAL_ACTIVITY_ID	111
CALLBACK	103
CAMMAILBOX	236
CAP_DATE	37, 154, 168, 224, 263
CAP_NBR	116

CAPABILITIES	161
CAPTURE_TYPE ..	146, 151, 167, 177
CARD_AUTH_REL_IND	238
CARD_AUTH_RES_CODE	238
CARD_CAP_CAPAB	157
CARD_CATEGORY	73
CARD_INPUT_CAPAB	156
CARD_LIFE	72
CARD_PREFIX	72
CARD_PRODUCT	197
CARD_RENEWAL_FEE	72
CARD_RENEWAL_IND	73
CARD_RPLCMNT_FEE	72
CARD_SCHEME ...	123, 126, 127, 134, 138, 155, 170
card_scheme	121, 124
CARD_SCHEME_NAME	127
CARD_SEQ_NR	145
CARD_SEQNO	170, 270
CARD_UPDATE	158
CARDALERT	205, 235, 237
CARDINDICATOR	94
CARDNAME	232
CARDPRODUCT	213, 244, 265
CARDS_RETAIN	31
CARDTYPE	91, 92
CARRIER_CD	143
CASH_BACK	154, 169, 222, 261
CASH_CUR_BAL	29
CASH_DEC	29
CASH_INC	29
CASH_OUT	29
CASH_PREV_BAL	29
CASH_START_BAL	29

CASHBACK_AMTG	149	CHECKEXP	235
CASSETTE_CFG_ID	25, 28, 30, 35	CHECKHOT	235
CASSETTE_CFG_TYPE	30	CHECKMOD10	235
CASSETTE_FITNESS	37	CHECKPIN	235
CASSETTE_NBR	28, 29, 35	CHECKSCODE	235
CAT_LEVEL	158	CHIP_COND_CD	145
CCARD_CRYPT_TRACE	145, 239	CHIP_COND_CODE	238
CCARD_PA_TRACE	239	CHIP_INDEX	170, 238, 271
CCARD_PURCH_TRACE	239	CHIP_TYPE	270
CCARD_SCH_CRYPT	240	CHK_DIGIT	181
CCPS_TXN_IND	238	CITY	131, 257
CCSTLMT	235	CLEARING_FLAG	126
CERT_LEVEL	51, 58	CLERK_ID	84
CERT_STATUS	58	CLIENT_ID	106, 108
CERT_TYPE	51, 58	CLOSE_DATE	147, 165, 167
CERT_VERSION	50, 58	CLOSE_FLAG	147, 151
CERTIFICATE	50, 58	CLOSE_TIME	147, 165, 167
CERTIFICATE_REQ	59	CLOSEHR	136
CFG	274	CMS_FUNC	93
CH_AMOUNT	81, 230, 270	CMS_MODE	93
CH_AUTH_CAPAB	157	CNTRY_CODE	127, 132
CH_AUTH_ENTITY	140, 172, 254	cntry_code	178
CH_CONV_DATE	231, 270	CNTRY_CODE_ALPHA2	127
CH_CONV_RATE	231, 270	CNTRY_CODE_ALPHA3	127
CH_CURRENCY_CODE	231, 270	CNTRY_NAME	127
CH_NEW_AMOUNT	230, 270	CODE	75
CHAIN_NR	149, 167	COM_KEY_LEN	182
CHARACTER_SET_IND	117	COM_KEY_NOW	182
CHECK_CLASS	103	COM_LOAD_DATE	182
CHECK_NR	256	COM_LOAD_TIME	182
CHECK_STRING	103	COM_OFF_KEY_NOW	182
CHECK_TYPE	255	COM_OFF_LOAD_DATE	182
CHECKCVV	235	COM_OFF_LOAD_TIME	182
CHECKER_ID	228, 268	COMM_CARD_REQ_IND	140, 171, 253

COMM_CARD_RESP_IND	140, 171, 253	COND7	104
COMM_CRD_DATA_IND	139, 170, 252	COND8	104
COMPANY_ID	119	COND9	104
COMPANY_TYPE	113	CONFIG	209
COND_CD	159	CONFIGID	37
COND1	103	CONSENT_DATE	70
COND10	104	COUNT	56
COND11	104	COUNT_USED	68
COND12	104	COUNTER_1	215
COND13	104	COUNTER_10	216
COND14	104	COUNTER_11	216
COND15	104	COUNTER_12	216
COND16	104	COUNTER_13	216
COND17	104	COUNTER_14	216
COND18	104	COUNTER_15	216
COND19	104	COUNTER_16	216
COND2	104	COUNTER_17	217
COND20	104	COUNTER_18	217
COND21	105	COUNTER_19	217
COND22	105	COUNTER_2	215
COND23	105	COUNTER_20	217
COND24	105	COUNTER_3	215
COND25	105	COUNTER_4	215
COND26	105	COUNTER_5	215
COND27	105	COUNTER_6	215
COND28	105	COUNTER_7	215
COND29	105	COUNTER_8	216
COND3	104	COUNTER_9	216
COND30	105	COUNTRY	127, 132
COND31	105	COUNTRY_CD	257
COND32	105	COUNTRY_CODE	236, 245
COND4	104	COUNTY	128, 132
COND5	104	COUNTY_ABBREV	128
COND6	104	COUNTY_CD	128, 132

COUPON_NR	143
CPS_ELIGIBLE	180
CR_DR_IND	81
CRC_AMT_ADJ	148
CRC_AMT_ADJG	149
CRC_AMT_CR	148, 176
CRC_AMT_CRG	149
CRC_AMT_DB	148, 176
CRC_AMT_DBG	149
CRC_AMT_NET	148
CRC_AMT_NETG	149
CRC_NUM_ADJ	148
CRC_NUM_ADJG	149
CRC_NUM_CR	148, 176
CRC_NUM_CRG	149
CRC_NUM_DB	148, 176
CRC_NUM_DBG	148
CREATED	237
CREATION_DATE	58, 59, 60, 111
CREATION_TIME	58, 59, 60
CRYPTO_AMOUNT	144, 239
CRYPTO_CB_AMOUNT	145, 239
CRYPTO_CURR_CODE	145, 239
CRYPTO_TXN_TYPE	144, 239
CRYPTO_VERSION	144, 239
CRYPTOGRAM	96, 144, 240
CS_MERCHANT_ID	126
CS_TIER_MERCH_ID	126
CURR_CODE	127, 129
CURR_CODE_ALPHA2	129
CURR_CODE_ALPHA3	129
CURR_EXPONENT	129
CURR_NAME	129
CURR_PATTERN	128

CURRENCY	25, 28, 34, 56, 89, 90, 91
CURRENCY CODE	122
CURRENCY NAME	122
CURRENCY_CODE	66, 79, 80, 129, 149, 167, 201, 236
CURRENCY_NAME	89
CURRENCY_ROLE	122
CURRPINFALS	55
CUST_REFERENCE_ID	141, 172
CUST_VAT_REG_NR	141, 172
CUSTOMER_TYPE	74
CUT_NR	164, 165
CUTOFF	235
CUTOVERTYPE	235
CVR	144, 239
CVV_ELIGIBLE	157, 158
CVV_RES_CODE	238
CVVDATE	235

D

DATE	106
DATE_FROM	164
DATE_PATTERN	128
DATE_TO	164
DAY_RATE	139, 171, 253
DAYS_TO_HOLD	114
DBC_AMT_ADJ	148
DBC_AMT_ADJG	148
DBC_AMT_CR	147, 176
DBC_AMT_CRG	148
DBC_AMT_DB	147, 175
DBC_AMT_DBG	148
DBC_AMT_NET	148
DBC_AMT_NETG	148

DBC_NUM_ADJ 148
 DBC_NUM_ADJG 148
 DBC_NUM_CR 147, 176
 DBC_NUM_CRG 148
 DBC_NUM_DB 147, 175
 DBC_NUM_DBG 148
 DEBIT_CREDIT 235
 DEC_TABLE 43
 DEF_CLASS 251
 DEF_FROM_ACCT 234
 DEF_INDEX 251
 DEF_POSTING_ENTITY 119
 DEF_TO_ACCT 235
 DEFAULT_CURR_CD 179
 DEFAULT_LANG_CODE 72
 DEFAULT_MCC 119, 180
 DEFAULT_PKVI 72
 DENOMINATION 28
 DENOMINATION_ID 28
 DEPOSIT_AMTG 149
 DEPOSIT_SIGN 149
 DEPT_DATE 143
 DEPT_TIME 143
 DERI_KEY_IDX 144, 238
 DESC 191
 DESC_LONG 191
 DESCRIPTION .. 30, 35, 44, 53, 72, 78,
 85, ... 86, 88, 103, 121, 134, 136,
 232, 244
 DEST_CITY_CD 143
 DEST_COUNTRY_CD 141, 172
 DEST_ZIP_CD 140, 172, 254
 DESTINATION 194, 195, 244
 DEVICE_CAP 154, 169, 226, 266

DEVICE_DEVCAP .. 154, 169, 229, 268
 DEVICE_FEE 270
 DEVICE_FITNESS 37
 DEVICE_TYPE 84, 159, 160, 197
 DEVICETYPE 186, 214
 DIRECTION 166
 DISCOUNT_AMT 140, 172, 254
 DISPENSE_CFG_ID 34, 35
 DISPENSE_TABLE_ID 25, 34, 35
 DISPLAY_LENGTH 138
 DNN_INVOICE_NBR 116
 DRIVER_LIC_NR 257
 DUKPT_BDK_NOW 181, 183
 DUN_NBR 116
 DURATION 140, 171, 253
 DUTY_AMT 140, 172, 254

E

E_DESC 90
 E_STRCODE 90
 ECHO 275
 ECHOTEST 236
 ECONOMIC_AREA_IND 128
 EFFECTIVE_DATE 120
 EKEY 75
 EMAIL_ADDRESS 132
 EMBOSSNAME_1 94
 EMERGENCY_ISSUE_FEE 72
 EMERGENCY_REISSUE 94
 EMULATION 26
 EMV_IDENTIFIER 37
 ENABLE_PROC_REQ 193
 END_DATE 27, 46, 139, 171, 253

END_TIME	27, 46
ENDSEQUENCE	40
ENTITY_ID	65, 67, 68, 70, 71, 72, 74, 76, 78, 83, 94, 110, 120, 126, 146, 162, 167, 175, 206, 244
ENTITY_LEVEL	129
ENTITY_LEVEL_IND	110, 129
ENTITY_NAME	110
ENTITY_STATUS	111
ENTITY_TYPE	67, 68, 76, 78, 86, 129
ENTITYID	226, 265
ENTRY_TYPE	256
EPP_PK_SIGNATURE	52
EPP_PUBLIC_KEY	52
EPP_SERIAL_NUM	52
ERROR_TYPE	162
ESTABLISH_ALPHA_ID	117
EU_DECIMAL	89
EVENTID	194, 195
EXI001	62
EXI002	62
EXI003	63
EXP_START_DATE	111
EXPIR_DATE	257
EXPIRY_DATE	153, 168
EXPIRYDATE	70, 94
EXPIRYOFFSET	43
EXPR_DATE	271
EXT_DATA	170
EXT_DATE	155
EXT_ID_DESC	211
EXT_PK_INSTID	52, 61
EXT_PK_SIGNATURE	61
EXT_PK_VERSION	52, 61

EXTERNAL_ENTITY_ID	111
EXTERNALID	211
EXTRA_CHARGES	139, 171, 253
EXTRACT_DATE	164, 165
EXTRACT_FLAG	147, 167
EXTRACT_TIME	164, 165

F

F_ID	174, 211, 225, 264
FAILEDPIPS	237
FARE_BASIS_CD	143
FAULT	27, 38
FAX	132
FEE	223, 262
FEE_CR_PROCESSING	202
FEE_CR_TRANSACTION	202
FEE_DB_PROCESSING	202
FEE_DB_TRANSACTION	202
FIELD_DATA	163
FIELD_NAME	133, 163
FIELD_NUMBER	163
FIELD_OFFSET	163
FIELD_VALUE	133
FIELD_VALUE_DESC	133
FIELD1	241
FIELD10	241
FIELD11	242
FIELD12	242
FIELD13	242
FIELD14	242
FIELD15	242
FIELD16	242
FIELD17	242

FIELD18	242	FILE_VERSION	245
FIELD19	242	FILENAME	40
FIELD2	241	FILLER1	229, 268
FIELD20	242	FILLER2	229, 268
FIELD21	242	FILLER3	229, 268
FIELD22	242	FILLER4	229, 269
FIELD23	242	FILM_RETAIN	31
FIELD24	242	FINTERVAL	193
FIELD25	242	FIRST_AUTH_AMT	140, 171, 253
FIELD26	242	FIT	41
FIELD27	242	FIT_ENTRY_ID	41, 42
FIELD28	242	FIT_LIST_ID	25, 41, 44
FIELD29	242	FLAG	57
FIELD3	241	FLAG1	36
FIELD30	243	FLAG2	36
FIELD31	243	FLAG3	36
FIELD32	243	FLAGS	137, 200, 247
FIELD33	243	FLAT_FEE	57
FIELD34	243	FLEET_ID_NR	140, 172, 254
FIELD35	243	FLEET_RESTRE	140, 172, 254
FIELD36	243	FLEET_TYPE	140, 172, 254
FIELD37	243	FLIGHT_NR	143
FIELD38	243	FLIPPED_MSGTYPE	174, 259
FIELD39	243	FLOOR_1	234
FIELD4	241	FLOOR_2	234
FIELD40	243	FLOOR_3	234
FIELD5	241	FORMAILBOX	194, 195
FIELD6	241	FORMAT	135, 177
FIELD7	241	FORMATTER_DEVCAP ..	155, 170, 229, 268
FIELD8	241	FORWARD_INST	200
FIELD9	241	FPERCENT	193
FILE_DATE	245	FPI	265
FILE_NAME	164, 165, 244	FRAUD_INFO	271
FILE_STATUS	164		

FREIGHT_AMT 140, 172, 254
 FRMVER 62
 FULLFILESIZE 193
 FUNC_FLAGS 24, 45
 FUNCTION_CODE 47, 185

G

GEO_LOC 21
 GEOCODE 132
 GLOBAL_SEQ_CTRL 133
 GLOBAL_VALUE_CTRL 133
 GOOD_BATCHES 164
 GOSERVICE 19, 45
 GROUP 44
 GROUP_NAME .19, 27, 29, 30, 31, 32,
 35, 36, 40, 45, 46, 47, 50, 52, 54,
 56, 57, 63, 64
 GROUP_NR 177
 GROUP_NUM 45
 GROUPTYPE 275
 GUIFLAG 191

H

H_LOCATION 21, 22
 HASH_AMTG 149, 167
 HASPIN 214
 HDL_ACK 25
 HEADING1 189
 HEADING2 189
 HIGHBIN 244
 HOST_CURRENCY_CODE 90
 HOST_TXN_CODE 88
 HOT_MERCHANT_FLAG 112

HOUR_ID 136, 179
 HRTINT 62

I

IATA_CD 118
 ICC_CARD_PREFIX 72
 ICC_INDICATOR 72
 ID 212
 ID_NUMBER 74
 ID_TYPE 74, 257
 IFD_DATA_1 258
 IFD_DATA_2 258
 INDIRECT_STATE 41
 INDUSTRY_DATA_IND ...139, 170, 252
 INFO 137
 INFO_REFUSAL_IND 114
 INIT_STATU 274
 INIT_STATUS 212
 INLOAD 182
 INQUIRY_NUM 176
 INST_CURR_CODE 130
 INST_FYEAR_ST_DT 130
 INST_ID 211
 INST_NAME 130
 INST_PROFILE_ID 275
 INST_TYPE 130
 INSTITUTION 130
 INSTITUTION ID 274
 INSTITUTION_ID 19, 27, 28, 29, 30, 31,
 32, 34, 35, 36, 40, 41, 42, 44, 45,
 46, 47, 50, 52, 53, 54, 55, 56, 57,
 58, 59, 60, 63, 64, 65, 67, 68, 69,
 70, 71, 72, 74, 76, 78, 80, 81, 83,
 84, 88, 94, 96, 103, 110, 120, 121,
 122, 123, 124, 125, 126, 127, 129,

130, 131, 146, 162, 164, 165, 167, 175, 178, 181, 182, 184, 185, 192,206, 215, 232, 245	ISSKEKSTAT	249
institution_id	ISSKME_LEN	251
INSTITUTION_TYPE	ISSKME1	248
INSTOFFSET	ISSKME1CHK	248
INSTRUMENT	ISSKME1CNT	251
INTERNAL_UNIT	ISSKME1STAT	249
INTERVAL	ISSKME2	248
INVOICE_BATCH	ISSKME2CHK	248
INVOICE_NR	ISSKME2CNT	251
INVOICE_NUMBER	ISSKME2STAT	249
INVOICE_SUB_CD	ISSKME3	248
ISS_BUS_DATE	ISSKME3CHK	248
ISS_CONV_DATE	ISSKME3CNT	251
ISS_CONV_RATE	ISSKME3STAT	249
ISS_CUR_CODE	ISSKMEIDX	248
ISS_CURRENCY_CODE	ISSKPE_LEN	251
ISS_DISCNT_AMT	ISSMAC_LEN	251
ISS_ENTITY_ID	ISSMAC1	247
ISS_ENTITYID	ISSMAC1CNT	247, 250
ISS_FEE_AMT	ISSMAC1STAT	249
ISS_INST_ID	ISSMAC2	247
ISS_MINAMOUNT	ISSMAC2CHK	247
ISS_PRNCPL_AMT	ISSMAC2CNT	251
ISS_RECON_DATE	ISSMAC2STAT	249
ISS_RECON_FLAG	ISSMAC3CHK	248
ISS_RECON_TIME	ISSMAC3CNT	251
ISS_SRCHGR_AMT	ISSMAC3STAT	249
ISS_USERBIN_ID	ISSMACIDX	246
ISSBIN	ISSPIN1	246
ISSDENY_DR	ISSPIN1CHK	246
ISSDENY_PCT	ISSPIN1CNT	250
ISSKEKCNT	ISSPIN1STAT	249
	ISSPIN2	246, 247
	ISSPIN2CHK	246

ISSPIN2CNT	250
ISSPIN2STAT	249
ISSPIN3CHK	247
ISSPIN3CNT	250
ISSPIN3STAT	249
ISSPINIDX	246
ISSUANCEFEE	94
ISSUEDATE	94
ISSUER	82, 186, 197, 200, 224, 264
ISSUER_APP_DATA	145, 240
ISSUER_AUTH_DATA	240
ISSUER_DATA	170, 229, 269
ISSUER_DISCRE_DATA	145, 239
ISSUER_RESP	103
ISSUER_SCRIPT_RES	145, 240
IST_RESPCODE	86
ISTCURPNT	89
ISTCURR	90
ISTCURSPR	91
ISTREPLAYTAB	192
ITEM_COMMODITY_CD	152
ITEM_DESCRIPTION	152
ITEM_SEQUENCE_NR_L	152
ITEM_SEQUENCE_NR_M	143
ITEM_TYPE	28
ITEMS_REJECTED	29
ITEMTYPE	34
IVAC	97
IVSMI	97
IX	136

K

KEK	245
-----	-----

KEK_LEN	251
KEKCHK	245
KEY_BLOCK	203
KEY_ID	203
KEY_INDEX	96
KEY_SET_ID	181
KEY_TYPE	203
KEY_VERSION	50, 52, 58, 59, 60
KEYPARAM	212
KEYS_LOAD_TYPE	158, 159
KEYTYPES	245
KME_KEY_LEN	183
KME_KEY_NOW	183
KME_LOAD_DATE	183
KME_LOAD_TIME	183
KME_OFF_KEY_NOW	183
KME_OFF_LOAD_DATE	183
KME_OFF_LOAD_TIME	183
KPE_TXN_THRESHOLD	45
KSN_DESCRIPTOR	183

L

LANE	228, 268
LANG_CODE_OFFSET	44
LANGUAGE	37, 131
LANGUAGE_CODE	70, 119, 122, 130, 131, 138
LANGUAGE_DESC	131
LANGUAGE_STATUS	122
LAST_ACTIVITY_DATE	66, 70
LAST_ACTIVITY_TIME	66, 70
LAST_CMDTYPE	37
LAST_DATE	67, 68
LAST_SEQ_NBR	133

LAST_TIME	67, 68
LAST_TRANS_CL_DATE	114
LAST_TXN_TIME	199
LAST_TXNTYPE	37
LAST_UPDATE_DATE	66
LAST_UPDATE_TIME	66
LASTMSG_TIME	37
LASTTXNACQUIRER	238
LASTTXNAMT	237
LASTTXNAUTHNUM	238
LASTTXNRESPCODE	238
LASTTXNTERMID	238
LASTTXNTIME	237
LATERESPLOG	218
LEDGER_BALANCE	65, 231, 270
LEDGER_BALANCE_TYPE	230, 269
LEN	166
LIFE_CYCLE	224, 263
LIMIT_AMOUNT	79
LIMIT_COUNT	80
LIMIT_ID	67, 68, 79, 80
LIMIT_LEVEL	79, 80
LINE_ITEM_CNT	170
LINE_ITEM_AMT	152
LINE_ITEM_CNT	155
LINE_ITEM_CNT_M	155, 170
LINE_ITEM_DISC_AMT	152
LOC_LANG_MERCHDESC	117
LOCAL_DATE	153, 168, 175, 224, 263, 273
LOCAL_PIN	20
LOCAL_TAX_AMT	141, 172
LOCAL_TAX_INCLUDED	141, 172
LOCAL_TIME	153, 168, 175, 224, 262

LOCATION	21
LOG	136
LOG_DATA	47
LOG_ID	241
LOGDATE	162, 166
LOGGED_BY	162
LOGGED_DATE	185
LOGGED_TIME	47, 185
LOGGING	21
LOGTIME	162, 166
LOWBIN	244
LUNO	37

M

MAC_DATE	46
MAC_KEY_LEN	183
MAC_KEY_NOW	183
MAC_LOAD_DATE	183
MAC_LOAD_TIME	183
MAC_NCR_EMV	23
MAC_NCR_OTHER	23
MAC_NCR_SOLITSTAT	23
MAC_NCR_TRACK1	23
MAC_NCR_TRACK2	23
MAC_NCR_TRACK3	23
MAC_NCR_TXNREPLY	23
MAC_NCR_TXNREQ	23
MAC_OFF_KEY_NOW	183
MAC_OFF_LOAD_DATE	183
MAC_OFF_LOAD_TIME	183
MAC_REQUIRED	22
MAC_TIME	46
MAC_TXN_THRESHOLD	45

MAGSTRIPNAME	94
MAILBOX	233, 274
MAIN_BUS_DATE	198
MAKE	20
MANUFACTURER	26
MAR001	62
MAR002	62
MAR003	62
MAR004	62
MARKET_SPEC_REQ	139, 171, 253
MARKET_SPEC_RESP	140, 171, 253
MASK_PAN	155, 237
MASTER_ADDRESS Table	131
MAX_COIN_DISPENSE	26
MAX_SEQ_NBR	133
MAXDISPENSE	21, 28
MAXOUT	193
MAXPINFAILS	55
MCARD_BATCH_TRACE	239
MCARD_TXN_TRACE	239
MCC	123, 134, 154, 168
MEMBER_ID	211, 225, 264
MER_LOC_NBR	149
MERCH_DNN_ID	116
MERCH_DNN_PREFIX	116
MERCH_ENTITY_ID	150
MERCH_REF_NBR	114
MERCH_VERIFI_VALUE	118
MERCH_VOL_IND	117
MERCHANT_TYPE	134, 267
MESSAGE	166
MESSAGE_BRAND	135
MESSAGE_VERSION	135
MICR_LENGTH	256

MICR_NR	256
MISC	275
MKSMI	97
MODEL	20
MODEL_SPECIFIC	38
MPS_ID	114
MSG_COORD_NUM	37
MSG_REASON_CODE	238
MSGTYPE	81, 153, 162, 168, 200, 211, 214, 221, 241, 259
MTI	194, 195
MUL_CL_SEQ_CNT	141, 172
MUL_CL_SEQ_NBR	141, 172
MULT_DIV	90
MVV	174, 265

N

NAME	85, 86, 88, 257
NAT_TAX_AMT	141, 173
NAT_TAX_INCL_FLAG	141, 173
NBR_OF_CASSETTES	30
NEG_FILE_VERSION	145, 239
NET_ACTIVITY	66
NET_NAME	45
NETCOD	271
NETCODE	175
NETFAIL_DR	187
NETFAIL_PCT	187
NETMGR	233
NETW_ID_CD	155, 170
NETWORK	232
NETWORK_DATA	201, 244
NETWORKID	192, 232
NEW_AMOUNT	223, 262

NEW_AMOUNT_EQUIV	229, 269
NEW_BALANCE	81
NEW_FEE	223, 262
NEW_SETL_AMOUNT	223, 262
NEW_SETL_FEE	230, 269
NEWEXPIRYDATE	94
NO_CR_DR	86
NO_SHOW_IND	139, 171, 253
NODE	38, 274
NON_QUAL_IND	112
NPERCENT	193
NPINTRY	234
NSTITUTION_ID	79
NUM_AUTH	202
NUM_AUTH_REV	202
NUM_CREDIT	201
NUM_CREDIT_REV	201
NUM_DEBIT	201
NUM_DEBIT_REV	201
NUM_INQUIRY	201
NUM_TRANSFER	201
NUM_TRANSFER_REV	201
NUM_TXN	198

O

O_COMMENT	46, 55
O_DECIMAL	89
O_ROWID	189, 202, 247
OAR_LINE	38
OAR_SCREEN	37
OAS_AUDIT2	106
OAS_COUNTER	108
OAS_USER	108
OIL_CO_BRAND_NAME	118
OLD_EXPIRYDATE	70
OLD_PIN_DATA	83
OLD_PKVI	83
ON_HOLD_IND	112
ON_HOLD_SETTL_PLAN	112
ONBEHALF_APP	97
ONBEHALF_DEC	98
ONBEHALF_REF	99
OOB_DATE	114
OPEN_DATE	74, 147
OPEN_TIME	147
OPENHR	136
OPER_ENV	157
ORI_CITY_AIRPRT_CD	141, 173
ORI_CITY_AIRPRT_CD_M	143
ORIG_BATCH_ID	146, 151, 175
ORIG_DATE	155, 169
ORIG_MSG	154, 169
ORIG_TIME	155, 169
ORIG_TRACE	155, 169
ORIGDATE	227, 266
ORIGFLIPPEDMSG	174, 266
ORIGINATOR	225, 264
ORIGMSG	137, 227, 266
ORIGTIME	227, 266
ORIGTRACE	227, 266
OTHER_A_RECON_DAY	207
OTHER_A_RECON_TIME	208
OTHER_BUS_DAY	206
OTHER_FCUTOVER_TM	207
OTHER_I_RECON_DAY	208
OTHER_I_RECON_TIME	209
OTHER_TAX_AMT	141, 173

OTHER_TYPE1	115
OTHER_TYPE2	116
OWNER	75
OWNER_ENTITY_ID	164, 165, 179, 182
OWNERSHIP_CHG_DATE	114

P

PAN 55, 81, 84, 92, 137, 153, 168, 221,	237, 259, 273
PAN_HI	57, 205
PAN_LOW	57, 205
PAN_REPL	92
PANLEN	42
PANPAD	43
PANVALLEN	42
PANVALOFFSET	42
PARENT_ENTITY_ID	111
PASS_NAME	141, 173
PASSWORD	108
PAY_NUM	176
PAY_NUM_REV	176
PC_ID	116
PCODE 37, 81, 87, 88, 153, 168, 175, 214,	221, 260
PERCENT_RATE_ID	57
PERCENTAGE	64
PFOLIOSALE_ACQ_BIN	114
PGMVER	62
PHONE	257
PHONE1	132
PHONE2	132
PICKUP_DR	187
PIN_ACTIVITY	84
PIN_CAPTURE	158

PIN_DATA	83
PIN_METHOD	83, 84, 85
PIN_TYPE	83, 84, 85
PIN_WAIT_OK	44
PINBLOCK	273
PINBLOCKTYPE	43
PINFAILDATE	55
PINLEN	42
PINMETHOD	43
PINOFFSET	43
PINPARM	233
PKVI	83
PM_DATE	93
PM_STATUS	93
PM_TIME	93
PORT	233, 274
PORT_ID	162
POS_A_RECON_DAY	207
POS_A_RECON_TIME	208
POS_ADD_VERSION	139, 170
POS_BATCH	146
POS_BATCH_ID	151
POS_BATCH_IDX	146, 151, 167
POS_BATCH_IDX_A	139
POS_BATCH_IDX_C	144
POS_BATCH_IDX_L	152
POS_BATCH_IDX_M	143
POS_BATCH_IDX_T	153
POS_BUS_DAY	206
POS_CAP_CODE ..	154, 169, 224, 263
POS_CHIP_VERSION	144
POS_COND_X	155, 170
POS_CONDITION_CODE ..	154, 169, 224, 263

POS_ENTRY_CODE	154, 169, 224, 263	POS_TRANS_IDX_C	144
POS_EXTRACT_TMP	167	POS_TRANS_IDX_L	152
POS_FCUTOVER_TIME	207	POS_TRANS_IDX_M	143
POS_FORMAT	135	POS_TRANS_IDX_T	153
pos_format	124	POS_TRANS_VERSION	153, 168
POS_GEO_LOC	271	POSLOG_500	175
POS_I_RECON_DAY	208	POSLOG_ERR	162
POS_I_RECON_TIME	209	POSLOG_EXTRACT	165
POS_LINE_IDX_L	152	POSLOG_EXTRACT_FILE	164
POS_LINE_IDX_M	143	POSLOG_XMF	166
POS_LINE_VERSION_L	152	POSTMAILBOX	234
POS_LINE_VERSION_M	143	POST_COM_LIM	125
POS_MESSAGE_BRAND	162	POSTAL_CD_ZIP	132
POS_MSG_BRAND	135, 138, 179	PRE_COM_LIM	125
POS_MSG_FORMAT	135	PRAUTH_AMOUNT	65
POS_OPEN_HOUR	136	PREST_PROP_IND	140, 171, 253
POS_PIN_CAP_CODE	154, 169, 224, 263	PRESTIGIOUS_PR_IND	118
POS_REFNUM	137	PREV_AMOUNT	56
POS_RESPONSE	138	PREV_COUNT	56
POS_SHC2POS_RC	138	PREV_RECYCLE_COUNT	29
POS_TERM_CAP_ADD	139	PRI001	63
POS_TERM_CAP_AIR	143	PRI002	63
POS_TERM_CAP_CHIP	144	PRI003	63
POS_TERM_CAP_LINE	152	PRI004	63
POS_TERM_CAP_TRANS	153	PRIORITY	214, 275
POS_TERM_KEYS	182	PRIORITY_ROUTING	25
POS_TERM_MAKE	156	PRO_DISCNT_AMT	198
POS_TERM_MODEL	156	PRO_FEE_AMT	198
POS_TERM_TYPE	156, 179	PRO_PRNCPL_AMT	198
POS_TKI_AUDIT	185	PRO_SRCHGR_AMT	198
POS_TKI_KEYS	184	PROCESS_BATCH	177
POS_TRANS_IDX	168	PROCESS_NR	177
POS_TRANS_IDX_A	139	PROCESSING_TYPE	113
		PROCESSOR_BUSDAY	271

PROCOD	62
PRODUCT_CD	139, 152, 171, 252
PRODUCTION_IND	95
PROGRAM_REGISTR_ID	118
PROP_LICENCE_FLAG	126
PROV_STATE_ABBREV	131
prov_state_abbrev	178
PROV_STATE_NUM_CD	128, 131
prov_state_num_cd	178
PROVINCE	178
PROVINCE_STATE	132
province_state	178
PUBLIC_KEY	60, 184
PURCH_ID	140, 171, 253
PURCH_ORDER_DATE	141, 173
PURCH_ORDER_NR	140, 172, 253
PWD_CHANGE_DATE	108
PWD_CHANGE_TIME	108
PWD_CNT	109
PWD_FAIL_DATE	109
PWD_FAIL_TIME	109
PWD_LIFE	109
PWD_MAX_CNT	109
PWD_MAX_RETRIES	109
PWD_RETRIES	109
PWD_STATUS	108
PWD_SUCC_DATE	109
PWD_SUCC_TIME	109

Q

QRYFROMDATE	190
QRYTODATE	190
QUANTITY	152

R

RAW_LEN	194, 195
RAW_MSG	194, 195
RAWDATA	185
RCVG_INST_ID	271
REASON_CODE	175, 226, 266
RECAP_REF_NBR	117
RECLASS_IND	114
RECORD_CNT	149
RECORD_NR	163
RECYCLE_COUNT	29
REFNUM 137, 154, 169, 175, 227, 267, 273	
REFRESH	234
REGION	78, 92
REIMB_ATTR	155, 170
REIMBURSEMENT_ATTR	254
REL_ID	77
REL_INDICATOR	77
REL_PARTICIPANT	142, 174
REL_SUBTYPE	77
REL_TYPE	76
RENTAL_RET_CITY	141, 173
RENTAL_RET_LOC_ID	141, 173
RENTAL_RET_STATE	141, 173
RENTER_NAME	141, 173
REPCOLUMNLEN	191
REPDESC	190
REPL_REASON	93
REPLACE_RESPONSES	193
REPLAY	194, 195
REPMEDIA	190
REPNUMBER	190

REPORTID 191
 REPPAGELEN 191
 REPPROGRAM 190
 REPRUNDATE 190
 REPRUNTIME 190
 REPSEQNO 191
 REPTYPE 190
 REQ_ACI 139, 171, 252
 REQ_PAYMENT_SRV 139, 171, 252
 REQ_VERSION 59
 REQRESP 241
 RESET_TIME 29, 31, 56
 RESP_ACI 139, 171, 252
 RESPCODE 37, 81, 154, 169, 175, 194,
 195, 201, 226, 266
 RESPONSE_TEXT 138
 RESTR_TICKET_IND 141, 173
 RETRY_COUNT 83
 REVCODE 174, 226, 266
 REVERSAL_IND 159
 REVLOG 219
 RINTERVAL 192
 RISK_ID_IND 117
 ROUTE 194, 195
 ROUTING_NR 256
 ROWFLD 63
 RSRV_FUND_STATUS 112
 RSRV_PERCENTAGE 112
 RSRV_TO_BE_MET 112

S

SAF 227, 266
 SAF_DATE 194, 195
 SAFAMOUNT 234, 237

SAFCUTOFFDATE 194, 195
 SAFCUTOFFTIME 194, 195
 SAFDATE 237
 SAFFILE 234
 SAFINTER 234
 SAFLIMIT 234
 SAFNUM 237
 SAFTYPE 233
 SALES_TAX 140, 172, 253
 SALES_TAX_FLAG 140, 172, 253
 SDESC 54
 SECONDARY_LANGUAGE_CODE .. 130
 SECRET_KEY 60, 184
 SELL_RATE 90
 SELL_SPREAD 91
 SEND_TIME 194, 195
 SEND_TO_BRANCH 95
 SEND500 235
 SENDS_320_TWICE 160, 161
 SENDS_BATCH_NR 159
 SEQ_BLOCK_SIZE 133
 SEQ_NAME 133
 SEQ_NO 70, 93, 194, 195
 SEQ_TRACE_NO 271
 SEQUENCE 71, 75
 SERIAL_1 228, 268
 SERIAL_2 228, 268
 SERIAL_NUMBER 180, 201
 SERVER_MBOX 161
 SERVICE_CODE 73, 174
 SESSION_ID 162, 166
 SETL_AVAL_BALANCE 230, 269
 SETL_LEDGER_BALANCE 230, 269
 SETTTL_AGT_NR 113

SETTLE_WITH	187
SETTLEMENT_AGENT	201
SETTLEMENT_AMOUNT	223, 262
SETTLEMENT_AMT	153, 168, 176
SETTLEMENT_CODE	223, 262
SETTLEMENT_DATE	81, 153, 168, 200, 224, 263
SETTLEMENT_FEE	223, 262
SETTLEMENT_RATE	223, 262
SETTLEMENT_TIME	167
SETUP_COMPLETE_IND	119
SETUP_STAGE	119
SEVERITY	38, 53
SHC_DATA_BUFFER	270
SHC_DEVCAP	155, 170, 229, 268
SHC_RESPONSE	138
SHCERROR	226, 266
SHCLOG_ID	47, 48
SHCLOG_IDX	252, 255, 258, 271
SHIFT_NUMBER	154, 168, 229, 268
SHIP_POST_CD	141, 173
SHORTDESC	88
SINTERVAL	193
SLOT_NUM	270
SRV_CLASS	143
SRV_RESTRICT_CODE	239
SRVRSTR_CD	159
START_DATE	46, 67, 68, 79, 80, 139, 171, 252
START_TIME	46
STARTINGDATE	40
STARTINGSEQUENCE	40
STARTINGTIME	40
STATE_CD	257

STATETABLENAME	38
STATETABLEVER	38
STATUS	46, 53, 54, 75, 78, 86, 93, 108, 165, 177, 194, 195, 205, 237, 244
STATUS_DATE	54
STATUS_TIME	54
STATUS1	36
STATUS2	36
STATUS3	36
STATUS4	36
STATUS5	36
STIP_APP	100
STIP_DEC	101
STIP_REF	102
STO001	62
STO002	62
STO003	62
STO004	62
STOP_OVER_CD	143
STORE_ID	82
STOREID	154, 169, 228, 268
SUMM_COMM_CD	142, 173
SUPERVISOR	84, 229, 268
SUPPORT_INFO	271
SWITCH_DATE	241

T

TAK	33
TAK_CHANGE_HOUR	34
TAK_DATE_TIME	34
TAK_TXN_COUNT	34
TAK_TXN_THRES	34
TAK1	33
TAK1_CHK_DIGITS	33

TAK2	33	TEXT1	75
TAK2_CHK_DIGITS	33	TEXT2	75
TAKLEN	33	TEXT3	75
TAX_AMT	142, 173	TEXT4	75
TAX_EXEMPT_IND	112	TEXT5	75
TAX_ID	113	TICKET_NR	142, 173
TAX_RATE	142, 173	TID	273
TBATCH_ID	146, 151, 167	TIER_IND	126
TBATCH_NR	163, 175	TIME_FROM	164
TBLVER	62	TIME_OFFSET	22
TERM_CAP_PROFILE	144, 239	TIME_TO	164
TERM_COMP	22	TIMEOUT	233
TERM_COUNTRY_CODE	144, 239	TIN_TYPE	114
TERM_ENTRY_CAP	238	TIP_AMT	155, 170
TERM_ID_NR	149, 167	TKI_STATE	184
TERM_NR	165	TKI_SUPPORT	184
TERM_REC_SEQ	175	TMFK	182
TERM_RECORD_SEQ .. 137, 146, 151,		TMFK_LEN	182
162, 165, 167, 178, 182		TMK	33
TERM_SER_NUM	144, 239	TMK1	32
TERM_TXN_DATE	144, 238	TMK1_CHK_DIGITS	32
TERM_TYPE	145, 238	TMK2	32
TERMID 22, 82, 84, 137, 146, 151, 153,		TMK2_CHK_DIGITS	32
.... 162, 168, 175, 182, 227, 267		TMKLEN	32
TERMINAL	178	TMPL	191
TERMINAL_BDK	181	TOTAL_AUTH_AMT	142, 173
TERMINAL_ID	185	TPDU	37
TERMINAL_ID_HIGH	178	TPK	33
TERMINAL_ID_LOW	178	TPK_CHANGE_HOUR	33
TERMINAL_ID_NR	179	TPK_DATE_TIME	33
TERMINAL_OUTPUT	158	TPK_TXN_COUNT	33
TERMINAL_TRACE . 155, 170, 228, 268		TPK_TXN_THRES	33
TERMINATION_DATE	111, 179	TPK1	32
TERMLOC	154, 169, 228, 267	TPK1_CHK_DIGITS	33

TPK2	32	TRIGGER_16	216
TPK2_CHK_DIGITS	33	TRIGGER_17	216
TPKLEN	32	TRIGGER_18	217
TRA_AMOUNT	223, 261	TRIGGER_19	217
TRA_CONV_DATE	223, 262	TRIGGER_2	215
TRA_CONV_RATE	223, 261	TRIGGER_20	217
TRA_CURRENCY_CODE	223, 261	TRIGGER_3	215
TRACE 37, 81, 136, 153, 163, 168, 175,	200, 223, 262	TRIGGER_4	215
TRACK	273	TRIGGER_5	215
TRACK2	227	TRIGGER_6	215
TRACK3	227	TRIGGER_7	215
TRAN_DATE	153, 168	TRIGGER_8	216
TRAN_TIME	153, 168	TRIGGER_9	216
TRANDATE	200, 223, 262	TRIGID	215
TRANS_CNT	150	TRIP_LEG_1_INFO	142, 173
TRANS_ID	265	TRIP_LEG_2_INFO	142, 173
TRANSACTION_ID	139, 171	TRIP_LEG_3_INFO	142, 174
TRANSF_NUM	176	TRIP_LEG_4_INFO	142, 174
TRANSF_NUM_REV	176	TVN	37
TRANSFEREE	225, 264	TVR	144, 239
TRANTIME	200, 223, 262	TVR_CVR_STATUS	240
TRAV_AGENCY_CD	150, 174	TX_DATE	93
TRAV_AGENCY_NAME	150, 174	TX_TIME	93
TRAVEL_AGENCY_CD	118	TXN_ALLOW	20
TRAVEL_AGENCY_NAME	118	TXN_AMOUNT	230, 269
TREEHEIGHT	97	TXN_CONV_DATE	230, 270
TRIGGER_1	215	TXN_CONV_RATE	230, 270
TRIGGER_10	216	TXN_CURRENCY_CODE	230, 269
TRIGGER_11	216	TXN_DATE	81, 84
TRIGGER_12	216	TXN_END_TIME	226, 266
TRIGGER_13	216	TXN_NEW_AMOUNT	230, 269
TRIGGER_14	216	TXN_SET	233
TRIGGER_15	216	TXN_SRC	82
		TXN_START_TIME	226, 265

TXN_TIME	81, 84
TXNAMOUNT	234
TXNCLASS	78
TXNCNT	62
TXNCODE	87, 88
TXNDEST 174, 197, 210, 213, 225, 264	
TXNSRC . 84, 196, 210, 213, 225, 264	
TXNTYP	62
TXNTYPE	186, 221, 260
TYPE	56
TZ_DIFF	113

U

UNIT 19, 27, 29, 31, 32, 36, 40, 46, 50,52, 54, 56, 63	
UNIT NUMBER	47
UNIT_COST	152
UNIT_OF_MEASURE	152
UNITS_TO_DISPENSE	35
UNPREDICTABLE_NUM	144, 239
UPD_TBL	251
URL	132
USAGE	123
USEKEYS	233
USER_ID	108
USERBIN ID	274
USERBIN_ID	211
USERBINID96, 103, 192, 232, 245	

V

VAL_CHK	251
VAL_NEW	251
VAL_SEQ	251
VALID_CD	139, 171, 252
VALID_FROM_DATE	51, 58
VALID_FROM_TIME	51, 58
VALID_TO_DATE	51, 59
VALID_TO_TIME	51, 59
VALUE_DATE	90
VAT_AMT	152
VAT_RATE	152
VAT_REG_NR	113
VERIF_METHOD	255
VERIFY_PIN_LOCAL	44
VERIFY_RESPONSE	193

W

WASH_RATE	90
WEL001	62
WEL002	62
WEL003	62

Z

ZIP_CD	257
--------------	-----

Statement of Confidentiality

The information contained in or supplied with this document is submitted solely for the purpose of evaluating the products and services of FIS, and/or its affiliates and subsidiaries. The information contained in or supplied with this document, in its entirety, is the confidential and proprietary information of FIS, and it may not be copied by or disclosed to any person or entity (other than to the intended recipient), without the prior written consent of FIS. With or without FIS' prior written consent, FIS accepts no liability whatsoever for any consequences arising from the reproduction of the information contained in or supplied with this document, or from its disclosure to any person or entity, including to the intended recipient. FIS additionally accepts no liability for the use of the information contained in, or supplied with this document, by the intended recipient, or by any other person or entity, with or without FIS' express prior consent. The intended recipient shall not use any part of the information contained in, or supplied with this document, in any way to the competitive disadvantage of FIS, and will take all steps designed to assure its compliance with this provision.

This proposal is neither an offer nor intended by FIS, upon acceptance by the intended recipient, or otherwise, to create a binding agreement with FIS. Such an agreement shall be reflected only by a definitive contract, executed by both parties.

Trademarks

All other trademarks are the property of their owners.

Company, product, and service names used by FIS within, or supplied with this document may be trademarks or service marks of other persons or entities.

Copyright

Copyright© 2013 FIS.
All Rights Reserved.