


MAB Lab Topology:



MAB Configuration:

MAB Configuration on SW

```
SW(config)#interface vlan 1
SW(config-if)#ip address 192.168.80.150 255.255.255.0
SW(config-if)#no shutdown
SW(config-if)#exit

SW(config)#aaa new-model
SW(config)#aaa authentication dot1x default group radius


SW(config)#radius server ISE
SW(config-radius-server)#address ipv4 192.168.80.250 auth-port 1812 acct-port 1813
SW(config-radius-server)#key test123

SW(config)#interface ethernet 0/0
SW(config-if)#switchport host
SW(config-if)#authentication port-control auto
SW(config-if)#mab
SW(config-if)#authentication order mab dot1x
SW(config-if)#authentication priority dot1x mab

SW# debug radius authentication
SW# show mab all
SW# show authentication sessions interface ethernet 0/0
SW# show authentication sessions interface ethernet 0/0 details
SW# show authentication sessions
```

Add Network Device:

Go to **Administration > Network Resources > Network Devices** to add the Device (SW), which will request to authenticate Dot1x Client.



Administration Work Centers 0

System
Deployment
Licensing
Certificates
Logging
Maintenance
Upgrade
Backup & Restore
Admin Access

Network Resources
Network Devices
Network Device Groups
Network Device Profiles
External RADIUS Servers
RADIUS Server Sequences
NAC Managers
External MDM
Location Services

pxGrid Services
Feed Service Profiler
Identity Mapping
AD Domain Controllers
Mapping Filters

Network Devices Network Device Groups Network Device Profiles External RADIUS Servers RADIUS Server Sequences


Network devices
Default Device

Network Devices

Edit Add Duplicate Import Export Generate PAC Delete

Name	IP/Mask	Profile Name	Location
------	---------	--------------	----------

Click on Add button to add Device, Configure **Name** of the device, **IP address** configured.



Network Devices List > **New Network Device**

Network Devices

* Name SW

Description SWITCH NAD

* IP Address: 192.168.80.150 / 32

* Device Profile Cisco

Model Name Unknown

Software Version Unknown

* Network Device Group

Device Type All Device Types Set To Default

Location All Locations Set To Default

Scroll down to set Authentication settings. Set Password configured as Server key on Switch device **test123** and save settings.

☒ **RADIUS Authentication Settings**

Enable Authentication Settings

Protocol **RADIUS**

* Shared Secret

Enable KeyWrap ☐ ⓘ

* Key Encryption Key

* Message Authenticator Code Key

Key Input Format ☒ ASCII ☐ HEXADECIMAL

CoA Port

Add MAC to Identity Store:

To add Windows 7 MAC address in ISE database, navigate to **Administration > Identities > End Points > Add**. Type Windows 7 MAC Address and click **"Save"** to save the setting.

Identity Services Engine | Home | Operations | Policy | Guest Access | **Administration** | Work Centers

System | **Identity Management** | Network Resources | Device Portal Management | pxGrid Services | Feed Service | Identity Mapping

Identities | Groups | External Identity Sources | Identity Source Sequences | Settings

EndPoints

Users

Latest Manual Network Scan Results

Endpoint List > New

Mac Address *

Description

Static Assignment ☐

Policy Assignment

Static Group Assignment ☐

Identity Group Assignment

Verify:

To verify navigate to **Operations > RADIUS Livelog**.

The live logs show the given MAC address has verified and allowed.

Identity Services Engine Home Operations Policy Guest Access Administration Work Centers

RADIUS Livelog TACACS Livelog Reports Troubleshoot Adaptive Network Control

Misconfigured Supplicants 0 Misconfigured Network Devices 0 RADIUS Drops 0 Client Stopped Respond 0

Show Live Sessions Add or Remove Columns Refresh Reset Repeat Counts Refresh Never

Time	Status	Details	Repeat Count	Identity	Endpoint ID	Endpoint Profile	Authentication Policy	Authorization Policy
2019-06-07 11:19:59.786	Auth		0	00:0C:29:55:68:E0	00:0C:29:55:68:E0	VMWare-Device	Default >> MAB >> D...	Default >> Basic_Aut...
2019-06-07 11:19:59.786	Auth		0	00:0C:29:55:68:E0	00:0C:29:55:68:E0	VMWare-Device	Default >> MAB >> D...	Default >> Basic_Aut...

Verify on Switch it show the method is MAB and authenticated.

SW#show authentication sessions

Interface	Identifier	Method	Domain	Status	Fg	Session ID
Et0/0	000c.2955.68e0	mab	DATA	Auth		C0A850960000001000458959

Verify on Switch it show more details about MAB configured interface.

SW#show authentication sessions interface ethernet 0/0 details

```
Interface: Ethernet0/0
MAC Address: 000c.2955.68e0
IPv6 Address: Unknown
IPv4 Address: 192.168.80.143
User-Name: 00-0C-29-55-68-E0
Status: Authorized
Domain: DATA
Oper host mode: single-host
Oper control dir: both
Session timeout: N/A
Restart timeout: N/A
Periodic Acct timeout: N/A
Session Uptime: 4526s
Common Session ID: C0A850960000001000458959
Acct Session ID: Unknown
Handle: 0xAD000005
Current Policy: POLICY_Et0/0
```

Local Policies:

Service Template: DEFAULT_LINKSEC_POLICY_SHOULD_SECURE (priority 150)
Security Policy: Should Secure
Security Status: Link Unsecure



Server Policies:

Method status list:

Method	State
--------	-------

mab	Authc Success
-----	---------------

Let us change the MAC Address of Windows 7.



Switch deducted the security violation and shutdown the interface.

```
SW#
*Jun 7 11:25:57.862: %PM-4-ERR_DISABLE: security-violation error detected on Et
0/0, putting Et0/0 in err-disable state
SW#
*Jun 7 11:25:57.863: %AUTHMGR-5-SECURITY_VIOLATION: Security violation on the i
nterface Ethernet0/0, new MAC address (0255.5555.5555) is seen.AuditSessionID U
nassigned
*Jun 7 11:25:58.862: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
0, changed state to down
...
```

Let us bring up the interface of switch.

```
SW(config)#interface ethernet 0/0
SW(config-if)#shutdown
SW(config-if)#no shutdown
```

Let us verify again from **Operations > RADIUS Livelog**. The new MAC address is not in local database that why it has been denied by cisco ISE.

