


FortiADC Initial Configuration Lab:



Management Subnet	192.168.100.0/24
FortiGate Management IP	192.168.100.200
FortiADC Management IP	192.168.100.210
Internal Servers Subnet	192.168.1.0/24
FortiADC External Subnet	192.168.2.0/24
FortiGate Firewall External	100.0.1.0/24
FortiADC Internal IP Address	192.168.1.254
FortiADC External IP Address	192.168.2.1
FortiGate Firewall Internal IP	192.168.2.254
FortiGate Firewall External IP	100.0.1.254
SRV1 IP Address	192.168.1.1
SRV2 IP Address	192.168.1.2
SRV3 IP Address	192.168.1.3
SRV3 IP Address	192.168.1.4
Virtual Sever-1	192.168.2.100
Virtual Sever-2	192.168.2.200
FortiGate VIP-1	100.0.1.100
FortiGate VIP-2	100.0.1.200
External PC1 IP Address	100.0.1.1
External PC2 IP Address	100.0.1.2
External PC3 IP Address	100.0.1.3
Username	Admin
Password	123

Hostname Configuration

```
FortiADC-KVM # config system global
FortiADC-KVM (global) # set hostname FortiADC
FortiADC-KVM (global) # end
```

Management Interface Configuration

```
FortiADC # config system interface
FortiADC (interface) # edit port1
FortiADC (port1) # set allowaccess https http ping ssh
FortiADC (port1) # set ip 192.168.100.210/24
FortiADC (port1) # end
```

Not secure | <https://192.168.100.210>



Your connection isn't private

Attackers might be trying to steal your information from **192.168.100.210** (for example, passwords, messages, or credit cards). [Learn more about this warning](#)

NET::ERR_CERT_AUTHORITY_INVALID

Advanced

Go back

Hide advanced

Go back

This server couldn't prove that it's **192.168.100.210**; its security certificate is not trusted by your computer's operating system. This may be caused by a misconfiguration or an attacker intercepting your connection.

[Continue to 192.168.100.210 \(unsafe\)](#)

Log in to the FortiADC-Primary GUI with the username **admin** and password **123**

 FortiADC

Login

FortiADC Setup

 Perform the following steps to complete the setup of this FortiADC.

- Change Your Password 
- Specify Hostname

Begin

Later

System Getting Started Wizard

1 Maintenance

2 Network

3 Server Load Balance

Welcome to FortiADC

The **Getting Started** wizard will help you get up and running in a few short steps.
Or, you can go to the [Dashboard](#).

Time

System Time

2024-11-29

10

:

59

:

04

Daylight Saving Time

☒

Time Zone

(GMT-8:00)Pacific Time(US&Canada)

NTP

☐

Next >

Cancel



Change the **Idle Timeout** for lab purpose make it **480**, configure the **Primary** and **secondary** DNS. Then click **Save**

Hostname	FortiADC
Serial Number	FADV0000000TRIAL
Language	English
Idle Timeout	480 Default: 30 Range: 1-480 minutes
HTTPS Server Cert	Factory
Default Intermediate CA Group	Click to select.
SSH Port	22 Default: 22 Range: 1-65535
Telnet Port	23 Default: 23 Range: 1-65535
Primary DNS	8.8.8.8
Secondary DNS	1.1.1.1
Virtual Domain	☐
HTTP Port	80 Default: 80 Range: 1-65535
Redirect to HTTPS	☒
HTTPS Port	443 Default: 443 Range: 1-65535
Config Sync	☐
Pre Login Banner	☐

Save

Refresh

Continuing on the FortiADC GUI, click **System > Settings**, and then click the **Maintenance** tab.
In the Time Zone drop-down list, select your time zone.
Enable NTP.
Keep the default values for the remaining settings, and then click **Save**

Basic
Maintenance
Services
Sync List
Backup&Restore

Time

System Time
2024-11-29
22
:
02
:
46

Daylight Saving Time
☒

Time Zone
(GMT+3:00)Kuwait,Riyadh

NTP
☐

Save
Refresh

Continuing on the FortiADC GUI, click **Log & Report > Log Setting**.

Enable all logging categories for **Status**, **Event**, **Traffic**, **Security**, and **Script**.

Click **Save**.

Dashboard
Security Fabric
FortiView
System
Shared Resources
Network
Server Load Balance
Link Load Balance
Global Load Balance
Web Application Firewall
Network Security
DoS Protection
User Authentication
Log & Report
Traffic Log
Security Log
Script Log
Event Log
Report
Log Setting

Local Log
Syslog Server
FortiAnalyzer
Fast Stats

Status
☒

Log Level
Information

Event
☒

☒ Configuration
☒ Admin
☒ System
☐ User
☒ Health Check
☐ SLB
☐ LLB

Event Category
☐ GLB
☐ Firewall
☒ Enable All

Required. Please select at least one category.

Traffic
☒

Traffic logging should be used mainly for debugging; traffic logging will consume extensive memory and CPU resources. Please disable traffic logging after debugging is complete.

Traffic Category
☒ SLB
☐ GLB
☐ LLB
☒ Enable All

Required. Please select at least one category.

Security
☒

☒ DDoS
☒ IP Reputation
☒ WAF
☐ GEO
☒ AV
☒ IPS
☒ FW
☐ ZTNA

Security Category
☒ Enable All

Required. Please select at least one category.

Script
☒

☒ SLB

Required. Please select at least one category.

Save
Refresh