


Backup Server Lab:



Management Subnet	192.168.100.0/24
FortiGate Management IP	192.168.100.200
FortiADC Management IP	192.168.100.210
Internal Servers Subnet	192.168.1.0/24
FortiADC External Subnet	192.168.2.0/24
FortiGate Firewall External	100.0.1.0/24
FortiADC Internal IP Address	192.168.1.254
FortiADC External IP Address	192.168.2.1
FortiGate Firewall Internal IP	192.168.2.254
FortiGate Firewall External IP	100.0.1.254
SRV1 IP Address	192.168.1.1
SRV2 IP Address	192.168.1.2
SRV3 IP Address	192.168.1.3
SRV3 IP Address	192.168.1.4
Virtual Sever-1	192.168.2.100
Virtual Sever-2	192.168.2.200
FortiGate VIP-1	100.0.1.100
FortiGate VIP-2	100.0.1.200
External PC1 IP Address	100.0.1.1
External PC2 IP Address	100.0.1.2
External PC3 IP Address	100.0.1.3

Navigate to **Server Load Balance > Real Server Pool** double click on **WEB-Pool** to open the setting.

Real Server Pool

Real Server Server SSL

Delete + Create New + Add Filter

Name	Address Type	Health Check
WEB-Pool	IPv4	Enable
SEC-Pool	IPv4	Disable

Showing 1 to 2 of 2 entries 0 rows selected Show 25 entries

Virtual Server
Application Resources
Application Optimization
Real Server Pool

Double-click **SRV3** or click on the **pencil** icon to edit it.

Member

Delete + Create New + Add Filter

ID	Name	Address	Health Check	Port	
1	SRV1	192.168.1.1	inherited	80	  
2	SRV2	192.168.1.2	inherited	80	  
3	SRV3	192.168.1.3	inherited	80	  

Enable **Backup**, and then click **Save**. Click **Save** to change the real server pool.

Real Server Pool

Scripting
SSL-FP Resources
Link Load Balance
Global Load Balance
Web Application Firewall
Network Security
DoS Protection
User Authentication
Log & Report

Direct Route Mode
Real Server SSL Prof
Member

Delete + Create New + Add Filter

ID	Name
1	SRV1
2	SRV2
3	SRV3

Showing 1 to 3 of 3

Connection Rate Limit Default: 0 (disabled) Range: 0-86400 connections per second

Backup ☒

Cookie rs3

Health Check Inherit ☒

RS Profile Inherit ☒


MySQL Read Only ☐

MySQL Group ID 0

MSSQL Read Only ☐

Proxy Protocol None V1 V2



Modify Host ☐




Test the Backup Server:

On the Kali Linux-External client, open the Firefox browser, and then connect to the virtual server at <http://100.0.1.100>.


Press **Ctrl+Shift+R** to refresh the browser page several times. Connections now go to only the SRV1 and SRV2. The SRV3 is a backup server, and is used only when all the other servers fail the health check.



Let's shutdown **SRV1** right click **Stop** or login to the server CLI Command **shutdown -h now**




Return to the Kali Linux-External client, select the browser tab that is connecting to the virtual server at <http://100.0.1.100> and then press F5 several times. Connection now go to SRV2 only.





Using the backup setting indicates to the FortiADC that the server should be used only when no other server is available in the real server pool.

As long as there is at least one other server available, no new connections are routed to the backup server.

Let's shutdown the SRV2 as well right click Stop or login to the server type the CLI Command `shutdown -h now`




Return to the Kali Linux-External client, select the browser tab that is connecting to the virtual server at <http://100.0.1.100> , and then press F5 several times to refresh the browser. Traffic is now routed to SRV3.



Restore the Servers and Disable the Backup Server:

Let's Start **SRV1** and **SRV2** right click on each Server click **Start**




click **Server Load Balance > Real Server Pool**.

Click the edit icon to edit **WEB-Pool**.

Double-click **SRV3** to edit it.

Disable **Backup**, and then click **Save**.

Click **Save**.



Return to the Kali Linux-External client, select the browser tab that is connecting to the virtual server at <http://100.0.1.100>, and then press **Ctrl+Shift+R** to refresh the browser page several times. Traffic is routed to all the Web servers.