



# Improvement of DGIM method


林宇浩







Sampling data from a stream (从流中采样数据) 上节课介绍的 暴力算法: 两种任务类型 空间复杂度O(N) Queries over sliding windows (对滑动窗口查询) 一致性假设: 问题:给定一个0和1的流,最后k位中有多少个1? 无法适应流分布变化的情况 010011011101010110110110 **Past Future** DGIM方法


### DGIM算法内容回顾







桶中1数量为4的桶有2个



桶中1的数量	 16	8	4	2	1
0代表桶数为1 1代表桶数为2	 0	1	1	0	1
					+1
	 0	1	1	1	0

### 改进后可以利用二进制加法代替原先的多次合并


# 

桶中1的数量	 16	8	4	2	1
0代表桶数为1 1代表桶数为2	 0	1	1	1	0

### 

桶中1的数量	 16	8	4	2	1
0代表桶数为1 1代表桶数为2	 0	1	1	1	0
					+1
	 0	1	1	1	1
					+1
	 1	0	0	0	0

### 改进后可以利用二进制加法代替原先的多次合并



#### 

桶中1的数量	 16	8	4	2	1
0代表桶数为1 1代表桶数为2	 0	1	1	1	0

### 

桶中1的数量	 16	8	4	2	1
0代表桶数为1 1代表桶数为2	 0	1	1	1	0
					+1
	 0	1	1	1	1
					+1
	 1	0	0	0	0


# 

r=2 桶的数量只能是1或2

桶中1的数量	32	16	8	4	2	1
0代表桶数为1 1代表桶数为2		0	1	1	0	1
					桶中	↓ 桶中? 1数量

桶中1数量为4的桶有2个

**r=4** 桶的数量只能是3或4



# Further Reducing the Error

- Instead of maintaining 1 or 2 of each size bucket, we allow either r-1 or r buckets (r > 2)
  - Except for the largest size buckets; we can have any number between
    1 and r of those
- Error is at most O(1/r)
- By picking r appropriately, we can tradeoff between number of bits we store and the error

	r值	错误率	桶的数量	存储桶中1的数量要用 的空间	存储时间戳要用的 空间	更新消耗
DGIM method	<b>↑</b>	<b>\</b>	<b>↑</b>	<b>↑</b>	<b>↑</b>	<b>↑</b>
改进后	<b>↑</b>	<b>\</b>	<b>↑</b>	<b>\</b>	<b>↑</b>	$\approx$

r=2 桶的数量只能是1或2



r=4 桶的数量只能是3或4



### 计算窗口内1的数量的估计值

r=2 桶的数量只能是1或2

桶中1的数量	32	16	8	4	2	1
0代表桶数为1 1代表桶数为2		0	1	1	0	1
桶中1的数量		$1\times2^4$	$2\times2^3$	$2\times2^2$	$1 \times 2^1$	$2\times2^{0}$

1的总数 = 
$$\left[\frac{1}{2} \times 1 \times 2^4 + (1-1) \times 2^4\right] + 2 \times 2^3 + 2 \times 2^2 + 1 \times 2^1 + 2 \times 2^0$$

r=4 桶的数量只能是3或4

桶中1的数量	32	16	8	4	2	1
0代表桶数为3 1代表桶数为4			2	0	0	1
			2×2 <sup>3</sup>	$3\times2^2$	3×2 <sup>1</sup>	4×2°

1的总数 = 
$$\left[\frac{1}{2} \times 2^3 + (2-1) \times 2^3\right] + 3 \times 2^2 + 3 \times 2^1 + 4 \times 2^0$$

### 对于r=2的情况还能在计算上优化

r=2

桶的数量只能是1或2

数值为0都会乘以1 数值为1都会乘以2 桶中1的数量 32 16 0代表桶数为1 ()01 1代表桶数为2  $1 \times 2^4$   $2 \times 2^3$   $2 \times 2^2$   $1 \times 2^1$   $2 \times 2^0$ 桶中1的数量

1的总数 =  $\left[\frac{1}{2} \times 1 \times 2^4 + (1-1) \times 2^4\right] + 2 \times 2^3 + 2 \times 2^2 + 1 \times 2^1 + 2 \times 2^0 = 36$ 

最高位会有一个桶乘以0.5

### 处理所有数值为0的

32	16	8	4	2	1
	0	1	1	0	1



逐	挕.	非	

32	16	8	4	2	1
0	1	0	0	1	0

### 处理所有数值为1的

32	16	8	4	2	1
	0	1	1	0	1



32	16	8	4	2	1
0	1	1	0	1	0

	32	16	8	4	2	1
	0	1	0	0	1	0
+	0	1	1	0	1	0
	1	0	1	1	0	0

	32	16	8	4	2	1
	1	0	1	1	0	0
-	0	0	1	0	0	0
	1	0	0	1	0	0

最左侧的桶乘以0.5

### 对于r=2的情况还能在计算上优化

r=2

桶的数量只能是1或2

数值为0都会乘以1 数值为1都会乘以2 桶中1的数量321684210代表桶数为1<br/>1代表桶数为2...11101桶中1的数量2×24<br/>2×242×23<br/>2×222×22<br/>1×211×21<br/>2×20

1的总数 =  $\left[\frac{1}{2} \times 1 \times 2^4 + (2-1) \times 2^4\right] + 2 \times 2^3 + 2 \times 2^2 + 1 \times 2^1 + 2 \times 2^0 = 52$ 

最高位会有一个桶乘以0.5

### 处理所有数值为0的

32	16	8	4	2	1
	1	1	1	0	1



32	16	8	4	2	1
0	0	0	0	1	0

### 处理所有数值为1的

32	16	8	4	2	1
•••	1	1	1	0	1



32	16	8	4	2	1
1	1	1	0	1	0

	32	16	8	4	2	1
	0	0	0	0	1	0
+	1	1	1	0	1	0
	1	1	1	1	0	0

	32	16	8	4	2	1		
	1	1	1	1	0	0		
-	0	0	1	0	0	0		
	1	1	0	1	0	0		

最左侧的桶乘以0.5

