Installing MAP3270

- 1. Download the CLE Distro V3 archive
- 2. Extract the CLEDST.AWS tape and RESTORE.JCL from the archive. All of the .txt files are compile listings and/or installation listings.
- 3. Edit the restore JCL. You may want to change the default userid HERC01 and volume PUB002 where you want the restore datasets to go. The tape drive is assumed to be 480. You can change this also. Submit the restore JCL. Besure to make these changes in the install JCL.
- 4. After the restore is complete, you will need to optionally edit and submit jobs contained in HERC01.CLE.DISTRO.CNTL. Member MAP32700, MAP32701, MAP32702.
- 5. If all three of these jobs execute successfully, you must now manually change additional members as indicated here:

```
_____BKUW5E_U5N = 5Y51.PKULLIB(I5ULU6UN)---
 ---+---1-----2-----3----+----4----+--
//TSOLOGON PROC
//IKJACCNT EXEC PGM=IKJEFT01,PARM=USRLOGON
//*STEPLIB DD DSN=CBTCOV.FILE261,DISP=SHR
            DD DSN=CBTCOV.FILE266,DISP=SHR
           DD
               DSN=SYS1.PL1LIB, DISP=SHR
//STEPLIB
//SYSHELP
           DD
               DISP=SHR, DSN=SYS1. HELP
               DISP=SHR, DSN=SYS1. CMDPROC
//SYSPROC
           DD
//DD1
           DD
               DYNAM
```

6. Make sure that the STEPLIB is pointing as indicated above. This is required only if you intend to run PL/I(F) programs under TSO. Note the PARM= since this must match a member name in SYS1.CMDPROC.

```
BROWSE DSN = SYS1.CMDPROC(USRLOGON)------------Col 001,lin
CMD =>
----+----1----+----2----+----3----+----4----+----5----+----6----
        PROC 0
CONTROL NOMSG, NOLIST, NOSYMLIST, NOCONLIST, NOFLUSH
FREE FILE(SYSHELP)
WRITE Logging on to BSP1 at &SYSTIME using &SYSPROC
ALLOC FILE(SYSHELP) DSN('SYS1.HELP', 'SYS2.HELP') SHR
ALLOC FILE(X1) DSN('&SYSUID..CMDPROC(STDLOGON)') SHR
IF &LASTCC = 0 THEN +
   DO
     WRITE Logging on using private logon procedure
     FREE FILE(SYSPROC)
     FREE FILE(X1)
     ALLOC FILE(SYSPROC) DSN('&SYSUID..CMDPROC', 'SYS1.CMDPROC') SHR
  END
ELSE +
  DO
     WRITE Logging on using public logon procedure
     FREE FILE(X1)
   END
EXIT
```

7. This sets up the customized logon. If you do not have a HERC01.CMDPROC, you can create RUN3270 in SYS1.CMDPROC.

```
BROWSE DSN = HERC01.CMDPROC(RUN3270)-----
CMD =>
---+---1---+---2---+---3---+---4--
PROC 1 PGM
CALL 'HERC01.MAP3270.LOADLIB(&PGM)'
```

- 8. This should complete your manual portion. Logoff and logon to complete the install.
- 9. At the READY propmpt, type in

RUN3270 ADEMO

