


Packet Tracer - Configuring IPv4 Static and Default Routes

Topology



Addressing Table

Device	Interface	IPv4 Address	Subnet Mask	Default Gateway
R1	G0/0	172.31.1.1	255.255.255.128	N/A
	S0/0/0	172.31.1.194	255.255.255.252	N/A
R2	G0/0	172.31.0.1	255.255.255.0	N/A
	S0/0/0	172.31.1.193	255.255.255.252	N/A
	S0/0/1	172.31.1.197	255.255.255.252	N/A
R3	G0/0	172.31.1.129	255.255.255.192	N/A
	S0/0/1	172.31.1.198	255.255.255.252	N/A
PC1	NIC	172.31.1.126	255.255.255.128	172.31.1.1
PC2	NIC	172.31.0.254	255.255.255.0	172.31.0.1
PC3	NIC	172.31.1.190	255.255.255.192	172.31.1.129

Objectives

Part 1: Examine the Network and Evaluate the Need for Static Routing

Part 2: Configure Static and Default Routes

Part 3: Verify Connectivity

Background

In this activity, you will configure static and default routes. A static route is a route that is entered manually by the network administrator to create a reliable and safe route. There are four different static routes that are used in this activity: a recursive static route, a directly attached static route, a fully specified static route, and a default route.

Part 1: Examine the Network and Evaluate the Need for Static Routing

- Looking at the topology diagram, how many networks are there in total? **5 networks**
- How many networks are directly connected to R1, R2, and R3? **R1(2); R3(2); R2(3)**
- How many static routes are required by each router to reach networks that are not directly connected?
R1- 3 ; R2- 2 ; R3- 3
- Test connectivity to the R2 and R3 LANs by pinging PC2 and PC3 from PC1.

Why were you unsuccessful? **The pings failed because no static routes have been configured yet. R1 only knows about its directly connected networks and has no information about how to reach the R2 or R3 LANs.**

Part 2: Configure Static and Default Routes

Step 1: Configure recursive static routes on R1.

- What is recursive static route?

It is a static route where the router must perform an additional lookup in its routing table to determine how to reach the specified next-hop IP address.

- Why does a recursive static route require two routing table lookups?

Because the router first looks up the destination network, then looks up the next-hop IP address to find the outgoing interface.

- Configure a recursive static route to every network not directly connected to R1, including the WAN link between R2 and R3.

- Test connectivity to the R2 LAN and ping the IP addresses of PC2 and PC3.

c ans:
R1(config)# ip route 172.31.0.0 255.255.255.0 172.31.1.193
R1(config)# ip route 172.31.1.196 255.255.255.252 172.31.1.193
R1(config)# ip route 172.31.1.128 255.255.255.192 172.31.1.193

Why were you unsuccessful?

Ping to PC2 is still failing because R2 and R3 lack routes to return traffic to R1's LAN.

Step 2: Configure directly attached static routes on R2.

- How does a directly attached static route differ from a recursive static route?

A directly attached static route uses the exit interface instead of a next-hop IP address. Because the exit interface is directly known, it only requires one routing table lookup, making it faster than a recursive static route.

b ans:
R2(config)# ip route 172.31.1.0 255.255.255.128 s0/0/0
R2(config)# ip route 172.31.1.128 255.255.255.192 s0/0/1

- Configure a directly attached static route from R2 to every network not directly connected.

- Which command only displays directly connected networks? **R2# show ip route connected**

- Which command only displays the static routes listed in the routing table? **R2# show ip route static**

- When viewing the entire routing table, how can you distinguish between a directly attached static route and a directly connected network?

A static route is refixed with "S" letter and directly connected is with "C" letter.

Step 3: Configure a default route on R3.

- a. How does a default route differ from a regular static route?

A default route (0.0.0.0/0) is used to forward traffic to a gateway when no more specific route exists in the routing table.

- b. Configure a default route on R3 so that every network not directly connected is reachable.

- c. How is a static route displayed in the routing table?

b ans:

R3(config)# ip route 0.0.0.0 0.0.0.0 s0/0/1

Displayed with "S" in the routing table.

Step 4: Document the commands for fully specified routes.

Note: Packet Tracer does not currently support configuring fully specified static routes. Therefore, in this step, document the configuration for fully specified routes.

- a. Explain a fully specified route.

A fully specified static route includes both the exit interface and the next-hop IP address. This eliminates any ambiguity the router doesn't need to do any additional lookup making it the most precise type of static route.

- b. Which command provides a fully specified static route from R3 to the R2 LAN?

ip route 172.31.0.0 255.255.255.0 s0/0/1 172.31.1.197

- c. Write a fully specified route from R3 to the network between R2 and R1. Do not configure the route; just calculate it.

ip route 172.31.1.192 255.255.255.252 s0/0/1 172.31.1.197

- d. Write a fully specified static route from R3 to the R1 LAN. Do not configure the route; just calculate it.

ip route 172.31.1.0 255.255.255.128 s0/0/1 172.31.1.197

Step 5: Verify static route configurations.

Use the appropriate **show** commands to verify correct configurations.

Which **show** commands can you use to verify that the static routes are configured correctly?

show ip route static

Part 3: Verify Connectivity

Every device should now be able to ping every other device. If not, review your static and default route configurations.

Suggested Scoring Rubric

Activity Section	Question Location	Possible Points	Earned Points
Part 1: Examine the Network and Evaluate the Need for Static Routing	a - d	10	
Part 1 Total		10	
Part 2: Configure Static and Default Routes	Step 1	7	
	Step 2	7	
	Step 3	3	
	Step 4	10	
	Step 5	3	
Part 2 Total		30	
Packet Tracer Score		60	
Total Score		100	