LAB - DATETIME2 Data Type

In this lab, you will learn how to use the SQL Server DATETIME2 to store both date and time data in a table.

To store both date and time in the database, you use the SQL Server DATETIME2 data type.

The syntax of DATETIME2 is as follows:

```
DATETIME2(fractional seconds precision)
```

The fractional seconds precision is optional. It ranges from 0 to 7.

The following statement illustrates how to create a table that consists of a DATETIME2 column:

The DATETIME2 has two components: date and time.

- The date has a range from January 01, 01 (0001-01-01) to December 31, 9999 (9999-12-31)
- The time has a range from 00:00:00 to 23:59:59.9999999.

The storage size of a DATETIME2 value depends on the fractional seconds precision. It requires 6 bytes for the precision that is less than 3, 7 bytes for the precision that is between 3 and 4, and 8 bytes for all other precisions.

The default string literal format of the DATETIME2 is as follows:

```
YYYY-MM-DD hh:mm:ss[.fractional seconds]
```

In this format:

- YYYY is a four-digit number that represents a year e.g., 2018. It ranges from 0001 through 9999.
- MM is a two-digit number that represents a month in a year e.g., 12. It ranges from 01 to 12.
- DD is a two-digit number that represents a day of a specified month e.g., 23. It ranges from 01 to 31.
- hh is a two-digit number that represents the hour. It ranges from 00 to 23.
- mm is a two-digit number that represents the minute. It ranges from 00 to 59.
- ss is a two-digit number that represents the second. It ranges from 00 to 59.
- The fractional seconds is zero to a seven-digit number that ranges from 0 to 9999999.

Example

The following statement creates a new table that has a created_at column whose data type is DATETIME2:

```
CREATE TABLE product_colors (
    color_id INT PRIMARY KEY IDENTITY,
    color_name VARCHAR (50) NOT NULL,
    created_at DATETIME2
);
```

To insert the current date and time into the created_at column, you use the following INSERT statement with the GETDATE () function:

The GETDATE () function is a system defined function that can be used to get system date and time.

To insert a literal value into the DATETIME2 column, you use the following statement:

```
INSERT INTO product_colors (color_name, created_at)
VALUES
     ('Green', '2018-06-23 07:30:20');
```

If you want to set the default value of the created_at column to the current date and time, you use the following ALTER TABLE statement:

```
ALTER TABLE product_colors

ADD CONSTRAINT df_current_time

DEFAULT CURRENT_TIMESTAMP FOR created_at;
```

In this statement, we use CURRENT_TIMESTAMP as the default value for the created_at column. Note that the CURRENT_TIMESTAMP returns the same value as the GETDATE () function.

Now, when you insert a new row to the table without specifying the value for the created_at column, SQL
Server will use the current date and time value for that column:

In this lab, you have learned how to use the SQL Server DATETIME2 data type to store both date and time data in a table.