### WikipediA

# Pointer (computer programming)

In <u>computer science</u>, a **pointer** is a <u>programming language</u> object that stores the <u>memory address</u> of another value located in <u>computer memory</u>. A pointer *references* a location in memory, and obtaining the value stored at that location is known as <u>dereferencing</u> the pointer. As an analogy, a page number in a book's index could be considered a pointer to the corresponding page; dereferencing such a pointer would be done by flipping to the page with the given page number and reading the text found on that page. The actual format and content of a pointer variable is dependent on the underlying computer architecture.


Using pointers significantly improves performance for repetitive operations like traversing <u>iterable</u> data structures, e.g. <u>strings</u>, <u>lookup tables</u>, <u>control tables</u> and <u>tree</u> structures. In particular, it is often much cheaper in time and space to copy and dereference pointers than it is to copy and access the data to which the pointers point.

Pointers are also used to hold the addresses of entry points for <u>called</u> subroutines in procedural programming and for run-time linking to dynamic link libraries (DLLs). In <u>object-oriented</u> programming, pointers to <u>functions</u> are used for binding methods, often using what are called virtual method tables.

A pointer is a simple, more concrete implementation of the more abstract <u>reference</u> <u>data type</u>. Several languages, especially <u>low-level languages</u> support some type of pointer, although some have more restrictions on their use than others. While "pointer" has been used to refer to references in general, it more properly applies to <u>data structures</u> whose <u>interface</u> explicitly allows the pointer to be manipulated (arithmetically via *pointer arithmetic*) as a memory address, as opposed to a <u>magic cookie</u> or <u>capability</u> which does not allow such. Because pointers allow both protected and unprotected access to memory addresses, there are risks associated with using them, particularly in the latter case. Primitive

I do consider <u>assignment statements</u> and pointer variables to be among computer science's "most valuable treasures."

<u>Donald Knuth</u>, Structured Programming with go to Statements<sup>[1]</sup>



Pointer **a** pointing to the memory address associated with variable **b**. In this diagram, the computing architecture uses the same address space and data primitive for both pointers and non-pointers; this need not be the case.

pointers are often stored in a format similar to an <u>integer</u>; however, attempting to dereference or "look up" such a pointer whose value is not a valid memory address will cause a program to crash. To alleviate this potential problem, as a matter of <u>type safety</u>, pointers are considered a separate type parameterized by the type of data they point to, even if the underlying representation is an integer. Other measures may also be taken (such as validation & bounds checking), to verify that the pointer variable contains a value that is both a valid memory address and within the numerical range that the processor is capable of addressing.

### **Contents**

History

Formal description

Use in data structures

Use in control tables

**Architectural roots** 

Uses

C pointers

C arrays

C linked list
Pass-by-address using pointers
Dynamic memory allocation
Memory-mapped hardware

Typed pointers and casting

Making pointers safer

**Null pointer** 

**Autorelative pointer** 

**Based pointer** 

**Multiple indirection** 

**Function pointer** 

**Dangling pointer** 

**Back pointer** 

Wild branch

Simulation using an array index

Support in various programming languages

Ada

**BASIC** 

C and C++

Pointer declaration syntax overview

C#

COBOL

PL/I

D

Eiffel

Fortran

Go

Java

Modula-2

Oberon

Pascal

Perl

See also

References

**External links** 

## **History**

Harold Lawson is credited with the 1964 invention of the pointer. [2] In 2000, Lawson was presented the Computer Pioneer Award by the IEEE "[f]or inventing the pointer variable and introducing this concept into PL/I, thus providing for the first time, the capability to flexibly treat linked lists in a general-purpose high level language". [3] His seminal paper on the concepts appeared in the June, 1967 issue of CACM entitled: PL/I List Processing. According to the Oxford English Dictionary, the word pointer first appeared in print as a *stack pointer* in a technical memorandum by the System Development Corporation.

## **Formal description**

In computer science, a pointer is a kind of reference.

A *data primitive* (or just *primitive*) is any datum that can be read from or written to <u>computer memory</u> using one memory access (for instance, both a *byte* and a *word* are primitives).

A *data aggregate* (or just *aggregate*) is a group of primitives that are <u>logically</u> contiguous in memory and that are viewed collectively as one datum (for instance, an aggregate could be 3 logically contiguous bytes, the values of which represent the 3 coordinates of a point in space). When an aggregate is entirely composed of the same type of primitive, the aggregate may be called an *array*; in a sense, a multi-byte *word* primitive is an array of bytes, and some programs use words in this way.

In the context of these definitions, a *byte* is the smallest primitive; each <u>memory address</u> specifies a different byte. The memory address of the initial byte of a datum is considered the memory address (or *base memory address*) of the entire datum.

A *memory pointer* (or just *pointer*) is a primitive, the value of which is intended to be used as a memory address; it is said that *a pointer points to a memory address*. It is also said that *a pointer points to a datum [in memory]* when the pointer's value is the datum's memory address.

More generally, a pointer is a kind of <u>reference</u>, and it is said that *a pointer references a datum stored somewhere in memory*; to obtain that datum is *to dereference the pointer*. The feature that separates pointers from other kinds of reference is that a pointer's value is meant to be interpreted as a memory address, which is a rather low-level concept.

References serve as a level of indirection: A pointer's value determines which memory address (that is, which datum) is to be used in a calculation. Because indirection is a fundamental aspect of algorithms, pointers are often expressed as a fundamental <u>data</u> <u>type</u> in <u>programming languages</u>; in <u>statically</u> (or <u>strongly</u>) typed programming languages, the <u>type</u> of a pointer determines the type of the datum to which the pointer points.

### Use in data structures

When setting up <u>data structures</u> like <u>lists</u>, <u>queues</u> and trees, it is necessary to have pointers to help manage how the structure is implemented and controlled. Typical examples of pointers are start pointers, end pointers, and <u>stack</u> pointers. These pointers can either be **absolute** (the actual <u>physical address</u> or a <u>virtual address</u> in <u>virtual memory</u>) or <u>relative</u> (an <u>offset</u> from an absolute start address ("base") that typically uses fewer bits than a full address, but will usually require one additional arithmetic operation to resolve).

Relative addresses are a form of manual memory segmentation, and share many of its advantages and disadvantages. A two-byte offset, containing a 16-bit, unsigned integer, can be used to provide relative addressing for up to 64 kilobytes of a data structure. This can easily be extended to 128K, 256K or 512K if the address pointed to is forced to be <u>aligned</u> on a half-word, word or double-word boundary (but, requiring an additional "shift left" <u>bitwise operation</u>—by 1, 2 or 3 bits—in order to adjust the offset by a factor of 2, 4 or 8, before its addition to the base address). Generally, though, such schemes are a lot of trouble, and for convenience to the programmer absolute addresses (and underlying that, a *flat address space*) is preferred.

A one byte offset, such as the hexadecimal  $\underline{ASCII}$  value of a character (e.g. X'29') can be used to point to an alternative integer value (or index) in an array (e.g., X'01'). In this way, characters can be very efficiently translated from ' $\underline{raw\ data}$ ' to a usable sequential  $\underline{index}$  and then to an absolute address without a  $\underline{lookup\ table}$ .

## Use in control tables

<u>Control tables</u> that are used to control <u>program flow</u> usually make extensive use of pointers. The pointers, usually embedded in a table entry, may, for instance, be used to hold the entry points to <u>subroutines</u> to be executed, based on certain conditions defined in the same table entry. The pointers can however be simply indexes to other separate, but associated, tables comprising an array of the actual addresses or the addresses themselves (depending upon the programming language constructs available). They can also be used to point to earlier table entries (as in loop processing) or forward to skip some table entries (as in a <u>switch</u> or "early" exit from a loop). For this latter purpose, the "pointer" may simply be the table entry number itself and can be transformed into an actual address by simple arithmetic.

## **Architectural roots**

Pointers are a very thin <u>abstraction</u> on top of the addressing capabilities provided by most modern <u>architectures</u>. In the simplest scheme, an <u>address</u>, or a numeric <u>index</u>, is assigned to each unit of memory in the system, where the unit is typically either a <u>byte</u> or a <u>word</u> – depending on whether the architecture is <u>byte-addressable</u> or <u>word-addressable</u> – effectively transforming all of memory into a very large <u>array</u>. The system would then also provide an operation to retrieve the value stored in the memory unit at a given address (usually utilizing the machine's general purpose registers).

In the usual case, a pointer is large enough to hold more addresses than there are units of memory in the system. This introduces the possibility that a program may attempt to access an address which corresponds to no unit of memory, either because not enough memory is installed (i.e. beyond the range of available memory) or the architecture does not support such addresses. The first case may, in certain platforms such as the Intel x86 architecture, be called a segmentation fault (segfault). The second case is possible in the current implementation of AMD64, where pointers are 64 bit long and addresses only extend to 48 bits. Pointers must conform to certain rules (canonical addresses), so if a non-canonical pointer is dereferenced, the processor raises a general protection fault.

On the other hand, some systems have more units of memory than there are addresses. In this case, a more complex scheme such as memory segmentation or paging is employed to use different parts of the memory at different times. The last incarnations of the x86 architecture support up to 36 bits of physical memory addresses, which were mapped to the 32-bit linear address space through the PAE paging mechanism. Thus, only 1/16 of the possible total memory may be accessed at a time. Another example in the same computer family was the 16-bit protected mode of the 80286 processor, which, though supporting only 16 MB of physical memory, could access up to 1 GB of virtual memory, but the combination of 16-bit address and segment registers made accessing more than 64 KB in one data structure cumbersome.

In order to provide a consistent interface, some architectures provide <u>memory-mapped I/O</u>, which allows some addresses to refer to units of memory while others refer to <u>device registers</u> of other devices in the computer. There are analogous concepts such as file offsets, array indices, and remote object references that serve some of the same purposes as addresses for other types of objects.

### **Uses**

Pointers are directly supported without restrictions in languages such as <u>PL/I</u>, <u>C</u>, <u>C++</u>, <u>Pascal</u>, <u>FreeBASIC</u>, and implicitly in most <u>assembly languages</u>. They are primarily used for constructing <u>references</u>, which in turn are fundamental to constructing nearly all data structures, as well as in passing data between different parts of a program.

In functional programming languages that rely heavily on lists, data references are managed abstractly by using primitive constructs like <u>cons</u> and the corresponding elements <u>car and cdr</u>, which can be thought of as specialised pointers to the first and second components of a cons-cell. This gives rise to some of the idiomatic "flavour" of functional programming. By structuring data in such <u>cons-lists</u>, these languages facilitate <u>recursive</u> means for building and processing data—for example, by recursively accessing the head and tail elements of lists of lists; e.g. "taking the car of the cdr of the cdr". By contrast, memory management based on pointer dereferencing in some approximation of an <u>array</u> of memory addresses facilitates treating variables as slots into which data can be assigned imperatively.

When dealing with arrays, the critical <u>lookup</u> operation typically involves a stage called *address calculation* which involves constructing a pointer to the desired data element in the array. In other data structures, such as <u>linked lists</u>, pointers are used as references to explicitly tie one piece of the structure to another.

Pointers are used to pass parameters by reference. This is useful if the programmer wants a function's modifications to a parameter to be visible to the function's caller. This is also useful for returning multiple values from a function.

Pointers can also be used to <u>allocate</u> and deallocate dynamic variables and arrays in memory. Since a variable will often become redundant after it has served its purpose, it is a waste of memory to keep it, and therefore it is good practice to deallocate it (using the original pointer reference) when it is no longer needed. Failure to do so may result in a <u>memory leak</u> (where available free memory gradually, or in severe cases rapidly, diminishes because of an accumulation of numerous redundant memory blocks).

### **C** pointers

The basic syntax to define a pointer is:<sup>[4]</sup>

```
int *ptr;
```

This declares ptr as the identifier of an object of the following type:

pointer that points to an object of type int

This is usually stated more succinctly as "ptr is a pointer to int."

Because the C language does not specify an implicit initialization for objects of automatic storage duration, [5] care should often be taken to ensure that the address to which ptr points is valid; this is why it is sometimes suggested that a pointer be explicitly initialized to the <u>null pointer</u> value, which is traditionally specified in C with the standardized macro NULL:[6]

```
int *ptr = NULL;
```

Dereferencing a null pointer in C produces <u>undefined behavior</u>, <sup>[7]</sup> which could be catastrophic. However, most implementations simply halt execution of the program in question, usually with a segmentation fault.

However, initializing pointers unnecessarily could hinder program analysis, thereby hiding bugs.

In any case, once a pointer has been declared, the next logical step is for it to point at something:

```
int a = 5;
int *ptr = NULL;
ptr = &a;
```

This assigns the value of the address of a to ptr. For example, if a is stored at memory location of 0x8130 then the value of ptr will be 0x8130 after the assignment. To dereference the pointer, an asterisk is used again:

```
*ptr = 8;
```

This means take the contents of ptr (which is 0x8130), "locate" that address in memory and set its value to 8. If a is later accessed again, its new value will be 8.

This example may be clearer if memory is examined directly. Assume that **a** is located at address 0x8130 in memory and **ptr** at 0x8134; also assume this is a 32-bit machine such that an int is 32-bits wide. The following is what would be in memory after the following code snippet is executed:

```
int a = 5;
int *ptr = NULL;
```

Address	Contents	
0x8130	0x00000005	
0x8134	0x00000000	

(The NULL pointer shown here is 0x00000000.) By assigning the address of a to ptr:

```
\mathsf{ptr} = \delta_{\mathsf{a}};
```

yields the following memory values:

Address	Contents	
0x8130	0x00000005	
0x8134	0x00008130	

Then by dereferencing ptr by coding:

```
*ptr = 8;
```

the computer will take the contents of ptr (which is 0x8130), 'locate' that address, and assign 8 to that location yielding the following memory:

Address	Contents
0x8130	0x00000008
0x8134	0x00008130

Clearly, accessing a will yield the value of 8 because the previous instruction modified the contents of a by way of the pointer ptr.

### C arrays

In C, array indexing is formally defined in terms of pointer arithmetic; that is, the language specification requires that array[i] be equivalent to \*(array + i).<sup>[8]</sup> Thus in C, arrays can be thought of as pointers to consecutive areas of memory (with no gaps),<sup>[8]</sup> and the syntax for accessing arrays is identical for that which can be used to dereference pointers. For example, an array array can be declared and used in the following manner:

This allocates a block of five integers and names the block <code>array</code>, which acts as a pointer to the block. Another common use of pointers is to point to dynamically allocated memory from <a href="mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:mailto:ma

While most operators on arrays and pointers are equivalent, the result of the <u>sizeof</u> operator differs. In this example, sizeof(array) will evaluate to 5\*sizeof(int) (the size of the array), while sizeof(ptr) will evaluate to sizeof(int\*), the size of the pointer itself.

Default values of an array can be declared like:

```
int array[5] = {2, 4, 3, 1, 5};
```

If array is located in memory starting at address 0x1000 on a 32-bit <u>little-endian</u> machine then memory will contain the following (values are in hexadecimal, like the addresses):

	0	1	2	3
1000	2	0	0	0
1004	4	0	0	0
1008	3	0	0	0
100C	1	0	0	0
1010	5	0	0	0

Represented here are five integers: 2, 4, 3, 1, and 5. These five integers occupy 32 bits (4 bytes) each with the least-significant byte stored first (this is a little-endian CPU architecture) and are stored consecutively starting at address 0x1000.

The syntax for C with pointers is:

- array means 0x1000;
- array + 1 means 0x1004: the "+ 1" means to add the size of 1 int, which is 4 bytes;
- \*array means to dereference the contents of array. Considering the contents as a memory address (0x1000), look up the value at that location (0x0002);
- array[i] means element number i, 0-based, of array which is translated into \*(array + i).

The last example is how to access the contents of array. Breaking it down:

- array + i is the memory location of the (i)<sup>th</sup> element of array, starting at i=0;
- \*(array + i) takes that memory address and dereferences it to access the value.

#### C linked list

Below is an example definition of a linked list in C.

This pointer-recursive definition is essentially the same as the reference-recursive definition from the <u>Haskell programming</u> language:

```
data Link a = Nil
| Cons a (Link a)
```

Nil is the empty list, and Cons a (Link a) is a cons cell of type a with another link also of type a.

The definition with references, however, is type-checked and does not use potentially confusing signal values. For this reason, data structures in C are usually dealt with via wrapper functions, which are carefully checked for correctness.

### Pass-by-address using pointers

Pointers can be used to pass variables by their address, allowing their value to be changed. For example, consider the following  $\underline{C}$  code:

```
/* a copy of the int n can be changed within the function without affecting the calling code */
void passByValue(int n) {
    n = 12;
}
```

```
/* a pointer m is passed instead. No copy of the value pointed to by m is created */
void passByAddress(int *m) {
    *m = 14;
}
int main(void) {
    int x = 3;
    /* pass a copy of x's value as the argument */
    passByValue(x);
    // the value was changed inside the function, but x is still 3 from here on
    /* pass x's address as the argument */
    passByAddress(&x);
    // x was actually changed by the function and is now equal to 14 here
    return 0;
}
```

### **Dynamic memory allocation**

In some programs, the required memory depends on what *the user* may enter. In such cases the programmer needs to allocate memory dynamically. This is done by allocating memory at the *heap* rather than on the *stack*, where variables usually are stored. (Variables can also be stored in the CPU registers, but that's another matter) Dynamic memory allocation can only be made through pointers, and names (like with common variables) can't be given.

Pointers are used to store and manage the addresses of <u>dynamically allocated</u> blocks of memory. Such blocks are used to store data objects or arrays of objects. Most structured and object-oriented languages provide an area of memory, called the *heap* or *free store*, from which objects are dynamically allocated.

The example C code below illustrates how structure objects are dynamically allocated and referenced. The <u>standard C library</u> provides the function <u>malloc()</u> for allocating memory blocks from the heap. It takes the size of an object to allocate as a parameter and returns a pointer to a newly allocated block of memory suitable for storing the object, or it returns a null pointer if the allocation failed.

```
/* Parts inventory item */
struct Item {
                id;
                        /* Part number
    int
    char *
                        /* Part name
                name;
                        /* Cost
    float
                cost:
;};
'/* Allocate and initialize a new Item object */
struct Item * make item(const char *name) {
    struct Item * item;
    /* Allocate a block of memory for a new Item object */
    item = (struct Item *)malloc(sizeof(struct Item));
    if (item == NULL)
        return NULL;
    /* Initialize the members of the new Item */
    memset(item, 0, sizeof(struct Item));
                 -1;
    item->id =
    item->name = NULL;
    item->cost = 0.0;
    /* Save a copy of the name in the new Item */
    item->name = (char *)malloc(strlen(name) + 1);
    if (item->name == NULL) {
        free(item);
        return NULL;
    strcpy(item->name, name);
    /* Return the newly created Item object */
    return item;
```

The code below illustrates how memory objects are dynamically deallocated, i.e., returned to the heap or free store. The standard C library provides the function free () for deallocating a previously allocated memory block and returning it back to the heap.

```
/* Deallocate an Item object */
void destroy_item(struct Item *item) {
    /* Check for a null object pointer */
    if (item == NULL)
        return;

    /* Deallocate the name string saved within the Item */
    if (item->name != NULL) {
        free(item->name);
        item->name = NULL;
    }

    /* Deallocate the Item object itself */
    free(item);
}
```

### Memory-mapped hardware

On some computing architectures, pointers can be used to directly manipulate memory or memory-mapped devices.

Assigning addresses to pointers is an invaluable tool when programming <u>microcontrollers</u>. Below is a simple example declaring a pointer of type int and initialising it to a hexadecimal address in this example the constant 0x7FFF:

```
int *hardware_address = (int *)0x7FFF;
```

In the mid 80s, using the <u>BIOS</u> to access the video capabilities of PCs was slow. Applications that were display-intensive typically used to access <u>CGA</u> video memory directly by casting the <u>hexadecimal</u> constant 0xB8000 to a pointer to an array of 80 unsigned 16-bit int values. Each value consisted of an <u>ASCII</u> code in the low byte, and a colour in the high byte. Thus, to put the letter 'A' at row 5, column 2 in bright white on blue, one would write code like the following:

```
#define VID ((unsigned short (*)[80])0xB8000)

void foo(void) {
	VID[4][1] = 0x1F00 | 'A';
}
```

## Typed pointers and casting

In many languages, pointers have the additional restriction that the object they point to has a specific <u>type</u>. For example, a pointer may be declared to point to an <u>integer</u>; the language will then attempt to prevent the programmer from pointing it to objects which are not integers, such as floating-point numbers, eliminating some errors.

For example, in C

```
int *money;
char *bags;
```

**money** would be an integer pointer and **bags** would be a char pointer. The following would yield a compiler warning of "assignment from incompatible pointer type" under <u>GCC</u>

```
bags = money;
```

because money and bags were declared with different types. To suppress the compiler warning, it must be made explicit that you do indeed wish to make the assignment by typecasting it

```
bags = (char *)money;
```

which says to cast the integer pointer of money to a char pointer and assign to bags.

A 2005 draft of the C standard requires that casting a pointer derived from one type to one of another type should maintain the alignment correctness for both types (6.3.2.3 Pointers, par. 7):<sup>[9]</sup>

In languages that allow pointer arithmetic, arithmetic on pointers takes into account the size of the type. For example, adding an integer number to a pointer produces another pointer that points to an address that is higher by that number times the size of the type. This allows us to easily compute the address of elements of an array of a given type, as was shown in the C arrays example above. When a pointer of one type is cast to another type of a different size, the programmer should expect that pointer arithmetic will be calculated differently. In C, for example, if the money array starts at 0x2000 and sizeof(int) is 4 bytes whereas sizeof(char) is 1 byte, then money + 1 will point to 0x2004, but bags + '1' would point to 0x2001. Other risks of casting include loss of data when "wide" data is written to "narrow" locations (e.g. bags[0] = 65537;), unexpected results when bit-shifting values, and comparison problems, especially with signed vs unsigned values.

Although it is impossible in general to determine at compile-time which casts are safe, some languages store <u>run-time type information</u> which can be used to confirm that these dangerous casts are valid at runtime. Other languages merely accept a conservative approximation of safe casts, or none at all.

## **Making pointers safer**

As a pointer allows a program to attempt to access an object that may not be defined, pointers can be the origin of a variety of <u>programming errors</u>. However, the usefulness of pointers is so great that it can be difficult to perform programming tasks without them. Consequently, many languages have created constructs designed to provide some of the useful features of pointers without some of their <u>pitfalls</u>, also sometimes referred to as *pointer hazards*. In this context, pointers that directly address memory (as used in this article) are referred to as **raw pointers**, by contrast with smart pointers or other variants.

One major problem with pointers is that as long as they can be directly manipulated as a number, they can be made to point to unused addresses or to data which is being used for other purposes. Many languages, including most <u>functional programming languages</u> and recent <u>imperative languages</u> like <u>Java</u>, replace pointers with a more opaque type of reference, typically referred to as simply a *reference*, which can only be used to refer to objects and not manipulated as numbers, preventing this type of error. Array indexing is handled as a special case.

A pointer which does not have any address assigned to it is called a <u>wild pointer</u>. Any attempt to use such uninitialized pointers can cause unexpected behavior, either because the initial value is not a valid address, or because using it may damage other parts of the program. The result is often a <u>segmentation fault</u>, <u>storage violation</u> or <u>wild branch</u> (if used as a function pointer or branch address).

In systems with explicit memory allocation, it is possible to create a <u>dangling pointer</u> by deallocating the memory region it points into. This type of pointer is dangerous and subtle because a deallocated memory region may contain the same data as it did before it was deallocated but may be then reallocated and overwritten by unrelated code, unknown to the earlier code. Languages with <u>garbage collection</u> prevent this type of error because deallocation is performed automatically when there are no more references in scope.

Some languages, like  $\underline{C++}$ , support  $\underline{smart\ pointers}$ , which use a simple form of  $\underline{reference\ counting}$  to help track allocation of dynamic memory in addition to acting as a reference. In the absence of reference cycles, where an object refers to itself indirectly through a sequence of smart pointers, these eliminate the possibility of dangling pointers and memory leaks.  $\underline{Delphi}$  strings support reference counting natively.

The <u>Rust programming language</u> introduces a *borrow checker*, *pointer lifetimes*, and an optimisation based around <u>optional types</u> for null pointers to eliminate pointer bugs, without resorting to a garbage collector.

## **Null pointer**

A **null pointer** has a value reserved for indicating that the pointer does not refer to a valid object. Null pointers are routinely used to represent conditions such as the end of a <u>list</u> of unknown length or the failure to perform some action; this use of null pointers can be compared to nullable types and to the *Nothing* value in an option type.

## **Autorelative pointer**

An **autorelative pointer** is a pointer whose value is interpreted as an offset from the address of the pointer itself; thus, if a data structure has an autorelative pointer member that points to some portion of the data structure itself, then the data structure may be relocated in memory without having to update the value of the auto relative pointer.<sup>[10]</sup>

The cited patent also uses the term **self-relative pointer** to mean the same thing. However, the meaning of that term has been used in other ways:

- to mean an offset from the address of a structure rather than from the address of the pointer itself;
- to mean a pointer containing its own address, which can be useful for reconstructing in any arbitrary region of memory a collection of data structures that point to each other.<sup>[11]</sup>

## **Based pointer**

A **based pointer** is a pointer whose value is an offset from the value of another pointer. This can be used to store and load blocks of data, assigning the address of the beginning of the block to the base pointer.<sup>[12]</sup>

## Multiple indirection

In some languages, a pointer can reference another pointer, requiring multiple dereference operations to get to the original value. While each level of indirection may add a performance cost, it is sometimes necessary in order to provide correct behavior for complex <u>data structures</u>. For example, in C it is typical to define a <u>linked list</u> in terms of an element that contains a pointer to the next element of the list:

```
struct element {
    struct element *next;
    int value;
};
struct element *head = NULL;
```

This implementation uses a pointer to the first element in the list as a surrogate for the entire list. If a new value is added to the beginning of the list, head has to be changed to point to the new element. Since C arguments are always passed by value, using double indirection allows the insertion to be implemented correctly, and has the desirable side-effect of eliminating special case code to deal with insertions at the front of the list:

```
// Given a sorted list at *head, insert the element item at the first
// location where all earlier elements have lesser or equal value.
void insert(struct element **head, struct element *item) {
    struct element **p; // p points to a pointer to an element
```

```
for (p = head; *p != NULL; p = &(*p)->next) {
    if (item->value <= (*p)->value)
        break;
}
item->next = *p;
*p = item;
}
// Caller does this:
insert(&head, item);
```

In this case, if the value of item is less than that of head, the caller's head is properly updated to the address of the new item.

A basic example is in the <u>argv</u> argument to the <u>main function in C (and C++)</u>, which is given in the prototype as **char** \*\*argv — this is because the variable argv itself is a pointer to an array of strings (an array of arrays), so \*argv is a pointer to the 0th string (by convention the name of the program), and \*\*argv is the 0th character of the 0th string.

## **Function pointer**

In some languages, a pointer can reference executable code, i.e., it can point to a function, method, or procedure. A <u>function</u> <u>pointer</u> will store the address of a function to be invoked. While this facility can be used to call functions dynamically, it is often a favorite technique of virus and other malicious software writers.

## **Dangling pointer**

A **dangling pointer** is a pointer that does not point to a valid object and consequently may make a program crash or behave oddly. In the <u>Pascal</u> or <u>C programming languages</u>, pointers that are not specifically initialized may point to unpredictable addresses in memory.

The following example code shows a dangling pointer:

```
int func(void) {
   char *p1 = malloc(sizeof(char)); /* (undefined) value of some place on the heap */
   char *p2;   /* dangling (uninitialized) pointer */
   *p1 = 'a';   /* This is OK, assuming malloc() has not returned NULL. */
   *p2 = 'b';   /* This invokes undefined behavior */
}
```

Here, p2 may point to anywhere in memory, so performing the assignment \*p2 = 'b'; can corrupt an unknown area of memory or trigger a segmentation fault.

## **Back pointer**

In doubly <u>linked lists</u> or <u>tree structures</u>, a back pointer held on an element 'points back' to the item referring to the current element. These are useful for navigation and manipulation, at the expense of greater memory use.

## Wild branch

Where a pointer is used as the address of the entry point to a program or start of a <u>function which doesn't return anything</u> and is also either uninitialized or corrupted, if a call or <u>jump</u> is nevertheless made to this address, a "<u>wild branch</u>" is said to have occurred. The consequences are usually unpredictable and the error may present itself in several different ways depending upon whether or not the pointer is a "valid" address and whether or not there is (coincidentally) a valid instruction (opcode) at that address. The detection of a wild branch can present one of the most difficult and frustrating debugging exercises since much of the evidence may already have been destroyed beforehand or by execution of one or more inappropriate instructions at the branch location. If available, an <u>instruction set simulator</u> can usually not only detect a wild branch before it takes effect, but also provide a complete or partial trace of its history.

## Simulation using an array index

It is possible to simulate pointer behavior using an index to an (normally one-dimensional) array.

Primarily for languages which do not support pointers explicitly but *do* support arrays, the <u>array</u> can be thought of and processed as if it were the entire memory range (within the scope of the particular array) and any index to it can be thought of as equivalent to a <u>general purpose register</u> in assembly language (that points to the individual bytes but whose actual value is relative to the start of the array, not its absolute address in memory). Assuming the array is, say, a contiguous 16 <u>megabyte</u> character <u>data structure</u>, individual bytes (or a <u>string</u> of contiguous bytes within the array) can be directly addressed and manipulated using the name of the array with a 31 bit unsigned <u>integer</u> as the simulated pointer (this is quite similar to the *C arrays* example shown above). Pointer arithmetic can be simulated by adding or subtracting from the index, with minimal additional overhead compared to genuine pointer arithmetic.

It is even theoretically possible, using the above technique, together with a suitable <u>instruction set simulator</u> to simulate <u>any machine code</u> or the intermediate (<u>byte code</u>) of <u>any processor/language</u> in another language that does not support pointers at all (for example <u>Java / JavaScript</u>). To achieve this, the <u>binary</u> code can initially be loaded into contiguous bytes of the array for the simulator to "read", interpret and action entirely within the memory contained of the same array. If necessary, to completely avoid buffer overflow problems, bounds checking can usually be actioned for the compiler (or if not, hand coded in the simulator).

## Support in various programming languages

#### Ada

<u>Ada</u> is a strongly typed language where all pointers are typed and only safe type conversions are permitted. All pointers are by default initialized to null, and any attempt to access data through a null pointer causes an <u>exception</u> to be raised. Pointers in Ada are called <u>access types</u>. Ada 83 did not permit arithmetic on access types (although many compiler vendors provided for it as a non-standard feature), but Ada 95 supports "safe" arithmetic on access types via the package System.Storage\_Elements.

#### **BASIC**

Several old versions of <u>BASIC</u> for the Windows platform had support for STRPTR() to return the address of a string, and for VARPTR() to return the address of a variable. Visual Basic 5 also had support for OBJPTR() to return the address of an object interface, and for an ADDRESSOF operator to return the address of a function. The types of all of these are integers, but their values are equivalent to those held by pointer types.

Newer dialects of <u>BASIC</u>, such as <u>FreeBASIC</u> or <u>BlitzMax</u>, have exhaustive pointer implementations, however. In FreeBASIC, arithmetic on ANY pointers (equivalent to C's void\*) are treated as though the ANY pointer was a byte width. ANY pointers cannot be dereferenced, as in C. Also, casting between ANY and any other type's pointers will not generate any warnings.

```
dim as integer f = 257
dim as any ptr g = @f
dim as integer ptr i = g
```

```
assert(*i = 257)
assert( (g + 4) = (@f + 1) )
```

#### C and C++

In  $\underline{C}$  and  $\underline{C++}$  pointers are variables that store addresses and can be null. Each pointer has a type it points to, but one can freely cast between pointer types (but not between a function pointer and an object pointer). A special pointer type called the "void pointer" allows pointing to any (non-function) object, but is limited by the fact that it cannot be dereferenced directly (it shall be cast). The address itself can often be directly manipulated by casting a pointer to and from an integral type of sufficient size, though the results are implementation-defined and may indeed cause undefined behavior; while earlier C standards did not have an integral type that was guaranteed to be large enough,  $\underline{C99}$  specifies the  $uintptr_t$  typedef name defined in  $\underline{<stdint.h>}$ , but an implementation need not provide it.

 $\underline{C}^{++}$  fully supports C pointers and C typecasting. It also supports a new group of typecasting operators to help catch some unintended dangerous casts at compile-time. Since  $\underline{C}^{++}$  the  $\underline{C}^{++}$  standard library also provides smart pointers (unique\_ptr, shared\_ptr and weak\_ptr) which can be used in some situations as a safer alternative to primitive C pointers. C++ also supports another form of reference, quite different from a pointer, called simply a *reference* or *reference* type.

**Pointer arithmetic**, that is, the ability to modify a pointer's target address with arithmetic operations (as well as magnitude comparisons), is restricted by the language standard to remain within the bounds of a single array object (or just after it), and will otherwise invoke <u>undefined behavior</u>. Adding or subtracting from a pointer moves it by a multiple of the size of its <u>datatype</u>. For example, adding 1 to a pointer to 4-byte integer values will increment the pointer's pointed-to byte-address by 4. This has the effect of incrementing the pointer to point at the next element in a contiguous array of integers—which is often the intended result. Pointer arithmetic cannot be performed on **Void** pointers because the <u>void type</u> has no size, and thus the pointed address can not be added to, although <u>gcc</u> and other compilers will perform byte arithmetic on **Void\*** as a non-standard extension, treating it as if it were **Char\***.

Pointer arithmetic provides the programmer with a single way of dealing with different types: adding and subtracting the number of elements required instead of the actual offset in bytes. (Pointer arithmetic with char \* pointers uses byte offsets, because sizeof(char) is 1 by definition.) In particular, the C definition explicitly declares that the syntax a[n], which is the n-th element of the array a, is equivalent to \*(a + n), which is the content of the element pointed by a + n. This implies that n[a] is equivalent to a[n], and one can write, e.g., a[3] or a[a] equally well to access the fourth element of an array a.

While powerful, pointer arithmetic can be a source of <u>computer bugs</u>. It tends to confuse novice <u>programmers</u>, forcing them into different contexts: an expression can be an ordinary arithmetic one or a pointer arithmetic one, and sometimes it is easy to mistake one for the other. In response to this, many modern high-level computer languages (for example <u>Java</u>) do not permit direct access to memory using addresses. Also, the safe C dialect <u>Cyclone</u> addresses many of the issues with pointers. See <u>C programming language</u> for more discussion.

The **void pointer**, or **void\***, is supported in ANSI C and C++ as a generic pointer type. A pointer to **void** can store the address of any object (not function), and, in C, is implicitly converted to any other object pointer type on assignment, but it must be explicitly cast if dereferenced. K&R C used **char\*** for the "type-agnostic pointer" purpose (before ANSI C).

C++ does not allow the implicit conversion of **void\*** to other pointer types, even in assignments. This was a design decision to avoid careless and even unintended casts, though most compilers only output warnings, not errors, when encountering other casts.

```
int x = 4;
void* p1 = &x;
```

In C++, there is no Void& (reference to void) to complement Void\* (pointer to void), because references behave like aliases to the variables they point to, and there can never be a variable whose type is Void.

#### Pointer declaration syntax overview

These pointer declarations cover most variants of pointer declarations. Of course it is possible to have triple pointers, but the main principles behind a triple pointer already exist in a double pointer.

```
char cff [5][5];  /* array of arrays of chars */
char *cfp [5];  /* array of pointers to chars */
char **cpp;  /* pointer to pointer to char ("double pointer") */
char (*cpf) [5];  /* pointer to array(s) of chars */
char *cpF();  /* function which returns a pointer to char(s) */
char (*CFp)();  /* pointer to a function which returns a char */
char (*cfpF())[5]; /* function which returns pointer to an array of chars */
char (*cpFf[5])();  /* an array of pointers to functions which return a char */
```

The () and [] have a higher priority than \*. [13]

#### C#

In the <u>C# programming language</u>, pointers are supported only under certain conditions: any block of code including pointers must be marked with the unsafe keyword. Such blocks usually require higher security permissions to be allowed to run. The syntax is essentially the same as in C++, and the address pointed can be either <u>managed</u> or <u>unmanaged</u> memory. However, pointers to managed memory (any pointer to a managed object) must be declared using the fixed keyword, which prevents the <u>garbage</u> <u>collector</u> from moving the pointed object as part of memory management while the pointer is in scope, thus keeping the pointer address valid.

An exception to this is from using the IntPtr structure, which is a safe managed equivalent to int\*, and does not require unsafe code. This type is often returned when using methods from the System.Runtime.InteropServices, for example:

```
// Get 16 bytes of memory from the process's unmanaged memory
IntPtr pointer = System.Runtime.InteropServices.Marshal.AllocHGlobal(16);
// Do something with the allocated memory
// Free the allocated memory
System.Runtime.InteropServices.Marshal.FreeHGlobal(pointer);
```

The <u>.NET</u> framework includes many classes and methods in the System and System.Runtime.InteropServices namespaces (such as the Marshal class) which convert .NET types (for example, System.String) to and from many <u>unmanaged</u> types and pointers (for example, LPWSTR or void\*) to allow communication with <u>unmanaged code</u>. Most such methods have the same security permission requirements as unmanaged code, since they can affect arbitrary places in memory.

#### COBOL

The <u>COBOL</u> programming language supports pointers to variables. Primitive or group (record) data objects declared within the LINKAGE SECTION of a program are inherently pointer-based, where the only memory allocated within the program is space for the address of the data item (typically a single memory word). In program source code, these data items are used just like any other WORKING-STORAGE variable, but their contents are implicitly accessed indirectly through their LINKAGE pointers.

Memory space for each pointed-to data object is typically <u>allocated dynamically</u> using external <u>CALL</u> statements or via embedded extended language constructs such as <u>EXEC</u> CICS or EXEC SQL statements.

Extended versions of COBOL also provide pointer variables declared with USAGE IS POINTER clauses. The values of such pointer variables are established and modified using SET and SET ADDRESS statements.

Some extended versions of COBOL also provide PROCEDURE - POINTER variables, which are capable of storing the <u>addresses</u> of executable code.

#### PL/I

The <u>PL/I</u> language provides full support for pointers to all data types (including pointers to structures), <u>recursion</u>, <u>multitasking</u>, string handling, and extensive built-in <u>functions</u>. PL/I was quite a leap forward compared to the programming languages of its time. PL/I pointers are untyped, and therefore no casting is required for pointer dereferencing or assignment. The declaration syntax for a pointer is DECLARE xxx POINTER;, which declares a pointer named "xxx". Pointers are used with BASED variables. A based variable can be declared with a default locator (DECLARE xxx BASED(ppp); or without (DECLARE xxx BASED;), where xxx is a based variable, which may be an element variable, a structure, or an array, and ppp is the default pointer). Such a variable can be address without an explicit pointer reference (xxx=1;, or may be addressed with an explicit reference to the default locator (ppp), or to any other pointer (qqq->xxx=1;).

Pointer arithmetic is not part of the PL/I standard, but many compilers allow expressions of the form  $ptr = ptr \pm expression$ . IBM PL/I also has the builtin function PTRADD to perform the arithmetic. Pointer arithmetic is always performed in bytes.

IBM *Enterprise* PL/I compilers have a new form of typed pointer called a HANDLE.

#### D

The D programming language is a derivative of C and C++ which fully supports C pointers and C typecasting.

#### **Eiffel**

The <u>Eiffel</u> object-oriented <u>language</u> employs value and reference semantics without pointer arithmetic. Nevertheless, pointer classes are provided. They offer pointer arithmetic, typecasting, explicit memory management, interfacing with non-Eiffel software, and other features.

#### **Fortran**

<u>Fortran-90</u> introduced a strongly typed pointer capability. Fortran pointers contain more than just a simple memory address. They also encapsulate the lower and upper bounds of array dimensions, strides (for example, to support arbitrary array sections), and other metadata. An *association operator*, => is used to associate a POINTER to a variable which has a TARGET attribute. The Fortran-90 ALLOCATE statement may also be used to associate a pointer to a block of memory. For example, the following code might be used to define and create a linked list structure:

```
type real_list_t
  real :: sample_data(100)
  type (real_list_t), pointer :: next => null ()
end type

type (real_list_t), target :: my_real_list
type (real_list_t), pointer :: real_list_temp

real_list_temp => my_real_list
do
  read (1,iostat=ioerr) real_list_temp%sample_data
  if (ioerr /= 0) exit
  allocate (real_list_temp%next)
  real_list_temp => real_list_temp%next
end do
```

Fortran-2003 adds support for procedure pointers. Also, as part of the *C Interoperability* feature, Fortran-2003 supports intrinsic functions for converting C-style pointers into Fortran pointers and back.

#### Go

<u>Go</u> has pointers. Its declaration syntax is equivalent to that of C, but written the other way around, ending with the type. Unlike C, Go has garbage collection, and disallows pointer arithmetic. Reference types, like in C++, do not exist. Some built-in types, like maps and channels, are boxed (i.e. internally they are pointers to mutable structures), and are initialized using the make function. In an approach to unified syntax between pointers and non-pointers, the arrow (->) operator has been dropped: the dot operator on a pointer refers to the field or method of the dereferenced object. This, however, only works with 1 level of indirection.

#### Java

Unlike <u>C</u>, <u>C++</u>, or <u>Pascal</u>, there is no explicit representation of pointers in <u>Java</u>. Instead, more complex data structures like <u>objects</u> and <u>arrays</u> are implemented using <u>references</u>. The language does not provide any explicit pointer manipulation operators. It is still possible for code to attempt to dereference a null reference (null pointer), however, which results in a run-time <u>exception</u> being thrown. The space occupied by unreferenced memory objects is recovered automatically by garbage collection at run-time. [14]

### Modula-2

Pointers are implemented very much as in Pascal, as are VAR parameters in procedure calls. <u>Modula-2</u> is even more strongly typed than Pascal, with fewer ways to escape the type system. Some of the variants of Modula-2 (such as <u>Modula-3</u>) include garbage collection.

#### Oberon

Much as with Modula-2, pointers are available. There are still fewer ways to evade the type system and so <u>Oberon</u> and its variants are still safer with respect to pointers than Modula-2 or its variants. As with <u>Modula-3</u>, garbage collection is a part of the language specification.

### **Pascal**

Unlike many languages that feature pointers, standard  $\underline{ISO}$   $\underline{Pascal}$  only allows pointers to reference dynamically created variables that are anonymous and does not allow them to reference standard static or local variables. It does not have pointer arithmetic. Pointers also must have an associated type and a pointer to one type is not compatible with a pointer to another type (e.g. a pointer to a char is not compatible with a pointer to an integer). This helps eliminate the type security issues inherent with other pointer implementations, particularly those used for  $\underline{PL/I}$  or  $\underline{C}$ . It also removes some risks caused by  $\underline{dangling}$   $\underline{pointers}$ , but the ability to dynamically let go of referenced space by using the  $\underline{dispose}$  standard procedure (which has the same effect as the  $\underline{free}$  library function found in  $\underline{C}$ ) means that the risk of dangling pointers has not been entirely eliminated.

However, in some commercial and open source Pascal (or derivatives) compiler implementations —like Free Pascal, [17] Turbo Pascal or the Object Pascal in Embarcadero Delphi— a pointer is allowed to reference standard static or local variables and can be cast from one pointer type to another. Moreover, pointer arithmetic is unrestricted: adding or subtracting from a pointer moves it by that number of bytes in either direction, but using the Inc or Dec standard procedures with it moves the pointer by the size of the data type it is declared to point to. An untyped pointer is also provided under the name Pointer, which is compatible with other pointer types.

#### Perl

The <u>Perl programming language</u> supports pointers, although rarely used, in the form of the pack and unpack functions. These are intended only for simple interactions with compiled OS libraries. In all other cases, Perl uses <u>references</u>, which are typed and do not allow any form of pointer arithmetic. They are used to construct complex data structures.<sup>[18]</sup>

### See also

- Address constant
- Bounded pointer
- Buffer overflow
- Fat pointer
- Function pointer
- Hazard pointer
- Opaque pointer
- Pointer swizzling
- Reference (computer science)
- Static program analysis
- Storage violation
- Tagged pointer
- Variable (computer science)

### References

- 1. Donald Knuth (1974). "Structured Programming with go to Statements" (https://web.archive.org/web/2009082407 3244/http://pplab.snu.ac.kr/courses/adv\_pl05/papers/p261-knuth.pdf) (PDF). Computing Surveys. 6 (5): 261–301. doi:10.1145/356635.356640 (https://doi.org/10.1145%2F356635.356640). Archived from the original (http://pplab.snu.ac.kr/courses/adv\_pl05/papers/p261-knuth.pdf) (PDF) on August 24 2009
- "Milestones in Computer Science and Information Technolog C&pg=PA204&lpg=PA204&dq=Harold+Lawson+pointer&sou H9xgEmxD5qzBc&hl=en&ei=lCuLSbTwKY\_-0AWErp2iBw&s Books.google.com. Retrieved 2018-04-13.
- "IEEE Computer Society awards list" (http://awards.compute Awards.computer.org. Retrieved 2018-04-13.
- 4. ISO/IEC 9899, clause 6.7.5.1, paragraph 1.
- 5. ISO/IEC 9899, clause 6.7.8, paragraph 10.
- 6. ISO/IEC 9899, clause 7.17, paragraph 3: NULL... which experience on the constant...
- In computer science, an **abstract data type** (**ADT**) is a mathematical model for data types, where a data type is defined by its behavior (semantics) from the point of view of a *user* of the data, specifically in terms of possible values, possible operations on data of this type, and the behavior of these operations. This contrasts with data structures.
- 7. <u>ISO/IEC 9899</u>, clause 6.5.3.2, paragraph 4, footnote 87: *If an invalid value has been assigned to the pointer, the behavior of the unary \* operator is undefined...* Among the invalid values for dereferencing a pointer by the unary \* operator are a null pointer...
- 8. <u>Plauger, P J</u>; Brodie, Jim (1992). *ANSI and ISO Standard C Programmer's Reference*. Redmond, WA: Microsoft Press. pp. 108, 51. <u>ISBN</u> <u>1-55615-359-7</u>. "An array type does not contain additional holes because all other types pack tightly when composed into arrays [at page 51]"
- 9. WG14 N1124 (http://www.open-std.org/jtc1/sc22/wg14/www/docs/n1124.pdf), C Approved standards: ISO/IEC 9899 Programming languages C (http://www.open-std.org/jtc1/sc22/wg14/www/standards.html), 2005-05-06.
- us patent 6625718 (https://worldwide.espacenet.com/textdoc?DB=EPODOC&IDX=us6625718), Steiner, Robert C. (Broomfield, CO), "Pointers that are relative to their own present locations", issued 2003-09-23, assigned to Avaya Technology Corp. (Basking Ridge, NJ)
- 11. us patent 6115721 (https://worldwide.espacenet.com/textdoc?DB=EPODOC&IDX=us6115721), Nagy, Michael (Tampa, FL), "System and method for database save and restore using self-pointers", issued 2000-09-05, assigned to IBM (Armonk, NY)
- 12. "Based Pointers" (http://msdn.microsoft.com/en-us/library/57a97k4e.aspx). Msdn.microsoft.com. Retrieved 2018-04-13.
- 13. Ulf Bilting, Jan Skansholm, "Vägen till C" (the Road to C), third edition, page 169, ISBN 91-44-01468-6

- 14. Nick Parlante, [1] (http://cslibrary.stanford.edu/102/PointersAndMemory.pdf#%22Pointers%20and%20Memory%2 2), Stanford Computer Science Education Library (http://cslibrary.stanford.edu#), pp. 9–10 (2000).
- 15. ISO 7185 Pascal Standard (unofficial copy), section <u>6.4.4 Pointer-types</u> (http://standardpascal.org/iso7185.html# 6.4.4%20Pointer-types) and subsequent.
- 16. J. Welsh, W. J. Sneeringer, and C. A. R. Hoare, "Ambiguities and Insecurities in Pascal," *Software Practice and Experience* 7, pp. 685–696 (1977)
- 17. Free Pascal Language Reference guide, section 3.4 Pointers (http://www.freepascal.org/docs-html/ref/refse15.html/x43-490003.4)
- 18. Contact details. "// Making References (Perl References and nested data structures)" (http://perldoc.perl.org/perlr ef.html#Making-References). Perldoc.perl.org. Retrieved 2018-04-13.

### **External links**

- PL/I List Processing (https://www.researchgate.net/publication/220424487\_PLI\_list\_processing)
   Paper from the June, 1967 issue of CACM
- cdecl.org (https://cdecl.org) A tool to convert pointer declarations to plain English
- Over IQ.com (https://overiq.com/c-programming-101/pointer-basics-in-c/) A beginner level guide describing pointers in a plain English.
- Pointers and Memory (http://cslibrary.stanford.edu/) Introduction to pointers Stanford Computer Science Education Library
- Pointers in C programming (http://www.onlinecomputerteacher.net/pointers-in-c.html) A visual model for the beginners in C programming
- Opointer.de (http://Opointer.de/) A terse list of minimum length source codes that dereference a null pointer in several different programming languages
- "The C book" containing pointer examples in ANSI C (https://publications.gbdirect.co.uk/c\_book/chapter5/pointe rs.html)
- Joint Technical Committee ISO/IEC JTC 1, Subcommittee SC 22, Working Group WG 14 (2007-09-08).
   International Standard ISO/IEC 9899 (http://www.open-std.org/jtc1/sc22/WG14/www/docs/n1256.pdf) (PDF).
   Committee Draft..

Retrieved from "https://en.wikipedia.org/w/index.php?title=Pointer\_(computer\_programming)&oldid=880768151"

This page was last edited on 29 January 2019, at 10:42 (UTC).

Text is available under the Creative Commons Attribution-ShareAlike License; additional terms may apply. By using this site, you agree to the Terms of Use and Privacy Policy. Wikipedia® is a registered trademark of the Wikimedia Foundation, Inc., a non-profit organization.