Package 'raster'

February 27, 2012

• • •
Type Package
Title Geographic analysis and modeling with raster data
Version 1.9-70
Date 27-February-2012
Depends methods, sp, R ($>= 2.11.0$)
Suggests rgdal (>= 0.5-33), rgeos (>= 0.2-1), ncdf, igraph, snow,tcltk
Author Robert J. Hijmans & Jacob van Etten
Maintainer Robert J. Hijmans <r.hijmans@gmail.com></r.hijmans@gmail.com>
Description Reading, writing, manipulating, analyzing and modeling of gridded spatial data. The package implements basic and high-level functions, as well as map algebra. Processing of very large files is supported.
License GPL (>= 3)
<pre>URL http://raster.r-forge.r-project.org/</pre>
Repository CRAN
Date/Publication 2012-02-27 09:28:05
R topics documented:
raster-package 1 addLayer 1 adjacency 1 adjacent 1 aggregate 1' alignExtent 1 approxNA 1 area 2
A side second and

as.data.frame	2
as.logical	3
as.matrix	4
as.raster	5
atan2	5
autocorrelation	6
bands	7
blockSize	8
boxplot	
brick	0
buffer	
calc	
cellFrom	
cellsFromExtent	
cellStats	
clearValues	
click	
clump	-
cluster	
compare	
Compare-methods	
contour	
· · · · · · · · · · · · · · · · · · ·	
crosstab	
cut	
ev	
datasource	
dataType	
density	
dim	
direction	
disaggregate	
distance	
distanceFromPoints	
draw	2
drawExtent	2
edge	3
expand	4
extension	6
extent	7
Extent coordinates	8
Extent math	9
Extent-class	0
extract	1
Extract by index	4
extremeValues	

factors	 . //
filename	 . 78
filledContour	 . 78
flip	 79
focal	
freq	
Gain and offset	
getData	
getValues	
getValuesBlock	
gridDistance	
hdr	
head	
hillShade	
hist	
image	
inifile	
initialize	 95
interpolate	 . 96
intersect	 98
intersectExtent	 99
isLonLat	 100
KML	 100
Logic-methods	
mask	
match	
Math-methods	
merge	
modal	
mosaic	
movingFun	
NAvalue	
ncell	
nlayers	
obsolete	113
Options	
origin	
overlay	 115
pairs	 118
persp	 119
plot	 120
plotRGB	 122
pointDistance	
predict	
Programming	
projection	
projectRaster	
properties	
properties	 132

quantile														 133
raster														 134
Raster-class												 		 137
rasterFromCells												 		 139
rasterFromXYZ												 		 140
rasterize												 		 141
rasterTmpFile												 		 144
rasterToContour														
rasterToPoints														
rasterToPolygons .														
readAll														
reclass														
rectify														150
replacement														151
resample														151
resolution														152
rotate														153
rotated														 100
round														
rowFromCell														
SampleInt														
sampleRandom														
sampleRegular														
sampickegular saverasterstack														
scalebar														
setExtent														
setMinMax														
setValues														
shift														
Slope and aspect .														
spplot														
stack														
stack stack Apply														
stackApply stackSelect														
subset														
substitute														
Summary														
Summary-methods														
terrain														
transpose														
trim														
union														
unionExtent														
unique														
unstack														
update														
validCell														
which		 										 		 182

rostar pockoga	4
raster-package	

rast	er-package			Αr	ıo	ve	rv	iev	v e	of	th	e f	ш	nci	tio	ns	ir	ı t	his	s p	a	cke	ag	e											
Index																																		1	94
	zoom			•	•			٠	•	•	•	•	•			•	•	•	•	•	•		•	٠	•	•	•	•	•	•	•	•	•	. 1	92
	zonal																																		
	zApply																																		
	z-values																																		
xyFromCell																																		. 1	8
writeValues																																			
	writeRaster																																	. 1	84
	writeFormats .																																		

Description

The raster package provides classes and functions to manipulate geographic (spatial) data in 'raster' format. Raster data divides space into cells (rectangles; pixels) of equal size (in units of the coordinate reference system). Such data are also referred to as 'grid' data.

The package should be particularly useful when using very large datasets that can not be loaded into the computer's memory. Functions will work correctly, because they they process large files in chunks, i.e., they read, compute, and write blocks of data, without loading all values into memory at once.

Below is a list of functions grouped by theme. See the vignette for more information and some examples (you can open it by running this command: vignette('Raster'))

Details

The package implements classes for Raster data (see Raster-class) and supports

- Creation of Raster* objects from scratch or from file
- · Handling extremely large raster files
- · Raster algebra and overlay functions
- Distance, neighborhood (focal) and patch functions
- Polygon, line and point to raster conversion
- · Model predictions
- Summarizing raster values
- Easy access to raster cell-values
- Plotting (making maps)
- Manipulation of raster extent, resolution and origin
- Computation of row, col and cell numbers to coordinates and vice versa
- · Reading and writing various raster file types

I. Creating Raster* objects

Raster* objects can be created, from scracth, files, or from objects of other classes, with the following functions:

raster To create a RasterLayer stack To create a RasterStack (multiple layers)

brick To create a RasterBrick (multiple layers)

addLayer Add a layer to a Raster* object

dropLayer Remove a layer from a RasterStack or RasterBrick unstack Create a list of RasterLayer objects from a RasterStack

RasterLayer, RasterStack, and RasterBrick objects are, as a group, referred to as Raster* objects

II. Changing the spatial extent and/or resolution of Raster* objects

merge Combine Raster* objects with different extents (but same origin and resolution)

mosaic Combine RasterLayers with different extents and a function to set values in overlap areas

crop Select a geographic subset of a Raster* object

expand Enlarge a Raster* object

trim Trim a Raster* object by removing exterior rows and/or columns that only have NA values

aggregate Combine cells of a Raster* object to create larger cells

disaggregate Subdivide cells

resample Warp values to a Raster* object with a different origin or resolution

projectRaster Warp values to a Raster* object with a different coordinate reference system

shift Move the location of Raster

flip Flip values horizontally or vertically

rotate Rotate values around the date-line (for lon/lat data)

t Transpose a Raster* object

III. Raster algebra

```
Arith-methods Arith functions (+, -, *, ^, %%, %/%, /)
```

Math-methods Math functions (abs, sqrt, trunc, log, log10, exp, sin, round among others)

Logic-methods Logic functions (!, &, |)

Summary-methods Summary functions (mean, max, min, range, prod, sum, any, all)

Compare-methods Compare functions (==, !=, >, <, <=, >=)

IV. Cell based computation

calc Computations on a single Raster* object overlay Computations on multiple RasterLayer objects

cover First layer covers second layer except where the first layer is NA

mask Use values from first Raster except where cells of the mask Raster are NA (these become NA)

cut Reclassify values using ranges

subs Reclassify values using a 'is-becomes' matrix reclass Reclassify using a 'from-to-becomes' matrix

init Initialize cells with new values

stackApply Computations on groups of layers in Raster* object

stackSelect Select cell values from different layers using an index RasterLayer

V. Spatial contextual computation

distance Shortest distance to a cell that is not NA

gridDistance Distance when traversing grid cells that are not NA
distanceFromPoints Shortest distance to any point in a set of points
direction Direction (azimuth) to or from cells that are not NA
focal Focal (neighborhood; moving window) functions

edge Edge detection clump Find clumps (patches)

adjacency Identify cells that are adjacent to a set of cells on a raster

area Compute area of cells (for longitude/latitude data)

terrain Compute slope, aspect and other characteristics from elevation data

Moran Compute global or local Moran or Geary indices of spatial autocorrelation

VI. Model predictions

predict Predict a non-spatial model to a RasterLayer interpolate Predict a spatial model to a RasterLayer

VII. Data type conversion

rasterize Rasterizing points, lines or polygons
rasterToPoints Create points from a RasterLayer
rasterToContour Contour lines from a RasterLayer
RasterI aver from regularly spaces points.

 ${\bf raster From XYZ} \qquad \quad {\bf Raster Layer \ from \ regularly \ spaces \ points}$

rasterFromCells RasterLayer from a Raster object and cell numbers raster RasterLayer from SpatialGrid*, image, or matrix objects

You can coerce Raster* objects to Spatial* objects using as, as in as (object, 'SpatialGridDataFrame')

VIII. Summarizing

cellStats Summarize a Raster cell values with a function Summary of the values of a Raster* object (quartiles and mean)

freq Frequency table of Raster cell values

count Count the frequency of a single (range of) value(s)

crosstab Cross-tabulate two RasterLayer objects unique Get the unique values in a Raster* object

zonal Summarize a Raster* object by zones in a RasterLayer

IX. Accessing values of Raster* object cells

getValues Get all cell values (fails with very large rasters), or a row of values (safer) Get values for a block (a rectangular area defined by start and end row and column getValuesBlock Get cell values as a matrix as.matrix Get cell values as an array as.array Extract cell values from a Raster* object (e.g., by cell, coordinates, polygon) extract Random sample sampleRandom sampleRegular Regular sample Get the minimum value of the cells of a Raster* object (not always known) minValue

maxValue Get the maximum value of the cells of a Raster* object (not always known)

setMinMax Compute the minimum and maximum value of a Raster* object if these are not known

You can also use indexing with [for cell numbers, and [[for row / column number combinations

X. Plotting

Maps

plot Plot a Raster* object. The main method to create a map

plotRGB Combine three layers (red, green, blue channels) into a single 'real color' image

spplot Plot a Raster* with the spplot function (sp package)

imagePlot a Raster* with the image functionperspPerspective plot of a RasterLayercontourContour plot of a RasterLayerfilledContourFilled contour plot of a RasterLayer

text Plot the values of a RasterLayer on top of a map

The rasterVis packages has additional plotting methods for Raster objects using methods from the

lattice package and from other packages.

Interacting with a map (plot of a RasterLayer)

zoom in on a plot of a RasterLayer

click Draw points and/or query values of RasterLayer by clicking on a map

drawPolydrawLinedrawExtentCreate a SpatialLines object by drawing itdrawExtentdrawExtentCreate an Extent object by drawing it

Other plots

plot x-y scatter plot of values of two RasterLayer objects

hist Histogram of Raster* object values
density Density plot of Raster* object values

pairsPairs plot for layers in a RasterStack or RasterBrickboxplotBox plot of the values of one or multiple layers

XI. Getting and setting Raster* dimensions

Basic parameters of existing Raster* objects can be obtained, and in most cases changed, with:

ncol The number of columns nrow The number of rows

ncell The number of cells (can not be set directly, only via ncol or nrow)

res The resolution (x and y)

xres The x resolution (can be set with res)
yres The y resolution (can be set with res)
xmin The minimum x coordinate (or longitude)
xmax The maximum x coordinate (or longitude)
ymin The minimum y coordinate (or latitute)
ymax The maximum y coordinate (or latitute)

extent The extent (minimum and maximum x and y coordinates)

origin The origin of a Raster* object

projection The coordinate reference system (map projection)

isLonLat Test if an object has a longitude/latitude coordinate reference system

filename Filename to which a RasterLayer or RasterBrick is linked

band Band (layer) of a multi-band file that this RasterLayer is linked to

nbands How many bands (layers) does the file have?

compare Compare for equality the basic parameters of two Raster* objects

NAvalue Get or set the NA value (for reading from file; see writeRaster for setting it when writing a file)

If there are values associated with a RasterLayer object (either in memory or via a link to a file) these are lost when you change the number of columns or rows or the resolution. This is not the case when the extent is changed (as the number of columns and rows will not be affected). Simlarly, with **projection** you can set the projection, but this does not transform the data (see projectRaster

for that).

XII. Computing row, column, cell numbers and coordinates

Cell numbers start at 1 in the upper-left corner. They increase within rows, from left to right, and then row by row from top to bottom. Likewise, row numbers start at 1 at the top of the raster, and column numbers start at 1 at the left side of the raster.

xFromCol x-coordinates from column numbers
yFromRow y-coordinates from row numbers
xFromCell x-coordinates from row numbers
yFromCell y-coordinates from cell numbers
xyFromCell x and y coordinates from cell numbers

colFromX Column numbers from x-coordinates (or longitute)
rowFromY Row numbers from y-coordinates (or latitute)
cellFromXY Cell numbers from x and y coordinates
cellFromRowCol Cell numbers from row and column numbers

cellsFromExtent Cell numbers from extent object coordinates x and y coordinates for all cells validCell Is this a valid cell number?

validCol Is this a valid column number?
validRow Is this a valid row number?

XIII. Writing files

Basic writing

setValues Put new values in a Raster* object writeRaster Write all values of Raster* object to disk

KML Save raster as KML file

Advanced writing of entire files or parts thereof

blockSize Get suggested block size for reading and writing

writeStart Open a file for writing
writeValues Write some values
writeStop Close the file after writing

update Change the values of an existing file

XIV. Extent objects

extent Create an extent object
intersect Intersect two extent objects
union Combine two extent objects

round round/floor/ceiling of the coordinates of an Extent object

```
alignExtent Align an extent with a Raster* object
drawExtent Create an Extent object by drawing it on top of a map (see plot)
```

You can also use S4 type coercion such as as(extent, 'SpatialPolygons')

XV. Options

setOptionsSet session optionsshowOptionsShow session optionssaveOptionsSave session options to make them persistentclearOptionsSet session options to default values

XVI. Miscellaneous

getData Download and geographic data pointDistance Distance between points readIniFile Read a (windows) 'ini' file

hdr Write header file for a number of raster formats

trim Remove leading and trainling blanks from a character string

extension Get or set the extentsion of a filename

cv Coefficient of variation

modal Modal value

sampleInt Random sample of (possibly very large) range of integer values

showTmpFiles Show temporary files removeTmpFiles Remove temporary files

XVII. For programmers

canProcessInMemory
pbCreate
 Initialize a progress bar
pbStep
 pbClose
 openConnection
closeConnection

Close a file can be created in memory
Initialize a progress bar
Close a progress bar
Open a file connection
Close a file connection

rasterTmpFile Get a name for a temporary file inMemory Are the cell values in memory? fromDisk Are the cell values read from a file?

addLayer 13

Acknowledgements

Extensive suggestions were made by Jonathan Greenberg, Agustin Lobo, Matteo Mattiuzzi, Steven Mosher, and Kevin Ummel. Contributions were also made by Neil Best, Andrew Bevan, Roger Bivand, Isabelle Boulangeat, Lyndon Estes, Josh Gray, Tim Haering, Herry Herry, Paul Hiemstra, Ned Hornig, Mayeul Kauffmann, Rainer Krug, Alice Laborte, John Lewis, Lennon Li, Justin McGrath, Richard Plant, Edzer Pebesma, Oscar Perpinan Lamigueiro, Etienne Racine, David Ramsey, Michael Sumner, Stefan Schlaffer, Jon Olav Skoien, Shaun Walbridge, Julian Zeidler, and others.

Author(s)

Robert J. Hijmans and Jacob van Etten

Maintainer: Robert J. Hijmans < r. hijmans@gmail.com>

addLayer

Add or drop a layer

Description

Add a layer to a Raster* object or drop a layer from a RasterStack or RasterBrick. The object returned is always a RasterStack (unless nothing to add or drop was provided, in which case the original object is returned).

Usage

```
addLayer(x, ...)
dropLayer(x, i, ...)
```

Arguments

x Raster object

i Indices of the layers to be dropped

... Additional arguments (none)

Value

RasterStack

Author(s)

Robert J. Hijmans

See Also

subset

14 adjacency

Examples

```
file <- system.file("external/test.grd", package="raster")
s <- stack(file, file, file)
r <- raster(file)
s <- addLayer(s, r/2, r*2)
s
s <- dropLayer(s, c(3, 5))
nlayers(s)</pre>
```

adjacency

Pairs of adjacent cells

Description

Identify pairs of cells that are adjacent.

Usage

```
adjacency(x, fromCells, toCells, directions)
```

Arguments

X	Raster* object
fromCells	a vector of cell numbers for which adjacent cells should be calculated

toCells a vector of cell numbers from which adjacent cells are selected. You can use the

adjacent function if you want all cells to be considered

directions in how many direction cells should be connected: 4, 8 or 16; or "bishop"

Details

Cell numbers start with 1 in the upper-left corner and increase from left to right and from top to bottom.

Number of directions: 4 connects cells with one-cell rook moves, 8 with one-cell queen moves, and 16 with knight and one-cell queen moves. "bishop" connects cells with one-cell diagonal moves.

The function connects the outer meridians for global rasters with a longitude/latitude coordinate reference system.

Value

A two column matrix with each row containing a pair of adjacent cells.

Author(s)

Jacob van Etten <jacobvanetten@yahoo.com>

adjacent 15

See Also

adjacent

Examples

```
r <- raster(nrows=10, ncols=10)</pre>
adj \leftarrow adjacency(r, fromCells = c(1,30,55,72,100),
toCells = 1:ncell(r), directions=4)
# put the result in a RasterLayer
r[] <- 0
r[c(1,30,55,72,100)] <- 1
r[adj[,2]] <- 2
plot(r)
# How many time does one cell value occur next to another cell value?
r <- raster(ncol=10, nrow=10)
set.seed(0)
r[] <- round(runif(ncell(r)) * 5)
a <- adjacency(r, 1:ncell(r), 1:ncell(r), 8)</pre>
v1 <- r[a[,1]]
v2 <- r[a[,2]]
m <- matrix(0, nrow=5,ncol=5)</pre>
for(i in 1:length(v1)) {m[v1[i], v2[i]] <- m[v1[i], v2[i]] +1}</pre>
```

adjacent

Adjacent cells

Description

Identify cells that are adjacent to a set of cells on a raster. See adjacency for an alternative implementation.

Usage

```
adjacent(x, cells, directions=4, pairs=FALSE, target=NULL, sorted=FALSE, include=FALSE, id=FALSE)
```

Arguments

X	Raster* object
cells	vector of cell numbers for which adjacent cells should be found
directions	the number of directions in which cells should be connected: 4 (rook's case), 8 (queen's case), 16, or 'bishop'. Or a neighborhood matrix (see Details)
pairs	logical. If TRUE, a matrix of pairs of adjacent cells is returned. If FALSE, a vector of cells adjacent to cells is returned

16 adjacent

target	optional vector of target cell numbers that should be considered. All other adjacent cells are ignored
sorted	logical. Should the results be sorted?
include	logical. Should the focal cells be included in the result?
id	logical. Should the id of the cells be included in the result? (numbered from 1 to length(cells)

Details

A neighborhood matrix indentifies the cells around each cell that are considered adjacent. The matrix should have one, and only one, cell with value 0 (the focal cell); at least one cell with value 1 (the adjacent cell(s)); All other cells are not considered adjacent and ignored.

Cell numbers start with 1 in the upper-left corner and increase from left to right and from top to bottom.

Value

matrix or vector with adjacent cells.

Author(s)

Robert J. Hijmans and Jacob van Etten

See Also

```
adjacency
```

Examples

aggregate 17

	aggregate	Aggregate cells	
--	-----------	-----------------	--

Description

Aggregate a Raster* object to create a new RasterLayer or RasterBrick with a lower resolution (larger cells). Aggregation groups rectangular areas to create larger cells. The value for the resulting cells is computed with a user-specified function.

Usage

```
## S4 method for signature 'Raster'
aggregate(x, fact=2, fun=mean, expand=TRUE, na.rm=TRUE, filename='', ...)
```

Arguments

x	Raster* object
fact	Integer. Aggregation factor expressed as number of cells in each direction (horizontally and vertically). Or two integers (horizontal and vertical aggregation factor). See Details
fun	Function used to aggregate values
expand	logical. If TRUE the output Raster* object will be larger then the input Raster* object if a division of the number of columns or rows with factor is not an integer
na.rm	logical. If TRUE, NA cells are removed from calculations
filename	Character. Output filename (optional)
	Additional arguments as for writeRaster

Details

Aggregation will result in a Raster* object with fact*fact fewer cells; if necessary this number is adjusted according to the value of expand. For example, fact=2 will result in a new Raster* object with 2*2=4 times fewer cells. If two numbers are supplied, e.g., fact=c(2,3), the first will be used for aggregating in the horizontal direction, and the second for aggregating in the vertical direction, and the new RasterLayer will have 2*3=6 times fewer cells.

Aggregation starts at the upper-left end of a raster. If a division of the number of columns or rows with factor does not return an integer, the extent of the resulting Raster object will either be somewhat smaller or somewhat larger then the original RasterLayer. For example, if an input RasterLayer has 100 columns, and fact=12, the output Raster object will have either 8 columns (expand=FALSE) (using 8 x 12 = 96 of the original columns) or 9 columns (expand=TRUE). In both cases, the maximum x coordinate of the output RasterLayer would, of course, also be adjusted.

The function fun should take multiple numbers, and return a single number. For example mean, modal, min or max. It should also accept a na.rm argument (or ignore it as one of the 'dots' arguments).

18 alignExtent

Value

RasterLayer or RasterBrick

Author(s)

Robert J. Hijmans and Jacob van Etten

See Also

```
disaggregate, resample
```

Examples

```
r <- raster()
# a new aggregated raster, no values
ra <- aggregate(r, fact=10)
r <- setValues(r, runif(ncell(r)))

# a new aggregated raster, max of the values
ra <- aggregate(r, fact=10, fun=max)

# multiple layers
s <- stack(r, r*2)
x <- aggregate(s,2)</pre>
```

alignExtent

Align an extent (object of class Extent)

Description

Align an Extent object with the (boundaries of the) cells of a Raster* object

Usage

```
alignExtent(extent, object, snap='near')
```

Arguments

extent Extent object object Raster* object

snap Character. One of 'near', 'in', or 'out', to determine in which direction the

extent should be aligned. To the nearest border, inwards or outwards

Details

Aligning an Extent object to another object assures that it gets the same origin and resolution. This should only be used to adjust objects because of imprecision in the data. alignExtent should not be used to force data to match that really does not match (use e.g. resample or (dis)aggregate for this).

approxNA 19

Value

Extent object

Author(s)

Robert J. Hijmans

See Also

```
extent, drawExtent, Extent-class
```

Examples

```
r <- raster()
e <- extent(-10.1, 9.9, -20.1, 19.9)
ea <- alignExtent(e, r)
e
extent(r)
ea</pre>
```

approxNA

Estimate values for cells that are NA

Description

approxNA uses the stats function approx to estimate values for cells that are NA by interpolation across layers. Layers are considered equidistant, unless an argument 'z' is used, or getZ returns values, in which case these values are used to determine distance between layers.

For estimation based on neighboring cells see focal

Usage

```
approxNA(x, ...)
```

Arguments

x RasterStack or RasterBrick object

additional arguments as in approxfun (except for x, y, which cannot be used) and an additional argument 'z' to indicated the distance between layers (e.g., time, depth)

Value

RasterBrick

20 area

Author(s)

Robert J. Hijmans

See Also

focal

Examples

```
r <- raster(ncols=5, nrows=5)
r1 <- setValues(r, runif(ncell(r)))
r2 <- setValues(r, runif(ncell(r)))
r3 <- setValues(r, runif(ncell(r)))
r4 <- setValues(r, runif(ncell(r)))
r5 <- setValues(r, NA)
r6 <- setValues(r, runif(ncell(r)))
r1[1:10] <- NA
r2[5:15] <- NA
r3[8:25] <- NA
s <- stack(r1,r2,r3,r4,r5,r6)
x1 <- approxNA(s)
x2 <- approxNA(s, rule=2)
x3 <- approxNA(s, rule=2, z=c(1,2,3,5,14,15))</pre>
```

area

Size of cells

Description

Compute the approximate surface area of cells in an unprojected (longitude/latitude) Raster object. It is an approximation because area is computed as the height (latitudial span) of a cell (which is constant among all cells) times the width (longitudinal span) in the (latitudinal) middle of a cell. The width is smaller at the poleward side than at the equator-ward side of a cell. This variation is greatest near the poles and the values are thus not very precise for very high latitudes.

Usage

```
## S4 method for signature 'RasterLayer'
area(x, filename="", na.rm=FALSE, weights=FALSE, ...)
## S4 method for signature 'RasterStackBrick'
area(x, filename="", na.rm=FALSE, weights=FALSE, ...)
```

Arith-methods 21

Arguments

X	Raster* object
filename	Character. Filename for the output Raster object (optional)
na.rm	Logical. If TRUE, cells that are NA are ignored
weights	Logical. If TRUE, the area of each cells is divided by the total area of all cells that are not NA
	Additional arguments as for writeRaster

Details

If x is a RasterStack/Brick, a RasterBrick will be returned if na.rm=TRUE. However, if na.rm=FALSE, a RasterLayer is returned, because the values would be the same for all layers.

Value

RasterLayer or RasterBrick. Cell values represent the size of the cell in km2, or the relative size if weights=TRUE

Author(s)

Robert J. Hijmans

Examples

```
r <- raster(nrow=18, ncol=36)
a <- area(r)
```

Arith-methods

Arithmetic with Raster* objects

Description

Standard arithmetic operators for computations with Raster* objects and numeric values. The following operators are available: +, -, *, /, ^, %%, %/%

Input Raster* objects should have the same extent, origin and resolution. If only the extent differs, the computation will continue for the intersection of the Raster objects. Operators are applied on a cell by cell basis. For a RasterLayer, numeric values are recycled by row. For a RasterStack or RasterBrick, recycling is done by layer. RasterLayer objects can be combined RasterStack/Brick objects, in which case the RasterLayer is 'recycled'. When using multiple RasterStack or RasterBrick objects, the number of layers of these objects needs to be the same.

Details

If the values of the output Raster* cannot be held in memory, they will be saved to a temporary file. You can use options to set the default file format, datatype and progress bar.

22 as.data.frame

Value

A Raster* object, and in some cases the side effect of a new file on disk.

Author(s)

Robert J. Hijmans

See Also

Math-methods, overlay, calc

Examples

```
r1 <- raster(ncols=10, nrows=10)
r1[] <- runif(ncell(r1))
r2 <- setValues(r1, 1:ncell(r1) / ncell(r1) )
r3 < - r1 + r2
r2 <- r1 / 10
r3 < -r1 * (r2 - 1 + r1^2 / r2)
# recycling by row
r4 <- r1 * 0 + 1:ncol(r1)
# multi-layer object mutiplication, no recycling
b1 <- brick(r1, r2, r3)
b2 <- b1 * 10
# recycling by layer
b3 \leftarrow b1 + c(1, 5, 10)
# adding twoh RasterBrick objects
b3 <- b2 + b1
# summing two RasterBricks and one RasterLayer. The RasterLayer is 'recycled'
b3 < -b1 + b2 + r1
```

as.data.frame

Get a data.frame with raster cell values

Description

as.matrix returns all values of a Raster* object as a matrix. For RasterLayers, rows and columns in the matrix represent rows and columns in the RasterLayer object. For other Raster* objects, the matrix returned by as.matrix has columns for each layer and rows for each cell.

as.array returns an array of matrices that are like those returned by as.matrix for a RasterLayer If there is insufficient memory to load all values, you can use getValues or getValuesBlock to read chunks of the file.

as.logical 23

Usage

```
as.data.frame(x, row.names=NULL, optional=FALSE, ...)
```

Arguments

x Raster* object

row.names NULL or a character vector giving the row names for the data frame. Missing

values are not allowed.

optional logical. If TRUE, setting row names and converting column names (to syntactic

names: see make.names) is optional.

... Additional arguments (none).

Value

data.frame

Author(s)

Robert J. Hijmans

Examples

```
r <- raster(ncol=3, nrow=3)
r[] = 1:ncell(r)
as.data.frame(r)
s <- stack(r,r)
as.data.frame(s)</pre>
```

as.logical

Change values to logical

Description

Change values of a Raster* object to logical values (zero becomes FALSE, all other values become TRUE) You can provide the standard additional arguments: filename, format, overwrite, and progress.

See Also

```
as.logical
```

Examples

```
r <- raster(nrow=10, ncol=10)
r[] <- round(runif(ncell(r)))
r <- as.logical(r)</pre>
```

24 as.matrix

as.matrix

Get a matrix with raster cell values

Description

as.matrix returns all values of a Raster* object as a matrix. For RasterLayers, rows and columns in the matrix represent rows and columns in the RasterLayer object. For other Raster* objects, the matrix returned by as.matrix has columns for each layer and rows for each cell.

as.array returns an array of matrices that are like those returned by as.matrix for a RasterLayer

If there is insufficient memory to load all values, you can use getValues or getValuesBlock to read chunks of the file.

Usage

```
as.matrix(x, ...) as.array(x, ...)
```

Arguments

x Raster* object

Additional arguments.

maxpixels Integer. To regularly subsample very large objects transpose Logical. Transpose the data? (for as.array only)

Value

matrix or array

Author(s)

Robert J. Hijmans

Examples

```
r <- raster(ncol=3, nrow=3)
r[] = 1:ncell(r)
as.matrix(r)
s <- stack(r,r)
as.array(s)</pre>
```

as.raster 25

as.raster

Coerce to a 'raster' object

Description

Implementation of the generic as.raster function to create a 'raster' (small r) object. NOT TO BE CONFUSED with the Raster* (big R) objects defined by the raster package! Such objects can be used for plotting with the rasterImage function.

Usage

```
as.raster(x, ...)
```

Arguments

x RasterLayer object

... Additional arguments.

maxpixels Integer. To regularly subsample very large objects col Vector of colors. Default is col=rev(terrain.colors(255)))

Value

'raster' object

Author(s)

Robert J. Hijmans

Examples

```
r <- raster(ncol=3, nrow=3)
r[] <- 1:ncell(r)
as.raster(r)</pre>
```

atan2

Two argument arc-tangent

Description

For RasterLayer arguments x and y, atan2(y, x) returns the angle in radians for the tangent y/x, handling the case when x is zero. See link[base]{Trig}

See Math-methods for other trigonometric and mathematical functions that can be used with Raster* objects.

26 autocorrelation

Usage

```
atan2(y, x)
```

Arguments

y RasterLayer object x RasterLayer object

Author(s)

Robert J. Hijmans

See Also

Math-methods

Examples

```
r1 <- r2 <- raster(nrow=10, ncol=10)
r1[] <- (runif(ncell(r1))-0.5) * 10
r2[] <- (runif(ncell(r1))-0.5) * 10
atan2(r1, r2)
```

autocorrelation

Spatial autocorrelation

Description

Compute Moran's I or Geary's C measuers of global spatial autocorrelation in a RasterLayer, or compute the local Moran or Geary index (Anselin, 1995).

Usage

```
Geary(x, w=3)
Moran(x, w=3)
MoranLocal(x, w=3)
GearyLocal(x, w=3)
```

Arguments

x RasterLayer

w Spatial weights. Either a single number or a vector of two numbers to define a neighborhood (as in focal) or a rectangular matrix with uneven sides

Details

The default setting uses a 3x3 neighborhoud to compute "Queen's case" indices. You can use a filter (weights matrix) to do other things, such as "Rook's case", or different lags.

bands 27

Value

A single value (Moran's I or Geary's C) or a RasterLayer (Local Moran or Geary values)

Author(s)

Robert J. Hijmans and Babak Naimi

References

Moran, P.A.P., 1950. Notes on continuous stochastic phenomena. Biometrika 37:17-23

Geary, R.C., 1954. The contiguity ratio and statistical mapping. The Incorporated Statistician 5: 115-145

Anselin, L., 1995. Local indicators of spatial association-LISA. Geographical Analysis 27:93-115

http://en.wikipedia.org/wiki/Indicators_of_spatial_association

See Also

The spdep package for additional and more general approaches for computing indices of spatial autocorrelation

Examples

```
r <- raster(nrows=10, ncols=10)
r[] <- 1:ncell(r)

Moran(r)
# Rook's case
f <- matrix(c(0,1,0,1,0,1,0,1,0), nrow=3)
Moran(r, f)

Geary(r)
x1 <- MoranLocal(r)
# Rook's case
x2 <- MoranLocal(r, w=f)</pre>
```

bands

Number of bands

Description

A 'band' refers to a single layer for a possibly multi-layer file. Most RasterLayer objects will refer to files with a single band. (The term 'band' is frequently used in remote sensing to refer to a variable (layer) in a multi-variable dataset and in that context bands could be stored in a single or in seperate files).

28 blockSize

nbands returns the number of bands of the file that a RasterLayer points to (and 1 if it does not point at any file). This functions also works for a RasterStack for which it is equivalent to nlayers.

band returns the specific band the RasterLayer refers to (1 if the RasterLayer points at single layer file or does not point at any file).

Usage

```
nbands(x)
bandnr(x, ...)
```

Arguments

x RasterLayer object

... Additional arguments (none at this time)

Value

```
a numeric value >= 1
```

Author(s)

Robert J. Hijmans

See Also

nlayers

Examples

```
r <- raster()
nbands(r)
bandnr(r)</pre>
```

blockSize

Block size for writing files

Description

This function can be used to suggest a chunk size, and corresponding row numbers, to be used when processing Raster objects chunk by chunk, normally together with writeValues.

Usage

```
blockSize(x, chunksize, n=nlayers(x), minblocks=4, minrows=1)
```

boxplot 29

Arguments

Χ	Raster* object
chunksize	Integer, normally missing. Can be used to set the block size; unit is number of cells. Block size is then computed in units of number of rows (always >= 1)
n	Integer. number of layers to consider. The function divides chunksize by n to determine blocksize
minblocks	Integer. Minimum number of blocks
minrows	Integer. Minimum number of rows in each block

Value

A list with rows, the suggested row numbers at which to start the blocks for reading and writing, size, the block size (number of rows) and n, the total number of blocks

Author(s)

Robert J. Hijmans

See Also

writeValues

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))</pre>
blockSize(r)
```

boxplot

Box plot of Raster objects

Description

Box plot of layers in a Raster object

Usage

```
boxplot(x, ...)
```

Arguments

```
Raster* object
Х
                  Additional arguments. See Methods
. . .
```

Methods

```
boxplot(x, maxpixels=100000, ...)
```

30 brick

maxpixels Integer. Number of pixels to sample from each layer of large Raster objects
... Argument passed to graphics::boxplot

Author(s)

Robert J. Hijmans

See Also

```
pairs, hist
```

Examples

```
r1 <- r2 <- r3 <- raster(ncol=10, nrow=10)
r1[] <- rnorm(ncell(r1), 100, 40)
r2[] <- rnorm(ncell(r1), 80, 10)
r3[] <- rnorm(ncell(r1), 120, 30)
s <- stack(r1, r2, r3)
layerNames(s) <- c('A', 'B', 'C')
boxplot(s, notch=TRUE, col=c('red', 'blue', 'orange'), main='Box plot', ylab='random')</pre>
```

brick

Create a RasterBrick object

Description

A RasterBrick is a multi-layer raster object. They are typically created from a multi-band file; but they can also exist entirely in memory. They are similar to a RasterStack, but processing time should be shorter when using a RasterBrick. Yet they are less flexible as they can only point to a single file.

A RasterBrick can be created from RasterLayer objects, from a RasterStack, or from a (multi-band) file. The can also be created from SpatialPixels*, SpatialGrid*, and Extent objects, and from an three-dimensional array.

Usage

```
brick(x, ...)
```

Arguments

```
x Filename (character), Raster* object, array, SpatialGrid*, SpatialPixels*, Extent, or list of Raster* objects
```

... Additional arguments. See under Details

brick 31

Value

RasterBrick object

Methods

1) Create a RasterBrick from a file

```
brick(x, ...)
```

x character. A filename of a file that the raster package can read. Supported file types are the 'native' raster package fo additional arguments.

Additional arguments:

native Logical. Default is FALSE except when package rgdal is missing. If TRUE, reading and writing of IDRISI, BIL, E

For netCDF files (CF convention):

varname character. The variable name (e.g. 'altitude' or 'precipitation'. If not supplied and the file has multiple variables integer > 0 (default=3). To select the 'level' (4th dimension variable) to use, if the data has 4 dimensions

To read netCDF files, the ncdf package needs to be available.

2) Create a RasterBrick from scratch

```
\label{lem:brick} $$ brick(nrows=180, ncols=360, xmn=-180, xmx=180, ymn=-90, ymx=90, crs="+proj=longlat+datum=WGS84", nl=1)$
```

nrows number of rows ncols number of columns xmn minimum x coordinate (left border)

xmx maximum x coordinate (ich border)
ymn minimum y coordinate (bottom border)
ymx maximum y coordinate (top border)

crs Character or object of class CRS. PROJ4 type description of a Coordinate Reference System (map projection)

nl the desired number of layers

(item x is 'missing' in this case)

3) Create a RasterBrick from an Extent object

brick(x, nrows=10, ncols=10, crs=NA, nl=1)

x Extent object

nrows number of rows ncols number of columns

crs Character or object of class CRS. PROJ4 type description of a Coordinate Reference System (map projection)

nl the desired number of layers

32 brick

4) Create a RasterBrick from a RasterStack

```
brick(x, values=TRUE, nl)
```

x a RasterStack object

values Logical. If TRUE, the values of the RasterStack are transferred to the RasterBrick

nl the desired number of layers (optional. If set, values becomes FALSE

5) Create a RasterBrick from a RasterLayer or RasterBrick

```
brick(x, nl=1)
```

This copies the parameters of a RasterStack object to a new RasterBrick. The values of the RasterStack are transferred to the RasterBrick, unless values=FALSE.

x a Raster* object

nl the desired number of layers

6) Create a RasterBrick from a SpatialPixels* or SpatialGrid*

brick(x, layer=0)

7) Create a RasterBrick from an array

The default extent is set to be between 0 and 1 in the x and y direction but can be changed at creation of the RasterLayer object or later. You can also provide a projection.

```
function(x, xmn=0, xmx=1, ymn=0, ymx=1, crs=NA, transpose=FALSE)
```

X	three-dimensional array (rows, columns, layers)
xmn	minimum x coordinate (left border)
xmx	maximum x coordinate (right border)
ymn	minimum y coordinate (bottom border)
ymx	maximum y coordinate (top border)
crs	PROJ4 type description of a map projection (optional)
transpose	Logical. Transpose the data?

Author(s)

Robert J. Hijmans

See Also

raster

Examples

```
b <- brick(system.file("external/rlogo.grd", package="raster"))
b
nlayers(b)
layerNames(b)
extract(b, 870)</pre>
```

buffer 33

Description

Calculate a buffer around all cells that are not NA.

Note that the distance unit of the buffer width parameter is meters if the RasterLayer is not projected (+proj=longlat), and in map units (typically also meters) when it is projected.

Usage

```
## S4 method for signature 'RasterLayer'
buffer(x, width=0, filename='', doEdge=FALSE, ...)
```

Arguments

X	RasterLayer object
width	Numeric. Number > 0 . Unit is meter if x has a longitude/latitude CRS, or mapunits in other cases
filename	Character. Filename for the output RasterLayer (optional)
doEdge	Logical. If TRUE, the edge function is called first. This may be efficient in cases where you compute a buffer around very large areas. Calling edge determines the edge cells that matter for distance computation
	Additional arguments as for writeRaster

Value

RasterLayer

Author(s)

Robert J. Hijmans

See Also

```
distance, gridDistance, pointDistance
```

Examples

```
r <- raster(ncol=36,nrow=18)
r[] <- NA
r[500] <- 1
b <- buffer(r, width=5000000)
#plot(b)</pre>
```

34 calc

Description

Calculate values for a new Raster* object from another Raster* object, using a formula.

If x is a RasterLayer, fun is typically a function that can take a single vector as input, and return a vector of values of the same length (e.g. sqrt). If x is a RasterStack or RasterBrick, fun should operate on a vector of values (one vector for each cell). calc returns a RasterLayer if fun returns a single value (e.g. sum) and it returns a RasterBrick if fun returns more than one number, e.g., fun=quantile.

In many cases, what can be achieved with calc in a more intuitive 'raster-algebra' notation (see Arith-methods). For example, r <- r * 2 rather than $r <- calc(r, fun=function(x){x * 2}, or <math>r <- sum(s)$ rather than r <- calc(s, fun=sum). However, calc should be faster when using complex formulas on large datasets. With calc it is possible to set an output filename and file type preferences.

See (overlay) to use functions that refer to specific layers, like (function(a,b,c) $\{a + sqrt(b) / c\}$)

Usage

```
## S4 method for signature 'Raster,function'
calc(x, fun, filename='', na.rm, forcefun=FALSE, forceapply=FALSE, ...)
```

Arguments

x	Raster* object
fun	function
filename	character. Output filename (optional)
na.rm	Remove NA values, if supported by 'fun' (only relevant when summarizing a multilayer Raster object into a RasterLayer)
forcefun	logical. For debugging. Force calc to not use fun with apply
forceapply	logical. For debugging. Force calc to use fun with apply
	Additional arguments as for writeRaster

Value

```
a Raster* object
```

calc 35

Note

For large objects calc will do computate values chunk by chunk. This means that for the result of fun to be correct it should not depend on having access to _all_ values at once. For example, to scale the values of a Raster* object by subtracting its mean value (for each layer), you would _not_ do, for Raster object x:

```
calc(x, function(x)scale(x, scale=FALSE))
```

Because the mean value of each chunk will likely be different. Rather do something like

```
m <- cellStats(x, 'mean')
x - m</pre>
```

Author(s)

Robert J. Hijmans and Matteo Mattiuzzi

See Also

```
overlay, reclass, Arith-methods, Math-methods, reclass
```

Examples

```
r <- raster(ncols=36, nrows=18)
r[] \leftarrow 1:ncell(r)
# multiply values with 10
fun <- function(x) { x * 10 }
rc1 <- calc(r, fun)</pre>
# set values below 100 to NA.
fun <- function(x) { x[x<100] <- NA; return(x) }
rc2 <- calc(r, fun)</pre>
# set NA values to -9999
fun <- function(x) { x[is.na(x)] <- -9999; return(x)}
rc3 <- calc(rc2, fun)
# using a RasterStack as input
s \leftarrow stack(r, r*2, sqrt(r))
# return a RasterLayer
rs1 <- calc(s, sum)
# return a RasterBrick
rs2 <- calc(s, fun=function(x)\{x * 10\})
# recycling by layer
rs3 <- calc(s, fun=function(x)\{x * c(1, 5, 10)\})
# use overlay when you want to refer to indiviudal layer in the function
# but it can be done with calc:
rs4 <- calc(s, fun=function(x)\{x[1]+x[2]*x[3]\})
##
```

36 cellFrom

```
# Some regression examples
# create data
r <- raster(nrow=10, ncol=10)
s1 <- s2<- list()
for (i in 1:12) {
s1[i] <- setValues(r, rnorm(ncell(r), i, 3) )</pre>
s2[i] <- setValues(r, rnorm(ncell(r), i, 3) )</pre>
s1 <- stack(s1)
s2 <- stack(s2)
# regression of values in one brick (or stack) with another
s <- stack(s1, s2)
# s1 and s2 have 12 layers; coefficients[2] is the slope
fun <- function(x) { lm(x[1:12] \sim x[13:24])$coefficients[2] }
x1 <- calc(s, fun)
# regression of values in one brick (or stack) with 'time'
time <- 1:nlayers(s)</pre>
fun <- function(x) { lm(x ~ time)$coefficients[2] }</pre>
x2 <- calc(s, fun)</pre>
# get multiple layers, e.g. the slope _and_ intercept
fun <- function(x) { lm(x \sim time)$coefficients }
x3 <- calc(s, fun)
```

cellFrom

Get cell, row, or column number

Description

Get cell number(s) of a Raster* object from row and/or column numbers. Cell numbers start at 1 in the upper left corner, and increase from left to right, and then from top to bottom. The last cell number equals the number of cells of the Raster* object.

Usage

```
cellFromRowCol(object, rownr, colnr)
cellFromRowColCombine(object, rownr, colnr)
cellFromRow(object, rownr)
cellFromCol(object, colnr)
colFromX(object, x)
rowFromY(object, y)
cellFromXY(object, xy)
cellFromLine(object, lns)
cellFromPolygon(object, p, weights=FALSE)
```

cellFrom 37

Arguments

object	Raster* object (or a SpatialPixels* or SpatialGrid* object)
colnr	column number; or vector of column numbers
rownr	row number; or vector of row numbers
x	x coordinate(s)
У	y coordinate(s)
ху	matrix of \boldsymbol{x} and \boldsymbol{y} coordinates, or a SpatialPoints or SpatialPointsDataFrame object
lns	SpatialLines object
p	SpatialPolygons object
weights	Logical. If TRUE, the fraction of each cell that is covered is also returned

Details

cellFromRowCol returns the cell numbers obtained for each row / col number pair. In contrast, cellFromRowColCombine returns the cell numbers obtained by the combination of all row and column numbers supplied as arguments.

Value

row, column or cell number(s). cellFromLine and cellFromPolygon return a list.

Author(s)

Robert J. Hijmans

See Also

```
xyFromCell, cellsFromExtent
```

```
r <- raster(ncols=10, nrows=10)
cellFromRowCol(r, 5, 5)
cellFromRowCol(r, 1:2, 1:2)
cellFromRowColCombine(r, 1:3, 1:2)
cellFromRow(r, 1)
cellFromRow(r, 1)
colFromX(r, 0.5)
rowFromY(r, 0.5)
cellFromXY(r, c(0.5, 0.5))</pre>
cds1 <- rbind(c(-180,-20), c(-160,5), c(-60, 0), c(-160,-60), c(-180,-20))
cds2 <- rbind(c(80,0), c(100,60), c(120,0), c(120,-55), c(80,0))
pols <- SpatialPolygons(list(Polygons(list(Polygon(cds1)), 1), Polygons(list(Polygon(cds2)), 2)))
cellFromPolygon(r, pols)</pre>
```

38 cellsFromExtent

cellsFromExtent

Cells from Extent

Description

This function returns the cell numbers for a Raster* object that are within a specified extent (rectangular area), supply either an object of class Extent, or another Raster* object.

Usage

```
cellsFromExtent(object, extent, expand=FALSE)
```

Arguments

object A Raster* object

extent An object of class Extent (which you can create with newExtent(), or another

Raster* object)

expand Logical. If TRUE, NA is returned for (virtual) cells implied by bndbox, that are

outside the RasterLayer (object). If FALSE, only cell numbers for the area

where object and bndbox overlap are returned (see intersect)

Value

a vector of cell numbers

Author(s)

Robert J. Hijmans

See Also

```
extent, cellFromXY
```

```
r <- raster()
bb <- extent(-5, 5, -5, 5)
cells <- cellsFromExtent(r, bb)
r <- crop(r, bb)
r[] <- cells</pre>
```

cellStats 39

cellStats

Cell statistics

Description

Compute statistics for the cells of each layer of a Raster object. In the raster package, functions such as max, min, and mean, when used with Raster objects as argument, return a new Raster object (with a value computed for each cell). In contrast, cellStats returns a single value, computed from the all the values of a layer.

Usage

```
cellStats(x, stat='mean', ...)
```

Arguments

. . .

A Raster* object Х The function to be applied stat Additional arguments

Details

cellStats will fail (gracefully) for very large Raster objects except for a number of known functions: sum, mean, min, max, sd, 'countNA'. 'countNA' must be supplied as a character value (with quotes), the other known functions may be supplied with or without quotes. For other functions you could perhaps use a sample of the RasterLayer that can be held in memory (see sampleRandom and sampleRegular)

Value

Numeric.

Author(s)

Robert J. Hijmans

See Also

```
quantile , minValue , maxValue , setMinMax
```

```
r <- raster(nrow=18, ncol=36)
r[] \leftarrow runif(ncell(r)) * 10
# works for large files
cellStats(r, 'mean')
# same, but does not work for very large files
cellStats(r, mean)
```

40 clearValues

```
# multi-layer object
cellStats(brick(r,r), mean)
```

clearValues

Clear values

Description

Clear cell values of a Raster* object from memory

Usage

```
clearValues(x)
```

Arguments

Х

Raster* object

Value

```
a Raster* object
```

Author(s)

Robert J. Hijmans

See Also

```
values, replacement
```

```
r <- raster(ncol=10, nrow=10)
r[] <- 1:ncell(r)
r <- clearValues(r)</pre>
```

click 41

|--|

Description

Click on a map (plot) to get values of a Raster* or SpatialGrid or SpatialPixels object at that location; and optionally the coordinates and cell number of the location.

Usage

```
## S4 method for signature 'Raster'
click(x, n=1, id=FALSE, xy=FALSE, cell=FALSE, type = "n", ...)
## S4 method for signature 'SpatialGrid'
click(x, n=1, id=FALSE, xy=FALSE, type = "n", ...)
```

Arguments

X	Raster*, or Spatial* object (or missing)
n	number of clicks on the map
id	Logical. If TRUE, a numeric ID is shown on the map that corresponds to the row number of the output
xy	Logical. If TRUE, xy coordinates are included in the output
cell	Logical. If TRUE, cell numbers are included in the output
type	One of "n", "p", "l" or "o". If "p" or "o" the points are plotted; if "l" or "o" they are joined by lines. See ?locator
•••	additional graphics parameters used if type != "n" for plotting the locations. See ?locator

Value

The value(s) of object at the point(s) clicked on; and the coordinates of the center of the cell if xy==TRUE.

Note

The plot only provides the coordinates (xy pair), the values are read from the Raster* object that is passed as an argument. Thus you can extract values for a Raster* object that is not plotted, as long as it shares the coordinate system (CRS) with the layer that is plotted.

Unless the process is terminated prematurely values at at most n positions are determined. The identification process can be terminated by clicking the second mouse button and selecting 'Stop' from the menu, or from the 'Stop' menu on the graphics window.

Author(s)

Robert J. Hijmans

42 clump

See Also

```
select, drawExtent
```

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
#plot(r)
#click(r)
#now click on the plot (map)</pre>
```

clump

Detect clumps

Description

Detect clumps (patches) of connected cells. Each clump gets a unique ID. NA and zero are used as background values (i.e. these values are used to seperate clumps). You can use queen's or king's case, using the directions argument. For larger files that are processed in chunks, the highest clump number is not necessarily equal to the number of clumps (unless you use argument gaps=FALSE).

Usage

```
## S4 method for signature 'RasterLayer'
clump(x, filename="", directions=8, gaps=TRUE, ...)
```

Arguments

x	RasterLayer object
filename	Character. Filename for the output RasterLayer (optional)
directions	Integer. Which cells are considered adjacent? Should be 8 (Queen's case) or 4 (Rook's case)
gaps	Logical. If TRUE (the default), there may be 'gaps' in the chunk numbers (e.g. you may have clumps with IDs 1, 2, 3 and 5, but not 4). If it is FALSE, these numbers will be recoded from 1 to n (4 in this example)
	Additional arguments as for writeRaster

Value

RasterLayer

Note

This function requires that the igraph package is available.

cluster 43

Author(s)

Robert J. Hijmans and Jacob van Etten

Examples

```
r <- raster(ncols=12, nrows=12)
r[] <- round(runif(ncell(r))*0.6 )
rc <- clump(r)
freq(rc)
#plot(rc)</pre>
```

cluster

Use a multi-core cluster

Description

beginCluster creates, and endCluster deletes a 'snow' cluster object. This object can be used for multi-core computing with those 'raster' functions that support it.

beginCluster determines the number of nodes (cores) that are available and uses all of them (unless the argument n is used).

NOTE: beginCluster may fail when the package 'nws' is installed. You can fix that by removing the 'nws' package, or by setting the cluster type manually, e.g. beginCluster(type="SOCK") endCluster closes the cluster and removes the object.

chactaster closes the claster and removes the object.

The use of the cluster is automatic in these functions" predict, projectRaster, resample and in extract when using polygons.

clusterR is a flexible interface for using cluster with other functions. This function only works with functions from the raster package that return Raster* objects that operate on a cell by cell basis and return an object with the same number of cells as the input raster object(s). Among other functions, it does _not_ work with mrege, crop, mosaic, (dis)aggregate, resample, projectRaster, focal, distance, direction.

Usage

```
beginCluster(n, type, nice, exclude)
endCluster()
clusterR(x, fun, args=NULL, filename='', cl=NULL, m=2, ...)
```

Arguments

n	Integer. The number of nodes to be used (optional)
type	Character. The cluster type to be used (optional). E.g. "SOCK", see the snow package for details
nice	Integer. To set the priority for the workers, between -20 and 20 (UNIX like platforms only)

44 cluster

exclude	Character. Packages to exclude from loading on the nodes (because they may fail there) but are required/loaded on the master
X	Raster* object
fun	function
args	arguments for the function (excluding \boldsymbol{x} , which should always be the first argument
filename	character. Output filename (optional)
cl	cluster object (do not use it if beginCluster() has been called
m	tuning parameter to determine how many blocks should be used. The number is rounded and multiplied with the number of nodes.
	additional arguments for writing Raster objects to disk

Value

None. The side effect is to create or delete a cluster object.

Note

If you want to write your own cluster-enabled functions see getCluster, returnCluster, and the vignette about writing functions

Author(s)

Matteo Mattiuzzi and Robert J. Hijmans

```
## Not run:
#beginCluster()
beginCluster(type="SOCK")

r <- raster()
r[] <- 1:ncell(r)

x <- clusterR(r, sqrt, verbose=T)

f1 <- function(x) calc(x, sqrt)
y <- clusterR(r, f1)

s <- stack(r, r*2, r*3)
f2 <- function(x) calc(x, range)
z <- clusterR(s, f2)

pts <- matrix(c(0,0, 45,45), ncol=2, byrow=T)
d <- clusterR(r, distanceFromPoints, args=list(xy=pts))
endCluster()</pre>
```

compare 45

```
## End(Not run)
```

compare	Compare	

Description

Evaluate whether a two or more rasters have the same extent, number of rows and columns, projection, resolution, and origin (or a subset of these comparisons). Cell values are not compared by this function.

Usage

```
 compare(x, \dots, extent=TRUE, rowcol=TRUE, crs=TRUE, res=FALSE, orig=FALSE, rotation=TRUE, tolerance, stopiffalse=TRUE, showwarning=FALSE) \\
```

Arguments

х	A Raster* object
	Additional Raster* objects
extent	Logical. If TRUE, bounding boxes are compared
rowcol	Logical. If TRUE, number of rows and columns of the objects are compared
crs	Logical. If TRUE, coordinate reference systems are compared.
res	Logical. If TRUE, resolutions are compared (redundant when checking extent and rowcol) $$
orig	Logical. If TRUE, origins are compared
rotation	Logical. If TRUE, rotations are compared
tolerance	Numeric value between 0 and 0.5. If not supplied, the default value is used (see showOptions. It sets difference (relative to the cell resolution) that is permissable for objects to be considered 'equal', if they have a non-integer origin or resolution. See all.equal.
stopiffalse	Logical. If TRUE, an error will occur if the objects are not the same
showwarning	Logical. If TRUE, an warning will be given if objects are not the same. Only relevant when stopiffalse is TRUE

Author(s)

Robert J. Hijmans

46 Compare-methods

Examples

```
r1 <- raster()
r2 <- r1
r3 <- r1
compare(r1, r2, r3)
nrow(r3) <- 10
# compare(r1, r3)
compare(r1, r3, stopiffalse=FALSE)
compare(r1, r3, rowcol=FALSE)</pre>
```

Compare-methods

Compare Raster* objects

Description

These methods compare the location and resolution of Raster* objects. That is, they compare their spatial extent, projection, and number of rows and columns.

For BasicRaster objects you can use == and !=, the values returned is a single logical value TRUE or FALSE

For RasterLayer objects, they also compare the values associated with the objects, and the result is a logical (Boolean) RasterLayer object. And the value returned is a RasterLayer object, if the location and resolution of the two RasterLayers match, or an error of they do not match.

The following methods have been implemented for RasterLayer objects:

```
==, !=, >, <, <=, >=
```

Value

A logical value or a RasterLayer object, and in some cases the side effect of a new file on disk.

Author(s)

Robert J. Hijmans

```
r1 <- raster()
r1 <- setValues(r1, round(10 * runif(ncell(r1))))
r2 <- setValues(r1, round(10 * runif(ncell(r1))))
as(r1, 'BasicRaster') == as(r2, 'BasicRaster')
r3 <- r1 == r2

b <- extent(0, 360, 0, 180)
r4 <- setExtent(r2, b)
as(r2, 'BasicRaster') != as(r4, 'BasicRaster')
# The following would give an error. You cannot compare RasterLayer
# that do not have the same BasicRaster properties.
#r3 <- r1 > r4
```

contour 47

contour

Contour plot

Description

Contour plot of a RasterLayer. This is a generic function, in this package implemented for Raster-Layer objects.

Usage

```
contour(x, ...)
```

Arguments

. . .

```
A Raster* object
Х
                  Any argument that can be passed to contour (graphics package)
```

Methods

```
contour(x, y=1, maxpixels=100000, ...)
               RasterLayer object
               The layer number (integer > 0) if x is a RasterStack or RasterBrick
  maxpixels Maximum number of pixels used to create the contours
               Any argument that can be passed to contour (graphics package)
```

Author(s)

Robert J. Hijmans

See Also

```
persp, filledContour
```

The rasterVis package has more advanced plotting methods for Raster* objects.

```
r <- raster(system.file("external/test.grd", package="raster"))</pre>
plot(r)
contour(r, add=TRUE)
```

48 count

count Count

Description

Count the frequency of a single value in a Raster object.

Usage

```
count(x, value, ...)
```

Arguments

x A Raster* object
 value The value to be counted, can be a number or a logical or NA
 ... Additional arugments: digits, the number of digits for rounding the values,

default is 0, i.e. numbers are compared as integers.

Value

numeric

Author(s)

Robert J. Hijmans

See Also

freq

```
r <- raster(nrow=18, ncol=36)
r[] <- runif(ncell(r))
r <- r * r * r * 10
count(r, 5)</pre>
```

cover 49

cover

Replace NA values with values of other layers

Description

Replace NA values in the first Raster object (x) with the values of the second (y), and so forth for additional Rasters. If x has multiple layers, the subsequent Raster objects should have the same number of layers, or have a single layer only (which will be recycled).

Usage

```
cover(x, y, ...)
```

Arguments

x Raster* object y Raster* object

... Additional Raster objects, and additional arguments as for writeRaster

Value

RasterLayer or RasterBrick object

Author(s)

Robert J. Hijmans

Examples

```
r1 <- raster(ncols=36, nrows=18)
r1[] <- 1:ncell(r1)
r2 <- setValues(r1, runif(ncell(r1)))
r2[r2<0.5] <- NA
r3 <- cover(r2, r1)</pre>
```

crop

Crop

Description

crop returns a geographic subset of an object as specified by an Extent object (or object from which an extent object can be extracted/created). If x is a Raster* object, the Extent is aligned to x. Areas included in y but outside the extent of x are ignored (see expand if you want a larger area)

50 crop

Usage

```
## S4 method for signature 'Raster'
crop(x, y, filename="", snap='near', ...)
## S4 method for signature 'Spatial'
crop(x, y, ...)
```

Arguments

X	Raster* object or SpatialPolygons* or SpatialLines* object
У	Extent object, or any object from which an Extent object can be extracted (see Details)
filename	Character, output filename. Optional
snap	Character. One of 'near', 'in', or 'out', for use with alignExtent
	Additional arguments as for writeRaster

Details

Objects from which an Extent can be extracted/created include RasterLayer, RasterStack, Raster-Brick and objects of the Spatial* classes from the sp package. You can check this with the extent function. New Extent objects can be also be created with function extent and drawExtent by clicking twice on a plot.

Value

RasterLayer or RasterBrick object; or SpatialLines or SpatialPolygons object.

Author(s)

Robert J. Hijmans

See Also

```
expand, merge
```

```
r <- raster(nrow=45, ncol=90)
r[] <- 1:ncell(r)
e <- extent(-160, 10, 30, 60)
rc <- crop(r, e)</pre>
```

crosstab 51

crosstab

Cross-tabulate

Description

Cross-tabulate two RasterLayer objects to create a contingency table.

Usage

```
crosstab(x, y, ...)
```

Arguments

x RasterLayer object y RasterLayer object

... Additional arguments. See Details

Details

```
A full call to the crosstab method for a RasterLayer is:
```

```
crosstab(x, y, digits=0, long=FALSE, progress)
```

digits Integer. The number of digits for rounding the values before cross-tabulation

long Logical. If TRUE the results are returned in 'long' format (matrix with three columns) instead of a table

progress Character. "text", "window", or "" (the default, no progress bar)

... Additional arguments that can be passed on to table, such as exclude=NULL to include NA values in the tabula

Value

A table or matrix

Author(s)

Robert J. Hijmans

See Also

```
freq, zonal
```

```
r <- raster()
r[] = runif(ncell(r)) * 5
s = setValues(r, runif(ncell(r)) * 10)
crosstab(r,s)</pre>
```

52 cut

cut

Convert values to classes

Description

Cut uses the base function cut to classify the values of a Raster* object according to which interval they fall in. The intervals are defined by the argument breaks. The leftmost interval corresponds to level one, the next leftmost to level two and so on.

Usage

```
cut(x, ...)
```

Arguments

```
x A Raster* object... additional arguments. See cut
```

Value

Raster* object

Author(s)

Robert J. Hijmans

See Also

```
subs, reclass, calc
```

```
r <- raster(ncols=36, nrows=18)
r[] <- rnorm(ncell(r))
breaks <- -2:2 * 3
rc <- cut(r, breaks=breaks)</pre>
```

cv 53

С٧

Coefficient of variation

Description

Compute the coefficient of variation (expressed as a percentage). If there is only a single value, sd is NA and cv returns NA if aszero=FALSE (the default). However, if (aszero=TRUE), cv returns 0.

Usage

```
## S4 method for signature 'ANY'
cv(x, ..., aszero=FALSE, na.rm = FALSE)
## S4 method for signature 'Raster'
cv(x, ..., aszero=FALSE, na.rm = FALSE)
```

Arguments

Х	A vector of numbers (typically integers for modal), or a Raster* object	
	additional (vectors of) numbers, or Raster objects	
aszero	logical. If TRUE, a zero is returned (rather than an NA) if the cv of single value is computed	
na.rm	Remove (ignore) NA values	

Value

vector or RasterLayer

Author(s)

Robert J. Hijmans

```
data <- c(0,1,2,3,3,3,3,4,4,4,5,5,6,7,7,8,9,NA)

cv(data, na.rm=TRUE)
```

54 datasource

datasource

Are values in memory and/or on disk?

Description

These are helper functons for programmers and for debugging that provide information about whether a Raster object has associated values, and if these are in memory or on disk.

 $from {\tt Disk}\ is\ {\tt TRUE}\ if\ the\ data\ source\ is\ a\ file\ on\ disk;\ and\ {\tt FALSE}\ if\ the\ object\ only\ exists\ in\ memory.$

inMemory is TRUE if all values are currently in memory (RAM); and FALSE if not (in which case they either are on disk, or there are no values).

has Values is TRUE if the object has cell values.

Usage

```
fromDisk(x)
inMemory(x)
hasValues(x)
```

Arguments

X

Raster* object

Value

Logical value

Author(s)

Robert J. Hijmans

```
rs <- raster(system.file("external/test.grd", package="raster"))</pre>
inMemory(rs)
fromDisk(rs)
rs <- readAll(rs)
inMemory(rs)
fromDisk(rs)
rs <- rs + 1
inMemory(rs)
fromDisk(rs)
rs <- raster(rs)
inMemory(rs)
fromDisk(rs)
rs <- setValues(rs, 1:ncell(rs))</pre>
inMemory(rs)
fromDisk(rs)
rs <- writeRaster(rs, filename='test', overwrite=TRUE)</pre>
```

dataType 55

```
inMemory(rs)
fromDisk(rs)
```

dataType	Data type		

Description

Get the datatype of a RasterLayer object. The datatype determines the interpretation of values written to disk. Changing the datatype of a Raster* object does not directly affect the way they are stored in memory; but it does affect how values are read from file (unless values are read via rgdal). If you change the datatype of a RasterLayer and then read values from disk these may be completely wrong, so only do this for debugging or when the information in the header file was wrong. To set the datatype of a new file, you can give a 'datatype' argument to the functions that write values to disk (e.g. writeRaster).

Usage

```
dataType(x)
dataType(x) <- value</pre>
```

Arguments

```
x A RasterLayer object
value A data type (see below)
```

Details

Setting the data type is useful if you want to write values to disk. In other cases use functions such as round()

Datatypes are described by 5 characters. The first three indicate whether the values are integers, decimal number or logical values. The fourth character indicates the number of bytes used to save the values on disk, and the last character indicates whether the numbers are signed (i.e. can be negative and positive values) or not (only zero and positive values allowed)

The following datatypes are available:

Datatype definition	minimum possible value	maximum possible value
LOG1S	FALSE (0)	TRUE (1)
INT1S	-127	127
INT1U	0	255
INT2S	-32,767	32,767
INT2U	0	65,534
INT4S	-2,147,483,647	2,147,483,647
INT4U	0	4,294,967,296
FLT4S	-3.4e+38	3.4e+38
FLT8S	-1.7e+308	1.7e+308

56 density

For all integer types, except the single byte types, the lowest (signed) or highest (unsigned) value is used to store NA. Single byte files do not have NA values. Logical values are stored as signed single byte integers, they do have an NA value (-127)

INT4U is available but they are best avoided as R does not support 32-bit unsigned integers.

Value

```
a Raster* object
```

Author(s)

Robert J. Hijmans

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
dataType(r)
s <- writeRaster(r, 'new.grd', datatype='INT2U', overwrite=TRUE)
dataType(s)</pre>
```

density

Density plot

Description

Create a density plots of values in a RasterLayer

Usage

```
density(x, ...)
```

Arguments

x RasterLayer object

... Additional arguments passed to plot

Value

A density plot (and a density object, returned invisibly of plot=TRUE).

Methods

```
A full call as implemented here:
```

```
density(x, layer, maxpixels=100000, plot=TRUE, main, ...)
```

layer can be used to subset the layers to plot in a multilayer object (RasterBrick or Raster-Stack)

maxpixels is the maximum number of (randomly sampled) cells to be used for creating the density plot

see plot for the other arguments

dim 57

Author(s)

Robert J. Hijmans

dim

Dimensions of a Raster* object

Description

Get (or set) the number of rows, columns, and layers of a Raster* object. You cannot use this function to set the dimentions of a RasterStack object.

Value

Integer

Methods

```
dim(x)
If x is a Raster* object
dim(x) <- value</pre>
```

x RasterLayer or RasterBrick)

value row number, or row _and_ column number (for a RasterLayer and a RasterBrick); or a row and column number _a

Author(s)

Robert J. Hijmans

See Also

```
ncell, extent, res
```

```
r <- raster()
dim(r)
dim(r) <- c(18)
dim(r)
dim(r) <- c(18, 36)
dim(r)
b <- brick(r)
dim(b)
dim(b) <- c(10, 10, 5)
dim(b)</pre>
```

58 direction

Description

The direction (azimuth) to or from the nearest cell that is not NA. The direction unit is in radians, unless you use argument degrees=TRUE.

Usage

```
direction(x, ...)
```

Arguments

x a RasterLayer object

... additional arguments. See Details.

Details

The following additional arguments can be passed, to replace default values for this function

filename Filename for the output RasterLayer

from Logical. Default is FALSE. If TRUE, the direction from (instead of to) the nearest cell that is not NA is returned

degrees Logical. If FALSE (the default) the unit of direction is radians.

format Character. Output file type. See writeRaster datatype Character. Output data type. See dataType

overwrite Logical. If TRUE, "filename" will be overwritten if it exists progress Character. "text", "window", or "" (the default, no progress bar)

Value

A RasterLayer object

Author(s)

Robert J. Hijmans

See Also

```
distance, gridDistance
```

For the direction between points, see the azimuth function in the geosphere package

```
r <- raster(ncol=36,nrow=18)
r[] <- NA
r[306] <- 1</pre>
```

disaggregate 59

```
b <- direction(r)
#plot(b)</pre>
```

disaggregate

Disaggregate

Description

Disaggregate a RasterLayer to create a new RasterLayer with a higher resolution (smaller cells). The values in the new RasterLayer are the same as in the larger original cells unless you specify method="bilinear", in which case values are locally interpolated (using the resample function).

Usage

```
## S4 method for signature 'Raster'
disaggregate(x, fact=NULL, method='', filename='', ...)
```

Arguments

x	a Raster object
fact	integer. amount of disaggregation expressed as number of cells (horizontally and vertically). This can be a single integer or two integers $c(x,y)$, in which case the first one is the horizontal disaggregation factor and y the vertical disaggregation factor. If a single integer values is supplied, cells are disaggregated with the same factor in x and y direction
method	Character. " or 'bilinear'. If 'bilinear', values are locally interpolated (using the resample function
filename	Character. Output filename (optional)
	Additional arguments as for writeRaster

Value

Raster object

Author(s)

Robert J. Hijmans

See Also

aggregate

60 distance

Examples

```
r <- raster(ncols=10, nrows=10)
rd <- disaggregate(r, fact=c(10, 2))
ncol(rd)
nrow(rd)
r[] <- 1:ncell(r)
rd <- disaggregate(r, fact=c(4, 2), method='bilinear')</pre>
```

distance

Distance

Description

Calculate the distance, for all cells that are NA, to the nearest cell that is not NA.

The distance unit is in meters if the RasterLayer is not projected (+proj=longlat) and in map units (typically also meters) when it is projected.

Usage

```
## S4 method for signature 'RasterLayer'
distance(x, filename='', doEdge=FALSE, ...)
```

Arguments

X	RasterLayer object
filename	Character. Filename for the output RasterLayer (optional)
doEdge	Logical. If TRUE, the edge function is called first. This may be efficient in cases where you compute the distance to large blobs. Calling edge determines the edge cells that matter for distance computation
	Additional arguments as for writeRaster

Value

RasterLayer

Author(s)

Robert J. Hijmans

See Also

distanceFromPoints, gridDistance, pointDistance

See the gdistance package for more advanced distances, and the geosphere package for great-circle distances (and more) between points in longitude/latitude coordinates.

distanceFromPoints 61

Examples

```
r <- raster(ncol=36,nrow=18)
r[] <- NA
r[500] <- 1
dist <- distance(r)
#plot(dist / 1000)</pre>
```

distanceFromPoints

Distance from points

Description

The function calculates the distance from a set of points to all cells of a RasterLayer.

The distance unit is in meters if the RasterLayer is not projected (+proj=longlat) and in map units (typically meters) when it is projected.

Usage

```
distanceFromPoints(object, xy, filename='', ...)
```

Arguments

object RasterLayer object

xy Matrix of x and y coordinates, or a SpatialPoints* object.

filename Filename for the output RasterLayer

... Additional arguments as for writeRaster

Value

RasterLayer object

Author(s)

Robert J. Hijmans

See Also

distance, gridDistance, pointDistance

```
r <- raster(ncol=36,nrow=18)
xy = c(0,0)
dist <- distanceFromPoints(r, xy)
#plot(dist)</pre>
```

62 drawExtent

draw

Draw a line or polygon

Description

Draw a line or polygon on a plot (map) and save it for later use. After calling the function, start clicking on the map. To finish, right-click and select 'stop'.

Usage

```
drawPoly(sp=TRUE, col='red', lwd=2, ...)
drawLine(sp=TRUE, col='red', lwd=2, ...)
```

Arguments

sp	logical. If TRUE, the output will be a sp object (SpatialPolygons or SpatialLines). Otherwise a matrix of coordinates is returned
col	the color of the lines to be drawn
lwd	the width of the lines to be drawn
	additional arguments padded to locator

Value

If sp==TRUE a SpatialPolygons or SpatialLines object; otherwise a matrix of coordinates

Author(s)

Robert J. Hijmans

See Also

locator

drawExtent

Create an Extent object by drawing on a map

Description

Click on two points of a plot (map) to obtain an object of class Extent ('bounding box')

Usage

```
drawExtent(show=TRUE, col="red")
```

edge 63

Arguments

show Logical. If TRUE, the extent will be drawn on the map

col Sets the color of the lines of the extent

Value

an object of class Extent

Author(s)

Robert J. Hijmans

Examples

```
## Not run:
r1 <- raster(nrow=10, ncol=10)
r1[] <- runif(ncell(r1))
plot(r1)
e <- drawExtent()
# now click on the map twice
mean(values(crop(r1, drawExtent())))
# now click on the map twice
## End(Not run)</pre>
```

edge

Edge detection

Description

Detect edges. Edges are cells that have more than one class in the 4 or 8 cells surrounding it, or, if classes=FALSE, cells with values and cells with NA.

Usage

```
## S4 method for signature 'RasterLayer'
edge(x, filename="", type='inner', classes=FALSE, directions=8, ...)
```

Arguments

x RasterLayer object

filename Character. Filename for the output RasterLayer (optional)

type Character. 'inner', or 'outer'

classes Character. Logical. If TRUE all different values are (after rounding) distin-

guished, as well as NA. If FALSE (the default) only edges between NA and non-NA

cells are considered

64 expand

```
directions Integer. Which cells are considered adjacent? Should be 8 (Queen's case) or 4 (Rook's case)

... Additional arguments as for writeRaster
```

Value

RasterLayer. Cell values are either 1 (and edge) or 0 (not an edge), or NA

Author(s)

Robert J. Hijmans

See Also

```
focal, clump
```

Examples

```
r <- raster(nrow=18, ncol=36, xmn=0)
r[150:250] <- 1
r[251:450] <- 2
plot( edge(r, type='inner') )
plot( edge(r, type='outer') )
plot( edge(r, classes=TRUE) )</pre>
```

expand

Expand

Description

Expand returns an Raster* object with a larger spatial extent. The output Raster object has the outer minimum and maximum coordinates of the input Raster and Extent arguments. Thus, all of the cells of the original raster are included. See crop if you (also) want to remove rows or columns.

There is also an expand method for extent objects to enlarge (or reduce) an Extent. You can also use algebraic notation to do that (see examples)

Usage

```
## S4 method for signature 'Raster'
expand(x, y, value=NA, filename='', ...)
## S4 method for signature 'Extent'
expand(x, y, ...)
```

expand 65

Arguments

Χ	Raster or Extent object
У	If x is a Raster object, y should be an Extent object, or any object that is or has an Extent object, or an object from which it can be extracted (such as sp objects). Alternatively, you can provide a vector of lenght 2 with the number indicating the amount of rows and columns that need to be added (or a single number when the number of rows and columns is equal) If x is an Extent object, y should be a numeric vector of 1, 2, or 4 elements
value	value to assign to new cells
filename	Character (optional)
	Additional arguments as for writeRaster

Value

RasterLayer or RasterBrick, or Extent

Author(s)

Robert J. Hijmans and Etienne B. Racine (Extent method)

See Also

```
crop, merge
```

```
r <- raster(xmn=-150, xmx=-120, ymx=60, ymn=30, ncol=36, nrow=18)
r[] <- 1:ncell(r)
e <- extent(-180, 0, 0, 90)
re <- expand(r, e)

# expand with a number of rows and columns (at each side)
re2 <- expand(r, c(2,10))

# Extent object
e <- extent(r)
e
expand(e, 10)
expand(e, 10, -10, 0, 20)
e + 10
e * 2</pre>
```

66 extension

extension

Filename extensions

Description

Get or change a filename extension

Usage

```
extension(filename, value=NULL, maxchar=10)
extension(filename) <- value</pre>
```

Arguments

filename A filename, with or without the path

value A file extension with or without a dot, e.g., ".txt" or "txt"

maxchar Maximum number of characters after the last dot in the filename, for that string

to be considered a filename extension

Value

A file extension, filename or path.

If ext(filename) is used without a value argument, it returns the file extension; otherwise it returns the filename (with new extions set to value

Author(s)

Robert J. Hijmans

```
fn <- "c:/temp folder/filename.exten sion"
extension(fn)
extension(fn) <- ".txt"
extension(fn)
fn <- extension(fn, '.document')
extension(fn)
extension(fn, maxchar=4)</pre>
```

extent 67

extent

Extent

Description

This function returns an Extent object of a Raster* or Spatial* object (or an Extent object), or creates an Extent object from a matrix (2x2; rows=xmin, xmax; cols=ymin, ymax), vector (length=4; order=xmin, xmax, ymin, ymax) or list (with at least two elements, with names 'x' and 'y')

bbox returns a sp package like 'bbox' object (a matrix)

Usage

```
extent(x, ...)
```

Arguments

x A Raster* or Extent object, a matrix, or a vector of four numbers

... Additional arguments. When x is a single number you can pass three additional numbers (xmin, xmax, ymin, ymax)

When x is a Raster* object, you can pass four additional arguments to crop the extent: r1, r2, c1, c2, representing the first and last row and column number

Value

An Extent object

Author(s)

Robert J. Hijmans; Etienne Racine write the extent function for a list

See Also

```
extent, drawExtent
```

```
r <- raster()
extent(r)
extent(c(0, 20, 0, 20))
#is equivalent to
extent(0, 20, 0, 20)
extent(matrix(c(0, 0, 20, 20), nrow=2))
x <- list(x=c(0,1,2), y=c(-3,5))
extent(x)
#crop the extent by row and column numbers
extent(r, 1, 20, 10, 30)</pre>
```

68 Extent coordinates

Extent coordinates

Coordinates of the Extent of a Raster object

Description

These functions return or set the extreme coordinates of a Raster* object.

Usage

```
xmin(x)
xmax(x)
ymin(x)
ymax(x)

xmin(x) <- value
xmax(x) <- value
ymin(x) <- value
ymax(x) <- value</pre>
```

Arguments

```
x A Raster* objectvalue A new x or y coordinate
```

Value

a single number

Author(s)

Robert J. Hijmans

See Also

```
extent, dimensions
```

```
r <- raster(xmn=-0.5, xmx = 9.5, ncols=10)
xmin(r)
xmax(r)
ymin(r)
ymax(r)
xmin(r) <- -180
xmax(r) <- 180</pre>
```

Extent math 69

Extent math

round Extent coordinates

Description

use round(x, digits=0) to round the coordinates of an Extent object to the number of digits specified. This can be useful when dealing with a small inprecision in the data (e.g. 179.9999 instead of 180). floor and ceiling move the coordinates to the outer or inner whole integer numbers.

It is also possible to use Arithmetic functions with Extent objects (but these work perhaps unexpectedly!)

See Math-methods for these (and many more) methods with Raster* objects.

Usage

```
## S4 method for signature 'Extent'
floor(x)
## S4 method for signature 'Extent'
ceiling(x)
```

Arguments

Х

Extent object

Author(s)

Robert J. Hijmans

See Also

Math-methods

```
e <- extent(c(0.999999, 10.000011, -60.4, 60))
round(e)
ceiling(e)
floor(e)</pre>
```

70 Extent-class

Extent-class

Class "Extent"

Description

Objects of class Extent are used to define the spatial extent (extremes) of objects of the BasicRaster and Raster* classes.

Objects from the Class

You can use the extent function to create Extent objects, or to extract them from Raster* and Spatial* objects.

Slots

```
xmin: minimum x coordinate
xmax: maximum x coordinate
ymin: minumum y coordinate
ymax: maximum y coordinate
```

Methods

show display values of a Extent object

Author(s)

Robert J. Hijmans

See Also

```
extent, setExtent
```

```
ext <- extent(-180,180,-90,90) ext
```

extract 71

ext	

Extract values from Raster objects

Description

Extract data from a Raster object using cell numbers or the locations of other spatial data (i.e., a spatial query). You can use coordinates (points), lines, polygons or an Extent (rectangle) object.

Usage

```
extract(x, y, ...)
```

Arguments

Raster*	object
	Raster*

y A vector (representing cell numbers); or a SpatialPoints object or a two-column data.frame or matrix (representing points); or a SpatialPolygons, SpatialLines, or Extent object

. . . Additional arguments, see under Details

Details

Below are additional arguments that can be used, depending on the type of objects used.

= all objects =

1) fun. Function to summarize the values (e.g. mean). The function should take a single numeric vector as argument and return a single values (e.g. mean, min or max), and accept a na.rm argument. Thus, standard R functions not including an na.rm argument must be wrapped as in this example: fun=function(x,...)length(x)

If y represents points supplying a fun argument is only useful when a buffer is used (see below).

2) na.rm. Only useful when fun is supplied. If na.rm=TRUE (the default value), NA values are removed before fun is applied. This argument may be ignored if the function used has a . . . argument and ignres an additional na.rm argument.

= points =

If y represents points, extract returns the values of a Raster* object for the cells in which a set of points fall. Additional arguments that can be suplied to this function if y represents points:

- 1) method. If method='simple' (the default), values for the cell a point falls in are returned. The alternative is method='bilinear', in which case the returned values are interpolated from the values of the four nearest raster cells.
- 2) buffer. The radius of a buffer around each point for which to extract cell values. If the distance between the sampling point and the center of a cell is less than or equal to the buffer, the cell is included. The buffer can be specified as a single value, or as a vector of the length of the number of points. If the data are not projected (latitude/longitude), the unit should be meters. Otherwise it should be in map-units (typically also meters).

72 extract

3) cellnumbers. Logical. If cellnumbers=TRUE and buffer is not NULL, cellnumbers will also be returned. cellnumbers is set to FALSE when an argument fun is used.

= lines =

df. Logical. If df=TRUE, results will be returned as a data.frame, rather than as a list.

And, if no fun argument is supplied:

cellnumbers. Logical. If cellnumbers=TRUE is used, cell-numbers will also be returned.

= polygons =

If y represents polygons, the extract method returns the values of the cells of a Raster* object that is covered by a polygon. A cell is covered if its center is inside the polygon (but see the weights option for considering partly covered cells; and argument small for getting values for small polygons anyway).

if y represents polygons are:

- 1) small. Logical. Default is FALSE. If TRUE a value is also returned for relatively small polygons (e.g. those smaller than a single cell of the Raster* object), or polygons with an odd shape, for which otherwise no values are returned because they do not cover any Raster* object's cell centers. In some cases, you could use alternatively use the centroids of such polygons, for example using extract(x, coordinates(y)) or extract(x, coordinates(y), method='bilinear').
- 2) df. Logical. If df=TRUE, results will be returned as a data.frame, rather than as a list.

Additional arguments that can be suplied to this function, if no fun argument is supplied:

- 3) weights. If TRUE, the function returns, for each polygon, a matrix with the cell values and the approximate fraction of each cell that is covered by the polygon(rounded to 1/100). The weights can be used for averaging; see examples. This option can be useful if the polygons are small relative to the cells size of the Raster* object.
- 4) cellnumbers. Logical. If cellnumbers=TRUE, cell-numbers will also be returned.

= focal values =

If y is missing, you can supply two arguments to get 'focal' values (i.e. the values in a neighborhood around each cell)

- 1) row. row number (this is a required argument).
- 2) ngb. The neighborhood to consider. Either a single integer or a vector of two integers. Default is 3. See focal

= all multi-layer objects =

If x is a RasterStack or RasterBrick object, extract accepts, in addition to the arguments listed above, these two additional arguments:

- 1)layer. Integer. First layer for which you want values
- 2) nl. Integer. Number of layers for which you want values

Value

A vector for RasterLayer objects, and a matrix for a RasterStack or RasterBrick object. A list if y is a SpatialPolygons* or SpatialLines* object or if a buffer argument is used (but not a fun argument). focal values are returned as a n column matrix. The first column has the column numbers, the remaining has the focal values for each layer.

extract 73

Author(s)

Robert J. Hijmans

See Also

values

```
r <- raster(ncol=36, nrow=18)
r[] \leftarrow 1:ncell(r)
# extract values by cell number
extract(r, c(1:2, 10, 100))
s <- stack(r, sqrt(r), r/r)</pre>
extract(s, c(1, 10, 100), layer=2, n=2)
# extract values with points
xy <- cbind(-50, seq(-80, 80, by=20))
extract(r, xy)
sp <- SpatialPoints(xy)</pre>
extract(r, sp, method='bilinear')
# examples with a buffer
extract(r, xy[1:3,], buffer=1000000)
extract(r, xy[1:3,], buffer=1000000, fun=mean)
## illustrating the varying size of a buffer (expressed in meters) on a longitude/latitude raster
z <- extract(r, xy, buffer=1000000)</pre>
s <- raster(r)</pre>
for (i in 1:length(z)) { s[z[[i]]] <- i }</pre>
## compare with raster that is not longitude/latitude
projection(r) <- "+proj=utm +zone=17"</pre>
xy[,1] < -50
z <- extract(r, xy, buffer=8)</pre>
for (i in 1:length(z)) { s[z[[i]]] \leftarrow i }
plot(s)
# library(maptools)
# data(wrld_simpl)
# plot(wrld_simpl, add=TRUE)
# extract values with lines
cds1 \leftarrow rbind(c(-50,0), c(0,60), c(40,5), c(15,-45), c(-10,-25))
```

74 Extract by index

```
cds2 \leftarrow rbind(c(80,20), c(140,60), c(160,0), c(140,-55))
lines <- SpatialLines(list(Lines(list(Line(cds1)), "1"), Lines(list(Line(cds2)), "2") ))</pre>
extract(r, lines)
####################################
# extract values with polygons
####################################
cds1 \leftarrow rbind(c(-180,-20), c(-160,5), c(-60, 0), c(-160,-60), c(-180,-20))
cds2 \leftarrow rbind(c(80,0), c(100,60), c(120,0), c(120,-55), c(80,0))
polys <- SpatialPolygons(list(Polygons(list(Polygon(cds1)), 1), Polygons(list(Polygon(cds2)), 2)))</pre>
#plot(r)
#plot(polys, add=TRUE)
v <- extract(r, polys)</pre>
# mean for each polygon
unlist(lapply(v, function(x) if (!is.null(x)) mean(x, na.rm=TRUE) else NA))
# v <- extract(r, polys, cellnumbers=TRUE)</pre>
# weighted mean
# v <- extract(r, polys, weights=TRUE, fun=mean)</pre>
# equivalent to:
# v <- extract(r, polys, weights=TRUE)</pre>
\# sapply(v, function(x) if (!is.null(x)) {sum(apply(x, 1, prod)) / sum(x[,2])} else NA )
# extract values with an extent
####################################
e <- extent(150,170,-60,-40)
extract(r, e)
#plot(r)
#plot(e, add=T)
####################################
# focal values
f <- extract(r, row=5, ngb=3)</pre>
f[1:15, ]
```

Extract by index 75

Description

These are shorthand methods that call other methods that should normally be used, such as getValues, extract, crop.

object[i] can be used to access values of a Raster* object, using cell numbers. You can also use row and column numbers as index, using object[i,j] or object[i,] or object[,j]. In addition you can supply an Extent, SpatialPolygons, SpatialLines or SpatialPoints object.

If drop=TRUE (the default) cell values are returned (a vector for a RasterLayer, a matrix for a RasterStack or RasterBrick). If drop=FALSE a Raster* object is returned that has the extent covering the requested cells, and with all other non-requested cells within this extent set to NA.

If you supply a RasterLayer, its values will be used as logical (TRUE/FALSE) indices if both Raster objects have the same extent and resolution; otherwise the cell values within the extent of the RasterLayer are returned.

Double brackes '[[]]' can be used to extract one or more layers from a multi-layer object.

Methods

If TRUE, cell values are returned. Otherwise, a Raster* object is returned

See Also

```
getValues, setValues, extract, crop, rasterize
```

Examples

```
r <- raster(ncol=10, nrow=5)
r[] <- 1:ncell(r)

r[1]
r[1:10]
r[1,]
r[,1]
r[1:2, 1:2]

s <- stack(r, sqrt(r))
s[1:3]
s[[2]]</pre>
```

drop

76 extreme Values

extremeValues

Minimum and maximum values

Description

Returns the minimum or maximum value of a RasterLayer or layer in a RasterStack

Usage

```
minValue(x, ...)
maxValue(x, ...)
```

Arguments

x RasterLayer or RasterStack object

... Additional argument: layer number (for RasterStack or RasterBrick objects)

Details

If a Raster* object is created from a file on disk, the min and max values are often not known (depending on the file format). You can use setMinMax to set them in the Raster* object.

Value

a number

Author(s)

Robert J. Hijmans

```
r <- raster()
r <- setValues(r, 1:ncell(r))
minValue(r)
maxValue(r)
r <- setValues(r, round(100 * runif(ncell(r)) + 0.5))
minValue(r)
maxValue(r)

r <- raster(system.file("external/test.grd", package="raster"))
# this raster is from an 'external' format, so min and maxValue are not known
minValue(r)
maxValue(r)

r1 <- setMinMax(r)
# now they are known:
minValue(r1)
maxValue(r1)</pre>
```

factors 77

```
r2 <- readAll(r)
# now they are known too:
minValue(r2)
maxValue(r2)</pre>
```

factors

Factors

Description

Factors are categorical variables. These functions allow for defining a layer as a categorical variable. This feature is under development, and whether a layer is defined as a factor or not is currently ignored by all other functions.

Usage

```
is.factor(x)
asFactor(x, ...)
labels(object, ...)
labels(object) <- value</pre>
```

Arguments

```
    x A Raster* object
    object A Raster* object
    value list
    ... Additional arguments
```

Value

Raster* object

Author(s)

Robert J. Hijmans

```
r <- raster(nrow=10, ncol=10)
r[] <- (runif(ncell(r)) * 10)
is.factor(r)
r <- round(r)
f <- asFactor(r)
is.factor(f)</pre>
```

78 filledContour

filename

Filename

Description

Get the filename of a Raster* object. You cannot set the filename of an object (except for Raster-Stack objects); but you can provide a 'filename=' argument to a function that creates a new Raster-Layer or RasterBrick* object.

Usage

```
filename(x)
```

Arguments

Χ

A Raster* object

Value

```
a Raster* object
```

Author(s)

Robert J. Hijmans

Examples

```
r <- raster( system.file("external/test.grd", package="raster") )
filename(r)</pre>
```

filledContour

Filled contour plot

Description

Filled contour plot of a RasterLayer. This is a wrapper around filled.contour for RasterLayer objects.

Usage

```
filledContour(x, y=1, maxpixels=100000, ...)
```

flip 79

Arguments

```
x A Raster* object
```

y Integer. The layer number of x (if x has multiple layers)

maxpixels The maximum number of pixels

... Any argument that can be passed to filled.contour (graphics package)

Author(s)

Robert J. Hijmans

See Also

```
filled.contour, persp, plot
```

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
filledContour(r)</pre>
```

flip

Flip

Description

Flip the values of a Raster* object by inverting the order of the rows (direction=y) or the columns direction='x'.

Usage

```
flip(x, direction, ...)
```

Arguments

```
x a Raster* object
```

direction Character. 'y' or 'x'; or 1 (=x) or 2 (=y)
... Additional arguments as for writeRaster

Value

RasterLayer or RasterBrick

Author(s)

Robert J. Hijmans

80 focal

See Also

```
transpose: t, rotate
```

Examples

```
r <- raster(nrow=18, ncol=36)
m <- matrix(1:ncell(r), nrow=18)
r[] <- as.vector(t(m))
rx <- flip(r, direction='x')
r[] <- as.vector(m)
ry <- flip(r, direction='y')</pre>
```

focal

Focal values

Description

Calculate focal ("moving window") values for the neighborhood of focal cells using a matrix of weights, perhaps in combination with a function.

Usage

```
## S4 method for signature 'RasterLayer'
focal(x, w=3, fun, filename='', na.rm=FALSE, pad=FALSE, padValue=NA, NAonly=FALSE, ...)
```

Arguments

x	RasterLayer
W	matrix of weights (the moving window), e.g. a 3 by 3 matrix; see Details. The matrix can also be expressed as the number of cells in a single direction or in two directions from the focal cell, in which case the weights are all set to 1. I.e. w=3 refers to a 3 by 3 matrix: 2 cells at each side of the focal cell, queen's case, 9 cells in total. This is equivalent to w=c(3,3). You can also specify a rectangular neighborhood, e.g. w=c(3,5); but the sides must be odd numbers. If you need even sides, you can add a column or row with weights of zero.
fun	function (optional). The function fun should take multiple numbers, and return a single number. For example mean, modal, min or max. It should also accept a na.rm argument (or ignore it, e.g. as one of the 'dots' arguments. For example, length will fail, but function(x ,){na.omit(length(x))} works.
filename	character. Filename for a new raster (optional)
na.rm	logical. If TRUE, NA will be removed from focal computations. The result will only be NA if all focal cells are NA. Except for some special cases (weights of 1, functions like min, max, mean), using na.rm=TRUE is generally not a good idea in this function because it will unbalance the effect of the weights
pad	logical. If TRUE, additional 'virtual' rows and columns are padded to x such that there are no edge effects. This can be useful when a function needs to have access to the central cell of the filter

focal 81

padValue logical. The value of the cells of the padded rows and columns

NAonly logical. If TRUE, only cell values that are NA are replaced with the computed

focal values

... additional arguments. See Details.

Details

focal uses a matrix of weights for the neighborhood of the focal cells. The default function is sum. It is computationally much more efficient to adjust the weights-matrix than to use another function through the fun argument. Thus while the following two statements are equivalent (if there are no NA values), the first one is faster than the second one:

```
a <- focal2(x, w=matrix(1/9, nc=3, nc=3))
b <- focal2(x, w=3, fun=mean)</pre>
```

There is, however, a difference if NA values are considered. One can use the na.rm=TRUE option which may make sense when using a function like mean. However, the results would be wrong when using a weights matrix.

```
Laplacian filter: filter=matrix(c(0,1,0,1,-4,1,0,1,0), nrow=3)
Sobel filter: filter=matrix(c(1,2,1,0,0,0,-1,-2,-1) / 4, nrow=3)
```

The following additional arguments can be passed, to replace default values for this function

overwrite Logical. If TRUE, "filename" will be overwritten if it exists

format Character. Output file type. See writeRaster datatype Character. Output data type. See dataType

progress Character. "text", "window", or "" (the default, no progress bar)

Value

RasterLayer

Note

This function has replaced a previous version of focal, and functions focalNA and focalFilter)

Author(s)

Robert J. Hijmans

```
r <- raster(ncols=36, nrows=18, xmn=0)
r[] <- runif(ncell(r))

# 3x3 mean filter
r3 <- focal(r, w=matrix(1/9,nrow=3,ncol=3))

# 5x5 mean filter
r5 <- focal(r, w=matrix(1/25,nrow=5,ncol=5))</pre>
```

82 freq

```
# Gaussian filter for square cells
fgauss <- function(sigma, n=5) {</pre>
m <- matrix(nc=n, nr=n)</pre>
col \leftarrow rep(1:n, n)
row <- rep(1:n, each=n)</pre>
x <- col - ceiling(n/2)
y \leftarrow row - ceiling(n/2)
# according to http://en.wikipedia.org/wiki/Gaussian_filter
m[cbind(row, col)] <- 1/(2*pi*sigma^2) * exp(-(x^2+y^2)/(2*sigma^2))
# sum of weights should add up to 1
m / sum(m)
}
gf=fgauss(1.5)
rg <- focal(r, w=gf)</pre>
# The max value for the lower-rigth corner of a 3x3 matrix around a focal cell
f = matrix(c(0,0,0,0,1,1,0,1,1), nrow=3)
rm <- focal(r, w=f, fun=max)</pre>
# global lon/lat data: no 'edge effect' for the columns
xmin(r) < -180
r3g <- focal(r, w=matrix(1/9,nrow=3,ncol=3))</pre>
```

freq

Frequency table

Description

Frequency table of the values of a RasterLayer.

Usage

```
freq(x, ...)
```

Arguments

x A RasterLayer object

... Additional arguments. See under Details

Value

A matrix

Gain and offset 83

Methods

```
A full call as implemented here:

freq(x, digits=0, progress, ...)

the digits argument is used passed to round

with progress, a progres bar can be specified. Choose from "text", "window", or "" (the
default, no progress bar)
```

Author(s)

Robert J. Hijmans

See Also

```
count, crosstab and zonal
```

Examples

```
r <- raster(nrow=18, ncol=36)
r[] <- runif(ncell(r))
r <- r * r * r * 10
freq(r)</pre>
```

Gain and offset

Gain and offset of values on file

Description

These functions can be used to get or set the gain and offset parameters used to transform values when reading from a file (currently these are ignored when writing a file). The gain and offset parameters are applied to the raw values using the formula below:

```
value <- value * gain + offset</pre>
```

The default value for gain is 1 and for offset is 0. 'gain' is sometimes referred to as 'scale'.

Note that setting gain and/or offset only affects reading of values from a file, it does not change values that are already (or only) in memory.

Usage

```
gain(x)
gain(x) <- value
offs(x)
offs(x) <- value</pre>
```

Arguments

```
x Raster* object
value Single numeric value
```

84 getData

Value

```
Raster* object or numeric value(s)
```

Author(s)

Robert J. Hijmans

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
gain(r)
offs(r)
r[1505:1510]
gain(r) <- 10
offs(r) <- 5
r[1505:1510]</pre>
```

getData

Get geographic data

Description

Get geographic data for anywhere in the world. Data are read from files that are first downloaded if necessary.

Usage

```
getData(name, download=TRUE, path='', ...)
```

Arguments

name	Data set name, currently supported are 'GADM', 'countries', 'SRTM', 'alt', and 'worldclim'. See Details for more info
download	Logical. If TRUE data will be downloaded if not locally available
path	Character. Path name indicating where to store the data. Default is the current working directory
	Additional required (!) parameters. These are data set specific. See Details

Details

'alt' stands for altitude (elevation); the data were aggregated from SRTM 90 m resolution data between -60 and 60 latitude. 'GADM' is a database of global administrative boundaries. 'worldclim' is a database of global interpolated climate data. 'SRTM' refers to the hole-filled CGIAR-SRTM (90 m resolution). 'countries' has polygons for all countries at a higher resolution than the 'wrld_simpl' data in the maptools pacakge.

getValues 85

If name is 'alt' or 'GADM' you must provide a 'country=' argument. Countries are specified by their 3 letter ISO codes. Use getData('ISO3') to see these codes. In the case of GADM you must also provide the level of administrative subdivision (0=country, 1=first level subdivision). In the case of alt you can set 'mask' to FALSE. If it is TRUE values for neighbouring countries are set to NA. For example:

```
getData('GADM', country='FRA', level=1)
getData('alt', country='FRA', mask=TRUE)
```

If name is 'SRTM' you must provide 'lon' and 'lat' arguments (longitude and latitude). These should be single numbers somewhere within the SRTM tile that you want.

```
getData('SRTM', lon=5, lat=45)
```

If name='worldclim' you must also provide a variable name 'var=', and a resolution 'res='. Valid variables names are 'tmin', 'tmax', 'prec' and 'bio'. Valid resolutions are 0.5, 2.5, 5, and 10 (minutes of a degree). In the case of res=0.5, you must also provide a lon and lat argument for a tile; for the lower resolutions global data will be downloaded. In all cases there are 12 (monthly) files for each variable except for 'bio' which contains 19 files.

```
getData('worldclim', var='tmin', res=0.5, lon=5, lat=45)
getData('worldclim', var='bio', res=10)
```

Value

A spatial object (Raster* or Spatial*)

Author(s)

Robert J. Hijmans

References

```
http://www.worldclim.org
http://www.gadm.org
http://srtm.csi.cgiar.org/
http://diva-gis.org/gdata
```

getValues

Get raster cell values

Description

getValues returns all values or a row of values for a Raster* object. It will take them from memory if available, else it will read them from disk. Function values is a shorthand version of getValues.

Usage

```
getValues(x, row, nrows, ...)
values(x, ...)
```

86 getValuesBlock

Arguments

X	Raster* object
row	Numeric. Row number, should be between 1 and $nrow(x)$, or missing in which case all values are returned
nrows	Numeric. Number of rows. Should be an integer number > 0, or missing
	Additional arguments, see Details

Details

Additional arguments when x is a RasterLayer: format Character. specify the output format. Either "" or "matrix". The default is "", in which case a vector is returned. The values returned for a RasterStack or RasterBrick are always a matrix, with the rows representing cells, and the columns representing layers.

Value

vector or matrix of raster values

Author(s)

Robert J. Hijmans

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
getValues(r)
getValues(r, row=10)</pre>
```

getValuesBlock

Get a block of raster cell values

Description

getValuesBlock returns values for a block (rectangular area) of values of a Raster* object. It will take them from memory if available, else it will read them from disk.

Usage

```
getValuesBlock(x, row, ...)
```

Arguments

X	Raster* object
row	Numeric. Row number, should be between 1 and $nrow(x)$, or missing in which case all values are returned
	Additional arguments, see Details

gridDistance 87

Details

Additional arguments:

```
nrows Integer. How many rows? Default is 1

col Integer. Start column. Default is 1

ncols Integer. How many columns? Default is the number of column left after the start column lyrs Integer (vector). Which layers? Default is all layers (1:nlayers(x))
```

Value

```
vector (x=RasterLayer) or matrix
```

Author(s)

Robert J. Hijmans

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
b <- getValuesBlock(r, row=100, nrows=3, col=10, ncols=5)
b
b <- matrix(b, nrow=3, ncol=5, byrow=TRUE)
b
logo <- brick(system.file("external/rlogo.grd", package="raster"))
getValuesBlock(logo, row=35, nrows=3, col=50, ncols=3, lyrs=2:3)</pre>
```

gridDistance

Grid distance

Description

The function calculates the distance to cells of a RasterLayer when the path has to follow the center of neighboring raster cells (currently only implemented as a 'queen' case).

The distance is in meters if the RasterLayer is not projected (+proj=longlat) and in map units (typically meters) when it is projected.

Distances are calculated by summing local distances between cells, which are connected with their neighbours in 8 directions.

Usage

```
gridDistance(x, origin, omit=NULL, filename="", ...)
```

88 gridDistance

Arguments

X	a RasterLayer object
origin	value(s) of the cells from which the distance is calculated
omit	value(s) of the cells which cannot be traversed (optional)
filename	character. output filename (optional)
	Additional arguments as for writeRaster

Details

If the RasterLayer to be processed is big, it will be processed in chunks automatically. This may lead to errors in the case of complex objects spread over different chunks (meandering rivers, for instance). You can try to solve these issues by varying the chunk size, see function setOptions().

Value

A RasterLayer object

Author(s)

Jacob van Etten and Robert J. Hijmans

See Also

See distance for 'as the crow flies' distance. Additional distance measures and options (directions, cost-distance) are available in the 'gdistance' package.

```
#world lonlat raster
r <- raster(ncol=10,nrow=10)
r[] <- 1
r[48] <- 2
r[66:68] <- 3
d <- gridDistance(r,origin=2,omit=3)
plot(d)

#UTM small area
projection(r) <- "+proj=utm +zone=15 +ellps=GRS80 +datum=NAD83 +units=m +no_defs"
d <- gridDistance(r,origin=2,omit=3)
plot(d)</pre>
```

hdr 89

Description

Write header files to use together with raster binary files to read the data in other applications.

Usage

```
hdr(x, format, extension='.wld')
```

Arguments

X	RasterLayer or RasterBrick object associated with a binary values file on disk
format	Type of header file: 'VRT', 'BIL', 'ENVI', 'ErdasRaw', 'IDRISI', 'SAGA', 'RASTER', 'WORLDFILE', 'PRJ'
extension	File extension, only used with an ESRI worldfile (format='WORLDFILE')

Details

The RasterLayer object must be associated with a file on disk.

You can use writeRaster to save a existing file in another format. But if you have a file in a 'raster' format (or similar), you can also only export a header file, and use the data file (.gri) that already exists. writeHeader can write a VRT (GDAL virtual raster) header (.vrt); an ENVI or BIL header (.hdr) file; an Erdas Raw (.raw) header file; an IDRISI (.rdc) or SAGA (.sgrd). This (hopefully) allows for reading the binary data (.gri), perhaps after changing the file extension, in other programs such as ENVI or ArcGIS.

Author(s)

```
Robert J. Hijmans
```

See Also

```
writeRaster, writeGDAL
```

```
r <- raster(system.file("external/test.grd", package="raster"))
r <- writeRaster(r, filename='export.grd', overwrite=TRUE)
hdr(r, format="ENVI")</pre>
```

90 head

head

Show the head or tail of a Raster* object

Description

Show the head (first rows/columns) or tail (last rows/columns) of the cell values of a Raster* object.

Usage

```
head(x, ...)
tail(x, ...)
```

Arguments

x Raster* object

... Additional arguments: rows=10 and cols=20, to set the maximum number of rows and columns that is shown. For RasterStack and RasterBrick objects there is an additional argument lyrs

Value

matrix

Author(s)

Robert J. Hijmans

See Also

```
getValuesBlock
```

```
r <- raster(nrow=25, ncol=25)
r[] = 1:ncell(r)
head(r)
tail(r, cols=10, rows=5)</pre>
```

hillShade 91

hillShade	Hill shading

Description

Compute hill shade from slope and aspect layers (both in radians). Slope and aspect can be computed with function terrain.

A hill shade layer is often used as a backdrop on top of which another, semi-transparant, layer is drawn.

Usage

```
hillShade(slope, aspect, angle=45, direction=0, filename='', normalize=FALSE, ...)
```

Arguments

slope	RasterLayer object with slope values (in radians)
aspect	RasterLayer object with aspect values (in radians)
angle	The the elevation angle of the light source (sun), in degrees
direction	The direction (azimuth) angle of the light source (sun), in degrees
filename	Character. Optional filename
normalize	Logical. If TRUE, values below zero are set to zero and the results are multiplied with 255
	Standard additional arguments for writing RasterLayer files

Author(s)

Andrew Bevan, Robert J. Hijmans

References

Horn, B.K.P., 1981. Hill shading and the reflectance map. Proceedings of the IEEE 69(1):14-47

See Also

terrain

```
## Not run:
alt <- getData('alt', country='CHE')
slope <- terrain(alt, opt='slope')
aspect <- terrain(alt, opt='aspect')
hill <- hillShade(slope, aspect, 40, 270)
plot(hill, col=grey(0:100/100), legend=FALSE, main='Switzerland')
plot(alt, col=rainbow(25, alpha=0.35), add=TRUE)
## End(Not run)</pre>
```

92 hist

hist

Histogram

Description

Create a histogram of the values of a RasterLayer. NA values are ignored. Large datasets are sampled using maxpixels.

Usage

```
hist(x, ...)
```

Arguments

```
x A Raster* object... Additional arguments. See under Methods and at hist
```

Value

This function is principally used for the side-effect of plotting a histogram, but it also returns an S3 object of class 'histogram' (invisibly if plot=TRUE).

Methods

```
A full call as implemented here:
```

```
hist(x, layer, maxpixels=100000, plot=TRUE, main, ...)
```

layer can be used to subset the layers to plot in a multilayer object (RasterBrick or Raster-Stack)

maxpixels is the maximum number of (randomly sampled) cells to be used for creating the histogram

see hist for the other arguments

See Also

```
pairs, boxplot
```

```
r1 <- raster(nrows=50, ncols=50)
r1 <- setValues(r1, runif(ncell(r1)))
r2 <- setValues(r1, runif(ncell(r1)))
rs <- r1 + r2
rp <- r1 * r2
par(mfrow=c(2,2))
plot(rs, main='sum')
plot(rp, main='product')
hist(rs)</pre>
```

image 93

```
a = hist(rp)
a
```

image

Image

Description

Create an "image" type plot of a RasterLayer. This is an implementation of a generic function in the graphics package. In most cases the plot function would be preferable because it produces a legend (and has some additional options).

Usage

```
image(x, ...)
```

Arguments

x A Raster* object

... Any argument that can be passed to image (graphics package)

Methods

Author(s)

Robert J. Hijmans

See Also

```
image, contour, plot
```

```
r <- raster(system.file("external/test.grd", package="raster"))
image(r)</pre>
```

94 inifile

inifile	Read a .ini file	

Description

This function reads '.ini' files. These are text file databases that are organized in [sections] containing pairs of "name = value".

Usage

```
readIniFile(filename, token='=', commenttoken=';', aslist=FALSE, case)
```

Arguments

filename	Character. Filename of the .ini file
token	Character. The character that seperates the "name" (variable name) from the "value"
commenttoken	Character. This token and everything that follows on the same line is considered a 'comment' that is not for machine consumption and is ignored in processing
aslist	Logical. Should the values be returned as a list
case	Optional. Function that operates on the text, such as toupper or tolower

Details

This function allows for using inistrings that have "=" as part of a value (but the token cannot be part of the 'name' of a variable!). Sections can be missing.

Value

A n*3 matrix of characters with columns: section, name, value; or a list if aslist=TRUE.

Author(s)

Robert J. Hijmans

initialize 95

initialize

Intitialize

Description

Create a new RasterLayer with values reflecting a cell property: v from 'x', 'y', 'col', 'row', or 'cell'. Alternatively, a function can be used. In that case, cell values are initialized without reference to pre-existing values. E.g., initialize with a random number (fun=runif). Either supply an argument to fun, or to v, but not both.

Usage

```
init(x, fun, v, filename="", ...)
```

Arguments

x A Raster* object

fun The function to be applied. This must be a function that can take the number of cells as a single argument to return a vector of values with a length equal to the number of cells

v 'x', 'y', 'row', 'col', or 'cell'

filename Output filename

Additional arguments as for writeRaster

Value

RasterLayer

Author(s)

Robert J. Hijmans

```
r <- raster(ncols=36, nrows=18)

x <- init(r, v='cell')

y <- init(r, fun=runif)

# there are different ways to set all values to 1

# for large rasters:
set1f <- function(x){rep(1, x)}
z1 <- init(r, fun=set1f, filename='test.grd', overwrite=TRUE)

# equivalent to
z2 <- setValues(r, rep(1, ncell(r)))
# or</pre>
```

96 interpolate

```
r[] \leftarrow rep(1, ncell(r))
# or
r[] <- 1
```

interpolate

Interpolate

Description

Make a RasterLayer with interpolated values based on a a fitted model object of classes such as 'gstat' or 'Krige'. I.e. these are models that have 'x' and 'y' as independent variables. If x and y are the only independent variables provide an empty (no associated data in memory or on file) RasterLayer for which you want predictions. If there are more spatial predictor variables provide these as a Raster* object in the first argument of the function. If you do not have x and y locations as implicit predictors in your model you should use predict instead.

Usage

```
interpolate(object, ...)
```

Arguments

a Raster* object object

Additional arguments. See below, under Methods . . .

Value

RasterLayer object

Methods

na.rm

```
A full call to the method is
```

```
interpolate(object, model, filename=", fun=predict, xyOnly=TRUE, ext=NULL, const=NULL,
index=1, na.rm=TRUE, ...)
```

object Raster* object model Fitted model object filename

Output filename for a new raster; if NA the result is not written to a file but returned with the RasterLayer objection. fun Function. Default value is 'predict', but can be replaced with e.g. 'predict.se' (depending on the class of the m Logical. If TRUE, values of the Raster* object are not considered as co-variables; and only x and y (longitude a xyOnly An Extent object to limit the prediction to a sub-region of x ext

data.frame. Can be used to add a constant for which there is no Raster object for model predictions. Particulal const Integer. To select the column if 'predict.model' returns a matrix with multiple columns index

Logical. Remove cells with NA values in the predictors before solving the model (and return a NA value for the

Additional arguments as for writeRaster

interpolate 97

Author(s)

Robert J. Hijmans

See Also

```
predict, predict.gstat, Tps
```

```
## Not run:
## Thin plate spline interpolation with x and y only
library(fields)
r <- raster(system.file("external/test.grd", package="raster"))</pre>
ra <- aggregate(r, 10)</pre>
xy <- data.frame(xyFromCell(ra, 1:ncell(ra)))</pre>
v <- getValues(ra)</pre>
tps <- Tps(xy, v)
p <- raster(r)</pre>
p <- interpolate(p, tps)</pre>
p \leftarrow mask(p, r)
plot(p)
se <- interpolate(p, tps, fun=predict.se)</pre>
se <- mask(se, r)
plot(se)
##gstat examples
library(gstat)
## inverse distance weighted interpolation with gstat
r <- raster(system.file("external/test.grd", package="raster"))</pre>
data(meuse)
mg <- gstat(id = "zinc", formula = zinc~1, locations = ~x+y, data=meuse, nmax=7, set=list(idp = .5))</pre>
z <- interpolate(r, mg)</pre>
z \leftarrow mask(z, r)
## kriging
coordinates(meuse) = ~x+y
v <- variogram(log(zinc)~1, meuse)</pre>
m <- fit.variogram(v, vgm(1, "Sph", 300, 1))</pre>
g <- gstat(NULL, "log.zinc", log(zinc)~1, meuse, model = m)</pre>
projection(r) <- projection(meuse)</pre>
x <- interpolate(r, g)</pre>
## End(Not run)
```

98 intersect

intersect

Intersect Extent

Description

Intersect two Extent objects. Returns the intersection, i.e. the area of overlap of two Extent objects. The second argument can also be any argument from which an Extent object can be extracted.

If the first object is a Raster* object, this function is equivalent to crop.

Usage

```
## S4 method for signature 'Extent'
intersect(x, y)
## S4 method for signature 'Raster'
intersect(x, y)
```

Arguments

x Extent or Raster* object

y Extent object, or any object from which an Extent can be extracted

Value

Extent or Raster* object

Author(s)

Robert J. Hijmans

See Also

```
union, extent, crop
```

```
e1 <- extent(-10, 10, -20, 20)
e2 <- extent(0, 20, -40, 5)
intersect(e1, e2)
```

intersectExtent 99

intersectExtent

Extent intersection

Description

```
Obsolete. See intersect
```

Usage

```
intersectExtent(x, ..., validate=TRUE)
```

Arguments

X	Extent object or object from which it can be coerced via extent (Raster* or
	Spatial* objects)

... Additional Extent or Raster* or Spatial* objects

validate Logical. If TRUE, an error is returned if the intersection is empty; else NULL is

returned if the intersection is empty

Value

Extent object

Author(s)

Robert J. Hijmans

See Also

```
union, intersect, extent
```

```
e1 <- extent(-10, 10, -20, 20)
e2 <- extent(0, 20, -40, 5)
intersectExtent(e1, e2)
```

100 KML

isLonLat

Is this longitude/latitude data?

Description

Test whether a Raster* object has the a longitude/latitude coordinate reference system.

Usage

```
isLonLat(x)
```

Arguments

Х

Raster* object

Value

Logical

Author(s)

Robert J. Hijmans

Examples

```
r <- raster()
isLonLat(r)
projection(r) <- "+proj=lcc +lat_1=48 +lat_2=33 +lon_0=-100 +ellps=WGS84"
isLonLat(r)</pre>
```

KML

Write a KML or KMZ file

Description

Export raster data to a KML file and an accompanying PNG image file. Multi-layer objects can be used to create an animation. The function attempts to combine these into a single (and hence more convenient) KMZ file (a zip file containing the KML and PNG files).

Usage

```
KML(x, ...)
```

Arguments

```
x Raster* object
```

... Additional arguments (see Details)

Logic-methods 101

Details

You can use the following additional argumetns:

filename output filename
time character vector with time lables for multilayer objects. The length of this vector should be nlayers(x) to indic
col color scheme to be used (see image
maxpixels
zip If there is no zip program on your path (on windows), you can supply the full path to a zip.exe here, in order to

.. Additional arguments that can be passed to image

Value

None. Used for the side-effect files written to disk.

Author(s)

This function was adapted for the raster package by Robert J. Hijmans, with ideas from Tony Fischbach, and based on functions in the maptools package by Duncan Golicher, David Forrest and Roger Bivand.

Examples

Logic-methods

Logical operators and functions

Description

The following logical (boolean) operators are available for computations with RasterLayer objects:

```
&, |, and !
```

The following functions are available with a Raster* argument:

```
is.na, is.nan, is.finite, is.infinite
```

102 mask

Value

A Raster object with logical (TRUE/FALSE values)

Note

These are convenient operators/functions that are most usful for relatively small RasterLayers for which all the values can be held in memory. If the values of the output RasterLayer cannot be held in memory, they will be saved to a temporary file. In that case it could be more efficient to use calc instead.

Author(s)

Robert J. Hijmans

See Also

```
Math-methods, overlay, calc
```

Examples

```
r <- raster(ncols=10, nrows=10)
r[] <- runif(ncell(r)) * 10
r1 <- r < 3 | r > 6
r2 <- !r1
r3 <- r >= 3 & r <= 6
r4 <- r2 == r3
r[r>3] <- NA
r5 <- is.na(r)
r[1:5]
r1[1:5]
r2[1:5]
r3[1:5]</pre>
```

mask

Mask values in a Raster object

Description

Create a new Raster* object where all cells that are NA in a 'mask' object are set to NA, and that has the same values as x in the other cells. Or use inverse=TRUE to set the cells that are not NA in the mask to NA.

Usage

```
mask(x, mask, ...)
```

match 103

Arguments

```
    x Raster* object
    mask Raster* object or a Spatial* object
    ... Additional arguments. See under Methods
```

Value

A new Raster* object, and in some cases the side effect of a new file on disk.

Methods

The following additional arguments can be passed, to replace default values for this function

```
reverse Boolean. If TRUE, areas on mask that are _not_ NA are masked.

filename Character. output filename

format Character. Output file type. See writeRaster

datatype Overwrite Logical. If TRUE, "filename" will be overwritten if it exists

progress Character. "text", "window", or "" (the default, no progress bar)
```

Author(s)

Robert J. Hijmans

Examples

```
r <- raster(ncol=10, nrow=10)
m <- raster(ncol=10, nrow=10)
r[] <- runif(ncell(r)) * 10
m[] <- runif(ncell(r))
m[m <0.5] <- NA
mr <- mask(r, m)</pre>
```

match

Value matching for Raster* objects

Description

match returns a Raster* object with the position of the matched values. The cell values are the index of the table argument.

%in% returns a logical Raster* object indicating if the cells values were matched or not.

Usage

```
match(x, table, nomatch = NA_integer_, incomparables = NULL)
x %in% table
```

104 Math-methods

Arguments

x Raster* object

table vector of the values to be matched against

nomatch the value to be returned in the case when no match is found. Note that it is

coerced to integer

incomparables a vector of values that cannot be matched. Any value in x matching a value

in this vector is assigned the nomatch value. For historical reasons, FALSE is

equivalent to NULL

Value

Raster* obeject

Author(s)

Robert J. Hijmans

See Also

```
calc, match
```

Examples

```
r <- raster(nrow=10, ncol=10)
r[] <- 1:100
m <- match(r, c(5:10, 50:55))
n <- r %in% c(5:10, 50:55)
```

Math-methods

Mathematical functions

Description

```
Generic mathematical functions that can be used with a Raster* object as argument: "abs", "sign", "sqrt", "ceiling", "floor", "trunc", "cummax", "cummin", "cumprod", "cumsum", "log", "log10", "log2", "log1p", "acos", "acosh", "asin", "asinh", "atan", "atanh", "exp", "expm1", "cos", "cosh", "sin", "sinh", "tanh", "tanh".
```

Note

You can use the, somewhat more flexible, function calc instead of the Math-methods.

Author(s)

Robert J. Hijmans

merge 105

See Also

```
Arith-methods, calc, overlay, atan2
```

Examples

```
r1 <- raster(nrow=10, ncol=10)
r1 <- (setValues(r1, runif(ncell(r1)))) * 10
r2 <- sqrt(r1)
s <- stack(r1, r2) - 5
b <- abs(s)</pre>
```

merge

Merge

Description

Merge Raster* objects to form a new Raster object with a larger spatial extent. If objects overlap, the values get priority in the same order as the arguments, but NA values are ignored (except when overlap=FALSE)

Usage

```
## S4 method for signature 'Raster,Raster'
merge(x, y, ..., tolerance=0.05, filename="", format, datatype, overwrite, progress, overlap=TRUE, extended
```

Arguments

x	Raster* or Extent object
У	Raster* or Extent object
	Additional Raster or Extent objects
tolerance	Numeric. Permissable difference in origin (relative to the cell resolution). See all.equal
filename	Character. output filename
overwrite	Logical. If TRUE, "filename" will be overwritten if it exists
format	Character. output file type. Either 'raster', 'ascii' or a supported GDAL 'driver' name see writeFormats
datatype	Character. Output data type. See dataType
progress	Character. "text", "window", or "" (the default, no progress bar)
overlap	Logical. If FALSE values of overlapping objects are based on the first layer, even if they are NA
ext	Extent object (optional) to limit the output to that extent

106 modal

Details

The Raster objects must have the same origin and resolution. In areas where the Raster objects overlap, the values of the Raster object that is first in the sequence of arguments will be retained. If you'd rather use the average of cell values, or do another computation, you can use mosaic instead of merge.

Value

RasterLayer or RasterBrick

Author(s)

Robert J. Hijmans

Examples

```
r1 <- raster(xmx=-150, ymn=60, ncols=30, nrows=30)
r1[] <- 1:ncell(r1)
r2 <- raster(xmn=-100, xmx=-50, ymx=50, ymn=30)
res(r2) <- c(xres(r1), yres(r1))
r2[] <- 1:ncell(r2)
rm <- merge(r1, r2)</pre>
```

modal

modal value

Description

Compute the mode for a vector of numbers, or across raster layers. The mode, or modal value, is the most frequent value in a set of values.

Usage

```
## S4 method for signature 'ANY'
modal(x, ..., ties='random', na.rm = FALSE)
## S4 method for signature 'Raster'
modal(x, ..., ties='random', na.rm = FALSE)
```

Arguments

Х	A vector of numbers (typically integers for modal), or a Raster* object
	additional (vectors of) numbers, or additional Raster* objects
ties	character. Indicates how to treat ties. Either 'random', 'lowest', 'highest', or 'NA'
na.rm	Remove (ignore) NA values

mosaic 107

Value

vector or RasterLayer

Author(s)

Robert J. Hijmans

Examples

```
data <- c(0,1,2,3,3,3,3,4,4,4,5,5,6,7,7,8,9,NA) modal(data, na.rm=TRUE)
```

mosaic

Merge Raster* objects, using a function to compute cell value for overlapping areas.

Description

Mosaic Raster* objects to form a new object with a larger spatial extent. A functions is used to compute cell values in areas where layers overlap (in contrast to the merge function which uses the values of the 'upper' layer). All objects must have the same origin, resolution, and coordinate reference system.

Usage

```
mosaic(x, y, ...)
```

Arguments

x Raster* object y Raster* object

... Additional RasterLayers and other arguments. See below, under Methods

Details

The RasterLayer objects must have the same origin and resolution.

Value

RasterLayer or RasterBrick object.

108 mosaic

Methods

```
A full call to mosaic is:

mosaic(x, y, ..., fun, na.rm=TRUE, tolerance=0.05, filename="", overwrite, format, progress)

Raster* object; or a list of Raster* objects

y Raster* object

... Additional Raster* objects

fun Function. E.g. mean, min, or max. Must be a function that accepts a 'na.rm' argument na.rm Logical. Only return NA when all values are NA

tolerance Numeric. Permissable difference in origin (relative to the cell resolution). See all.equal filename Character. output filename

overwrite Logical. If TRUE, "filename" will be overwritten if it exists

format Character. output file type. Either 'raster', 'ascii' or a supported GDAL 'driver' name see writeFormats

datatype Character. Output data type. See dataType

progress Character. "text", "window", or "" (the default, no progress bar)
```

Author(s)

Robert J. Hijmans

See Also

```
merge, expand
```

```
r <- raster(ncol=100, nrow=100)
r1 <- crop(r, extent(-10, 11, -10, 11))
r2 <- crop(r, extent(0, 20, 0, 20))
r3 <- crop(r, extent(9, 30, 9, 30))

r1[] <- 1:ncell(r1)
r2[] <- 1:ncell(r2)
r3[] <- 1:ncell(r3)

m1 <- mosaic(r1, r2, r3, fun=mean)

s1 <- stack(r1, r1*2)
s2 <- stack(r2, r2/2)
s3 <- stack(r3, r3*4)
m2 <- mosaic(s1, s2, s3, fun=min)</pre>
```

movingFun 109

|--|

Description

Helper function to compute 'moving' functions, such as the 'moving average'

Usage

```
movingFun(x, n, fun=mean, type='around', circular=FALSE, na.rm=FALSE)
```

Arguments

x n	A vector of numbers Size of the 'window', i.e. the number of sequential elements to use in the function
fun	A function like mean, min, max, sum
type	Character. One of 'around', 'to', or 'from'. The choice indicates which values should be used in the computation. The focal element is always used. If type is 'around', the other elements are before and after the focal element. Alternatively, you can select the elements preceding the focal element ('to') or those coming after it 'from'. For example, to compute the movingFun with n=3 for element 5 of a vector; 'around' used elements 4,5,6; 'to' used elements 3,4,5, and 'from' uses elements 5,6,7
circular	Logical. If true, the data are considered to have a circular nature (e.g. months of the year), and the last elements in vector x are used in the computation of the moving function of the first element(s) of the vector, and the first elements are used in the computation of the moving function for the last element(s)
na.rm	Logical. If TRUE, NA values should be ingored (by fun)

Value

Numeric

Author(s)

Robert J. Hijmans (who was inspired by Diethelm Wuertz' rollFun function in the fTrading package)

```
movingFun(1:12, 3, mean)
movingFun(1:12, 3, mean, 'to')
movingFun(1:12, 3, mean, 'from')
movingFun(1:12, 3, mean, circular=TRUE)
```

NAvalue NAvalue

```
v \leftarrow c(0,1,2,3,3,3,3,4,4,4,5,5,6,7,7,8,9,NA) movingFun(v, n=5) movingFun(v, n=5, na.rm=TRUE)
```

NAvalue

Set the NA value of a RasterLayer

Description

NAvalue returns the value that is used to write NA values to disk (in 'raster' type files). If you set the NA value of a RasterLayer, this value will be interpreted as NA when reading the values from a file. Values already in memory will not be affected.

If the NA value is smaller than zero, all values smaller or equal to that number will be set to NA.

Usage

```
NAvalue(x) <- value
```

Arguments

x A RasterLayer object

value the value to be interpreted as NA; set this before reading the values from the file.

Integer values are matched exactely; for decimal values files any value <= the

value will be interpreted as NA

Value

Returns or set the NA value used for storage on disk.

Author(s)

Robert J. Hijmans

```
r1 <- raster(system.file("external/rlogo.grd", package="raster"))
r2 <- r1
NAvalue(r2)
NAvalue(r2) <- 255
#plot(r1)
#x11()
#plot(r2)</pre>
```

ncell 111

ncell

Number or rows, columns, and cells of a Raster* object

Description

Get the number of rows, columns, or cells of a Raster* object.

Usage

```
ncol(x)
nrow(x)
ncell(x)
ncol(x) <- value
nrow(x) <- value</pre>
```

Arguments

```
x a Raster objectvalue row or column number (integer > 0)
```

Value

Integer

Author(s)

Robert J. Hijmans

See Also

```
dim, extent, res
```

```
r <- raster()
ncell(r)
ncol(r)
nrow(r)
dim(r)

nrow(r) <- 18
ncol(r) <- 36
# equivalent to
dim(r) <- c(18, 36)</pre>
```

112 nlayers

nlayers

Number of layers

Description

Get or set layer properties of a RasterStack object

Usage

```
nlayers(object)
layerNames(object) <- value</pre>
```

Arguments

object Raster* object

value a vector of character

Value

nlayers: A single numeric value >= 1 layerNames: a vector of character

Author(s)

Robert J. Hijmans

See Also

bands

```
#using a new default raster (1 degree global)
r <- raster(ncols=10, nrows=10)
r[] <- 1:ncell(r)
s <- stack(r, r, r)
nlayers(s)
layerNames(s)
layerNames(s) <- c('a', 'b', 'c')
layerNames(s)[2] <- c('bb')</pre>
```

obsolete 113

obsolete

Obsolete functions

Description

Obsolete functions. Use extract or rasterize instead.

Usage

```
polygonValues(...)
lineValues(...)
xyValues(...)
pointsToRaster(...)
linesToRaster(...)
polygonsToRaster(...)
```

Arguments

.. arguments

Value

An error message

See Also

```
extract, rasterize
```

Options

Global options for the raster package

Description

setOptions allows you to set, and inspect, a number of global options used by the raster package.

Most of these options are used when writing files to disk. They can be ignored by specific functions if the corresponding argument is provided as an argument to these functions.

The default location is returned by rasterTmpDir. It is the same as that of the R tempdir but you can change it (for the current session) with rasterOptions(tmpdir= .

To permanentely set any of these options, you can add them to <your R installation>/etc/Rprofile.site. For example, to change the default directory used to save temporary files, add a line like this: options(rasterTmpDir='c:/temp/') to that file. All raster files in that folder that are older than 24 hrs are deleted when the raster package is loaded.

showOptions shows the current options.

saveOptions attempts to save the current options (with the exception of the 'todisk' option) to the /etc/Rprofile.site file to make them persistent (they will be set when starting a new R session). clearOptions resets the options to their default values.

Options Options

Usage

```
setOptions(format, overwrite, datatype, tmpdir, progress, timer, chunksize,
maxmemory, todisk, setfileext, tolerance)
showOptions()
saveOptions()
clearOptions()
```

Arguments

format	Character. The default file format to use. See writeFormats
overwrite	Logical. The default value for overwriting existing files. If TRUE, existing files will be overwritten
datatype	Character. The default data type to use. See dataType
tmpdir	$Character.\ The\ default\ location\ for\ writing\ temporary\ files;\ See\ {\tt rasterTmpFile}$
progress	Character. Valid values are "text", "window" and "" (the default in most functions, no progress bar) $$
timer	Logical. If TRUE, the time it took to complete the function is printed
chunksize	Integer. Maximum number of cells to read/write in a single chunk while processing (chunk by chunk) disk based Raster* objects
maxmemory	Integer. Maximum number of cells to read into memory. I.e., if a Raster* object has more than this number of cells, canProcessInMemory will return FALSE
todisk	Logical. For debugging only. Default is FALSE and should normally not be changed. If TRUE, results are always written to disk, even if no filename is supplied (a temporary filename is used)
setfileext	Logical. Default is TRUE. If TRUE, the file extension will be changed when writing (if known for the file type). E.g. GTiff files will be saved with the .tif extension
tolerance	Numeric. The tolerance used when comparing the origin and resolution of Raster* objects. Expressed as the fraction of a single cell. This should be a number between 0 and 0.5

Value

None. This function is used for the side-effect of setting global options.

Author(s)

Robert J. Hijmans

See Also

options, rasterTmpFile

origin 115

origin

Origin

Description

Origin returns the coordinates of the point of origin of a Raster* object. This is the point closest to (0, 0) that you could get if you moved towards that point in steps of the x and y resolution.

Usage

```
origin(x)
```

Arguments

Х

Raster* object

Value

A vector of two numbers (x and y coordinates).

Author(s)

Robert J. Hijmans

See Also

```
ncell, coordinates
```

Examples

```
r <- raster(xmn=-0.5, xmx = 9.5, ncols=10)
origin(r)</pre>
```

overlay

Overlay Raster objects

116 overlay

Description

Create a new Raster* object, based on two or more Raster* objects. (You can also use a single object, but perhaps calc is what you are looking for in that case).

You should supply a function fun to set the way that the RasterLayers are combined. The number of arguments in the function must match the number of Raster objects (or take any number). For example, if you combine two RasterLayers you could use multiply: $fun=function(x,y)\{return(x*y)\}$ percentage: $fun=function(x,y)\{return(100 * x / y)\}$. If you combine three layers you could use $fun=function(x,y,z)\{return((x + y) * z)\}$

Note that the function must work for vectors (not only for single numbers). That is, it must return the same number of elements as its input vectors. Alternatively, you can also supply a function such as sum, that takes n arguments (as '...'), and perhaps also has a na.rm argument, like in sum(..., na.rm).

If a single mutli-layer object is provided, its layers are treated as individual RasterLayer objects if the argument "unstack=TRUE" is used. If multiple objects are provided, they should have the same number of layers, or it should be possible to recycle them (e.g., 1, 3, and 9 layers, which would return a RasterBrick with 9 layers).

Usage

```
## S4 method for signature 'Raster,Raster'
overlay(x, y, ..., fun, filename="", datatype, format, overwrite, progress, recycle=TRUE)
## S4 method for signature 'Raster,missing'
overlay(x, y, ..., fun, filename="", datatype, format, overwrite, progress, unstack=TRUE)
```

Arguments

x	Raster* object
у	Raster* object, or missing (only useful if x has multiple layers)
	Additional Raster objects
fun	Function to be applied. When using RasterLayer objects, the number of arguments of the function should match the number of Raster objects, or it should take any number of arguments. When using mult-layer objects the function should match the number of layers of the RasterStack/Brick object (unless unstack=FALSE)
filename	Character. Output filename (optional)
format	Character. Output file type. See writeFormats
datatype	Character. Output data type. See dataType
overwrite	Logical. If TRUE, "filename" will be overwritten if it exists
progress	Character. "text", "window", or "" (the default, no progress bar)
recycle	Logical. Should layers from Raster objects with fewer layers be recycled?
unstack	Logical. Should layers be ustacked before computation (i.e. does the fun refer

to individual layers in a multilayer object)?

overlay 117

Details

Instead of the overlay function you can also use aritmethic functions such as *, /, +, - with Raster objects (see examples). In that case you cannot specify an output filename. Moreover, the overlay function should be more efficient when using large data files that cannot be loaded into memory, as the use of the complex arithmetic functions might lead to the creation of many temporary files.

While you can supply functions such as sum or mean, it would be more direct to use the Raster* objects are arguments to those functions (e.g. sum(r1,r2,r3))

See rasterize and extract for "overlays" involving Raster* objects and polygons, lines, or points.

Value

Raster* object

Author(s)

Robert J. Hijmans

See Also

calc, Arith-methods

```
r <- raster(ncol=10, nrow=10)
r1 <- init(r, fun=runif)</pre>
r2 <- init(r, fun=runif)
r3 <- overlay(r1, r2, fun=function(x,y){return(x+y)})
# long version for multiplication
r4 <- overlay(r1, r2, fun=function(x,y)\{(x*y)\})
#use the individual layers of a RasterStack to get a RasterLayer
s \leftarrow stack(r1, r2)
r5 <- overlay(s, fun=function(x,y) x*y )
# equivalent to
r5c <- calc(s, fun=function(x) x[1]*x[2])
#Combine RasterStack and RasterLayer objects (s2 has four layers. r1 (one layer) and s (two layers) are recycled)
s2 <- stack(r1, r2, r3, r4)
b <- overlay(r1, s, s2, fun=function(x,y,z){return(x*y*z)} )</pre>
# use a single RasterLayer (same as calc function)
r6 <- overlay(r1, fun=sqrt)
# multiplication with more than two layers (make sure the number of RasterLayers matches the arguments of 'fun'
r7 <- overlay(r1, r2, r3, r4, fun=function(a,b,c,d){return(a*b+c*d)})
# equivalent function, efficient if values can be loaded in memory
r8 <- r1 * r2 + r3 * r4
```

pairs pairs

```
# Also works with multi-layer objects.
s1 <- stack(r1, r2, r3)
x <- overlay(s1, s1, fun=function(x,y)x+y+5)

# in this case the first layer of the shorter object is recycled.
# i.e., s2 is treated as stack(r1, r3, r1)
s2 <- stack(r1, r3)
y <- overlay(s1, s2, fun=sum)</pre>
```

pairs

Pairs plot (matrix of scatterplots)

Description

Pair plots of layers in a RasterStack or RasterBrick. This is a wrapper around graphics function pairs.

Usage

```
## S4 method for signature 'RasterStackBrick'
pairs(x, hist=TRUE, cor=TRUE, use="pairwise.complete.obs", maxpixels=100000, ...)
```

Arguments

X	RasterBrick or RasterStack
hist	Logical. If TRUE a histogram of the values is shown on the diagonal
cor	Logical. If TRUE the correlation coefficient is shown in the upper panels
use	Argument passed to the cor function
maxpixels	Integer. Number of pixels to sample from each layer of large Raster objects
	Additional arguments (only cex and main)

Author(s)

Robert J. Hijmans

See Also

```
boxplot, hist, density
```

```
r <- raster(system.file("external/test.grd", package="raster") )
s <- stack(r, 1/r, sqrt(r))
pairs(s)
## Not run:
# to make indvidual histograms:</pre>
```

persp 119

```
hist(r)
# or scatter plots:
plot(r, 1/r)
## End(Not run)
```

persp

Perspective plot

Description

Perspective plot of a RasterLayer. This is an implementation of a generic function in the graphics package.

Usage

```
persp(x, ...)
```

Arguments

x A Raster* object

... Any argument that can be passed to persp (graphics package)

Methods

```
persp(x, y=1, z=NULL, ...)

x a Raster* object
y a index of x = RasterStack
z values of z are ignored
```

Author(s)

Robert J. Hijmans

See Also

```
persp, contour, plot
```

```
r <- raster(system.file("external/test.grd", package="raster"))
persp(r)</pre>
```

120 plot

plot

Plot a Raster* object

Description

Plot (that is, make a map of) the values of a Raster* object, or make a scatterplot of their values.

Points, lines, and polygons can be drawn on top of a map using plot(..., add=TRUE), or functions like points, lines, polygons

text plots a textual (rather than color) representation of values of the cells on top of the cells.

Details

Most of the code for this function was taken from image.plot (fields package). Raster objects with a color-table (e.g. a graphics file) will be plotted according to the color table.

Methods

```
x=RasterLayer
```

```
plot(x, col=rev(terrain.colors(25)), maxpixels=100000, axes = TRUE, xlab="",
ylab="", alpha=1, useRaster=TRUE, ...)
x - RasterLayer object
col - A color palette, i.e. a vector of n contiguous colors such as rainbow, heat.colors, and
topo.colors, or one or your own making, perhaps using colorRampPalette
maxpixels - Maximum number of pixels used for the map
alpha - Number between 0 and 1 to set transparancy. 0 is entirely transparant, 1 is not
transparant
useRaster - If TRUE, the rasterImage function is used for plotting. Otherwise the image
function is used. This can be useful if rasterImage does not work well on your system
... - Any argument that can be passed to image.plot and to plot
If x has a 'Color table', the default all to plot is:
plot(x, maxpixels=500000, ext=NULL, interpolate=FALSE, axes=FALSE, xlab="",
ylab="", ...)
           An extent object to zoom in a region
```

ext interpolate Logical. Should the image be interpolated? Logical. Should axes be drawn? axes

Function. functions adding additional items such as points or polygons to the plot (map). Typically contain addfun

Graphical parameters

x=RasterStack or RasterBrick, y=numeric or missing

```
plot(x, col=rev(terrain.colors(25)), subsample=TRUE, maxpixels=100000, alpha=1,
axes=TRUE, xlab="", ylab="", ...)
```

plot 121

y The index of a RasterLayer in a RasterStack to be plotted. Either a single number between 1 and nl other arguments See above

x=Extent, **y="ANY"** Draws the (rectangular) bounding box of a raster object. plot(ext)

ext a Extent object

Author(s)

Robert J. Hijmans

See Also

```
spplot, plotRGB, persp, contour, pairs, hist
```

The rasterVis package has more advanced plotting methods for Raster* objects.

```
# RasterLayer
r <- raster(nrows=10, ncols=10)
r <- setValues(r, 1:ncell(r))
plot(r)
text(r)

e <- extent(r)
plot(e, add=TRUE, col='red', lwd=4)
e <- e / 2
plot(e, add=TRUE, col='red')

# Scatterplot of 2 RasterLayers
r2 <- sqrt(r)
plot(r, r2)

# Multi-layer object (RasterStack / Brick)
s <- stack(r, r2, r/r)
plot(s, 2)</pre>
```

122 plotRGB

```
plot(s)
# two objects, different range, one scale:
r[] <- runif(ncell(r))
r2 <- r/2
brks <- seq(0, 1, by=0.1)
nb <- length(brks)-1</pre>
par(mfrow=c(1,2))
plot(r, breaks=brks, col=rev(terrain.colors(nb)), lab.breaks=brks, zlim=c(0,1))
plot(r2, breaks=brks, col=rev(terrain.colors(nb)), lab.breaks=brks, zlim=c(0,1))
# breaks and labels
x <- raster(nc=10, nr=10)</pre>
x[] <- runif(ncell(x))
brk <- c(0, 0.25, 0.75, 1)
arg <- list(at=c(0.12,0.5,0.87), labels=c("Low","Med.","High"))
plot(x, col=terrain.colors(3), breaks=brk)
plot(x, col=terrain.colors(3), breaks=brk, axis.args=arg)
par(mfrow=c(1,1))
# color ramp
plot(x, col=colorRampPalette(c("red", "white", "blue"))(255))
# adding random points to the map
xy \leftarrow cbind(-180 + runif(10) * 360, -90 + runif(10) * 180)
points(xy, pch=3, cex=5)
# for SpatialPolygons do
# plot(pols, add=TRUE)
# adding random points to each map of each layer of a RasterStack
fun <- function() {</pre>
points(xy, cex=2)
points(xy, pch=3, col='red')
plot(s, addfun=fun)
```

plotRGB

Red-Green-Blue plot of a multi-layered Raster object

Description

Make a Red-Green-Blue plot based on three layers (in a RasterBrick or RasterStack). Three layers (bands) are combined such that one is the red channel, one is the green channel, and one is the blue channel. This function could be used to make 'True (or false) color images' from Landsat and other multi-band satellite images.

pointDistance 123

Methods

```
plotRGB(x, r=1, g=2, b=3, scale, maxpixels=500000, stretch=NULL, ext=NULL,
             a RasterBrick or RasterStack object
Х
             Integer. Index of the Red channel, between 1 and nlayers(x)
r
             Integer. Index of the Green channel, between 1 and nlayers(x)
g
             Integer. Index of the Blue channel, between 1 and nlayers(x)
b
             Integer. Maximum (possible) value in the three channels. Defaults to 255 or to the maximum value of x if that
scale
maxpixels
             Maximum number of pixels to use
             Option to stretch the values to increase the contrast of the image: "lin" or "hist"
stretch
             An extent object to zoom in a region
ext
             graphical parameters as in rasterImage
```

Author(s)

Robert J. Hijmans; stretch option based on functions by Josh Gray

See Also

plot

Examples

```
b <- brick(system.file("external/rlogo.grd", package="raster"))
plotRGB(b)
plotRGB(b, 3, 2, 1)
plotRGB(b, 3, 2, 1, stretch='hist')</pre>
```

pointDistance

Distance between points

Description

Calculate the geographic distance between two (sets of) points on a sphere (longlat=TRUE) or on a plane (longlat=FALSE).

Usage

```
pointDistance(p1, p2, longlat, ...)
```

124 predict

Arguments

p1	x and y coordinate of first (set of) point(s), either as $c(x, y)$, matrix(ncol=2), or SpatialPoints*.
p2	x and y coordinate of second (set of) second point(s) (like for p1). If this argument is missing, a distance matrix is computed for p1
longlat	Logical. If TRUE, coordinates should be in degrees; else they should represent planar ('Euclidean') space (e.g. units of meters)
• • •	Additional arguments. Can be used to set the radius, r, of the world (modeled as a sphere), when longlat=TRUE Default is r=6378137

Value

A single value, or a vector, or matrix of values giving the distance in meters (longlat=TRUE) or map-units (for instance, meters in the case of UTM) If p2 is missing, a distance matrix is returned

Author(s)

Robert J. Hijmans and Jacob van Etten

See Also

```
distanceFromPoints, distance, gridDistance, spDistsN1
```

Examples

```
a <- cbind(c(1,5,55,31),c(3,7,20,22))
b <- cbind(c(4,2,8,65),c(50,-90,20,32))

pointDistance(c(0, 0), c(1, 1), longlat=FALSE)
pointDistance(c(0, 0), c(1, 1), longlat=TRUE)
pointDistance(c(0, 0), a, longlat=TRUE)
pointDistance(a, b, longlat=TRUE)

#Make a distance matrix
dst <- pointDistance(a, longlat=TRUE)

# coerce to dist object
dst <- as.dist(dst)</pre>
```

predict

Spatial model predictions

Description

Make a Raster* object with predictions based on a a fitted model object. The first argument is a Raster* object with the independent variables. The layerNames in the RasterStack should exactely match those expected by the model. This will be the case if the same Raster* object was used (via extract) to obtain the values to fit the model (see the example). Any type of model (e.g. glm. gam, randomForest) for which a predict method has been implemented (or can be implemented) can be used.

predict 125

Usage

```
## S4 method for signature 'Raster'
predict(object, model, filename="", fun=predict, ext=NULL, const=NULL, index=1, na.rm=TRUE, format, da
```

Arguments

object	Raster* object. Typcially a multi-layer type (RasterStack or RasterBrick)
model	A fitted model of any class that has a 'predict' method (or for which you can supply a similar method as fun argument. E.g. glm, gam, or randomForest
filename	Optional output filename
fun	Function. Default value is 'predict', but can be replaced with e.g. predict.se (depending on the type of model), or your own custom function.
ext	An Extent object to limit the prediction to a sub-region of x
const	data.frame. Can be used to add a constant for which there is no Raster object for model predictions. Particulalry useful if the constant is a character-like factor value for which it is currently not possible to make a RasterLayer
index	Integer. To select the column if predict.'model' returns a matrix with multiple columns
na.rm	Logical. Remove cells with NA values in the predictors before solving the model (and return a NA value for those cells). This option prevents errors with models that cannot handle NA values. In most other cases this will not affect the output. An exception is when predicting with a boosted regression trees model because these return predicted value even if some (or all!) variables are NA
format	Character. Output file type. See writeRaster (optional)
datatype	Character. Output data type. See dataType (optional)
overwrite	Logical. If TRUE, "filename" will be overwritten if it exists
progress	Character. "text", "window", or "" (the default, no progress bar)
	Additional arguments to pass to the predict.'model' function

Value

RasterLayer or RasterBrick

Author(s)

Robert J. Hijmans

See Also

Use interpolate if your model has 'x' and 'y' as implicit independent variables (e.g., in kriging).

126 predict

Examples

```
# A simple model to predict the location of the R in the R-logo using 20 presence points
# and 50 (random) pseudo-absence points. This type of model is often used to predict species distributions
# see the dismo package for more of that.
# create a RasterStack or RasterBrick with with a set of predictor layers
logo <- brick(system.file("external/rlogo.grd", package="raster"))</pre>
layerNames(logo)
## Not run:
# the predictor variables
par(mfrow=c(2,2))
plotRGB(logo, main='logo')
plot(logo, 1, col=rgb(cbind(0:255,0,0), maxColorValue=255))
plot(logo, 2, col=rgb(cbind(0,0:255,0), maxColorValue=255))
plot(logo, 3, col=rgb(cbind(0,0,0:255), maxColorValue=255))
par(mfrow=c(1,1))
## End(Not run)
#get presence and pseudo-absence points
p <- matrix(c(48, 48, 48, 53, 50, 46, 54, 70, 84, 85, 74, 84, 95, 85, 66, 42, 26, 4, 19, 17, 7, 14, 26, 29, 39, 45, 51,
a <- cbind(runif(250)*(xmax(logo)-xmin(logo))+xmin(logo), runif(250)*(ymax(logo)-ymin(logo))+ymin(logo))
#extract values for points from stack
xy <- rbind(cbind(1, p), cbind(0, a))</pre>
v <- data.frame(cbind(xy[,1], extract(logo, xy[,2:3])))</pre>
colnames(v)[1] \leftarrow 'pa'
#build a model, here an example with glm
model <- glm(formula=pa~., data=v)</pre>
#predict to a raster
r1 <- predict(logo, model, progress='window')</pre>
plot(r1)
points(p, bg='blue', pch=21)
points(a, bg='red', pch=21)
# use a modified function to get a RasterBrick with p and se
# from the glm model. The values returned by 'predict' are in a list,
# and this list needs to be transformed to a matrix
predfun <- function(model, data) {</pre>
  v <- predict(model, data, se.fit=TRUE)</pre>
  cbind(p=as.vector(v$fit), se=as.vector(v$se.fit))
}
# predfun returns two variables, so use index=1:2
```

r2 <- predict(logo, model, fun=predfun, index=1:2)</pre>

Programming 127

```
# principal components of a RasterBrick
# here using sampling to simulate an object too large
# too feed all its values to prcomp
sr <- sampleRandom(logo, 100)</pre>
pca <- prcomp(sr)</pre>
# note the use of the 'index' argument
x <- predict(logo, pca, index=1:3)</pre>
plot(x)
## Not run:
require(randomForest)
rfmod <- randomForest(pa ~., data=v)</pre>
## note the additional argument "type='response'" that is passed to predict.randomForest
r3 <- predict(logo, rfmod, type='response', progress='window')</pre>
## get a RasterBrick with class membership probabilities
v$pa <- as.factor(v$pa)
rfmod2 <- randomForest(pa ~., data=v)</pre>
r4 <- predict(logo, rfmod2, type='prob', index=1:2)
spplot(r4)
## End(Not run)
```

Programming

Helper functions for programming

Description

These are low level functions that can be used by programmers to develop new functions. If in doubt, it is almost certain that you do not need these as these functions are already embedded in all other functions in the raster package.

canProcessInMemory is typically used within functions. In the raster package this function is used to determine if the amount of memory needed for the function is available. If there is not enough memory available, the function returns FALSE, and the function that called it will write the results to a temporary file.

openConnection opens a file connection for reading, closeConnection removes it.

pbCreate creates a progress bar, pbStep sets the progress, and pbClose closes it.

Usage

```
canProcessInMemory(x, n=4)
closeConnection(x)
openConnection(x, silent=FALSE)
pbCreate(nsteps, progress, style=3, ...)
```

Programming Programming

```
pbStep(pb, step=NULL, label='')
pbClose(pb, timer)
getCluster()
returnCluster()
```

Arguments

X	RasterLayer or RasterBrick object
n	Integer. The number of copies of a RasterLayer object with values that a function needs to store in memory
silent	Logical. passed on to GDAL.open
nsteps	Integer. Number of steps the progress bar will make from start to end (e.g. nrow(raster))
progress	Character. 'text', 'window', or "
style	style for text progress bar. See txtProgressBar
	additinal arguments
pb	a progress bar object created with pbCreate
step	which step is this ($1 <= {\sf step} <= {\sf nsteps}$). If step is NULL, a single step is taken
label	label for the non-text progress bars
timer	Logical. If TRUE, time to completion will be printed. If missing, the value will

be taken from the rasterOptions

Value

```
canProcessInMemory: logical
closeHandle: RasterLayer object
getCluster: snow cluster object
```

Author(s)

```
Robert J. Hijmans
```

```
r <- raster(nrow=100, ncol=100)
canProcessInMemory(r, 4)
r <- raster(nrow=100000, ncol=100000)
canProcessInMemory(r, 2)</pre>
```

projection 129

Description

Get or set the projection of a Raster* object

Usage

```
projection(x, asText = TRUE)
projection(x) <- value</pre>
```

Arguments

x A Raster* object

asText logical. If TRUE, the projection is returned as text. Otherwise a CRS object is

returned

value a CRS object or a character string describing a projection and datum in PROJ4

format

Details

projections are done by with the PROJ.4 library exposed by rgdal

Value

```
a Raster* object
```

Author(s)

Robert J. Hijmans

See Also

```
projectRaster, CRS-class, spTransform-methods, projInfo
```

```
r <- raster()
projection(r)
projection(r) <- "+proj=lcc +lat_1=48 +lat_2=33 +lon_0=-100 +ellps=WGS84"
projection(r)</pre>
```

projectRaster

projectRaster Project a Raster object

Description

Project the values of a Raster* object to a new Raster* object with another projection (coordinate reference system, (CRS)). You can do this by providing the new projection as a single argument in which case the function sets the extent and resolution of the new object. To have more control over the transformation, and, for example, to assure that the new object lines up with other datasets, you can provide a Raster* object with the properties that the input data should be projected to.

projecExtent returns a RasterLayer with a projected extent, but without any values. This Raster-Layer can then be adjusted (e.g. by setting its resolution) and used as a template 'to' in projectRaster.

Usage

```
projectRaster(from, to, res, crs, method="bilinear", filename="", ...)
projectExtent(object, crs)
```

Arguments

from	Raster* object
to	Raster* object with the parameters to which 'from' should be projected
res	Single or (vector of) two numerics. To, optionally, set the output resolution if 'to' is missing
crs	Character or object of class 'CRS'. PROJ.4 description of the coordinate reference system. In projectRaster this is used to set the output CRS if 'to' is missing, or if 'to' has no valid CRS
method	Method used to compute values for the new RasterLayer. Either 'ngb' (nearest neighbor), which is useful for categorical variables, or 'bilinear' (bilinear interpolation; the default value), which is appropriate for continuous variables.
filename	Character. Output filename
	Additional arguments as for writeRaster
object	Raster* object

Details

There are two approaches you can follow to project the values of a Raster object.

- 1) Provide a crs argument, and, optionally, a res argument, but do not provide a to argument.
- 2) Create a template Raster with the CRS you want to project to. You can use an existing object, or use projectExtent for this or an existing Raster* object. Also set the number of rows and columns (or the resolution), and perhaps adjust the extent. The resolution of the output raster should normally be similar to that of the input raster. Then use that object as from argument to project the input Raster to. This is the preferred method because you have most control. For example you can assure that the resulting Raster object lines up with other Raster objects.

projectRaster 131

Projection is performed using the PROJ.4 library accessed through the rgdal package.

One of the best places to find PROJ.4 coordinate reference system descriptions is http://www.spatialreference.org.

You can also consult this page: http://www.remotesensing.org/geotiff/proj_list/ to find the parameter options and names for projections.

Also see projInfo('proj'), projInfo('ellps'), and projInfo('datum') for valid PROJ.4 values.

Value

RasterLayer or RasterBrick object.

Note

Vector (points, lines, polygons) can be transformed with spTransform.

projecExtent does not work very well when transforming projected circumpolar data to (e.g.) longitude/latitude. Which such data you may need to adjust the returned object. E.g. do ymax(object) <- 90

Author(s)

Robert J. Hijmans

See Also

```
resample CRS-class, projInfo, spTransform
```

```
# create a new (not projected) RasterLayer with cellnumbers as values
r < - raster(xmn=-110, xmx=-90, ymn=40, ymx=60, ncols=40, nrows=40)
r <- setValues(r, 1:ncell(r))</pre>
projection(r)
# proj.4 projection description
newproj <- "+proj=lcc +lat_1=48 +lat_2=33 +lon_0=-100 +ellps=WGS84"</pre>
# we need the rgdal package for this
if (require(rgdal)) {
#simplest approach
pr1 <- projectRaster(r, crs=newproj)</pre>
# alternatively also set the resolution
pr2 <- projectRaster(r, crs=newproj, res=20000)</pre>
# inverse projection, back to the properties of 'r'
inv <- projectRaster(pr2, r)</pre>
# to have more control, provide an existing Raster object, here we create one
# using projectExtent (no values are transferred)
```

properties properties

```
pr3 <- projectExtent(r, newproj)
# Adjust the cell size
res(pr3) <- 200000
# now project
pr3 <- projectRaster(r, pr3)

## Not run:
# using a higher resolution
res(pr1) <- 10000
pr <- projectRaster(r, pr1, method='bilinear')
inv <- projectRaster(pr, r, method='bilinear')
dif <- r - inv
# small difference
plot(dif)

## End(Not run)
}</pre>
```

properties

Raster file properties

Description

Properties of the values of the file that a RasterLayer object points to dataSize returns the number of bytes used for each value (pixel, grid cell) dataSigned is TRUE for data types that include negative numbers.

Usage

```
dataSize(object)
dataSigned(object)
```

Arguments

object

Raster* object

Value

varies

Author(s)

Robert J. Hijmans

See Also

filename

quantile 133

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
dataSize(r)
dataSigned(r)
dataType(r)</pre>
```

quantile

Raster quantiles

Description

Compute quantiles for the cell values of a RasterLayer. If you want to compute quantiles for each cell across a number of layers, you can use calc(x, fun=quantile).

Usage

```
quantile(x, ...)
```

Arguments

x Raster object

Additional arguments: na.rm=TRUE, ncells=NULL, and additional arguments to the stats::quantile function, see quantile ncells can be used to set the number of cells to be sampled, for very large raster datasets.

Value

A vector of quantiles

Author(s)

Robert J. Hijmans

See Also

```
density, cellStats
```

```
r <- raster(ncol=100, nrow=100)
r[] <- rnorm(ncell(r), 0, 50)
quantile(r)
quantile(r, probs = c(0.25, 0.75), type=7,names = FALSE)</pre>
```

134 raster

raster

Create a RasterLayer object

Description

Methods to create a RasterLayer object. RasterLayer objects can be created from scratch, a filename, an Extent object, a matrix, an 'image' object, or from a Raster*, Spatial*, asc, kasc (adehabitat*), grf (geoR) or kde object.

In many cases, e.g. when a RasterLayer is created from a file, it does (initially) not contain any cell (pixel) values, it only has the parameters that describe the RasterLayer.

For an overview of the functions in the raster package have a look here: raster-package.

Usage

```
raster(x, ...)
```

Arguments

x Filename (character), Extent, Raster*, SpatialPixels*, SpatialGrid* object, matrix, or missing

... Additional arguments, see below

Details

A new RasterLayer object normally has no cell-values in memory. If it is created from a file on disk, you can access cell-values with getValues, extract and related functions. You can assign new values with setValues and with replacement.

Value

RasterLayer object

Methods

1) Create a RasterLayer object from a file

```
raster(x, band=1, ...)

x character. Name of raster file
band integer. Band number in case of a file of multiple bands, default = 1
... additional arguments.
```

Additional arguments:

native Logical. Default is FALSE except when package rgdal is missing. If TRUE, reading and writing of IDRISI, BIL, offset Integer. To indicated the number of header rows on non-standard ascii files (rarely useful; use with caution)

raster 135

For netCDF files (CF convention):

varname character. The variable name (e.g. 'altitude' or 'precipitation'. If not supplied and the file has multiple variables integer > 0. The 'band' (layer) number of the file. E.g., the 'time' variable (if there are any) (default=NA)

To read netCDF files, the ncdf package needs to be available.

If x is a character value, it should be a filename of a file that the raster package can read. Supported file types are the 'native' raster package format and those that can be read via rgdal. See readGDAL help for supported file types.

2) Create a RasterLayer object from scratch

```
raster(nrows=180, ncols=360, xmn=-180, xmx=180, ymn=-90, ymx=90, crs, ext)
```

ncols number of columns

xmn minimum x coordinate (left border)

xmx maximum x coordinate (right border)

ymn minimum y coordinate (bottom border)

ymx maximum y coordinate (top border)

number of rows

nrows

crs Character or object of class CRS. PROJ4 type description of a Coordinate Reference System (map projection). If the chief class Extent If present the appropriate type and type are innered.

ext object of class Extent. If present, the arguments xmn, xmx, ymn and ynx are ignored

(item x is 'missing' in this case)

3) Create a RasterLayer object from an Extent-class object

raster(x, nrows=10, ncols=10, crs=NA)

x Extent object
nrows number of rows
ncols number of columns
crs PROJ4 type description of a map projection

4) Create a RasterLayer object from a Raster* object.

This copies the parameters of a Raster* object to a new RasterLayer, but does not copy the filename nor the cell values associated with the original Raster* object.

raster(x)

x a Raster* object

5) Create a RasterLayer object from a RasterStack or RasterBrick object.

```
raster(x, layer=0)
```

x a RasterStack, SpatialPixels* or SpatialGrid* object

layer Integer. The layer from which to copy values to the new RasterLayer, if layer>0.

136 raster

6) Create a RasterLayer object from a RasterStack, RasterBrick, SpatialPixels* or SpatialGrid* object.

```
raster(x, layer=0)
```

x RasterStack, RasterBrick, SpatialPixels* or SpatialGrid* object
 layer Integer. the layer from which to copy values to the new RasterLayer, if layer>0

7) Create a RasterLayer object from a matrix.

The default extent is set to be between 0 and 1 in the x and y direction but can be changed at creation of the RasterLayer object or later. You can also provide a projection.

```
function(x, xmn=0, xmx=1, ymn=0, ymx=1, crs=NA)
```

```
x matrix
xmn minimum x coordinate (left border)
xmx maximum x coordinate (right border)
ymn minimum y coordinate (bottom border)
ymx maximum y coordinate (top border)
crs PROJ4 type description of a map projection (optional)
```

8) Create a RasterLayer object from an 'image' object (a list with vectors x and y and matrix z), or from an asc, kasc, or kde object

```
raster(img, crs)
```

x RasterStack, SpatialPixels* or SpatialGrid* objectcrs PROJ4 type description of a map projection (optional)

Author(s)

Robert J. Hijmans

See Also

```
stack, brick
```

```
# Create a RasterLayer object from a file
# N.B.: For your own files, omit the 'system.file' and 'package="raster"' bits
# these are just to get the path to files installed with the package

f <- system.file("external/test.grd", package="raster")
f
r <- raster(f)
logo <- raster(system.file("external/rlogo.grd", package="raster"))</pre>
```

Raster-class 137

```
#from scratch
r1 <- raster(nrows=108, ncols=21, xmn=0, xmx=10)
#from an Extent object
e <- extent(r)
r2 <- raster(e)
#from another Raster* object
r3 <- raster(r)
s <- stack(r, r, r)
r4 <- raster(s)
r5 <- raster(s, 3)</pre>
```

Raster-class

Raster* classes

Description

A raster is a database organized as a rectangular grid that is sub-divided into rectangular cells of equal area (in terms of the units of the coordinate reference system). The 'raster' package defines a number of "S4 classes" to manipulate such data.

The main user level classes are RasterLayer, RasterStack and RasterBrick. They all inherit from BasicRaster and can contain values for the raster cells.

An object of the RasterLayer class refers to a single layer (variable) of raster data. The object can point to a file on disk that holds the values the raster cells, or hold these values in memory. Or it can not have any associated values at all.

A RasterStack represents a collection of RasterLayer objects with the same extent and resolution. Organizing RasterLayer objects in a RasterStack can be practical when dealing with multiple layers; for example to summarize their values (see calc) or in spatial modeling (see predict).

An object of class RasterBrick can also contain multiple layers of raster data, but they are more tightly related. An object of class RasterBrick can refer to only a single (multi-band) data file, whereas each layer in a RasterStack can refer to another file (or another band in a multi-band file). This has implications for processing speed and flexibility. A RasterBrick should process quicker than a RasterStack (irrespective if values are on disk or in memory). However, a RasterStack is more flexible as a single object can refer to layers that have values stored on disk as well as in memory. If a layer that does not refer to values on disk (they only exists in memory) is added to a RasterBrick, it needs to load all its values into memory (and this may not be possible because of memory size limitations).

Objects can be created from file or from each other with the following functions: raster, brick and stack.

Raster* objects can also be created from SpatialPixels* and SpatialGrid* objects from the sp package using as, or the simply with the function raster, brick, or stack. Vice versa, Raster* objects can be coerced into a sp type object with as(,), e.g. as(x, 'SpatialGridDataFrame').

Common generic methods implemented for these classes include:

138 Raster-class

```
summary, show, dim, and plot, ... [ is implemented for RasterLayer.
```

The classes described above inherit from the BasicRaster class which inherits from BasicRaster. The BasicRaster class describes the main properties of a raster such as the number of columns and rows, and it contains an object of the link[raster]{Extent-class} to describe its spatial extent (coordinates). It also holds the 'coordinate reference system' in a slot of class CRS-class defined in the sp package. A BasicRaster cannot contain any raster cell values is therefore seldomly used.

The Raster* class inherits from BasicRaster. It is is a virtual class; which means that you cannot create an object of this class. It is used only to define methods for all the classes that inherit from it (RasterLayer, RasterStack and RasterBrick). Another virtual class is the RasterStackBrick class. It is formed by a class union of RasterStack and RasterBrick. You cannot make objects of it, but methods defined for objects of this class as arguments will accept objects of the RasterLayer and RasterStack as that argument.

Classes RasterLayer and RasterBrick have a slot with an object of class RasterFile that describes the properties of the file they point to (if they do). RasterLayer has a slot with an object of class SingleLayerData, and the RasterBrick class has a slot with an object of class MultipleLayerData. These 'datalayer' classes can contain (some of) the values of the raster cells

These classes are not further described here because users should not need to directly access these slots. The 'setter' functions such as setValues should be used instead. Using such 'setter' functions is much safer because a change in one slot should often affect the values in other slots.

Objects from the Class

Objects can be created by calls of the form new("RasterLayer", ...), or with the helper functions such as raster.

Slots

```
Slots for Raster* objects

title: Character

file: Object of class ".RasterFile"

data: Object of class ".SingleLayerData" or ".MulitpleLayerData". Not in RasterStack objects

history: To record processing history, not yet in use

legend: Object of class .RasterLegend, Default legend. Should store preferences for plotting. Not yet implemented except that it stores the color table of images, if available extent: Object of Extent-class

ncols: Integer

nrows: Integer

crs: Object of class "CRS", i.e. the coordinate reference system. In Spatial* objects this slot is called 'proj4string'
```

Author(s)

Robert J. Hijmans

rasterFromCells 139

Examples

```
showClass("RasterLayer")
```

rasterFromCells

Subset a raster by cell numbers

Description

This function returns a new raster based on an existing raster and cell numbers for that raster. The new raster is cropped to the cell numbers provided, and, if values=TRUE has values that are the cell numbers of the original raster.

Usage

```
rasterFromCells(x, cells, values=TRUE)
```

Arguments

x Raster* object (or a SpatialPixels* or SpatialGrid* object)

cells vector of cell numbers

values Logical. If TRUE, the new RasterLayer has cell values that correspond to the cell

numbers of x

Details

Cell numbers start at 1 in the upper left corner, and increase from left to right, and then from top to bottom The last cell number equals the number of cells of the Raster* object.

Value

RasterLayer

Author(s)

Robert J. Hijmans

See Also

```
rowFromCell
```

```
r <- raster(ncols=100, nrows=100)
cells <- c(3:5, 210)
r <- rasterFromCells(r, cells)
cbind(1:ncell(r), getValues(r))</pre>
```

140 rasterFromXYZ

rasterFromXYZ

Create a RasterLayer from x, y, z values

Description

Create a RasterLayer from x, y, and z values. x and y must be on a regular grid. If the resolution is not supplied, it is assumed to be the minimum distance between x and y coordinates, but a resolution of up to 10 times smaller is evaluated if a regular grid can otherwise not be created. If the exact properties of the RasterLayer are known beforehand, it may be preferable to simply create a new RasterLayer with the raster function instead, compute cell numbers and assign the values with these (see example below).

Usage

```
rasterFromXYZ(xyz, res=c(NA,NA), crs=NA, digits=5)
```

Arguments

xyz	Matrix or data.frame with three colomns: x and y coordinates, and value z
res	The x and y cell resolutin (optional)
crs	A CRS object or a character string describing a projection and datum in PROJ.4 format
digits	Precision for detecting wether points are on a regular grid (i.e., a low number of digits is a low precision)

Value

RasterLayer

Author(s)

Robert J. Hijmans

See Also

For random-like point distributions, see rasterize

```
r <- raster(nrow=10, ncol=10, xmn=0, xmx=10, ymn=0, ymx=10, crs=NA)
r[] <- runif(ncell(r))
r[r<0.5] <- NA
xyz <- rasterToPoints(r)

r2 <- rasterFromXYZ(xyz)

# equivalent to:
r3 <- raster(nrow=10, ncol=10, xmn=0, xmx=10, ymn=0, ymx=10)</pre>
```

rasterize 141

```
cells <- cellFromXY(r3, xyz[,1:2])
r3[cells] <- xyz[,3]</pre>
```

rasterize

Rasterize points, lines, or polygons

Description

Transfer values associated with 'vector' type spatial data (points, lines, polygons) to the spatially overlapping raster cells.

For polygons, 'spatially overlapping' means that the polygon must cover the center of a raster cell. All cells that are touched by a line are considered to be overlapping. Points that fall on a border between cells are placed in the cell to the right and/or in the cell below.

Usage

```
rasterize(x, y, ...)
```

Arguments

x points (a SpatialPoints* object, or a two-column matrix), SpatialLines*, SpatialPolygons*, or an Extent object

y Raster* object

... Additional arguments, see under Details

Value

RasterLayer or RasterBrick

Methods

= all cases =

If x is a Spatial*DataFrame, the index (integer), or column name (character) of the variable to be transfered. If field < 0, all features get the attribute value 1, and if field == 0, the attribute index is used (i.e. numbers from 1 to the number of features). If the Spatial object has a data.frame, all values >= 1 will use the attribute index. In all cases you can also provide a vector with the same length as the number of spatial features, or a matrix where the number of rows matches the number of spatial features

field Determine what values to assign to cells that are covered by multiple spatial features. You can use functions such as min, max, or mean, or one of the following character values: 'first', 'last', 'sum', 'min', or 'max'. The default value is 'last'

background Value to put in the cells that are not covered by any of the features of x. Default is NA mask Logical. If TRUE the values of the input Raster object are 'masked' by the spatial features of x. That is, cells that spatially overlap with the spatial features retain their values, the other cells become NA. Default is FALSE. This option cannot be used when update=TRUE

142 rasterize

update Logical. If TRUE, the values of the Raster* object are updated for the cells that overlap the spatial features of x. Default is FALSE. Cannot be used when mask=TRUE

updateValue Numeric (normally an integer), or character. Only relevant when update=TRUE. Select, by their values, the cells to be updated with the values of the spatial features. Valid character values are 'all', 'NA', and '!NA'. Default is 'all'

filename Character. Output filename (optional)

overwrite Logical. If TRUE, "filename" will be overwritten if it exists

format Character. Output file type. See writeRaster

datatype Character. Output data type. See dataType

progress Character. "text", "window", or "" (the default, no progress bar)

= points =

The value of a grid cell is determined by the values associated with the points and function fun.

If x represents points, each point is assinged to a grid cell. The default result is that cells with one or more points get value 1 and the other cells get the background value (default is NA).

If you want to know the number of points in each grid cell, use $fun=function(x,...)\{length(x)\}$. I.e., for each cell it computes the length of the vector of points. You can also use fun=sum, because the default 'field' value of a point is 1. For the number of unique values use fun=function(x, x)

...){ length(unique(na.rm(x)))}

There is one additional argument:

na.rm If TRUE, NA values are removed if fun honors the na.rm argument

Because of this argument, all functions fun must accept an na.rm argument, either explicitly or through 'dots'. This means that fun=length fails, but fun=function(x,...)length(x) works, although it ignores the na.rm argument. To use the na.rm argument you can use a function like this fun=function(x,na.rm){if (na.rm) length(na.omit(x)) else (length(x)), or use a function that removes NA values in all cases, like this function to compute the number of unique values "richness": fun=function(x, ...){length(unique(na.omit(x)))}. You can also pass multiple functions using a statement like fun=function(x)c(lenght(x),mean(x)), in which case the returned object is a RasterBrick (multiple layers).

= polygons and Extent =

A polygon value is transferred to a raster-cell if it covers the center of the cell. Either values associated with each polygon, or a polygon ID is transferred. Holes in polygons are recognized if they are correctly specified. The following additional arguments are available:

getCover Logical. If TRUE, the fraction of each grid cell that is covered by the polygons is returned (and the values of field, fun, mask, and update are ignored. The fraction covered is estimated by dividing each cell into 100 subcells and determining presence/absence of the polygon in the center of each subcell

silent Logical. If TRUE, feedback on the polygon count is suppressed. Default is FALSE

Author(s)

Robert J. Hijmans

See Also

extract

rasterize 143

```
# rasterize points
###################################
r <- raster(ncols=36, nrows=18)
n <- 1000
x < -runif(n) * 360 - 180
y < -runif(n) * 180 - 90
xy \leftarrow cbind(x, y)
# point or not?
r1 <- rasterize(xy, r)</pre>
# how many points?
r2 <- rasterize(xy, r, fun=sum)</pre>
vals <- runif(n)</pre>
# sum of the values associated with the points
r3 <- rasterize(xy, r, vals, fun=sum)
# with a SpatialPointsDataFrame
vals <- 1:n
p <- as.data.frame(cbind(xy, name=vals))</pre>
coordinates(p) <- ~x+y</pre>
r <- rasterize(p, r, 'name', fun=min)</pre>
#r2 <- rasterize(p, r, 'name', fun=max)</pre>
\#plot(r, r2, cex=0.5)
# rasterize lines
cds1 \leftarrow rbind(c(-180,-20), c(-140,55), c(10, 0), c(-140,-60))
cds2 \leftarrow rbind(c(-10,0), c(140,60), c(160,0), c(140,-55))
cds3 \leftarrow rbind(c(-125,0), c(0,60), c(40,5), c(15,-45))
lines <- SpatialLines(list(Line(cds1)), "1"), Lines(list(Line(cds2)), "2"), Lines(list(Line(cds3)), "3")</pre>
r <- raster(ncols=90, nrows=45)
r <- rasterize(lines, r)</pre>
## Not run:
plot(r)
plot(lines, add=TRUE)
r <- rasterize(lines, r, fun='count')</pre>
plot(r)
r[] \leftarrow 1:ncell(r)
r <- rasterize(lines, r, mask=TRUE)</pre>
plot(r)
r[] <- 1
r[lines] <- 10
plot(r)
```

144 rasterTmpFile

```
## End(Not run)
# rasterize polygons
###################################
p1 \leftarrow rbind(c(-180,-20), c(-140,55), c(10, 0), c(-140,-60), c(-180,-20))
hole <- rbind(c(-150,-20), c(-100,-10), c(-110,20), c(-150,-20))
p2 \leftarrow rbind(c(-10,0), c(140,60), c(160,0), c(140,-55), c(-10,0))
p3 \leftarrow rbind(c(-125,0), c(0,60), c(40,5), c(15,-45), c(-125,0))
pols <- SpatialPolygons( list( Polygons(list(Polygon(p1), Polygon(hole)), 1), Polygons(list(Polygon(p2)), 2), Polygons(li
pols@polygons[[1]]@Polygons[[2]]@hole <- TRUE</pre>
r <- raster(ncol=180, nrow=90)
r <- rasterize(pols, r, fun='sum')</pre>
## Not run:
plot(r)
plot(pols, add=T)
# add a polygon
p5 < -rbind(c(-180,10), c(0,90), c(40,90), c(145,-10), c(-25, -15), c(-180,0), c(-180,10))
addpoly <- SpatialPolygons(list(Polygons(list(Polygon(p5)), 1)))</pre>
addpoly <- as(addpoly, "SpatialPolygonsDataFrame")</pre>
addpoly@data[1,1] <- 10
r2 <- rasterize(addpoly, r, field=1, update=TRUE, updateValue="NA")
plot(r2)
plot(pols, border="blue", lwd=2, add=TRUE)
plot(addpoly, add=TRUE, border="red", lwd=2)
# get the percentage cover of polygons in a cell
r3 <- raster(ncol=36, nrow=18)
r3 <- rasterize(pols, r3, getCover=TRUE)
## End(Not run)
```

rasterTmpFile

Temporary files

Description

Functions in the raster package create temporary files if the values of an output RasterLayer cannot be stored in memory (ram). This can happen when no filename is provided to a function and in functions where you cannot provide a filename (e.g. when using 'raster algebra').

Temporary files are automatically removed at the start of each session. During a session you can use showTmpFiles to see what is there and removeTmpFiles to delete all the temporary files. rasterTmpFile returns a temporary filename. These can be useful when developing your own functions.

rasterToContour 145

Usage

```
rasterTmpFile(prefix='raster_tmp_')
showTmpFiles()
removeTmpFiles(h=24)
```

Arguments

prefix Character. Prefix to the filename (which will be followed by 10 random num-

bers)

h Numeric. The minimum age of the files in number of hours (younger files are

not deleted)

Details

The default path where the temporary files are stored is returned by showOptions(); you can change it (for the current session) with setOptions.

Value

```
rasterTmpFile returns a valid file name
showTmpFiles returns the names (.grd only) of the files in the temp directory
removeTmpFiles returns nothing
```

Author(s)

Robert J. Hijmans

See Also

```
setOptions, showOptions, tempfile
```

Examples

```
#rasterTmpFile('mytemp_')
showTmpFiles()
removeTmpFiles(h=24)
```

rasterToContour

Raster to contour lines conversion

Description

RasterLayer to contour lines. This is a wrapper around contourLines

```
rasterToContour(x, maxpixels=100000, ...)
```

146 rasterToPoints

Arguments

x a RasterLayer object
 maxpixels Maximum number of raster cells to use; this function fails when too many cells are used
 ... Any argument that can be passed to contourLines

Details

Most of the code was taken from maptools::ContourLines2SLDF, by Roger Bivand & Edzer Pebesma

Value

SpatialLinesDataFrame

Author(s)

Robert J. Hijmans

Examples

```
f <- system.file("external/test.grd", package="raster")
r <- raster(f)
x <- rasterToContour(r)
class(x)
plot(r)
plot(x, add=TRUE)</pre>
```

rasterToPoints

Raster to points conversion

Description

Raster to point conversion. Cells with NA are not converted. A function can be used to select a subset of the raster cells (by their values).

Usage

```
rasterToPoints(x, fun=NULL, spatial=FALSE, ...)
```

Arguments

X	A Raster* object
fun	Function to select a subset of raster values
spatial	Logical. If TRUE, the function returns a SpatialPointsDataFrame object
• • •	Additional arguments. Currently only progress to specify a progress bar. "text", "window", or "" (the default, no progress bar)

rasterToPolygons 147

Details

fun should be a simple function returning a logical value e.g.: fun=function(x){x==1} or fun=function(x){x>3}

Value

A matrix with three columns: x, y, and v (value), or a SpatialPointsDataFrame object

Author(s)

Robert J. Hijmans

Examples

```
r <- raster(nrow=18, ncol=36)
r[] <- runif(ncell(r)) * 10
r[r>8] <- NA
p <- rasterToPoints(r)
p <- rasterToPoints(r, fun=function(x){x>6})
#plot(r)
#points(p)
```

rasterToPolygons

Raster to polygons conversion

Description

Raster to polygons conversion. Cells with NA are not converted. A function can be used to select a subset of the raster cells (by their values).

Usage

```
rasterToPolygons(x, fun=NULL, n=4, na.rm=TRUE, digits=12, dissolve=FALSE)
```

Arguments

х	a Raster* object
fun	function to select a subset of raster values (only allowed if x has a single layer
n	The number of nodes for each polygon. Only 4, 8, and 16 are allowed
na.rm	If TRUE, cells with NA values in all layers are ignored
digits	number of digits to round the coordinates to
dissolve	logical. If TRUE, polygons with the same attribute value will be dissolved into multi-polygon regions. This option requires the rgeos package

148 readAll

Details

fun should be a simple function returning a logical value e.g.: fun=function(x){x==1} or fun=function(x){x>3 & x<6}

Value

SpatialPolygonsDataFrame

Author(s)

Robert J. Hijmans

Examples

```
r <- raster(nrow=18, ncol=36)
r[] <- runif(ncell(r)) * 10
r[r>8] <- NA
pol <- rasterToPolygons(r, fun=function(x){x>6})
#plot(r)
#plot(pol, add=T, col='red')
```

readAll

Read values from disk

Description

Read all values from a raster file associated with a Raster* object into memory. This function should normally not be used. In most cases getValues or getValuesBlock is more approprate as readAll will fail when there is no file associated with the RasterLayer (values may only exist on memory).

Usage

```
readAll(object)
```

Arguments

object

a Raster* object

Author(s)

Robert J. Hijmans

See Also

```
getValues, getValuesBlock, extract
```

reclass 149

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
r <- readAll(r)</pre>
```

reclass

Reclassify

Description

Reclassify values of a Raster* object. The function (re)classifies groups of values to other values. E.g. All values between 1 and 10 become 1, and all values between 11 and 15 become 2.

Reclassification is done with matrix "rcl". For simple cases, the functions subs and cut may be more efficient. Reclassification is done in the order of the reclass table. Thus, if there are overlapping ranges, the last range applies.

Usage

```
## S4 method for signature 'Raster'
reclass(x, rcl, filename='', include.lowest=FALSE, right=TRUE, ...)
```

Arguments

X	Raster* object
rcl	matrix for reclassification. This matrix must have 3 columns. The first two columns are "from" "to" of the input values, and the third column "becomes" has the new value for that range. (You can also supply a vector that can be coerced into a n*3 matrix (with byrow=TRUE)). You can also provide a two column matrix ("is", "becomes") which can be useful for integer values. In that case, the right argument is automatically set to NA
filename	character. Output filename (optional)
include.lowest	logical, indicating if a value equal to the lowest value in rcl (or highest value in the second column, for right = $FALSE$) should be included. The default is $FALSE$
right	logical, indicating if the intervals should be closed on the right (and open on the left) or vice versa. The default is TRUE. A special case is to use right=NA. In this case both the left and right intervals are open
	additional arguments as for writeRaster

Value

Raster* object

Author(s)

Robert J. Hijmans

rectify rectify

See Also

```
subs, cut, calc
```

Examples

```
r <- raster(ncols=36, nrows=18)
r[] <- runif(ncell(r))
# reclassify the values into three groups
# all values >= 0 and <= 0.25 become 1, etc.
m <- c(0, 0.25, 1, 0.25, 0.5, 2, 0.5, 1, 3)
rclmat <- matrix(m, ncol=3, byrow=TRUE)
rc <- reclass(r, rclmat)
# equivalent to
rc <- reclass(r, c(-Inf,0.25,1, 0.25,0.5,2, 0.5,Inf,3))</pre>
```

rectify

rectify a Raster object

Description

rectify changes a rotated Raster* object into a non-rotated (rectangular) object. This is wrapper function around resample.

Usage

```
rectify(x, ext, res, method='ngb', filename='', ...)
```

Arguments

x	Raster* object to be rectified
ext	Optional. Extent object or object from which an Extent object can be extracted
res	Optional. Single or two numbers to set the resolution
method	Method used to compute values for the new RasterLayer, should be "bilinear" for bilinear interpolation, or "ngb" for nearest neighbor
filename	Character. Output filename
	Additional arguments as for writeRaster

Value

RasterLayer or RasterBrick object

Author(s)

Robert J. Hijmans

resample 151

replacement

Replace cell values of a Raster* object

Description

You can set values of a Raster* object, when i is a vector of cell numbers, a Raster*, Extent, or Spatial* object.

These are shorthand methods that only work for relatively small Raster* objects. In other cases you can use functions such as calc and rasterize.

Methods

See Also

calc, rasterize

Examples

```
r <- raster(ncol=10, nrow=5)
r[] <- 1:ncell(r) * 2
r[1,] <- 1
r[,1] <- 2
r[1,1] <- 3

s <- stack(r, sqrt(r))
s[s<5] <- NA</pre>
```

resample

Resample a Raster object

Description

Resample transfers values between non matching Raster* objects (in terms of origin and resolution). Use projectRaster if the target has a different coordinate reference system (projection).

Before using resample, you may want to consider using these other functions instead: aggregate, disaggregate, crop, expand, merge.

152 resolution

Usage

```
## S4 method for signature 'Raster, Raster'
resample(x, y, method="bilinear", filename="", ...)
```

Arguments

x Raster* object to be resampled

y Raster* object with parameters that x should be resample to

method used to compute values for the new RasterLayer, should be "bilinear"

for bilinear interpolation, or "ngb" for using the nearest neighbor

filename character. Output filename (optional)
... Additional arguments as for writeRaster

Value

RasterLayer or RasterBrick object

Author(s)

Robert J. Hijmans

See Also

aggregate, disaggregate, crop, expand, merge, projectRaster

Examples

```
r <- raster(nrow=3, ncol=3)
r[] <- 1:ncell(r)
s <- raster(nrow=10, ncol=10)
s <- resample(r, s, method='bilinear')
#par(mfrow=c(1,2))
#plot(r)
#plot(s)</pre>
```

resolution

Resolution

Description

Get (or set) the x and/or y resolution of a Raster* object

```
xres(x)
yres(x)
res(x)
res(x) <- value</pre>
```

rotate 153

Arguments

x Raster* object

value Resolution (single number or vector of two numbers)

Value

A single numeric value or two numeric values.

Author(s)

Robert J. Hijmans

See Also

```
extent, ncell
```

Examples

```
r <- raster(ncol=18, nrow=18)
xres(r)
yres(r)
res(r)

res(r) <- 1/120
# set yres diffrently
res(r) <- c(1/120, 1/60)</pre>
```

rotate

Rotate

Description

Rotate a Raster* object that has x coordinates (longitude) from 0 to 360, to standard coordinates between -180 and 180 degrees. Longitude between 0 and 360 is frequently used in data from global climate models.

Usage

```
rotate(x, ...)
```

Arguments

```
x Raster* object
```

... Additional arguments as for writeRaster

154 rotated

Value

RasterLayer or a RasterBrick object

Author(s)

Robert J. Hijmans

See Also

flip

Examples

```
r <- raster(nrow=18, ncol=36)
m <- matrix(1:ncell(r), nrow=18)
r[] <- as.vector(t(m))
extent(r) <- extent(0, 360, -90, 90)
rr <- rotate(r)</pre>
```

rotated

Do the raster cells have a rotation?

Description

Do the raster cells have a rotation?

Usage

```
rotated(x)
```

Arguments

Χ

A Raster* object

Value

Logical value

Author(s)

Robert J. Hijmans

See Also

```
rectify
```

round 155

Examples

```
r <- raster()
rotated(r)</pre>
```

round

Integer values

Description

These functions take a single RasterLayer argument x and change its values to integers.

ceiling returns a RasterLayer with the smallest integers not less than the corresponding values of x.

floor returns a RasterLayer with the largest integers not greater than the corresponding values of x.

trunc returns a RasterLayer with the integers formed by truncating the values in x toward 0.

round returns a RasterLayer with values rounded to the specified number of digits (decimal places; default 0).

Details

```
see ?base::round
```

Value

a RasterLayer object

Methods

```
\begin{aligned} & ceiling(x) \; floor(x) \; trunc(x, ...) \; round(x, digits = 0) \\ & a \; Raster Layer \; object \end{aligned}
```

digits integer indicating the precision to be used

... additional arguments

Author(s)

Robert J.Hijmans

See Also

round

Examples

```
r <- raster(ncol=10, nrow=10)
r[] <- runif(ncell(r)) * 10
s <- round(r)</pre>
```

156 rowFromCell

rowFromCell

Row or column number from a cell number

Description

These functions get the row and/or column number from a cell number of a Raster* object)

Usage

```
colFromCell(object, cell)
rowFromCell(object, cell)
rowColFromCell(object, cell)
```

Arguments

```
object Raster* object (or a SpatialPixels* or SpatialGrid* object)
cell cell number(s)
```

Details

The colFromCell and similar functions accept a single value, or a vector or list of these values, Cell numbers start at 1 in the upper left corner, and increase from left to right, and then from top to bottom The last cell number equals the number of cells of the Raster* object.

Value

```
row of column number(s)
```

Author(s)

Robert J. Hijmans

See Also

```
cellFrom
```

Examples

```
r <- raster(ncols=10, nrows=10)
colFromCell(r, c(5,15))
rowFromCell(r, c(5,15))
rowColFromCell(r, c(5,15))</pre>
```

SampleInt 157

Sample Integer values

Description

Take a random sample from a range of integer values between 1 and n. Its purpose is similar to that of sample, but that function fails when n is very large.

Usage

```
sampleInt(n, size, replace=FALSE)
```

Arguments

n Positive number (integer); the number of items to choose from

size Non-negative integer; the number of items to choose replace Logical. Should sampling be with replacement?

Value

vector of integer numbers

Author(s)

Robert J. Hijmans

Examples

```
sampleInt(1e+12, 10)

# this may fail:
# sample.int(1e+12, 10)
# sample.int(1e+9, 10)
```

sampleRandom

Random sample

Description

Take a random sample from the cell values of a Raster* object (without replacement).

```
sampleRandom(x, size, ...)
```

158 sampleRegular

Arguments

x a Raster object size positive integer giving the number of items to choose.

... Additional arguments:

 ${\tt na.rm}$ Logical. If TRUE (the default), NA values are removed from random sam-

ple

ext Extent. To limit regular sampling to the area within the extent cells Logical. If TRUE, sampled cell numbers are also returned

rowcol Logical. If TRUE, sampled row and column numbers are also returned

sp Logical. If TRUE, a SpatialPointsDataFrame is returned

asRaster Logical. If TRUE, a Raster* object is returned with random cells with

values, all other cells with NA

Details

With na.rm=TRUE, the returned sample may be smaller than requested

Value

A vector, matrix (if cells=TRUE or x is a multi-layered object), or a SpatialPointsDataFrame (if sp=TRUE)

Author(s)

Robert J. Hijmans

See Also

```
sampleRegular
```

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
sampleRandom(r, size=10)
s <- stack(r, r)
sampleRandom(s, size=10, cells=TRUE, sp=TRUE)</pre>
```

sampleRegular

Regular sample

Description

Take a systematic sample from a Raster* object.

```
sampleRegular(x, size, ext=NULL, cells=FALSE, asRaster=FALSE, useGDAL=FALSE)
```

saverasterstack 159

Arguments

Х	a Raster object
size	positive integer giving the number of items to choose.
ext	Extent. To limit regular sampling to the area within that box
cells	Logical. Also return sampled cell numbers (if asRaster=FALSE)
asRaster	Logical. If TRUE, a RasterLayer or RasterBrick is returned, rather then the sampled values
useGDAL	Logical. If TRUE, GDAL is used to sample in some cases. This is quicker, but can result in values for a different set of cells. Only for rasters that are accessed via rgdal, are not rotated, and when cells=FALSE.

Value

A vector, matrix (if cells=TRUE; or for a multi-layered object), or RasterLayer (if asRaster=TRUE)

Author(s)

Robert J. Hijmans

See Also

sampleRandom

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
v <- sampleRegular(r, size=100)
x <- sampleRegular(r, size=100, asRaster=TRUE)</pre>
```

saverasterstack

Save or open a RasterStack file

Description

A RasterStack is a collection of RasterLayers with the same spatial extent and resolution. They can be crated from RasterLayer objects, or from file names. These two functions allow you to save the references to raster files and recreate a rasterStack object later. They only work if the RasterStack points to layers that have their values on disk. The values are not saved, only the references to the files.

```
stackOpen(stackfile)
stackSave(x, filename)
```

160 scalebar

Arguments

stackfile Filename for the RasterStack (to save it on disk)

x RasterStack object

filename File name

Details

When a RasterStack is saved to a file, only pointers (filenames) to raster datasets are saved, not the data. If the name or location of a raster file changes, the RasterStack becomes invalid.

Value

RasterStack object

Author(s)

Robert J. Hijmans

See Also

```
writeRaster, stack, addLayer
```

Examples

```
file <- system.file("external/test.grd", package="raster")
s <- stack(c(file, file))
s <- stackSave(s, "mystack")
# note that filename adds an extension .stk to a stackfile
## Not run:
s2 <- stackOpen("mystack.stk")
s2
## End(Not run)</pre>
```

scalebar

scalebar

Description

Add a scalebar to a plot

```
scalebar(d, xy = NULL, type = "line", divs = 2, below = "", lonlat = NULL, label, adj=c(0.5, -0.5), lwd = 1.5 colors | 1
```

setExtent 161

Arguments

d	distance covered by scalebar
ху	x and y coordinate to place the plot. Can be NULL. Use xy=click() to make this interactive
type	"line" or "bar"
divs	Number of divisions for a bar type. 2 or 4
below	Text to go below scalebar (e.g., "kilometers")
lonlat	Logical or NULL. If logical, TRUE indicates if the plot is using longitude/latitude coordinates. If NULL this is guessed from the plot's coordinates
adj	adjustment for text placement
label	Vector of three numbers to label the scale bar (beginning, midpoint, end)
lwd	line width for the "line" type scalebar
	arguments to be passed to other methods

Value

None. Use for side effect of a scalebar added to a plot

Author(s)

Robert J. Hijmans; partly based on a function by Josh Gray

See Also

plot

Examples

```
r <- raster( system.file("external/test.grd", package="raster") )
plot(r)
scalebar(1000)
scalebar(1000, xy=c(178000, 333500), type='bar', divs=4)</pre>
```

setExtent

Set the extent of a RasteLayer

Description

setExtent sets the extent of a Raster* object. Either by providing a new Extent object or by setting the extreme coordinates one by one.

```
setExtent(x, ext, keepres=FALSE, snap=FALSE)
extent(x) <- value</pre>
```

162 setMinMax

Arguments

X	A Raster*	object
---	-----------	--------

ext An object of class Extent (which you can create with extent, or an object that

has an extent (e.g. a Raster* or Spatial* object))

keepres logical. If TRUE, the resolution of the cells will stay the same after adjusting

the bounding box (by adjusting the number of rows and columns). If FALSE, the number of rows and columns will stay the same, and the resolution will be

adjusted.

snap logical. If TRUE, the extent is adjusted so that the cells of the input and output

RasterLayer are aligned

value An object of class Extent (which you can create with extent)

Value

```
a Raster* object
```

Author(s)

Robert J. Hijmans

See Also

```
extent, Extent-class
```

Examples

```
r <- raster()
bb <- extent(-10, 10, -20, 20)
extent(r) <- bb
r <- setExtent(r, bb, keepres=TRUE)</pre>
```

setMinMax

Compute min and max values

Description

The minimum and maximum value of a RasterLayer are computed (from a file on disk if necessary) and stored in the returned Raster* object.

Usage

```
setMinMax(x)
```

Arguments

x A Raster* object

setValues 163

Value

```
a Raster* object
```

Author(s)

Robert J. Hijmans

See Also

```
getValues
```

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
r
r <- setMinMax(r)</pre>
```

setValues

Set values of a Raster object

Description

You can use the setValues function to assign values to a RasterLayer or RasterBrick object. While you can access the 'values' slot of the objects directly, you would do that at your own peril because when setting values, multiple slots need to be changed; which is what these functions do.

Usage

```
setValues(x, values, layer)
values(x) <- value</pre>
```

Arguments

X	A RasterLayer or RasterBrick object
values	Cell values to associate with the RasterLayer object. There should be values for all cells
value	Cell values to associate with the RasterLayer object. There should be values for all cells
layer	Layer number (only relevant for RasterBrick objects). If missing, the values of all layers is set

Value

```
a Raster* object
```

164 shift

Author(s)

Robert J. Hijmans

See Also

```
replacement
```

Examples

```
r <- raster(ncol=10, nrow=10)
vals <- 1:ncell(r)
r <- setValues(r, vals)
# equivalent to
r[] <- vals</pre>
```

shift

Shift

Description

Shift the location of a Raster* object in the x and/or y direction

Usage

```
shift(object, ...)
```

Arguments

object A Raster* object
... Additional arguments, see Details

Details

The following additional arguments can be passed, to replace default values for this function

x Numeric. The shift in horizontal directiony Numeric. The shift in vertical direction

filename Character. Output filename

format Character. Output file type. See writeRaster datatype Character. Output data type. See dataType

overwrite Logical. If TRUE, "filename" will be overwritten if it exists progress Character. "text", "window", or "" (the default, no progress bar)

Value

```
a Raster* object
```

Slope and aspect 165

Author(s)

Robert J. Hijmans

See Also

```
flip, rotate
```

Examples

```
r <- raster()
r <- shift(r, x=1, y=-1)
```

Slope and aspect

Slope and aspect

Description

This is a depracated function. Use terrain in stead.

Usage

```
slopeAspect(dem, filename='', out=c('slope', 'aspect'), unit='radians', neighbors=8, flatAspect, ...)
```

Arguments

dem	RasterLayer object with elevation values in map units, or in meters when the crs is longitude/latitude
C : 1	

filename Character. Filename. optional

out Character vector containing one or more of these options: 'slope', 'aspect'

unit Character. 'degrees' or 'radians'

neighbors Integer. Indicating how many neighboring cells to use to compute slope for any

cell. Either 8 (queen case) or 4 (rook case), see Details

flatAspect Numeric or NA. What value to use for aspect when slope is zero (and hence the

aspect is undefined)? The default value is 90 degrees (or 0.5*pi radians)

. . . Standard additional arguments for writing RasterLayer files

Author(s)

Robert J. Hijmans

See Also

terrain

166 stack

spplot

Use spplot to plot a Raster* object

Description

A wrapper functions around spplot (sp package). With spplot it is easy to map several layers with a single legend for all maps. ssplot is itself a wrapper around the levelplot function in the lattice package, and see the help for these functions for additional options.

One of the advantages of these wrapper functions is the additional maxpixels argument to sample large Raster objects for faster drawing.

Methods

Author(s)

Robert J. Hijmans

See Also

```
plot, plotRGB
```

The rasterVis package has more advanced plotting methods for Raster objects

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
s <- stack(r, r*2)
layerNames(s) <- c('meuse', 'meuse x 2')
spplot(s)</pre>
```

stack

Create a RasterStack object

Description

A RasterStack is a collection of RasterLayer objects with the same spatial extent and resolution. A RasterStack can be created from RasterLayer objects, or from raster files, or both. It can also be created from SpatialPixels or SpatialGrid objects.

stackApply 167

Value

RasterStack

Methods

```
stack(x, ..., bands=NULL)
filename (character), Raster* object, SpatialGrid*, SpatialPixels*, or list (of filenames and/or
Raster* objects). If x is a list, additional arguments ... are ignored.
.. x additional Raster* objects (or filenames)
```

Author(s)

Robert J. Hijmans

See Also

```
addLayer, dropLayer, raster, brick
```

Examples

```
# file with one layer
fn <- system.file("external/test.grd", package="raster")
s <- stack(fn, fn)
r <- raster(fn)
s <- stack(r, fn)
nlayers(s)

# file with three layers
slogo <- stack(system.file("external/rlogo.grd", package="raster"))
nlayers(slogo)
slogo</pre>
```

bands Which bands (layers) of the file should be used (default is all layers)

stackApply

Apply a function on subsets of a RasterStack or RasterBrick

Description

Apply a function on subsets of a RasterStack or RasterBrick. The layers to be combined are indicated with the vector indices. The function used should return a single value, and the number of layers in the output Raster* equals the number of unique values in indices. For example, if you have a RasterStack with 6 layers, you can use indices=c(1,1,1,2,2,2) and fun=sum. This will return a RasterBrick with two layers. The first layer is the sum of the first three layers in the input RasterStack, and the second layer is the sum of the last three layers in the input RasterStack. See calc if you want to use a function that returns multiple layers based on _all_ layers in the Raster* object.

168 stackSelect

Usage

```
stackApply(x, indices, fun, filename='', na.rm=TRUE, ...)
```

Arguments

X	A Raster* object
indices	A vector of length nlayers(x) containing all integer values between 1 and the number of layers of the output Raster*
fun	A function that returns a single value, e.g. mean or min, and that takes an 'na.rm' argument
na.rm	Logical. If TRUE, NA cells are removed from calculations
filename	Character. Optional output filename
	Additional arguments as for writeRaster

Value

A new Raster* object, and in some cases the side effect of a new file on disk.

Author(s)

Robert J. Hijmans

See Also

```
calc, stackSelect
```

Examples

```
r <- raster(ncol=10, nrow=10)
r[]=1:ncell(r)
s <- brick(r,r,r,r,r,r)
s <- s * 1:6
b1 <- stackApply(s, indices=c(1,1,1,2,2,2), fun=sum)
b1
b2 <- stackApply(s, indices=c(1,2,3,1,2,3), fun=sum)
b2</pre>
```

stackSelect

Select cell values from a multi-layer Raster* object

Description

Use a Raster* object to select cell values from different layers in a multi-layer Raster* object. The object to select values y should have cell values between 1 and nlayers(x). The values of y are rounded.

See extract for extraction of values by cell, point, or otherwise.

subset 169

Usage

```
## S4 method for signature 'RasterStackBrick,Raster'
stackSelect(x, y, recycle=FALSE, type='index', filename='', ...)
```

Arguments

x RasterStack or RasterBrick object

y Raster* object

recycle Logical. Recursively select values (default = FALSE. Only relevant if y has mul-

tiple layers. E.g. if x has 12 layers, and y has 4 layers, the indices of the y layers

are used three times.

type Character. Only relevant when recycle=TRUE. Can be 'index' or 'truefalse'. If it

is 'index', the cell values of y should represent layer numbers. If it is 'truefalse'

layer numbers are indicated by 0 (not used, NA returned) and 1 (used)

filename Character. Output filename (optional)
... Additional arguments as for writeRaster

Value

Raster* object

Author(s)

Robert J. Hijmans

See Also

```
stackApply, extract
```

Examples

```
r <- raster(ncol=10, nrow=10)
r[] <- 1
s <- stack(r, r+2, r+5)
r[] <- round((runif(ncell(r)))*3)
x <- stackSelect(s, r)</pre>
```

subset

Subset layers in a Raster* object

Description

Extract layers from a Raster* object.

```
subset(x, ...)
```

170 substitute

Arguments

x RasterBrick or RasterStack object

... Additional arguments: subset, which should indicate the layers (represented as integer or by their name). drop=TRUE. If TRUE, a selection of a single layer will be returned as a RasterLayer

Value

Raster* object

Author(s)

Robert J. Hijmans

See Also

dropLayer

Examples

```
r <- raster(system.file("external/test.grd", package="raster"))
s <- stack(r,r,r)
sel <- subset(s, 2:3)
sel <- subset(s, 2)
sel <- subset(s, 2, drop=FALSE)

# sel <- subset(s, 2:3) is equivalent to
sel <- dropLayer(s, 1)</pre>
```

substitute

Substitute values in a RasterLayer

Description

Substitute (replace) values in a RasterLayer with values in a data.frame. The data.frame should have a column to identify the key (ID) to match with the values of the RasterLayer, and a column with the replacement values. By default these are the first and second column but you can specify other columns with arguments by and which (see under Methods).

Usage

```
subs(x, y, ...)
```

Arguments

x A RasterLayer object

y A data.frame

. . . Additional arguments. See under Methods

substitute 171

Details

You could obtain the same result with reclass, but subs is more efficient for simple replacement. Use reclass if you want to replace ranges of values with new values.

You can also replace values using a fitted model. E.g. fit a model to glm or loess and then call predict

Value

A new RasterLayer object, and in some cases, the side effect of a new file on disk.

Methods

```
A full call to subs is:
        subs(x, y, by=1, which=2, subsWithNA=TRUE, filename=", ... )
        RasterLayer
y data.frame
  by The column number or name that is the key (ID) to match a the data. frame row to a value of
        the RasterLayer. Default is 1
  which The column number or name that has the new (replacement) values. Default is 2
   subsWithNA Logical. If TRUE values that are not matched become NA. If FALSE, they retain their
        original value (which could also be NA. This latter option is handy when you want to replace
        only one or a few values).
   filename Character. output filename
   ... Standard additional variables, see below
  overwrite Logical. If TRUE, "filename" will be overwritten if it exists
   format Character. output file type. Either 'raster', 'ascii' or a supported GDAL 'driver' name see
        writeFormats
   datatype Character. Output data type. See dataType
   progress Character. "text", "window", or "" (the default, no progress bar)
```

Author(s)

Robert J. Hijmans

See Also

reclass

Examples

```
r <- raster(ncol=10, nrow=10)
r[] <- round(runif(ncell(r)) * 10)
df = data.frame(id=2:8, v=c(10,10,11,11,12:14))
x = subs(r, df)
x2 = subs(r, df, subsWithNA=FALSE)</pre>
```

172 Summary-methods

Summary

Summary

Description

Summarize a Raster* object. A sample is used for very large files.

Details

summary(x, maxsamp=5000, ...) You can set the sample size with maxsamp

Value

A RasterSummary object

See Also

cellStats

Summary-methods

Summary methods

Description

The following summary methods are available for Raster* objects:

```
mean, max, min, range, prod, sum, any, all
```

All methods take na.rm as an additional logical argument. Default is na.rm=FALSE. If TRUE, NA values are removed from calculations. These methods compute a summary statistic based on cell values of RasterLayers and the result of these methods is always a single RasterLayer. See calc for functions not included here (e.g. median) or any other custom functions.

You can mix RasterLayer, RasterStack and RasterBrick objects with single numeric or logical values. However, because generic functions are used, the method applied is chosen based on the first argument: 'x'. This means that if r is a RasterLayer object, mean(r, 5) will work, but mean(5, r) will not work.

The generic function range returns 2 values (the minimum and maximum value of a vector). The Raster* implementations returns a single values (the maximum minus the minimum)

To summarize all cells within a single RasterLayer, see cellStats and maxValue and minValue

Value

a RasterLayer

Author(s)

Robert J. Hijmans

terrain 173

See Also

calc

Examples

```
r1 <- raster(nrow=10, ncol=10)
r1 <- setValues(r1, runif(ncell(r1)))
r2 <- setValues(r1, runif(ncell(r1)))
r3 <- setValues(r1, runif(ncell(r1)))
r <- max(r1, r2, r3)
r <- range(r1, r2, r3, 1.2)

s <- stack(r1, r2, r3)
r <- mean(s, 2)</pre>
```

terrain

Terrain characteristics

Description

Compute slope, aspect and other terrain characteristics from a raster with elevation data. The elevation data should be in map units (typically meter) for projected (planar) raster data. They should be in meters when the coordinate reference system (CRS) is longitude/latitude.

This function is the replacement for the depracated function slopeAspect

Usage

```
terrain(x, opt='slope', unit='radians', neighbors=8, filename='', ...)
```

Arguments

X	RasterLayer object with elevation values. Values should have the same unit as the map units, or in meters when the crs is longitude/latitude
opt	Character vector containing one or more of these options: slope, aspect, TPI, TRI, roughness, flowdir (see Details)
unit	Character. 'degrees' or 'radians'. Only relevant for slope and aspect
neighbors	Integer. Indicating how many neighboring cells to use to compute slope for any cell. Either 8 (queen case) or 4 (rook case). Only used for slope and aspect, see Details
filename	Character. Filename. optional
	Standard additional arguments for writing Raster* objects to file

174 terrain

Details

When neighbors=4, slope and aspect are computed according to Fleming and Hoffer (1979) and Ritter (1987). When neigbors=8, slope and aspect are computed according to Horn (1981). The Horn algorithm may be best for rough surfaces, and the Fleming and Hoffer algorithm may be better for smoother surfaces (Jones, 1997; Burrough and McDonnell, 1998). If slope = 0, aspect is set to 0.5*pi radians (or 90 degrees if unit='degrees'). When computing slope or aspect, the CRS (projection) of the RasterLayer x must be known (may not be NA), to be able to safely differentiate between planar and longitude/latitude data.

flowdir returns the 'flow direction' (of water), i.e. the direction of the greatest drop in elevation (or the smallest rise if all neighbors are higher). The are enocded as powers of 2 (0 to 8). The cell right to the focal cell 'x' is 1, the one below that is 2, and so on:

If two cells have the same drop in elevation, a random cell is picked. That is not ideal as it may prevent the creation of connected flow networks. ArcGIS implements to the approach of Greenlee (1987) and I might adopt that in the future.

The terrain indices are according to Wilson et al. (2007), as in gdaldem. TRI (Terrain Ruggedness Index) is the mean of the absolute differences between the value of a cell and the value of its 8 surrounding cells. TPI (Topographic Position Index) is the difference between the value of a cell and the mean value of its 8 surrounding cells. Roughness is the difference between the maximum and the minimum value of a cell and its 8 surrounding cells.

Such measures can also be computed with the focal function:

```
f \leftarrow matrix(1, nrow=3, ncol=3)

TRI \leftarrow focal(x, w=f, fun=function(x, ...) sum(abs(x[-5]-x[5]))/8)

TPI \leftarrow focal(x, w=f, fun=function(x, ...) x[5] - mean(x[-5]))

rough \leftarrow focal(x, w=f, fun=function(x, ...) max(x) - min(x))
```

Author(s)

Robert J. Hijmans

References

Burrough, P., and R.A. McDonnell, 1998. Principles of Geographical Information Systems. Oxford University Press.

Fleming, M.D. and Hoffer, R.M., 1979. Machine processing of landsat MSS data and DMA topographic data for forest cover type mapping. LARS Technical Report 062879. Laboratory for Applications of Remote Sensing, Purdue University, West Lafayette, Indiana.

Greenlee, D.D., 1987. Raster and vector processing for scanned linework. Photogrammetric Engineering and Remote Sensing 53:1383-1387

Horn, B.K.P., 1981. Hill shading and the reflectance map. Proceedings of the IEEE 69:14-47

transpose 175

Jones, K.H., 1998. A comparison of algorithms used to compute hill slope as a property of the DEM. Computers & Geosciences 24: 315-323

Ritter, P., 1987. A vector-based slope and aspect generation algorithm. Photogrammetric Engineering and Remote Sensing 53: 1109-1111

Wilson, M.F.J., O'Connell, B., Brown, C., Guinan, J.C., Grehan, A.J., 2007. Multiscale terrain analysis of multibeam bathymetry data for habitat mapping on the continental slope. Marine Geodesy 30: 3-35.

See Also

hillShade

Examples

```
## Not run:
elevation <- getData('alt', country='CHE')
x <- terrain(elevation, opt=c('slope', 'aspect'), unit='degrees')
plot(x)
## End(Not run)</pre>
```

transpose

Transpose

Description

Transpose a Raster* object

Usage

t(x)

Arguments

Х

a Raster* object

Value

RasterLayer or RasterBrick

Author(s)

Robert J. Hijmans

See Also

```
transpose: flip, rotate
```

176 trim

Examples

```
r <- raster(nrow=18, ncol=36)
r[] <- 1:ncell(r)
rt <- t(r)</pre>
```

trim

Trim

Description

Trim (shrink) a Raster* object by removing outer rows and columns that have no data.

Or remove the whitespace before or after a string of characters.

Usage

```
trim(x, ...)
```

Arguments

x A Raster* object or a character string... additional arguments. See Details.

Details

If x is a Raster* object, the following additional arguments can be passed, to replace default values for this function

```
padding Integer. Number of outer rows/columns with NA values to keep; default=0

filename Output filename. Default = "

Character. Output file type. See writeRaster

Character. Output data type; can be 'INT', 'FLT', or a complete datatype description, See dataType

overwrite Logical. If TRUE, "filename" will be overwritten if it exists

progress Character. "text", "window", or "" (the default, no progress bar)
```

Value

A RasterLayer or RasterBrick object (if x is a Raster* object).

A character string If x is a character string.

Author(s)

Robert J. Hijmans and Jacob van Etten

Examples

```
r1 <- raster(ncol=36,nrow=18)
```

union 177

```
r1[309:310] <- 1:2
r1[353:355] <- 3:5
r1[400] <- 6
s <- trim(r1)
trim(" hi folks ")
```

union

Union Extent

Description

Union of two Extent objects. See crop and expand to union a Raster object with an Extent object.

Usage

```
## S4 method for signature 'Extent,Extent'
union(x, y)
```

Arguments

x Extenty Extent

Value

Extent

Author(s)

Robert J. Hijmans

See Also

```
intersect, extent, setExtent
```

Examples

```
e1 <- extent(-10, 10, -20, 20)
e2 <- extent(0, 20, -40, 5)
union(e1, e2)
```

178 unique

unionExtent

Extent union

Description

```
Obsolete. See union
```

Usage

```
unionExtent(x, ...)
```

Arguments

```
x A Extent or Raster* object... additional Extent or Raster* objects
```

Value

Extent object

Author(s)

Robert J. Hijmans

See Also

```
union, intersect, extent
```

Examples

```
e1 <- extent(-10, 10, -20, 20)
e2 <- extent(0, 20, -40, 5)
unionExtent(e1, e2)
```

unique

Unique values

Description

This function returns the unique values in a RasterLayer

```
unique(x, incomparables=FALSE, ...)
```

unstack 179

Arguments

```
x A RasterLayer objectincomparables Ignored. Must be missing... Ignored. Must be missing
```

Value

a vector

Author(s)

Robert J.Hijmans

See Also

unique

Examples

```
r <- raster(ncol=10, nrow=10)
r[] <- round(runif(ncell(r))*10)
unique(r)</pre>
```

unstack

Unstack

Description

Create or list of RasterLayer objects from a RasterStack or RasterBrick

Usage

```
unstack(x, ...)
```

Arguments

x a RasterStack object

... not used. further arguments passed to or from other methods

Value

A list of RasterLayer objects

Author(s)

Robert J. Hijmans

180 update

See Also

stack

Examples

```
file <- system.file("external/test.grd", package="raster")
s <- stack(file, file)
list1 <- unstack(s)
b <- brick(s)
list2 <- unstack(b)</pre>
```

update

Update raster cells of files (on disk)

Description

Update cell values of a file (i.e., cell values on disk) associated with a RasterLayer or RasterBrick.

User beware: this function _will_ make changes to your file (first make a copy if you are not sure what you are doing).

Writing starts at a cell number cell. You can write a vector of values (in cell order), or a matrix. You can also provide a vector of cell numbers (of the same length as vector v) to update individual cells.

See writeFormats for supported formats.

Usage

```
update(object, ...)
```

Arguments

object RasterLayer or RasterBrick that is associated with a file

.. Additional arguments.

v - vector or matrix with new values

cell - cell from where to start writing. Or a vector of cell numbers if v is a

vector of the same lenght.

band - band (layer) to update (for RasterBrick objects).

Value

RasterLayer or RasterBrick

Author(s)

Robert J. Hijmans

validCell 181

Examples

```
# setting up an example RasterLayer with file
r <- raster(nrow=5, ncol=10)
r <- writeRaster(r, 'test', overwrite=TRUE, datatype='INT2S')</pre>
as.matrix(r)
# update with a vector starting a cell
r <- update(r, v=rep(1, 5), cell=6)</pre>
# 99.99 gets rounded because this is an integer file
r <- update(r, v=9.99, cell=50)</pre>
as.matrix(r)
# update with a vector of values and matching vector of cell numbers
r \leftarrow update(r, v=5:1, cell=c(5,15,25,35,45))
as.matrix(r)
# updating with a marix, anchored at a cell number
m = matrix(1:10, ncol=2)
r <- update(r, v=m, cell=2)
as.matrix(r)
```

validCell

Validity of a cell, column or row number

Description

Simple helper functions to determine if a row, column or cell number is valid for a certain Raster* object

Usage

```
validCell(object, cell)
validCol(object, colnr)
validRow(object, rownr)
```

Arguments

object Raster* object (or a SpatialPixels* or SpatialGrid* object)

cell cell number(s)

colnr column number; or vector of column numbers

rownr row number; or vector of row numbers

Value

logical value

182 which

Author(s)

Robert J. Hijmans

Examples

```
#using a new default raster (1 degree global)
r <- raster()
validCell(r, c(-1, 0, 1))
validRow(r, c(-1, 1, 100, 10000))</pre>
```

which

Which cells are TRUE?

Description

Which returns a RasterLayer with TRUE or FALSE. Cells with 1 are set to TRUE, all other cells, including NA are set to FALSE

Usage

```
Which(x, ...)
```

Arguments

x A RasterLayer object or a logical expression resulting in a RasterLayer object

... Additional arguments. See Details

Details

You can use the additional logical argument cells. If cells=FALSE (the default), a (logical) Raster-Layer is returned, if cells=TRUE, the cell numbers are returned for which the condition is TRUE

Value

a RasterLayer object

Author(s)

Robert J.Hijmans

See Also

which

writeFormats 183

Examples

```
r <- raster(ncol=10, nrow=10)
r[] <- runif(ncell(r))
r[r< 0.2] <- NA
s <- Which(r > 0.5, cells=TRUE)
s[1:5]
s <- Which(r > 0.5)
```

writeFormats

File types for writing

Description

List supported file types for writing RasterLayer values to disk.

When a function writes a file to disk, the file format is determined by the 'format=' argument if supplied, or else by the file extension (if the extension is known). If other cases the default format is used. The 'factory-fresh' default format is 'raster', but this can be changed using setOptions.

Usage

writeFormats()

Details

writeFormats returns a matrix of the file formats (the "drivers") that are supported.

Supported formats include:

File type	Long name	default extension	Multiband support
raster	'Native' raster package format	.grd	Yes
ascii	ESRI Ascii	.asc	No
SAGA	SAGA GIS	.sdat	No
IDRISI	IDRISI	.rst	No
CDF	netCDF (requires ncdf)	.nc	Yes
GTiff	GeoTiff (requires rgdal)	.tif	Yes
ENVI	ENVI .hdr Labelled	.envi	Yes
EHdr	ESRI .hdr Labelled	.bil	Yes
HFA	Erdas Imagine Images (.img)	.img	Yes

Author(s)

Robert J. Hijmans

See Also

GDALDriver-class

184 writeRaster

Examples

```
writeFormats()
```

writeRaster

Write raster data to a file

Description

Write an entire Raster* object to a file, using one of the many supported formats. See writeValues for writing in chunks (e.g. by row).

When writing a file to disk, the file format is determined by the 'format=' argument if supplied, or else by the file extension (if the extension is known). If other cases the default format is used. The 'factory-fresh' default format is 'raster', but this can be changed using setOptions.

Usage

```
## S4 method for signature 'RasterLayer, character'
writeRaster(x, filename, format, ...)
## S4 method for signature 'RasterStackBrick, character'
writeRaster(x, filename, format, ...)
```

Arguments

X	Raster* object
filename	Output filename

format Character. Output file type. See writeFormats. If this argument is not provided, it is attempted to infer it from the filename extension. If that fails, the

default format is used. The default format is 'raster', but this can be changed using setOptions

Additional arguments:

datatype: Character. Output data type (e.g. 'INT2S' or 'FLT4S'). See dataType

overwrite: Logical. If TRUE, "filename" will be overwritten if it exists

NAflag: Numeric. To overwrite the default value used to represent NA in a file bandorder: Character. 'BIL', 'BIP', or 'BSQ'. For 'native' file formats only. For some other formats you can use the 'options' argument (see below)

options: Character. File format specific GDAL options. E.g., when writing a geotiff file: options=c("COMPRESS=NONE", "TFW=YES")

NetCDF files have the following additional, optional, arguments: varname, varunit, longname, xname, yname, zname, zunit.

writeRaster 185

Details

See writeFormats for supported file types ("formats", "drivers").

The rgdal package is needed, except for these file formats: 'raster', 'BIL', 'BIP', 'BSQ', 'SAGA', 'ascii', 'IDRISI', and 'CDF'. Some of these formats can be used with or without rgdal (idrisi, SAGA, ascii). You need the 'ncdf' library for the 'CDF' format.

In multi-band files (i.e. files saved from RasterStack or RasterBrick objects), in the native 'raster' format, the bandorder can be set to BIL ('Bands Interleaved by Line'), BIP ('Bands Interleaved by Pixels') or BSQ ('Bands SeQuential'). Note that bandorder is not the same as filetype here.

Supported file types include:

File type	Long name	default extension	Multiband support
raster	'Native' raster package format	.grd	Yes
ascii	ESRI Ascii	.asc	No
SAGA	SAGA GIS	.sdat	No
IDRISI	IDRISI	.rst	No
CDF	netCDF (requires ncdf)	.nc	Yes
GTiff	GeoTiff (requires rgdal)	.tif	Yes
ENVI	ENVI .hdr Labelled	.envi	Yes
EHdr	ESRI .hdr Labelled	.bil	Yes
HFA	Erdas Imagine Images (.img)	.img	Yes

Value

This function is used for the side-effect of writing values to a file.

Author(s)

Robert J. Hijmans

See Also

writeFormats, writeValues

```
r <- raster(system.file("external/test.grd", package="raster"))
# take a small part
r <- crop(r, extent(179880, 180800, 329880, 330840) )
# write to an integer binary file
rf <- writeRaster(r, filename="allint.grd", datatype='INT4S', overwrite=TRUE)
# make a brick and save multi-band file
b <- brick(r, sqrt(r))
bf <- writeRaster(b, filename="multi.grd", bandorder='BIL', overwrite=TRUE)</pre>
```

186 write Values

```
# write to a new geotiff file (depends on rgdal)
if (require(rgdal)) {
    rf <- writeRaster(r, filename="test.tif", format="GTiff", overwrite=TRUE)
    bf <- writeRaster(b, filename="multi.tif", options="INTERLEAVE=BAND", overwrite=TRUE)
}

# write to netcdf
if (require(ncdf)) {
    rnc <- writeRaster(r, filename='netCDF.nc', format="CDF", overwrite=TRUE)
}</pre>
```

writeValues

Write values to a file

Description

Functions for writing blocks (>= 1 row(s)) of values to files. Writing has to start at the first cell of a row (identified with argument start) and the values written must represent 1 or more entire rows. Begin by opening a file with writeStart, then write values to it in chunks. When writing is done close the file with writeStop.

If you want to write all values of a Raster* object at once, you can also use writeRaster which is easier to use but more limited. The functions described here allow writing values to file using chunks of different sizes (e.g. 1 or 10 rows). Function blockSize can be used to suggest a chunk size to use.

Usage

```
writeStart(x, filename, ...)
writeValues(x, v, start)
writeStop(x)
```

Arguments

X	Raster* object
filename	Output filename
	Additional arguments as for writeRaster
V	vector (RasterLayer) or matrix (RasterBrick) of values
start	Integer. Row number (counting starts at 1) from where to start writing v

Value

RasterLayer or RasterBrick

Author(s)

Robert J. Hijmans

xyFromCell 187

See Also

```
writeRaster, blockSize, update
```

```
r <- raster(system.file("external/test.grd", package="raster"))</pre>
# write to a new binary file in chunks
s <- raster(r)
tr <- blockSize(r)</pre>
s <- writeStart(s, filename='test.grd', overwrite=TRUE)</pre>
for (i in 1:tr$n) {
v <- getValuesBlock(r, row=tr$row[i], nrows=tr$nrows[i])</pre>
s <- writeValues(s, v, tr$row[i])</pre>
s <- writeStop(s)</pre>
if(require(rgdal)){
s2 <- writeStart(s, filename='test2.tif', format='GTiff', overwrite=TRUE)</pre>
# writing last row first
for (i in tr$n:1) {
v <- getValuesBlock(r, row=tr$row[i], nrows=tr$nrows[i])</pre>
s2 <- writeValues(s2, v, tr$row[i])</pre>
# row number 5 once more
v <- getValuesBlock(r, row=5, nrows=1)</pre>
writeValues(s2, v, 5)
s2 <- writeStop(s2)</pre>
## write values of a RasterStack to a RasterBrick
s <- stack(system.file("external/rlogo.grd", package="raster"))</pre>
# create empty brick
b <- brick(s, values=FALSE)</pre>
b <- writeStart(b, filename="test.grd", format="raster",overwrite=TRUE)</pre>
tr <- blockSize(b)</pre>
for (i in 1:tr$n) {
v <- getValuesBlock(s, row=tr$row[i], nrows=tr$nrows[i])</pre>
b <- writeValues(b, v, tr$row[i])</pre>
}
b <- writeStop(b)</pre>
# note that the above is equivalent to
# b <- writeRaster(s, filename="test.grd", format="raster",overwrite=TRUE)</pre>
```

188 xyFromCell

Description

These functions get coordinates of the center of raster cells for a row, column, or cell number of a Raster* object.

Usage

```
xFromCol(object, colnr)
yFromRow(object, rownr)
xyFromCell(object, cell, spatial=FALSE)
xFromCell(object, cell)
yFromCell(object, cell)
```

Arguments

object	Raster* object (or a SpatialPixels* or SpatialGrid* object)
cell	cell number(s)
colnr	column number; or vector of column numbers
rownr	row number; or vector of row numbers
spatial	return a SpatialPoints object (sp package) instead of a matrix

Details

Cell numbers start at 1 in the upper left corner, and increase from left to right, and then from top to bottom The last cell number equals the number of cells of the Raster* object.

Value

xFromCol, yFromCol, xFromCell; vector of x or y coordinate(s) <math>xyFromCell: matrix(x,y) of pairs of coordinates

Author(s)

Robert J. Hijmans

See Also

```
cellFromXY
```

```
#using a new default raster (1 degree global)
r <- raster()
xFromCol(r, c(1, 120, 180))
yFromRow(r, 90)
xyFromCell(r, 10000)
xyFromCell(r, c(0, 1, 32581, ncell(r), ncell(r)+1))
#using a file from disk
r <- raster(system.file("external/test.grd", package="raster"))</pre>
```

z-values 189

```
r
cellFromXY(r, c(180000, 330000))
#xy for corners of a raster:
xyFromCell(r, c(1, ncol(r), ncell(r)-ncol(r)+1, ncell(r)))
```

z-values

Get or set z-values

Description

Initial functions for a somewhat more formal approach to get or set z values (e.g. time) associated with layers of Raster* objects. In development.

Usage

```
setZ(x, z, name='time')
getZ(x)
```

Arguments

```
x Raster* objectz vector of z values of any type (e.g. of class 'Date')name character label
```

Value

```
setZ: Raster* object
getZ: vector
```

Author(s)

Robert J. Hijmans

```
r <- raster(ncol=10, nrow=10)
s <- stack(lapply(1:3, function(x) setValues(r, runif(ncell(r)))))
s <- setZ(s, as.Date('2000-1-1') + 0:2)
s
getZ(s)</pre>
```

190 zApply

zApply z (time) apply

Description

Experimental function to apply a function over a (time) series of layers of a Raster object

Usage

```
zApply(x, by, fun=mean, name='', ...)
```

Arguments

x	Raster* object
by	aggregation indices or function
fun	function to compute aggregated values
name	character label of the new time series
	additional arguments

Value

Raster* object

Author(s)

Oscar Perpinan Lamigueiro & Robert J. Hijmans

```
# 12 values of irradiation, 1 for each month
G0dm=c(2.766,3.491,4.494,5.912,6.989,7.742,7.919,7.027,5.369,3.562,2.814,2.179)*1000;
# RasterBrick with 12 layers based on G0dm + noise
r <- raster(nc=10, nr=10)
s <- brick(lapply(1:12, function(x) setValues(r, G0dm[x]+100*rnorm(ncell(r)) )))
# time
tm <- seq(as.Date('2010-01-15'), as.Date('2010-12-15'), 'month')
s <- setZ(s, tm, 'months')
# library(zoo)
# x <- zApply(s, by=as.yearqtr, fun=mean, name='quarters')</pre>
```

zonal 191

zonal Zonal statistics

Description

Compute zonal statistics, values of a Raster* object for each "zone" in a RasterLayer.

Usage

```
zonal(x, zones, stat='mean', digits=0, na.rm=TRUE, progress='')
```

Arguments

X	Raster* object
zones	RasterLayer object with codes representing zones
stat	The function to be applied. Either as character: 'mean', 'min', 'max', 'sum'; or a function (see Details)
digits	Integer. Number of digits to maintain in 'zones'. By default averaged to an integer (zero digits)
na.rm	Logical. If TRUE, NA values in x are ignored
progress	Character. "text", "window", or "" (the default, no progress bar)

Details

If stat is a function, zonal will fail (gracefully) for very large RasterLayers. The function should accept a na.rm argument. For example, fun=length will fail, but fun=function(x, ...){length(x)} will work; the '...' arguments catches the na.rm argument, even though it is not used by the function in this case. To remove NA values, you could use this function: fun=function(x, na.rm){ if(na.rm){length(na.omit(x))}else{length(x)}}

Value

A matrix with a value for each zone (unique value in zones)

Author(s)

Robert J. Hijmans

See Also

See cellStats for 'global' statistics (i.e., all of x is considered a single zone)

192 zoom

Examples

```
r <- raster(ncols=10, nrows=10)
r[] <- runif(ncell(r)) * 1:ncell(r)
z <- r
z[] <- rep(1:5, each=20)
zonal(r, z, mean)
zonal(r, z, min)
# for big files, use a character value rather than a function
zonal(r, z, 'sum')
# multiple layers
zonal(stack(r, r*10), z, 'sum')</pre>
```

zoom

Zoom in on a plot

Description

Zoom in on a plot (map) by providing a new extent, by default this is done by clicking twice on the map

Usage

```
zoom(x, ...)
## S4 method for signature 'Raster'
zoom(x, ext=drawExtent(), maxpixels=100000, layer=1, new=TRUE, useRaster=TRUE, ...)
## S4 method for signature 'Spatial'
zoom(x, ext=drawExtent(), new=TRUE, ...)
```

Arguments x

x Raster* or Spatial* (vector type) object
ext Extent object
maxpixels Maximum number of pixels used for the map
layer Positive integer to select the layer to be used if x is a mutilayer Raster object
new Logical. If TRUE, the zoomed in map will appear on a new device (window)
useRaster Logical. If TRUE, a bitmap raster is used to plot the image instead of polygons
additional paramters for plot

Value

Extent object (invisibly)

Author(s)

Robert J. Hijmans

zoom 193

See Also

drawExtent, plot

Index

!,Raster-method(Logic-methods), 101	filledContour, 78
!=,BasicRaster,BasicRaster-method	Gain and offset, 83
(Compare-methods), 46	getValues, 85
*Topic classes	getValuesBlock, 86
Extent-class, 70	head, 90
Raster-class, 137	hist, 92
readAll, 148	image, 93
*Topic file	interpolate, 96
extension, 66	intersect, 98
inifile, 94	Logic-methods, 101
*Topic math	mask, 102
Arith-methods, 21	match, 103
atan2, 25	Math-methods, 104
Compare-methods, 46	merge, 105
cv, 53	mosaic, 107
Logic-methods, 101	obsolete, 113
Math-methods, 104	overlay, 115
modal, 106	persp, 119
*Topic methods	plot, 120
aggregate, 17	plotRGB, 122
area, 20	predict, 124
Arith-methods, 21	quantile, 133
as.data.frame,22	raster, 134
as.logical, 23	rasterFromXYZ, 140
as.matrix, 24	rasterize, 141
as.raster, 25	replacement, 151
atan2, 25	setMinMax, 162
blockSize, 28	setValues, 163
brick, 30	spplot, 166
calc, 34	stack, 166
clearValues, 40	stackApply, 167
Compare-methods, 46	stackSelect, 168
contour, 47	substitute, 170
cover, 49	Summary, 172
crosstab, 51	Summary-methods, 172
edge, 63	union, 177
extract, 71	unstack, 179
Extract by index, 74	update, 180
factors, 77	writeRaster, 184

	writeValues, 186	extent, 67
*To	pic package	Extent coordinates, 68
	raster-package, 5	Extent math, 69
*To	pic spatial	Extent-class, 70
	addLayer, 13	extract, 71
	adjacency, 14	Extract by index, 74
	adjacent, 15	extremeValues, 76
	aggregate, 17	factors, 77
	alignExtent, 18	filename, 78
	approxNA, 19	filledContour, 78
	area, 20	flip, 79
	Arith-methods, 21	focal, 80
	as.data.frame, 22	freq, 82
	as.logical, 23	Gain and offset, 83
	as.matrix, 24	getData, 84
	as.raster, 25	getValues, 85
	autocorrelation, 26	getValuesBlock, 86
	bands, 27	gridDistance,87
	blockSize, 28	hdr, 89
	boxplot, 29	head, 90
	brick, 30	hillShade, 91
	buffer, 33	hist, 92
	calc, 34	image, 93
	cellFrom, 36	initialize, 95
	cellsFromExtent, 38	interpolate, 96
	cellStats, 39	intersect, 98
	clearValues, 40	intersectExtent, 99
	click, 41	isLonLat, 100
	clump, 42	KML, 100
	cluster, 43	mask, 102
	compare, 45	match, 103
	contour, 47	Math-methods, 104
	cover, 49	merge, 105
	crop, 49	mosaic, 107
	crosstab, 51	movingFun, 109
	cut, 52	NAvalue, 110
	datasource, 54	ncell, 111
	dataType, 55	nlayers, 112
	density, 56	Options, 113
	dim, 57	origin, 115
	direction, 58	overlay, 115
	disaggregate, 59	pairs, 118
	distance, 60	persp, 119
	distanceFromPoints, 61	plot, 120
	draw, 62	plotRGB, 122
	drawExtent, 62	pointDistance, 123
	edge, 63	predict, 124
	expand, 64	Programming, 127

projection, 129	unstack, 179
projectRaster, 130	update, 180
properties, 132	validCell, 181
quantile, 133	which, 182
raster, 134	writeFormats, 183
Raster-class, 137	writeRaster, 184
raster-package, 5	writeValues, 186
rasterFromCells, 139	xyFromCell, 187
rasterFromXYZ, 140	z-values, 189
rasterize, 141	zApply, 190
rasterTmpFile, 144	zonal, 191
rasterToContour, 145	zoom, 192
rasterToPoints, 146	*Topic univar
rasterToPolygons, 147	cellStats, 39
readAll, 148	count, 48
reclass, 149	cv, 53
rectify, 150	freq, 82
replacement, 151	modal, 106
resample, 151	==,BasicRaster,BasicRaster-method
resolution, 152	(Compare-methods), 46
rotate, 153	[,Raster,Extent,missing-method
rotated, 154	(Extract by index), 74
round, 155	[,Raster,RasterLayer,missing-method
rowFromCell, 156	(Extract by index), 74
SampleInt, 157	[,Raster,Spatial,missing-method
sampleRandom, 157	(Extract by index), 74
sampleRegular, 158	[,Raster,logical,missing-method
saverasterstack, 159	(Extract by index), 74
scalebar, 160	[,Raster,matrix,missing-method
setExtent, 161	(Extract by index), 74
setMinMax, 162	[,Raster,missing,missing-method
setValues, 163	(Extract by index), 74
shift, 164	[,Raster,missing,numeric-method
Slope and aspect, 165	(Extract by index), 74
spplot, 166	[,Raster,numeric,missing-method
stack, 166	(Extract by index), 74
stackApply, 167	[,Raster,numeric,numeric-method
stackSelect, 168	(Extract by index), 74
subset, 169	<pre>[<-,Raster,Extent,missing-method</pre>
substitute, 170	(replacement), 151
Summary, 172	<pre>[<-,Raster,Spatial,missing-method</pre>
Summary-methods, 172	(replacement), 151
terrain, 173	<pre>[<-,Raster,logical,missing-method</pre>
transpose, 175	(replacement), 151
trim, 176	[<-,Raster,matrix,missing-method
union, 177	(replacement), 151
unionExtent, 178	<pre>[<-,Raster,missing,numeric-method</pre>
unique, 178	(replacement), 151

[<-,Raster,numeric,missing-method	as.data.frame,RasterStackBrick-method
(replacement), 151	(as.data.frame), 22
[<-,Raster,numeric,numeric-method	as.logical, 23, 23
(replacement), 151	as.logical, Raster-method(as.logical),
[<-,RasterLayer,RasterLayer,missing-method	23
(replacement), 151	as.matrix, $9,24$
[<-,RasterLayer,missing,missing-method	as.matrix,RasterLayer-method
(replacement), 151	(as.matrix), 24
[<-,RasterStackBrick,Raster,missing-method	as.matrix,RasterStackBrick-method
(replacement), 151	(as.matrix), 24
[<-,RasterStackBrick,missing,missing-method	as.raster, 25, 25
(replacement), 151	as.raster,RasterLayer-method
[[,RasterLayer,ANY,ANY-method(Extract	(as.raster), 25
by index), 74	asFactor (factors), 77
[[,RasterStackBrick,ANY,ANY-method	asFactor, ANY-method (factors), 77
(Extract by index), 74	asFactor, RasterBrick-method (factors),
[[<-,RasterStack,numeric,missing-method	77
(replacement), 151	asFactor, RasterLayer-method (factors),
%in% (match), 103	77
%in%,Raster-method (match), 103	atan2, 25, 105
,	atan2, RasterLayer, RasterLayer-method
addLayer, 7, 13, 160, 167	(atan2), <mark>25</mark>
addLayer, Raster-method (addLayer), 13	autocorrelation, 26
, , ,	
adjacency, 8, 14, 15, 16	band, <i>10</i>
adjacent, 14, 15, 15	bandnr (bands), 27
aggregate, 7, 17, 59, 151, 152	bandnr,RasterLayer-method(bands),27
aggregate, Raster-method (aggregate), 17	bands, 27, <i>112</i>
alignExtent, 12, 18, 50	BasicRaster-class (Raster-class), 137
all.equal, 45, 105, 108	bbox, Extent-method (extent), 67
approx, 19	bbox, Raster-method (extent), 67
approxfun, 19	beginCluster (cluster), 43
approxNA, 19	blockSize, 11, 28, 186, 187
approxNA,RasterStackBrick-method	boxplot, 10, 29, 30, 92, 118
(approxNA), 19	boxplot, Raster-method (boxplot), 29
area, 8, 20	brick, 7, 30, 136, 137, 167
area, RasterLayer-method (area), 20	brick, array-method (brick), 30
area,RasterStackBrick-method(area),20	brick, character-method (brick), 30
Arith-methods, <i>34</i> , <i>105</i> , <i>117</i>	brick, Extent-method (brick), 30
Arith-methods, 7, 21, 35	brick, grf-method (brick), 30
as.array, 9	brick, kasc-method (brick), 30
as.array(as.matrix), 24	brick, list-method (brick), 30
as.array,RasterLayer-method	brick, missing-method (brick), 30
(as.matrix), 24	brick, RasterBrick-method (brick), 30
as.array,RasterStackBrick-method	brick, RasterLayer-method (brick), 30
(as.matrix), 24	brick, RasterStack-method (brick), 30
as.data.frame, 22	brick, SpatialGrid-method (brick), 30
as.data.frame,RasterLayer-method	brick, SpatialPixels-method (brick), 30
(as.data.frame), 22	buffer, 33

buffer, RasterLayer-method (buffer), 33	count, 9, 48, 83
	<pre>count,RasterLayer-method(count),48</pre>
calc, 7, 22, 34, 52, 102, 104, 105, 116, 117,	<pre>count,RasterStackBrick-method(count),</pre>
133, 137, 150, 151, 167, 168, 172,	48
173	cover, 7, 49
calc, Raster, function-method (calc), 34	cover,RasterLayer,RasterLayer-method
canProcessInMemory, 12, 114	(cover), 49
canProcessInMemory (Programming), 127	cover, RasterStackBrick, Raster-method
ceiling,Extent-method(Extent math),69	(cover), 49
ceiling, RasterLayer-method (round), 155	crop, 7, 49, 64, 65, 75, 98, 151, 152, 177
cellFrom, 36, 156	crop, Raster-method (crop), 49
cellFromCol (cellFrom), 36	crop, Spatial-method (crop), 49
cellFromLine (cellFrom), 36	crosstab, 9, 51, 83
cellFromPolygon (cellFrom), 36	crosstab, RasterLayer, RasterLayer-method
cellFromRow (cellFrom), 36	(crosstab), 51
cellFromRowCol, 11	CRS-class, 129, 131, 138
cellFromRowCol (cellFrom), 36	cut, 8, 52, 52, 149, 150
cellFromRowColCombine (cellFrom), 36	cut, Raster-method (cut), 52
cellFromXY, 11, 38, 188	cv, 12, 53
cellFromXY (cellFrom), 36	cv, ANY-method (cv), 53
cellsFromExtent, 11, 37, 38	cv, Raster-method (cv), 53
cellStats, 9, 39, 133, 172, 191	cv, kaster - lilethou (cv), 33
clearOptions, 12	dataSigned (properties), 132
clearOptions (Options), 113	dataSize (properties), 132
clearValues, 40	datasource, 54
click, 10, 41	dataType, 55, 58, 81, 103, 105, 108, 114, 116,
click, missing-method (click), 41	125, 142, 164, 171, 176, 184
click,Raster-method(click),41	dataType<- (dataType), 55
click, SpatialGrid-method (click), 41	
	density, 10, 56, 118, 133
click, SpatialPixels-method (click), 41	density, RasterLayer-method (density), 56
closeConnection, 12	density, RasterStackBrick-method
closeConnection (Programming), 127	(density), 56
clump, 8, 42, 64	dim, 57, 111
clump, RasterLayer-method (clump), 42	dim, BasicRaster-method (dim), 57
cluster, 43	dim, RasterStackBrick-method (dim), 57
clusterR (cluster), 43	dim<-,BasicRaster-method (dim), 57
colFromCell (rowFromCell), 156	dim<-,RasterBrick-method(dim), 57
colFromX, 11	dim<-,RasterLayer-method(dim),57
colFromX (cellFrom), 36	dimensions, 68
colorRampPalette, 120	direction, $8,58$
compare, 10, 45	direction,RasterLayer-method
Compare-methods, 7, 46	(direction), 58
contour, 9, 47, 47, 93, 119, 121	disaggregate, 7, 18, 59, 151, 152
contour, RasterLayer-method (contour), 47	disaggregate,Raster-method
contour,RasterStackBrick-method	(disaggregate), 59
(contour), 47	distance, 8, 33, 58, 60, 61, 88, 124
contourLines, 145, 146	${\tt distance}, {\tt RasterLayer-method} \ ({\tt distance}),$
coordinates, 11, 115	60
cor. 118	distanceFromPoints, 8, 60, 61, 124

draw, 62	extract,Raster,SpatialPoints-method
drawExtent, 10, 12, 19, 42, 50, 62, 67, 193	(extract), 71
drawLine, 10	extract,Raster,SpatialPolygons-method
drawLine (draw), 62	(extract), 71
drawPoly, 10	<pre>extract,Raster,vector-method(extract),</pre>
drawPoly (draw), 62	71
dropLayer, 7, 167, 170	extract,Spatial,Raster-method
dropLayer (addLayer), 13	(extract), 71
dropLayer,RasterBrick-method	extremeValues, 76
(addLayer), 13	
dropLayer,RasterStack-method	factors, 77
(addLayer), 13	filename, 10, 78, 132
	filled.contour, 78, 79
edge, 8, 33, 60, 63	filledContour, 9, 47, 78
edge, RasterLayer-method (edge), 63	flip, 7, 79, 154, 165, 175
endCluster (cluster), 43	flip,RasterLayer-method(flip),79
expand, 7, 49, 50, 64, 108, 151, 152, 177	flip,RasterStackBrick-method(flip),79
expand, Extent-method (expand), 64	floor, Extent-method (Extent math), 69
expand, Raster-method (expand), 64	floor, RasterLayer-method (round), 155
extension, 12, 66	focal, 8, 19, 20, 26, 64, 72, 80, 174
extension<- (extension), 66	focal, RasterLayer-method (focal), 80
Extent, 31, 62, 71	freq, 9, 48, 51, 82
Extent (Extent-class), 70	freq, RasterLayer-method (freq), 82
extent, 10, 11, 19, 38, 50, 57, 67, 67, 68, 70,	fromDisk, 12
98, 99, 111, 153, 162, 177, 178	fromDisk (datasource), 54
Extent coordinates, 68	Trombisk (datasourec), 5 T
Extent math, 69	gain (Cain and offset) 83
extent, BasicRaster-method (extent), 67	gain (Gain and offset), 83
extent, Extent-method (extent), 67	Gain and offset, 83
extent, list-method (extent), 67	gain<- (Gain and offset), 83
extent, matrix-method (extent), 67	GDALDriver-class, 183
extent, numeric-method (extent), 67	Geary (autocorrelation), 26
extent, Spatial-method (extent), 67	GearyLocal (autocorrelation), 26
Extent-class, 19, 138, 162	getCluster, 44
Extent-class, 70, 135	getCluster (Programming), 127
extent<- (setExtent), 161	getData, 12, 84
extract, 9, 43, 71, 75, 113, 117, 134, 142,	getValues, 9, 22, 24, 75, 85, 134, 148, 163
148, 168, 169	getValues,RasterBrick,missing,missing-method
Extract by index, 74	(getValues), 85
extract, Raster, data. frame-method	getValues,RasterBrick,numeric,missing-method
(extract), 71	(getValues), 85
extract, Raster, Extent-method (extract),	getValues,RasterBrick,numeric,numeric-method
71	(getValues), 85
extract, Raster, matrix-method (extract),	getValues,RasterLayer,missing,missing-method
71	(getValues), 85
extract, Raster, missing-method	getValues,RasterLayer,numeric,missing-method
(extract), 71	(getValues), 85
extract, Raster, SpatialLines-method	getValues,RasterLayer,numeric,numeric-method
(extract), 71	(getValues), 85

${\tt getValues}, {\tt RasterStack}, {\tt missing}, {\tt missing-method}$	is.factor,RasterStack-method(factors),
(getValues), 85	77
<pre>getValues,RasterStack,numeric,missing-method</pre>	is.finite,Raster-method
(getValues), 85	(Logic-methods), 101
<pre>getValues,RasterStack,numeric,numeric-method</pre>	is.infinite,Raster-method
(getValues), 85	(Logic-methods), 101
getValuesBlock, 9, 22, 24, 86, 90, 148	is.na,Raster-method(Logic-methods), 101
getValuesBlock,RasterBrick,numeric-method	is.nan,Raster-method(Logic-methods),
(getValuesBlock), 86	101
getValuesBlock,RasterLayer,numeric-method	isLonLat, 10, 100
(getValuesBlock), 86	<pre>isLonLat, character-method (isLonLat),</pre>
getValuesBlock,RasterStack,numeric-method	100
(getValuesBlock), 86	<pre>isLonLat,CRS-method(isLonLat), 100</pre>
getZ, <i>19</i>	isLonLat,Raster-method(isLonLat), 100
getZ (z-values), 189	<pre>isLonLat,Spatial-method(isLonLat), 100</pre>
gridDistance, 8, 33, 58, 60, 61, 87, 124	
	KML, 11, 100
hasValues (datasource), 54	KML, RasterLayer-method (KML), 100
hdr, 12, 89	KML, RasterStackBrick-method (KML), 100
head, 90	
head, RasterLayer-method (head), 90	labels (factors), 77
head, RasterStackBrick-method (head), 90	labels, Raster-method (factors), 77
heat.colors, 120	labels, RasterStack-method (factors), 77
hillShade, 91, 175	labels<- (factors), 77
hist, 10, 30, 92, 92, 118, 121	labels<-,RasterBrick,list-method
hist, RasterLayer-method (hist), 92	(factors), 77
hist, RasterStackBrick-method (hist), 92	labels<-,RasterLayer,list-method
, , , , , , , , , , , , , , , , , , , ,	(factors), 77
image, 9, 93, 93, 101	layerNames (nlayers), 112
image, RasterLayer-method (image), 93	layerNames<- (nlayers), 112
<pre>image,RasterStackBrick-method(image),</pre>	levelplot, 166
93	linesToRaster (obsolete), 113
image.plot, 120	lineValues (obsolete), 113
inifile, 94	locator, 62
init, 8	log, Raster-method (Math-methods), 104
init (initialize), 95	Logic, Raster, Raster-method
initialize, 95	(Logic-methods), 101
inMemory, <i>12</i>	Logic-methods, 7, 101
inMemory (datasource), 54	mask, 7, 102
interpolate, 8, 96, 125	mask, Raster, Spatial-method (mask), 102
interpolate,Raster-method	mask, RasterLayer, RasterLayer-method
(interpolate), 96	(mask), 102
intersect, 11, 38, 98, 99, 177, 178	mask,RasterLayer,RasterStackBrick-method
intersect, Extent-method (intersect), 98	(mask), 102
intersect, Raster-method (intersect), 98	mask,RasterStackBrick,RasterLayer-method
intersectExtent, 99	(mask), 102
is. factor (factors), 77	mask,RasterStackBrick,RasterStackBrick-method
is.factor,Raster-method(factors),77	(mask), 102

match 103 104	nlayors PasicPastor-mothod (nlayors)
match, 103, 104 match, Raster-method (match), 103	nlayers,BasicRaster-method(nlayers), 112
Math-methods, 22, 25, 26, 69, 102	
Math-methods, 7, 35, 104	nlayers, Raster-method (nlayers), 112
	nlayers, RasterBrick-method (nlayers),
maxValue, 9, 39, 172	112
maxValue (extremeValues), 76	nlayers, RasterStack-method (nlayers),
maxValue,RasterBrick-method	112
(extremeValues), 76	nlayers, Spatial-method (nlayers), 112
maxValue, RasterLayer-method	nrow, <i>10</i>
(extremeValues), 76	nrow(ncell), 111
maxValue,RasterStack-method	nrow,BasicRaster-method(ncell),111
(extremeValues), 76	nrow<- (ncell), 111
mean, Raster-method (Summary-methods),	
172	obsolete, 113
merge, 7, 50, 65, 105, 107, 108, 151, 152	offs (Gain and offset), 83
merge, Extent, Extent-method (merge), 105	offs<- (Gain and offset), 83
merge, Raster, Raster-method (merge), 105	openConnection, 12
minValue, 9, 39, 172	openConnection (Programming), 127
minValue (extremeValues), 76	Options, 113
minValue,RasterBrick-method	options, 21, 114
(extremeValues), 76	origin, 10, 115
minValue,RasterLayer-method	— · · · · ·
(extremeValues), 76	origin, BasicRaster-method (origin), 115
minValue,RasterStack-method	overlay, 7, 22, 34, 35, 102, 105, 115
(extremeValues), 76	overlay,Raster,missing-method
modal, 12, 106	(overlay), 115
modal, ANY-method (modal), 106	overlay,Raster,Raster-method(overlay),
modal, Raster-method (modal), 106	115
Moran, 8	
Moran (autocorrelation), 26	pairs, 10, 30, 92, 118, 118, 121
MoranLocal (autocorrelation), 26	<pre>pairs,RasterStackBrick-method(pairs),</pre>
mosaic, 7, 106, 107	118
	pbClose, 12
mosaic, list, missing-method (mosaic), 107	pbClose (Programming), 127
mosaic, Raster, Raster-method (mosaic),	pbCreate, 12
107	pbCreate (Programming), 127
movingFun, 109	pbStep, <i>12</i>
NAvalue 10 110	pbStep (Programming), 127
NAvalue, <i>10</i> , 110 NAvalue<- (NAvalue), 110	persp, 9, 47, 79, 119, 119, 121
· · · · · · · · · · · · · · · · · · ·	persp, RasterLayer-method (persp), 119
nbands, 10	persp,RasterStackBrick-method(persp),
nbands (bands), 27	
ncell, 10, 57, 111, 115, 153	119
ncell, ANY-method (ncell), 111	plot, 9, 10, 56, 79, 93, 119, 120, 120, 123,
ncell, BasicRaster-method (ncell), 111	161, 166, 192, 193
ncol, 10	plot, Extent, ANY-method (plot), 120
ncol (ncell), 111	plot,Extent,missing-method(plot), 120
ncol,BasicRaster-method(ncell),111	plot,Raster,Raster-method(plot), 120
ncol<- (ncell), 111	<pre>plot,RasterLayer,missing-method(plot),</pre>
nlayers, 28, 112	120

plot,RasterStackBrick,ANY-method	rasterImage, 25, 123
(plot), 120	rasterize, <i>8</i> , <i>75</i> , <i>113</i> , <i>117</i> , <i>140</i> , 141, <i>151</i>
plotRGB, 9, 121, 122, 166	rasterize,data.frame,Raster-method
plotRGB,RasterStackBrick-method	(rasterize), 141
(plotRGB), 122	rasterize,Extent,Raster-method
pointDistance, 12, 33, 60, 61, 123	(rasterize), 141
pointsToRaster (obsolete), 113	rasterize,matrix,Raster-method
polygonsToRaster (obsolete), 113	(rasterize), 141
polygonValues (obsolete), 113	rasterize, SpatialLines, Raster-method
predict, 8, 43, 96, 97, 124, 137, 171	(rasterize), 141
predict, Raster-method (predict), 124	rasterize,SpatialPoints,Raster-method
predict.gstat, 97	(rasterize), 141
print, Raster-method (Raster-class), 137	rasterize,SpatialPolygons,Raster-method
Programming, 127	(rasterize), 141
projectExtent (projectRaster), 130	RasterLayer-class (Raster-class), 137
projection, 10, 129, 174	RasterStack-class (Raster-class), 137
projection<- (projection), 129	<pre>RasterStackBrick-class(Raster-class),</pre>
projectRaster, 7, 10, 43, 129, 130, 151, 152	137
projInfo, <i>129</i> , <i>131</i>	rasterTmpFile, <i>12</i> , <i>114</i> , 144
properties, 132	rasterToContour, 8 , 145
	rasterToPoints, 8, 146
quantile, 39, 133, 133	rasterToPolygons, 8, 147
quantile, Raster-method (quantile), 133	readAll, 148
rainbow, 120	<pre>readAll,RasterBrick-method(readAll),</pre>
raster, 7, 8, 32, 134, 137, 167	148
raster, asc-method (raster), 134	<pre>readAll,RasterLayer-method(readAll),</pre>
raster, BasicRaster-method (raster), 134	148
raster, character-method (raster), 134	<pre>readAll,RasterStack-method(readAll),</pre>
raster, Extent-method (raster), 134	148
raster, grf-method (raster), 134	readGDAL, <i>31</i> , <i>135</i>
raster, kasc-method (raster), 134	readIniFile, <i>12</i>
raster, kde-method (raster), 134	readIniFile (inifile), 94
raster, list-method (raster), 134	reclass, 8, 35, 52, 149, 171
raster, matrix-method (raster), 134	reclass, Raster-method (reclass), 149
raster, missing-method (raster), 134	rectify, 150, 154
raster, RasterBrick-method (raster), 134	removeTmpFiles, 12
raster, RasterLayer-method (raster), 134	<pre>removeTmpFiles (rasterTmpFile), 144</pre>
raster, RasterStack-method (raster), 134	replacement, 40, 134, 151, 164
raster, Spatial-method (raster), 134	res, 10, 57, 111
raster, SpatialGrid-method (raster), 134	res (resolution), 152
raster, SpatialPixels-method (raster),	res, BasicRaster-method (resolution), 152
134	res<- (resolution), 152
raster-package, 134	resample, 7, 18, 43, 59, 150, 151
Raster-class, 5, 137	resample,Raster,Raster-method
raster-package, 5	(resample), 151
RasterBrick-class (Raster-class), 137	resolution, 152
rasterFromCells, 8, 139	returnCluster, 44
rasterFromXYZ. 8. 140	returnCluster (Programming), 127

rotate, 7, 80, 153, 165, 175	<pre>show,RasterLayer-method(Raster-class),</pre>
rotate, Raster-method (rotate), 153	137
rotated, 154	<pre>show,RasterStack-method(Raster-class),</pre>
round, 11, 83, 155, 155	137
round, RasterLayer-method (round), 155	show, RasterSummary-method (Summary), 172
<pre>rowColFromCell (rowFromCell), 156</pre>	showOptions, <i>12</i> , <i>45</i> , <i>145</i>
rowFromCell, 139, 156	showOptions (Options), 113
rowFromY, 11	showTmpFiles, 12
rowFromY (cellFrom), 36	<pre>showTmpFiles(rasterTmpFile), 144</pre>
	Slope and aspect, 165
sample, <i>157</i>	slopeAspect, 173
SampleInt, 157	slopeAspect (Slope and aspect), 165
sampleInt, 12	SpatialLines, 71
sampleInt (SampleInt), 157	SpatialPolygons, 71
sampleRandom, 9, 39, 157, 159	spDistsN1, 124
sampleRandom, Raster-method	spplot, 9, 121, 166, 166
(sampleRandom), 157	spplot, Raster-method (spplot), 166
sampleRegular, 9, 39, 158, 158	${\it spTransform}, 131$
saveOptions, 12	${\sf spTransform-methods}, 129$
saveOptions (Options), 113	stack, 7, 136, 137, 160, 166, 180
saverasterstack, 159	stack, character-method (stack), 166
scalebar, 160	stack, kasc-method (stack), 166
select, 42	stack, list-method (stack), 166
setExtent, 70, 161, 177	stack, missing-method (stack), 166
setMinMax, 9, 39, 76, 162	stack, Raster-method (stack), 166
setMinMax,RasterBrick-method	stack,SpatialGridDataFrame-method
(setMinMax), 162	(stack), 166
setMinMax,RasterLayer-method	stack,SpatialPixelsDataFrame-method
(setMinMax), 162	(stack), 166
setMinMax,RasterStack-method	stackApply, 8, 167, 169
(setMinMax), 162	stackOpen (saverasterstack), 159
setOptions, 12, 145, 183, 184	stackSave (saverasterstack), 159
setOptions (Options), 113	stackSelect, 8, 168, 168
setValues, 11, 75, 134, 163	stackSelect,RasterStackBrick,Raster-method
setValues,RasterBrick-method	(stackSelect), 168
(setValues), 163	subs, <i>8</i> , <i>52</i> , <i>149</i> , <i>150</i>
setValues,RasterLayer-method	subs (substitute), 170
(setValues), 163	subs,RasterLayer,data.frame-method
setValues,RasterStack-method	(substitute), 170
(setValues), 163	subset, <i>13</i> , 169
setZ (z-values), 189	subset, RasterBrick-method (subset), 169
shift, 7, 164	subset, RasterLayer-method (subset), 169
shift, Raster-method (shift), 164	subset, RasterStack-method (subset), 169
<pre>show,BasicRaster-method(Raster-class),</pre>	substitute, 170
137	Summary, 172
show, Extent-method (Extent-class), 70	summary, 9
<pre>show,RasterBrick-method(Raster-class),</pre>	summary, Raster-method (Summary), 172
137	<pre>summary,RasterBrick-method(Summary),</pre>

172	validCell, <i>11</i> , 181
<pre>summary,RasterStack-method(Summary),</pre>	validCol, <i>11</i>
172	validCol(validCell), 181
Summary-methods, 7, 172	validRow, 11
	validRow(validCell), 181
t, 7, 80	values, 40, 73
t (transpose), 175	values (getValues), 85
t, RasterLayer-method (transpose), 175	values, Raster-method (getValues), 85
t,RasterStackBrick-method(transpose),	values<- (setValues), 163
175	values<-,RasterBrick-method
table, <i>51</i>	(setValues), 163
tail (head), 90	values<-,RasterLayer-method
tail, RasterLayer-method (head), 90	(setValues), 163
tail, RasterStackBrick-method (head), 90	values<-,RasterStack-method
tempfile, 145	(setValues), 163
terrain, 8, 91, 165, 173	
text, 9	Which (which), 182
text (plot), 120	which, 182, 182
text, RasterLayer-method (plot), 120	Which, RasterLayer-method (which), 182
tolower, 94	writeFormats, 105, 108, 114, 116, 171, 180,
topo.colors, 120	183, 184, 185
toupper, 94	writeGDAL, 89
Tps, 97	writeRaster, 10, 11, 17, 21, 33, 34, 42, 49,
transpose, 175	50, 58–61, 64, 65, 79, 81, 88, 89, 95,
trim, 7, 12, 176	96, 103, 125, 130, 142, 149, 150,
trim, character-method (trim), 176	152, 153, 160, 164, 168, 169, 176,
trim, data.frame-method (trim), 176	184, 186, 187
trim, matrix-method (trim), 176	writeRaster,RasterLayer,character-method
trim, Raster-method (trim), 176	(writeRaster), 184
trunc, RasterLayer-method (round), 155	${\tt writeRaster,RasterStackBrick,character-method}$
txtProgressBar, 128	(writeRaster), 184
	writeStart, 11
union, 11, 98, 99, 177, 178	writeStart (writeValues), 186
union, Extent, Extent-method (union), 177	writeStart,RasterBrick,character-method
unionExtent, 178	(writeValues), 186
unique, 9, 178, 179	$write Start, Raster Layer, character-{\tt method}$
unique,RasterLayer,missing-method	(writeValues), 186
(unique), 178	writeStop, 11
unique,RasterStackBrick,missing-method	writeStop (writeValues), 186
(unique), 178	writeStop,RasterBrick-method
unstack, 7, 179	(writeValues), 186
unstack, RasterBrick-method (unstack),	writeStop,RasterLayer-method
179	(writeValues), 186
unstack, RasterStack-method (unstack),	writeValues, 11, 28, 29, 184, 185, 186
179	writeValues,RasterBrick,matrix-method
update, 11, 180, 187	(writeValues), 186
update, RasterBrick-method (update), 180	writeValues,RasterLayer,vector-method
update, RasterLayer-method (update), 180	(writeValues), 186

xFromCell, 11	zApply, 190
xFromCell (xyFromCell), 187	zonal, 9, 51, 83, 191
xFromCol, 11	zoom, 10, 192
xFromCol(xyFromCell), 187	zoom, Raster-method (zoom), 192
xmax, 10	zoom, Spatial-method (zoom), 192
xmax (Extent coordinates), 68	
xmax,BasicRaster-method(Extent	
coordinates), 68	
xmax, Extent-method (Extent	
coordinates), 68	
xmax<- (Extent coordinates), 68	
xmin, 10	
xmin (Extent coordinates), 68	
xmin, BasicRaster-method (Extent	
coordinates), 68	
xmin,Extent-method (Extent	
coordinates), 68	
xmin<- (Extent coordinates), 68	
xres, 10	
<pre>xres (resolution), 152 xres,BasicRaster-method (resolution),</pre>	
•	
152	
xyFromCell, 11, 37, 187	
xyValues (obsolete), 113	
yFromCell, 11	
yFromCell(xyFromCell), 187	
yFromRow, 11	
yFromRow(xyFromCell), 187	
ymax, 10	
ymax (Extent coordinates), 68	
ymax,BasicRaster-method(Extent	
coordinates), 68	
ymax,Extent-method(Extent	
coordinates), 68	
ymax<- (Extent coordinates), 68	
ymin, <i>10</i>	
ymin (Extent coordinates), 68	
ymin,BasicRaster-method(Extent	
coordinates), 68	
ymin, Extent-method (Extent	
coordinates), 68	
ymin<- (Extent coordinates), 68	
yres, 10	
yres (resolution), 152	
yres,BasicRaster-method(resolution),	
152	
102	
z-values, 189	