Main page Contents Featured content Current events Random article Donate to Wikipedia Wikipedia store Interaction Help About Wikipedia Community portal Recent changes Contact page Tools What links here Related changes Upload file Special pages Permanent link Page information Wikidata item Cite this page Print/export Create a book

Download as PDF

Printable version

Languages

Deutsch

Español

فارسى

Français 한국어

日本語

Polski

Русский

Српски / srpski Suomi

Українська

中文

Article Talk Read Edit View history Search Q

Circular buffer

From Wikipedia, the free encyclopedia

This article has multiple issues. Please help improve it or discuss these issues on the talk page.

- This article's tone or style may not reflect the encyclopedic tone used on Wikipedia. (April 2011)
- This article needs additional citations for verification. (September 2014)
- This article or section appears to contradict itself about the end pointer: it is confused with the next pointer, resulting in a contradiction. (April 2013)

A circular buffer, cyclic buffer or ring buffer is a data structure that uses a single, fixed-size buffer as if it were connected end-to-end. This structure lends itself easily to buffering data streams.

Contents 1 Uses 2 How it works 3 Circular buffer mechanics 3.1 Start/end pointers (head/tail) 4 Difficulties 4.1 Full / Empty Buffer Distinction 4.1.1 Always keep one slot open 4.1.2 Use a fill count 4.1.3 Mirroring 4.1.4 Read / Write Counts 4.1.5 Absolute indices 4.1.6 Record last operation 4.1.7 Split buffer into two regions 4.2 Multiple read pointers 4.3 Chunked Buffer 5 Optimization 6 Variants 7 External links


Aring showing, conceptually, a circular buffer. This visually shows that the buffer has no real end and it can loop around the buffer. However, since memory is never physically created as a ring, a linear representation is generally used as is done below.

Uses [edit]


The useful property of a circular buffer is that it does not need to have its elements shuffled around when one is consumed. (If a non-circular buffer were used then it would be necessary to shift all elements when one is consumed.) In other words, the circular buffer is well-suited as a FIFO buffer while a standard, non-circular buffer is well suited as a LIFO buffer.

Circular buffering makes a good implementation strategy for a queue that has fixed maximum size. Should a maximum size be adopted for a queue, then a circular buffer is a completely ideal implementation; all queue operations are constant time. However, expanding a circular buffer requires shifting memory, which is comparatively costly. For arbitrarily expanding queues, a linked list approach may be preferred instead.

In some situations, overwriting circular buffer can be used, e.g. in multimedia. If the buffer is used as the bounded buffer in the producer-consumer problem then it is probably desired for the producer (e.g., an audio generator) to overwrite old data if the consumer (e.g., the sound card) is unable to momentarily keep up. Also, the LZ77 family of lossless data compression algorithms operates on the assumption that strings seen more recently in a data stream are more likely to occur soon in the stream. Implementations store the most recent data in a circular buffer.



This image shows a full buffer with two elements having been overwritten:



What to note about the second one is that after each element is overwritten then the start pointer is incremented as well

Difficulties [edit]

Full / Empty Buffer Distinction [edit]

A small disadvantage of relying on pointers or relative indices of the start and end of data is, that in the case the buffer is entirely full, both pointers point to the same element: [contradiction]

```
Circular buffer - 6789AB5 full.svg
```

This is exactly the same situation as when the buffer is empty:

```
Circular buffer - 6789AB5 empty.svg
```

To solve this confusion there are a number of solutions:

- · Always keep one slot open.
- Use a fill count to distinguish the two cases.
- Use an extra mirroring bit to distinguish the two cases.
- Use read and write counts to get the fill count from.
- Use absolute indices.
- Record last operation.
- Split buffer into two regions.

Always keep one slot open [edit]

This design always keeps one slot unallocated. A full buffer has at most slots. If both pointers refer to the same slot, the buffer is empty. If the end (write) pointer refers to the slot preceding the one referred to by the start (read) pointer, the buffer is full.

The advantage is:

• The solution is simple and robust.

The disadvantages are:

- One slot is lost, so it is a bad compromise when the buffer size is small or the slot is big or is implemented in hardware.
- The test for full requires a modulo operation

Use a fill count [edit]

This approach replaces the end pointer with a counter that tracks the number of readable items in the buffer. This unambiguously indicates when the buffer is empty or full and allows use of all buffer slots.

The performance impact should be negligible, since this approach adds the costs of maintaining the counter and computing the tail slot on writes but eliminates the need to maintain the end pointer and simplifies the fullness test.

The advantage is:

• The test for full/empty is simple

The disadvantages are:

- · You need modulo for read and write
- Read and write operation must share the counter field, so it requires synchronization in multi-threaded situation.

Note: When using semaphores in a Producer-consumer model, the semaphores act as a fill count.

Mirroring [edit]

Another solution is to remember the number of times each read and write pointers have wrapped and compare this to distinguish empty and full situations. In fact only the parity of the number of wraps is necessary, so you

only need to keep an extra bit. You can see this as if the buffer adds a virtual mirror and the pointers point either to the normal or to the mirrored buffer.

Circular buffer - mirror solution full and empty.svg

It is easy to see above that when the pointers (including the extra msb bit) are equal, the buffer is empty, while if the pointers differ only by the extra msb bit, the buffer is full.

The advantages are:

- The test for full/empty is simple
- · No modulo operation is needed
- The source and sink of data can implement independent policies for dealing with a full buffer and overrun
 while adhering to the rule that only the source of data modifies the write count and only the sink of data
 modifies the read count. This can result in elegant and robust circular buffer implementations even in multithreaded environments. [citation needed]

The disadvantage is:

· You need one more bit for read and write pointer

Read / Write Counts [edit]

Another solution is to keep counts of the number of items written to and read from the circular buffer. Both counts are stored in unsigned integer variables that overflow and wrap freely, with numerical limits equal or larger than the number of items that can be stored.

The unsigned difference (write_count - read_count) always yields the number of items placed in the buffer and not yet retrieved. This can indicate that the buffer is empty, partially full, completely full (without waste of a storage location) or in a state of overrun.

The advantage is:

The source and sink of data can implement independent policies for dealing with a full buffer and overrun
while adhering to the rule that only the source of data modifies the write count and only the sink of data
modifies the read count. This can result in elegant and robust circular buffer implementations even in multithreaded environments.

The disadvantage is:

· You need two additional variables.

Absolute indices [edit]

It is possible to optimize the previous solution by using indices instead of pointers: indices can store read/write counts instead of the offset from start of the buffer, the separate variables in the above solution are removed and relative indices are obtained on the fly by division modulo the buffer's length.

The advantage is:

• No extra variables are needed.

The disadvantages are:

- Every access needs an additional modulo operation.
- If counter wrap is possible, complex logic can be needed if the buffer's length is not a divisor of the counter's capacity.

On binary computers, both of these disadvantages disappear if the buffer's length is a power of two—at the cost of a constraint on possible buffers lengths.

Record last operation [edit]

Another solution is to keep a flag indicating whether the most recent operation was a read or a write. If the two pointers are equal, then the flag will show whether the buffer is full or empty: if the most recent operation was a write, the buffer must be full, and conversely if it was a read, it must be empty.

The advantages are:

 Only a single bit needs to be stored (which may be particularly useful if the algorithm is implemented in hardware) • The test for full/empty is simple

The disadvantage is:

- · You need an extra variable
- Read and write operations must share the flag, so it will probably require synchronization in multi-threaded situation.

Split buffer into two regions [edit]

This approach solves the wrap-around problem by splitting the buffer into a primary region and a secondary region. The secondary region always begins at the buffer start and is not activated until the primary region has reached the buffer's end. Additionally, if the primary region is emptied of data, the secondary region becomes the new primary.

The advantages are:

- The test for full/empty is simple.
- No modulo operation is needed.

The disadvantages are:

- An extra pointer variable is needed.
- · Read and write operations are complicated.

Multiple read pointers [edit]

A little bit more complex are multiple read pointers on the same circular buffer. This is useful if you have *n* threads, which are reading from the same buffer, but *one* thread writing to the buffer.

Chunked Buffer [edit]

Much more complex are different chunks of data in the same circular buffer. The writer is not only writing elements to the buffer, it also assigns these elements to chunks [citation needed].

The reader should not only be able to read from the buffer, it should also get informed about the chunk borders.

Example: The writer is reading data from small files, writing them into the same circular buffer. The reader is reading the data, but needs to know when and which file is starting at a given position.

Optimization [edit]

A circular-buffer implementation may be optimized by mapping the underlying buffer to two contiguous regions of virtual memory. (Naturally, the underlying buffer's length must then equal some multiple of the system's page size.) Reading from and writing to the circular buffer may then be carried out with greater efficiency by means of direct memory access; those accesses which fall beyond the end of the first virtual-memory region will automatically wrap around to the beginning of the underlying buffer. When the read offset is advanced into the second virtual-memory region, both offsets—read and write—are decremented by the length of the underlying buffer. [1]

Variants [edit]

Perhaps the most common version of the circular buffer uses 8-bit bytes as elements.

Some implementations of the circular buffer use fixed-length elements that are bigger than 8-bit bytes—16-bit integers for audio buffers, 53-byte ATM cells for telecom buffers, etc. Each item is contiguous and has the correct data alignment, so software reading and writing these values can be faster than software that handles non-contiguous and non-aligned values.

Ping-pong buffering can be considered a very specialized circular buffer with exactly two large fixed-length elements.

The Bip Buffer is very similar to a circular buffer, except it always returns contiguous blocks (which can be variable length).^[1]

Compressing circular buffers use an alternative indexing strategy, based on elementary number theory, to maintain a fixed-sized, compressed, representation of the entire data sequence [2]

External links [edit]

- 1. ^a b Simon Cooke. "The Bip Buffer The Circular Buffer with a Twist" ☑. 2003.
- 2. ^ John C. Gunther. 2014. Algorithm 938: Compressing circular buffers. ACM Trans. Math. Softw. 40, 2, Article 17 (March 2014) [1] 🗗
- CircularBuffer at the Portland Pattern Repository
- Boost: Templated Circular Buffer Container ☑
- http://www.dspguide.com/ch28/2.htm₽

v· t· e	Data structures
Types	Collection · Container
Abstract	$\label{eq:local_property} Associative \ array \cdot \ Double-ended \ priority \ queue \cdot \ Double-ended \ queue \cdot \ List \cdot \ Map \cdot \ Multimap \cdot \ Priority \ queue \cdot \ Queue \cdot \ Set \ (multiset) \cdot Disjoint \ Sets \cdot \ Stack$
Arrays	$\textbf{Bit array} \cdot \textbf{Circular buffer} \cdot \textbf{Dynamic array} \cdot \textbf{Hash table} \cdot \textbf{Hashed array tree} \cdot \textbf{Sparse array}$
Linked	Association list · Linked list · Skip list · Unrolled linked list · XOR linked list
Trees	$ B-tree \cdot Binary search \ tree \ (AA \cdot AVL \cdot red-black \cdot self-balancing \cdot splay) \cdot Heap \ (binary \cdot binomial \cdot Fibonacci) \cdot R-tree \ (R^* \cdot R + \cdot Hilbert) \cdot Trie \ (Hash \ tree) $
Graphs	Binary decision diagram · Directed acyclic graph · Directed acyclic word graph
	List of data structures

This page was last modified on 23 August 2015, at 01:39.

Categories: Computer memory | Arrays

Text is available under the Creative Commons Attribution-ShareAlike License; additional terms may apply. By using this site, you agree to the Terms of Use and Privacy Policy. Wikipedia® is a registered trademark of the Wikimedia Foundation, Inc., a non-profit organization.

Privacy policy About Wikipedia Disclaimers Contact Wikipedia Developers Mobile view

