#### **12.520 Lecture Notes #10**

#### **Finite Strain**

The "paradox" of finite strain and preferred orientation – pure vs. simple shear

Suppose: 1) Anisotropy develops as mineral grains grow such that they are preferentially oriented with the "easy slip" direction facilitating deformation.

- 2) New grain growth is determined by the state of stress. (What else would a mineral grain "know" about?)
- 3) The state of stress for pure shear and simple shear are identical pure and simple shear stress differ only by a rotation of 45° in coordinate system.
- 4) In pure shear there is only one slip direction, whereas in pure shear, 2 systems could be active.

**Paradox**: If the stress state is the same, how does the rock "know" to have 1 preferred orientation in simple shear, but not in pure shear?




Fig. 10\_1


Up to now, we have considered infinitesimal strain, where  $e_{ij} = (\partial u_i/\partial x_j + \partial u_j/\partial x_i)/2 <<1$ .

For the kinds of deformations common in structural geology, as well as for the deforming telephone book example shown in class, this condition of "infinitesimal" deformation no longer holds.

Life becomes complicated. In particular, it's important to know whether one is coming or going:

### • Reference frame:

Consider a medium undergoing motion & deformation, with the displacement a (vector) function of position.



Since the mapping  $a_i < --> b_j$  is one-to-one, we could also say

$$a_j = a_j(b_i)$$
.

It turns out (consider the telephone book example in class) that the description of strain depends on whether the reference frame is:

**Lagrangian** ∫ fixed to particles (the "a" frame)

$$u_i = b_i(a_j) - a_i$$

Example: elasticity -- the particles return to where they started

**Eulerian** ∫ fixed to space (the "b" frame)

$$u_i = b_i - a_i(b_j)$$

Example: fluid mechanics, geology -- no idea where the particles started or where they will end up; no stable frame fixed to the materials.

Finite strain depends on whether the reference frame is fixed to the particle or to "space:"


Lagrangian strain:  $E_{ij} = (\partial u_i/\partial a_j + \partial u_j/\partial a_i + \partial u_j/\partial a_i \partial u_j/\partial a_j)/2$ 

Eulerian strain:  $e_{ij} = (\partial u_i/\partial b_j + \partial u_j/\partial b_i - \partial u_l/\partial b_i \partial u_l/\partial b_j)/2$ 

When strain is small, the 3rd term is small<sup>2</sup>, and both strains converge to the infinitesmal value.

## Physical interpretation:

diagonal elements - e.g., elongation, given by  $ds = (1 + E_1) ds_0$ .



For the Lagrangian system,  $E_1 = (1 + 2E_{11})^{1/2} - 1$ 

off diagonal —>change in angles of coordinate axes:




Fig. 10\_4

$$\sin a = 2E_{12}/[(1 + E_{11})(1 + E_{22})]1/2$$

These quantities go to the infinitesimal values when  $E_{ij} \ll 1$ .

Because  $e_{ij} \neq E_{ij}$ , the principal values & principal directions of the Lagrangian and Eulerian strain tensors differ. We will discuss these later.

Consider two particles initially separated by  $da_i$  (note: not just a function of strain tensor) which undergo a displacement  $u_i$ , and are then separated by  $dx_i$ .

### Lagrangian:

$$dx_{i} = da_{i} + \frac{\partial u_{i}}{\partial a_{j}} daj = \left[ \delta_{ij} + \frac{\partial u_{i}}{\partial a_{i}} \right] da_{j}$$

This can be written, including the finite strain tensor,

$$dx_{i} = \left[\delta_{ij} + \frac{1}{2} \left( \frac{\partial u_{i}}{\partial a_{j}} + \frac{\partial u_{j}}{\partial a_{i}} + \frac{\partial u_{s}}{\partial a_{i}} \frac{\partial u_{s}}{\partial a_{j}} \right) + \frac{1}{2} \left( \frac{\partial u_{i}}{\partial a_{j}} - \frac{\partial u_{j}}{\partial a_{i}} - \frac{\partial u_{s}}{\partial a_{i}} \frac{\partial u_{s}}{\partial a_{j}} \right) \right] da_{j}$$

$$= \left[\delta_{ij} + \mathbf{E}_{ij} + \Omega_{ij}\right] da_{j}$$

 $\Omega_{ij}$  — Lagrangian rotation tensor

if  $\mathbf{E}_{ii} = \mathbf{0} \rightarrow \text{rotation alone}$ 

Similarly, for the **Eulerian** case:

$$\omega_{ij} = \frac{1}{2} \left( \frac{\partial u_i}{\partial b_j} - \frac{\partial u_j}{\partial b_i} + \frac{\partial u_s}{\partial b_i} \frac{\partial u_s}{\partial b_j} \right)$$

$$da_i = \left[ \delta_{ij} + e_{ij} + \omega_{ij} \right] dx_j$$

for small deformation:  $\Omega_{ij}$  rotation needed to bring a fiber  $da_i$  into position.

For large deformation: no easy way to separate into pure rotation and pure shear—the two are intimately connected.

THIS IS OF UTMOST IMPORTANCE IN PROBLEMS LIKE THE DEVELOPMENT OF ROCK FABRIC. ALSO—REGIONAL TECTONICS.

### Consider homogeneous strain




Fig. 10\_5


This holds if

$$\begin{split} E_{ij} &= \frac{1}{2} \left( \delta_{lm} \frac{\partial r_l}{\partial R_i} \frac{\partial r_m}{\partial R_j} - \delta_{ij} \right) \neq E_{ij}(R_i) \\ \Rightarrow \frac{\partial 1}{\partial 2} &= \text{constant} \Rightarrow R \& r \text{ linearly related} \end{split}$$

Define 
$$R_i \to x, y \ r_i \to x', y'$$
  
In general  $x' = ax + by$   $y' = cx + dy$  
$$E_{ij} = \frac{1}{2} \begin{bmatrix} a^2 + c^2 - 1 & ab + cd & 0 \\ ab + cd & b^2 + d^2 - 1 & 0 \\ 0 & 0 & 0 \end{bmatrix}$$

## Examples


$$x' = kx$$
$$y' = y$$



Simple extension

Fig. 10\_6


$$x' = k_1 x$$
$$y' = k_2 y$$



## Extension along both directions

Fig. 10\_7


$$x' = kx$$
$$y' = \frac{1}{k}y$$



## Pure shear

Fig. 10\_8

$$x' = x + 2sy$$
$$y' = y$$



# Simple shear

Fig. 10\_9




Fig. 10\_10

Unstrained		Strained
$x = \frac{1}{h^2}(dx' - by')$		x' = ax + by
$x = \frac{1}{h^2}(dx' - by')$ $y = \frac{1}{h^2}(-cx' + ay')$	$h^2 = ad - bc$	y' = cx + dy
	Principal Axes A, B	
	Roots of	
	$R^{4} - (a^{2} + b^{2} + c^{2} + d^{2})R^{2} + h^{4} = 0$	
$\tan 2\alpha = \frac{2(ab + cd)}{a^2 + c^2 - b^2 - d^2}$		$\tan 2\alpha' = \frac{2(ac + bd)}{a^2 + b^2 - c^2 - d^2}$
	No Length Change	
$\tan \delta = \pm [(1 - B^2) / (A^2 - 1)]^{1/2}$		$\tan \delta' = \pm \frac{B(A^2 - 1)^{1/2}}{A(1 - B^2)^{1/2}}$
relative to reciprocal axis		relative to principal axis
	Maximum Shear	
$\tan 2\varphi = \frac{b^2 + d^2 - a^2 - c^2}{2(ab + cd)}$		$\tan \varphi' = (B/A)$
relative to coord. axis		relative to principal axis
	Principal axis of infinitesimal	
	strain	
	$\alpha_0 = \frac{\alpha + \alpha'}{2}$	