
搭建负载均衡的 LAMP 平台——LVS+LAMP

服务器和数据库服务器的规划拓扑图:



下载 php 镜像: https://downloads.php.net/~stas/或者 https://secure.php.net/releases/

下载 mariadb(mysql 数据库)镜像: https://downloads.mariadb.org/MariaDB/+files/

下载 httpd 镜像: https://httpd.apache.org/download.cgi

下载 WordPress 镜像: https://wordpress.org/download/release-archive/ 安装 http 软件:

1、首先安装 apr 和 apr-util 软件

cd /usr/src/LAMP

tar zxvf apr-1.5.2.tar.gz

cd apr-1.5.2

./configure --prefix=/usr/local/apr

make && make insttall

cd /usr/local/LAMP

tar zxvf apr-util-1.5.4.tar.gz

cd apr-util-1.5.4

./configure --prefix=/usrlocal/apr-util --with-apr=/usr/local/apr

make && make install

2、安装 httpd 所需要的软件和库文件:

yum install pcre-devel mod_ssl openssl-devel

3、安装 httpd 软件:

tar zxvf httpd-2.4.23.tar.gz

cd httpd-2.4.23

./configure --prefix=/usr/local/apache --sysconfdir=/etc/httpd/ --enable-so --enable-rewirte --enable-ssl --enable-cgi --enable-cgid --enable-modules=most --enable-mods-shared=most --enable-mpms-shared=all --with-apr=/usr/local/apr --with-apr-util=/usr/local/apr-util/

make && make install

```
4、修改配置文件:
    cd /etc/httpd/
    echo "ServerName localhost:80" >> /httpd.conf
    sed -i 's@index.html@index.html index.php@g' httpd.conf
    在 httpd.conf 中添加如下内容:
    AddType application/x-httpd-php .php
    Include conf/vhost/vhost.conf
    make /etc/httpd/conf/vhost
    cat /etc/httpd/conf/vhost/vhost.conf #建立一个基于域名的虚拟主机:
    <VirtualHost 192.168.138.100:80>
         ServerName www.boke.com
         DocumentRoot /mydata/boke
         <Directory "/mydata/boke">
             Options Indexes FollowSymLinks
             Allowverride None
             Require all granted
         </Directory>
    </VirtualHost>
5、检测 httpd 的配置文件的语法并且重启 apachectel 服务
    apachectl-t
    apachectl start
安装 mysql 数据库软件
1、利用源码安装 mysql:
    tar zxvf mysql-5.7.15-linux-glibc2.5-x86_64.tar.gz -C /usr/local
    cd /usr/local
    ln -sv mysql-5.7.15-linux-glibc2.5-x86_64 mysql
    groupadd mysql
    useradd -r -g mysql -s /sbin/nologin mysql
    chown -R mysql:mysql ./mysql/*
    mkdir/mydata/data-pv
    chown -R mysql:mysql/mydata/data
    ./bin/mysqld --initialize --user=mysql --datadir=/mydata/data
    sed -i 's@datadir=@datadir=/mydata/data@g' ./support/mysql.server
    ./support/mysql.server start
    echo "export PATH=$PATH:/usr/local/mysql/bin" > /etc/profile.d/mysql.sh
    echo "/usr/local/mysql/lib" > /etc/ld.so.conf.d/mysqld.conf
    . /etc/profile.d/mysql.sh
    mysql -uroot -p
    mysql>set passowrd=password('密码');
    mysql>flush privileges;
    mysql>\q
安装 php 软件:
1、安装 PHP 所需的软件和库文件:
    yum install libxml2-devel bzip2-devel
2、解压并安装 PHP 软件:
    tar jxvf php-5.4.40.tar.bz2
    cd php-5.4.40
```

 $./configure --prefix=/usr/local/php --with-mysql=mysqlnd --with-openssl --with-mysqli=mysqlnd \ --enable-mbstring \\ --with-freetype-dir --with-jpeg-dir --with-png-dir --with-zlib --with-libxml-dir=/usr/ --enable-xml --enable-sockets \\ --with-freetype-dir --with-jpeg-dir --with-png-dir --with-zlib --with$

--with-apxs2=/usr/local/apache/bin/apxs --with-mcrypt --with-config-file-path=/etc/php.ini

--with-config-file-scan-dir=/etc/php.d/ --with-bz2 --enable-maintainer-zts

make && make install

安装 ipvsadm 软件:

1、首先查看内核是否加载了 ipvs 模块(注:内核版本在 2.4 以后内核都默认加载了 ipvs 模块) modprobe -1 | grep ipvs

2、解压安装 ipvsadm 软件:

cd /usr/src/

tar zxvf ipvsadm.tar.gz

cd ipvsadm-1.24

ln -sv /usr/src/kernels/2.6.32-504.el6.x86_64 /usr/src/linux #添加内核的链接

make && make install

LVS 负载均衡技术:

1、在调度器上设置 RS:

service iptables stop

ipvsadm -A -t 192.168.138.100:80 -s rr -p 3600

ipvsadm -a -t 192.168.138.100:80 -r 192.168.139.129 -g -w 1

ipvsadm -a -t 192.168.138.100:80 -r 192.168.139.130 -g -w 2

2、在RS上添加VIP地址:

echo 2 > /proc/sys/net/ipv4/conf/eth0/arp_announce

echo 2 > /proc/sys/net/ipv4/conf/all/arp_announce

echo 1 > /proc/sys/net/ipv4/conf/all/arp_ignore

echo 1 > /proc/sys/net/ipv4/conf/eth0/arp_ignore

ifconfig lo:0 192.168.138.100 broadcast 192.168.138.100 netmask 255.255.255.255 up

route add -host 192.168.138.100 dev lo:0