文档 9: gluster 中的 NFS 环境配置手册

- 1、通过 service glusterd start 命令把 glusterd 服务启动。
- 2、通过 service nfs stop 命令把系统自带的 NFS 服务关掉,这样做是为了避免与 Gluster-NFS 服务端口产生冲突。
- 3、通过 gluster volume create test 192.168.56. {104,102}:/home/brick/force 命令建立一个名为 test 的逻辑卷, 创建成功会提示 volume create:test:success:please start the volume to access data。

注:

pc1 IP:192.168.0.104 pc2 IP:192.168.0.102

- 4、根据上面创建卷成功的提示,可通过 service volue start test 命令把 test 逻辑卷启动。
- 5、通过 gluster volume set test nfs. disable off 命令把 nfs. disable 参数设置成 off。

```
[root@pc1 home]# gluster volume create test 192.168.0.{104,102}:/home/brick forc
volume create: test: success: please start the volume to access data
[root@pc1 home]# gluster volume start test
volume start: test: success
[root@pc1 home]# gluster volume set test nfs.disable off
volume set: success
[root@pc1 home]# gluster volume info
Volume Name: test
Type: Distribute
Volume ID: 98b7a0ad-5c27-4708-bca7-94ad4e36f72a
Status: Started
Number of Bricks: 2
Transport-type: tcp
Bricks:
Brick1: 192.168.0.104:/home/brick
Brick2: 192.168.0.102:/home/brick
Options Reconfigured:
nfs.disable: off
performance.readdir-ahead: on
[root@pc1 home]# _
```

6、通过 gluster volume get test all 查看 nfs. disable 参数是否为 off。

```
debug.error-fops
nfs.enable-ino32
                                           no
nfs.mem-factor
                                           15
nfs.export-dirs
                                           on
nfs.export-volumes
                                           on
nfs.addr-namelookup
                                           off
nfs.dynamic-volumes
                                           off
nfs.register-with-portmap
                                           on
nfs.outstanding-rpc-limit
                                           16
                                           2049
nfs.port
nfs.rpc-auth-unix
                                           on
nfs.rpc-auth-null
                                           on
nfs.rpc-auth-allow
                                           all
nfs.rpc-auth-reject
                                           none
nfs.ports-insecure
                                           off
nfs.trusted-sync
                                           off
nfs.trusted-write
                                           off
nfs.volume-access
                                           read-write
nfs.export-dir
nfs.disable
                                           off
nfs.nlm
nfs.acl
                                           on
nfs.mount-udp
                                           off
                                           /var/lib/glusterd/nfs/rmtab
nfs.mount-rmtab
nfs.rpc-statd
                                           /sbin/rpc.statd
```

7、CentOS7.2 下防火墙规则:

分别使用如下命令进行配置:

```
firewall-cmd --zone=public --add-service=rpc-bind --permanent firewall-cmd --zone=public --add-service=nfs --permanent firewall-cmd --permanent --add-port=24007/tcp firewall-cmd --permanent --add-port=38465/tcp firewall-cmd --permanent --add-port=38465/udp firewall-cmd --permanent --reload
```

8、使用以上命令进行配置完之后,通过命令 systemctl restart firewalld. service 把防火墙进行重启。

```
[root@pc1 /]# systemctl restart firewalld.service
[root@pc1 /]# _
```

- 9、在 pc2 机器上通过 mount -t nfs pc1:/test /mnt/nfs/ 把 test 逻辑卷挂载到/mnt/nfs/目录下。
- 10、通过 mount 挂载命令或者是 df -Th 命令可以查看到 gluster-nfs 挂载是否成功。

```
[root@pc2 ~]# mount -t nfs pc1:/test /mnt/nfs
[root@pc2 ~]# df -Th
Filesystem Type
/dev/mapper/centos-root xfs
                                Type
                                              Size
                                                      Used Avail Use% Mounted on
                                             8.5G
910M
921M
                                                             6.9G
910M
921M
                                                      1.7G
                                                                      20% /
                                devtmpfs
                                                                       0% /dev
0% /dev/shm
devtmpfs
                                                          0
tmpfs
                                tmpfs
                                                                      1% /run

0% /sys/fs/cgroup

26% /boot
tmpfs
                                tmpfs
                                              921M
                                                      8.4M
                                                              912M
                                                             921M
372M
185M
tmpfs
                                tmpfs
                                              921M
                                                         0
                                              497M
185M
/dev/sda1
                                                      125M
                                xfs
                                tmpfs
                                                                      0% /run/user/0
21% /mnt/nfs
tmpfs
                                                         0
pc1:/test
                                              8.5G
                                                      1.8G
                                                             6.8G
                                nfs
[root@pc2 ~1# _
```