MICROMAX SUGAR MILLS ERP · OPERATOR GUIDE

Gate, gross & tare

Token at the gate, the 1st weight (gross) and the 2nd weight (tare): with the live CCTV cameras, the platform sensors that stop a vehicle being weighed half on the bridge, auto-weigh, and the grower display that shows the driver and grower the weight.

1 · Gate

Scan indent, vehicle, driver code → token. Gate cameras photograph the vehicle.

2 · Gross

Scan token → platform OK → stable → weight (auto) → gross slip.

3 · Tare

Scan gross slip → compare with gross photos → tick → weight → CPR.

Who: **Token Clerk** · **Gross / Tare Weighman** · **Cane Manager / Admin** (typed weights, setup).


Menu

Cane Procurement →	Used by	For
Gate · token issue	Token Clerk	Scan the indent, vehicle and driver, issue and print the token.
Gross · 1st weight	Gross Weighman	Loaded weight; lists vehicles waiting for gross.
Tare · 2nd weight	Tare Weighman	Empty weight after the gross photo check; lists vehicles waiting for tare.
Weighbridge (both)	a bridge doing both	Takes whichever weight is due on the scanned token.
Payee displays	display PC	The grower display at each weighbridge (and the payee display at each cash counter).


Scanning: a barcode scanner types and presses Enter itself. The weighbridge accepts the **token, indent, gross slip** or the **vehicle no.**

1 Gate · issue the token

1. **Scan the indent.** The grower, village, source, load and rates fill in. A red box says why a token can't be issued.
2. Type the **vehicle no.** and choose the **vehicle type**.
3. **Driver:** type the **driver code** (e.g. `DRV-00001`) and press Enter. Name, CNIC and mobile fill in. Or type the **name and CNIC**: a known CNIC picks the driver, and a new one is registered with a code when the token is issued.
4. **Issue token & print.** The gate cameras save a photo of each view with the token.



Indent scanned, vehicle SGD-4417, driver fetched by code; the gate cameras are live above.




New driver: name + CNIC → registered on issue.



Token slip with the driver code.

2 Gross · 1st weight — platform sensors and auto-weigh


1. Open **Gross · 1st weight**. **Scan the token** (or the indent). The vehicle, grower and limits show on screen and on the **grower display**.
2. The **platform** box shows the beams at both ends of the deck. If a beam is **cut**, the vehicle is not fully on: the red light comes on, the weight is refused, and the display tells the driver to move fully onto the platform.
3. When every beam is clear and the weight is **stable**, the screen counts down and **takes the weight by itself** (auto-weigh). Or click **Take Gross weight**. **Stop auto** pauses it.
4. The weight and a photo from each bridge camera are saved. The **gross slip** prints and the vehicle goes to the yard.




Exit-2 and Exit-3 cut: red light ON, weight refused.



Grower display: "move fully onto the platform" (English + Urdu).




Platform OK, stable 8,840 kg: auto-weigh in 2 s.




Grower display after the gross: "go to the yard".

3 Tare · 2nd weight — same vehicle?


1. Open **Tare · 2nd weight**. **Scan the gross slip** (or token, indent, vehicle no.), or click the vehicle in *Waiting for tare*.
2. **Same vehicle?** Each photo taken at gross is shown beside the same camera live now. Body, trolley, wheels and plate must match; only the load is gone. Not the same: don't tick, and call the Yard Supervisor.
3. Tick **Same vehicle**. With the platform OK and the empty weight stable, the tare is taken (auto or by the button). **CPR and TPT bilty** are made and printed, and the display shows the **net weight**.



Gross photos (amber) beside the live tare cameras; "Same vehicle" ticked.




Gross 8,840 − tare 3,970 = net 4,870 kg; CPR and bilty.



Grower display: net weight and the CPR number.

Slips, problems and setup



MicroMax Sugar Mills Ltd.
GROSS WEIGHT SLIP · SEASON 2026-27 **WGT-26-005018**

WGT-26-005018

Vehicle	**SGD-4417 · Tractor Trolley**
Driver	**Muhammad Aslam · DRV-00001**
Grower	**Syed Akram Noon · 003-007-0003**
Token · Indent	**TKN-26-005027 · 26-003-100032**
From	**Mill Gate**
Weighbridge	**WB-1 Gross · 01 Nov 21:35**
Camera photos	**5 views saved at gross**

GROSS **8,840 kg**

Unload in the yard (Lane 1 - Trolley), then show this slip at the **tare** weighbridge

Scanned at the tare; the vehicle is compared with the gross photos.
Printed 01 Nov 2026 21:38 by Administrator.

Gross slip — scanned at the tare.



MicroMax Sugar Mills Ltd.
CANE PURCHASE RECEIPT (CPR) · SEASON 2026-27 **CPR-26-005002**

CPR-26-005002

GROWER		LOAD	
Name	**Syed Akram Noon s/o Mian Sarwar Sipra**	Day · Posted	**01 Nov 2026 · 01 Nov 21:36**
Grower ID	**003-007-0003**	Vehicle	**SGD-4417 · Tractor Trolley**
CNIC	**38403-1520976-9**	Driver	**Muhammad Aslam**
Passbook	**PB-003-007-0003**	From	**Mill Gate**
Village · Circle	**Chak 32 JB · Kot Momin**	Entry	**Gate**
Indent	**26-003-100032**	Token	**TKN-26-005027**

WEIGHT (KG)		AMOUNT (RS)	
Gross	8,840	Govt rate 425.00/md	51,605.63
Tare	− 3,970	Road cess 1.0% (grower 50.0%)	− 258.03
Net	4,870	Subsidy 10.00/md	+ 1,214.25
Binding (0.265 kg/qtl)	− 13	Additional subsidy 5.00/md	+ 607.13
Payable	**4,857 kg 121.425 md**	Net amount	**53,168.98**
		TPT 30.00/md (bilty BLT-26-004351)	− 3,642.75
		Payable to grower	**49,526.23**

PKR Forty Nine Thousand, Five Hundred And Twenty Six and Twenty Three Paisa only.

Weighman Cane office Grower

Paid to the grower's bank account by payment scroll. Keep this receipt; the bank payment quotes its number. Journal JV-26-04567. Printed 01 Nov 2026 21:38 by Administrator.

CPR — payable to the grower; the TPT bilty is paid at the cash counter.

You see	Do this
"Not fully on the platform (… cut)"	Ask the driver to move forward / back until every beam is clear.
"The gross (1st weight) is not taken yet" on the tare screen	Send the vehicle to the gross weighbridge (link on screen).
"Compare … and tick Same vehicle"	Check the photos, then tick only if it is the same vehicle.
Weight NO SIGNAL / amber	Wait for it to stand still. If the indicator is down, a Cane Admin types the weight with a reason.
Camera tile "offline"	Weighing continues; the photo is recorded as missing. Tell IT.
"… already inside on token …"	That vehicle hasn't finished its tare.

Setup (admin): *Weighbridge Terminal*: the PC's IP, **Platform position sensors fitted**, **Auto-weigh** and its seconds. *CCTV Camera*: place, terminal, view, snapshot URL and login. The weighbridge agent reads the indicator and the beams, and drives the red light. The grower display: **Payee displays → the weighbridge** on the screen facing the drivers (F11).

Screens from the MicroMax test system with demo data (1 November 2026). Video: *08-One-indent-token-to-payment-with-grower-display-and-sensors.mp4*.