

Week 7: Virtual Memory

Sherif Khattab

http://www.cs.pitt.edu/~skhattab/cs1550

Administrivia

- Project 1 due on 2/21 @11:59pm
- Midterm on 2/22
- Project 2 up this weekend


Agenda

- Background
- Demand Paging
 - Copy-on-Write
 - Page Replacement
 - Allocation of Frames
 - Thrashing
 - Memory-Mapped Files
- Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Background


- Virtual memory separation of user logical memory from physical memory
- Only part of the program needs to be in memory for execution
- Logical address space can therefore be much larger than physical address space
- Allows address spaces to be shared by several processes
- Allows for more efficient process creation
- More programs running concurrently
- Less I/O needed to load or swap processes
- Virtual memory can be implemented via:
 - Demand paging

Virtual Memory That is Larger Than Physical Memory




Virtual-address Space

- Stack to start at Max logical address and grow "down" while heap grows "up"
 - Maximizes address space use
 - No physical memory needed until heap or stack grows to a new page
- Enables sparse address spaces with holes left for growth, dynamically linked libraries, etc.
- System libraries shared via mapping into virtual address space
- Shared memory by mapping pages read-write
- Pages can be shared during fork(), speeding process creation




Shared Library Using Virtual Memory



Demand Paging

- Bring a page into memory only when it is needed
 - Less I/O needed, no unnecessary I/O
 - Less memory needed
 - Faster response
 - More users
- Similar to paging system with swapping (diagram on right) but:
 - Page is needed ⇒ reference to it
 - invalid reference ⇒ abort
 - not-in-memory ⇒ bring to memory
 - Lazy swapper never swaps a page into memory unless page will be needed
 - Swapper that deals with pages is a pager




Swapper vs. Pager


- With swapping, pager guesses which pages will be used before swapping out again
 - avoid unnecessary swapping in then out
- Pager brings in only those pages into memory
- How to determine that set of pages?
 - Need new MMU functionality to implement demand paging
- If pages needed are already memory resident
 - No difference from non demand-paging
- If page needed and not memory resident
 - Need to detect and load the page into memory from storage
 - Without changing program behavior
 - Without programmer needing to change code

Valid-Invalid Bit

- With each page table entry a valid—invalid bit is associated
 (v ⇒ in-memory memory resident, i ⇒ not-in-memory)
- Initially valid—invalid bit is set to i on all entries
- During MMU address translation, if valid—invalid bit in page table entry is i ⇒ page fault




Page Fault



Aspects of Demand Paging

- Extreme case start process with no pages in memory
 - OS sets instruction pointer to first instruction of process, nonmemory-resident -> page fault
 - And for every other process pages on first access
 - Pure demand paging
- Actually, a given instruction could access multiple pages -> multiple page faults
 - Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
 - Pain decreased because of locality of reference
- Hardware support needed for demand paging
 - Page table with valid / invalid bit
 - Secondary memory (swap device with swap space)
 - Instruction restart
 - block move



Performance of Demand Paging

- Three major activities
 - Service the interrupt careful coding means just several hundred instructions needed
 - Read the page lots of time
 - Restart the process again just a small amount of time
- Page Fault Rate 0 ≤ p ≤ 1
 - if p = 0 no page faults
 - if p = 1, every reference is a fault
- Effective Access Time (EAT)
 - $EAT = (1 p) \times memory access$
 - + p (page fault overhead + swap page out
 - + swap page in)

Demand Paging Example

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds
- EAT = $(1 p) \times 200 + p (8 \text{ milliseconds})$ = $(1 - p \times 200 + p \times 8,000,000$ = $200 + p \times 7,999,800$
- If one access out of 1,000 causes a page fault, then
 EAT = 8.2 microseconds.
 - This is a slowdown by a factor of 40!!
- If want performance degradation < 10 percent
 - 220 > 200 + 7,999,800 x p
 20 > 7,999,800 x p
 - p < .0000025
 - < one page fault in every 400,000 memory accesses

Demand Paging Optimizations

- Copy entire process image to swap space at process load time
 - Then page in and out of swap space
 - Used in older BSD Unix
 - Swap space I/O faster than file system I/O even if on the same device
 - Swap allocated in larger chunks, less management needed than file system
- Demand page in from program binary (code) on disk, but discard rather than paging out when freeing frame
 - Used in Solaris and current BSD
 - Still need to write to swap space pages that are:
 - not associated with a file (like stack and heap) anonymous memory
 - modified in memory but not yet written back to the file system


Demand Paging Optimizations (contd.)

- In general, free pages are allocated from a pool of zero-fill-on-demand pages
 - Pool should always have free frames for fast demand page execution
 - Don't want to have to free a frame as well as other processing on page fault
 - Why zero-out a page before allocating it?
- Mobile systems
 - Typically don't support swapping
 - Instead, demand page from file system and reclaim readonly pages (such as code)


Copy-on-Write

- Copy-on-Write (COW) allows both parest and child processes to initially share the same pages in memory and child processes in

If either process modifies a shared page, only then is the page physical




after process 1 writes to page C




process_o

Page Replacement

- Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- If there is no free frame, use a page replacement algorithm to select a victim frame
 - Write victim frame to disk in dirty
- Note now potentially 2
 page transfers for page
 fault increasing EAT






Page and Frame Replacement Algorithms

- Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
 - String is just page numbers, not full addresses
 - Results depend on number of frames available

First-In-First-Out (FIFO) Algorithm

- Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
- 3 frames (3 pages can be in memory at a time per process)




15 page faults

- Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
 - Adding more frames can cause more page faults!
 - Belady's Anomaly
- How to track ages of pages?
 - Just use a FIFO queue


Optimal Algorithm

- Replace page that will not be used for longest period of time
 - 9 page faults is optimal for the example
- How do you know this?
 - Can't read the future
- Used for measuring how well your algorithm performs



Least Recently Used (LRU) Algorithm

- Use past knowledge rather than future
- Replace page that has not been used in the most amount of time
- Associate time of last use with each page




- 12 faults better than FIFO but worse than OPT
- Generally good algorithm and frequently used
- But how to implement?

LRU Algorithm (cont.)

- Stack implementation
 - Keep a stack of page numbers in a doubly-linked form:
 - Page referenced:
 - move it to the top
 - requires 6 pointers to be changed
 - But each update more expensive
 - No search for replacement
- LRU and OPT are cases of stack algorithms that don't have Belady's Anomaly

Use Of A Stack to Record Most Recent Page References






LRU Approximation Algorithms

- LRU needs special hardware and still slow
- Reference bit
 - With each page associate a bit, initially = 0
 - When page is referenced bit set to 1
 - Replace any with reference bit = 0 (if one exists)
 - We do not know the order, however
- Second-chance algorithm
 - Generally FIFO, plus hardware-provided reference bit
 - Clock replacement
 - If page to be replaced has
 - Reference bit = 0 -> replace it
 - reference bit = 1 then:
 - set reference bit 0, leave page in memory
 - replace next page, subject to same rules

Second-Chance (clock) Page-Replacement Algorithm



Spring 2018

Enhanced Second-Chance Algorithm

- Improve algorithm by using reference bit and modify bit (if available) in concert
- Take ordered pair (reference, modify)
- 1. (0, 0) neither recently used nor modified best page to replace
- 2. (0, 1) not recently used but modified not quite as good, must write out before replacement
- (1, 0) recently used but clean probably will be used again soon
- (1, 1) recently used and modified probably will be used again soon and need to write out before replacement
- When page replacement called for, use the clock scheme but use the four classes replace page in lowest non-empty class
 - Might need to search circular queue several times

Counting Algorithms

- Keep a counter of the number of references that have been made to each page
 - Not common
- Lease Frequently Used (LFU) Algorithm: replaces page with smallest count

Most Frequently Used (MFU) Algorithm: based on the argument that the page with the smallest count was probably just brought in and has yet to be used

Page-Buffering Algorithms

- Keep a pool of free frames, always
 - Then frame available when needed, not found at fault time
 - Read page into free frame and select victim to evict and add to free pool
 - When convenient, evict victim
- Keep list of modified pages
 - When backing store otherwise idle, write pages there and set to non-dirty
- Keep free frame contents intact and note what is in them
 - If referenced again before reused, no need to load contents again from disk
 - Generally useful to reduce penalty if wrong victim frame selected

Applications and Page Replacement

- All of these algorithms have OS guessing about future page access
- Some applications have better knowledge i.e. databases
- Memory intensive applications can cause double buffering
 - OS keeps copy of page in memory as I/O buffer
 - Application keeps page in memory for its own work
- Operating system can given direct access to the disk, getting out of the way of the applications
 - Raw disk mode
- Bypasses buffering, locking, etc

Allocation of Frames to Processes

- Each process needs minimum number of frames
- Example: IBM 370 6 pages to handle SS MOVE instruction:
 - instruction is 6 bytes, might span 2 pages
 - 2 pages to handle from
 - 2 pages to handle to
- Maximum (of course) is total frames in the system
- Two major allocation schemes
 - fixed allocation
 - priority allocation

Fixed Allocation

- Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames
 - Keep some as free frame buffer pool
- Proportional allocation Allocate according to the size of process
 - Dynamic as degree of multiprogramming, process sizes change

Priority Allocation

Use a proportional allocation scheme using priorities rather than size

- If process P_i generates a page fault,
 - select for replacement one of its frames, or
 - select for replacement a frame from a process with lower priority number

Global vs. Local Allocation

- Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
 - But then process execution time can vary greatly
 - But greater throughput so more common

- Local replacement each process selects from only its own set of allocated frames
 - More consistent per-process performance
 - But possibly underutilized memory


Non-Uniform Memory Access

- So far all memory accessed equally
- Many systems are NUMA speed of access to memory varies
 - Consider system boards containing CPUs and memory, interconnected over a system bus
- Optimal performance comes from allocating memory "close to" the CPU on which the thread is scheduled
 - And modifying the scheduler to schedule the thread on the same system board when possible
 - Solved by Solaris by creating Igroups
 - Structure to track CPU / Memory low latency groups
 - Used by schedule and pager
 - When possible schedule all threads of a process and allocate all memory for that process within the Igroup

Thrashing

- If a process does not have "enough" pages, the page-fault rate is very high
 - Page fault to get page
 - Replace existing frame
 - But quickly need replaced frame back
 - This leads to:
 - Low CPU utilization
 - Operating system thinking that it needs to increase the degree of multiprogramming
 - Another process added to the system

Thrashing ≡ a process is busy swapping pages in and out




Demand Paging and Thrashing

- Why does demand paging work?
 Locality model
 - Process migrates from one locality to another
 - Localities may overlap

- Why does thrashing occur?
 size of locality > total memory size
 - Limit affected by using local or priority page replacement

Working-Set Model

- Δ = working-set window = a fixed number of page references Example: 10,000 instructions
- WSS_i (working set of Process P_i) = total number of pages referenced in the most recent Δ (varies in time)
 - if Δ too small will not encompass entire locality
 - if Δ too large will encompass several localities
 - if $\Delta = \infty \Rightarrow$ will encompass entire program



Thrashing

- $D = \Sigma WSS_i \equiv \text{total demand frames}$
- if $D > m \Rightarrow$ Thrashing occurs
- Policy: if D > m, then suspend or swap out one of the processes


Keeping Track of the Working Set

- Approximate with interval timer + a reference bit
- Example: $\Delta = 10,000$
 - Timer interrupts after every 5000 time units
 - Keep in memory 2 bits for each page
 - Whenever a timer interrupts copy and set the values of all reference bits to 0
 - If one of the bits in memory = $1 \Rightarrow$ page in working set
- Why is this not completely accurate?
- Improvement = 10 bits and interrupt every 1000 time units

Page-Fault Frequency

- More direct approach than WSS
- Establish "acceptable" page-fault frequency (PFF)
 rate and use local replacement policy
 - If actual rate too low, process loses frame
 - If actual rate too high, process gains frame

Working Sets and Page Fault Rates




Memory-Mapped Files

- Memory-mapped file I/O allows file I/O to be treated as routine memory access by mapping a disk block to a page in memory
- A file is initially read using demand paging
 - A page-sized portion of the file is read from the file system into a physical page
 - Subsequent reads/writes to/from the file are treated as ordinary memory accesses
- Simplifies and speeds file access by driving file I/O through memory rather than read() and write() system calls
- Also allows several processes to map the same file allowing the pages in memory to be shared
- But when does written data make it to disk?
 - Periodically and / or at file close() time
 - For example, when the pager scans for dirty pages


Memory-Mapped File Technique for all I/O

- Some OSes uses memory mapped files for standard I/O
- Process can explicitly request memory mapping a file via mmap () system call
 - Now file mapped into process address space
- For standard I/O (open(), read(), write(), close()), mmap anyway
 - But map file into kernel address space
 - Process still does read() and write()
 - Copies data to and from kernel space and user space
 - Uses efficient memory management subsystem
 - Avoids needing separate subsystem
- COW can be used for read/write non-shared pages
- Memory mapped files can be used for shared memory (although again via separate system calls)

Memory Mapped Files



Shared Memory via Memory-Mapped I/O



Allocating Kernel Memory


- Treated differently from user memory
- Often allocated from a free-memory pool
 - Kernel requests memory for structures of varying sizes
 - Some kernel memory needs to be contiguous
 - e.g. for device I/O

Buddy System

- Allocates memory from fixed-size segment consisting of physically-contiguous pages
- Memory allocated using power-of-2 allocator
 - Satisfies requests in units sized as power of 2
 - Request rounded up to next highest power of 2
 - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
 - Continue until appropriate sized chunk available
- For example, assume 256KB chunk available, kernel requests 21KB
 - Split into A_L and A_R of 128KB each
 - One further divided into B_I and B_R of 64KB
 - One further into C_L and C_R of 32KB each one used to satisfy request
- Advantage quickly coalesce unused chunks into larger chunk
- Disadvantage fragmentation

Buddy System Allocator


physically contiguous pages



Slab Allocator

- Alternate strategy
- Slab is one or more physically contiguous pages
- Cache consists of one or more slabs
- Single cache for each unique kernel data structure
 - Each cache filled with objects instantiations of the data structure
- When cache created, it is filled with objects marked as free
- When structures stored, objects marked as used
- If slab is full of used objects, next object allocated from empty slab
 - If no empty slabs, new slab allocated
- Benefits include no fragmentation, fast memory request satisfaction

Slab Allocation



Slab Allocator in Linux

- For example process descriptor is of type struct task_struct
- Approx 1.7KB of memory
- New task -> allocate new struct from cache
 - Will use existing free struct task_struct
- Slab can be in three possible states
 - 1. Full all used
 - 2. Empty all free
 - 3. Partial mix of free and used
- Upon request, slab allocator
 - 1. Uses free struct in partial slab
 - 2. If none, takes one from empty slab
 - 3. If no empty slab, create new empty

Slab Allocator in Linux (Cont.)

- Slab started in Solaris, now wide-spread for both kernel mode and user memory in various OSes
- Linux 2.2 had SLAB, now has both SLOB and SLUB allocators
 - SLOB for systems with limited memory
 - Simple List of Blocks maintains 3 lists for small, medium, large objects
 - SLUB is performance-optimized SLAB
 - removes per-CPU queues, metadata stored in page structure

Other Considerations -- Prepaging

Prepaging

- To reduce the large number of page faults that occurs at process startup
- Prepage all or some of the pages a process will need, before they are referenced
- But if prepaged pages are unused, I/O and memory was wasted
- Assume s pages are prepaged and α of the pages is used
 - Benefit: s * α saved page faults
 - Cost: s * (1- α) unnecessary page loads
 - α near zero ⇒ prepaging loses

Other Issues – Page Size

- Sometimes OS designers have a choice
 - Especially if running on custom-built CPU
- Page size selection must take into consideration:
 - Fragmentation
 - Page table size
 - Resolution
 - I/O overhead
 - Number of page faults
 - Locality
 - TLB size and effectiveness
- Always power of 2, usually in the range 2¹² (4,096 bytes) to 2²² (4,194,304 bytes)
- On average, growing over time

Other Issues – TLB Reach

- TLB Reach The amount of memory accessible from the TLB
- TLB Reach = (TLB Size) X (Page Size)
- Ideally, the working set of each process is stored in the TLB
 - Otherwise there is a high degree of page faults
- Increase the Page Size
 - This may lead to an increase in fragmentation as not all applications require a large page size
- Provide Multiple Page Sizes
 - This allows applications that require larger page sizes the opportunity to use them without an increase in fragmentation

Other Issues – Program Structure

- Program structure
 - int[128,128] data;
 - Each row is stored in one page
 - Program 1


 $128 \times 128 = 16,384$ page faults

Program 2

128 page faults only!

Other Issues – I/O interlock

- I/O Interlock Pages must sometimes be locked into memory
- Consider I/O Pages that are used for copying a file from a device
 - must be locked from being selected for eviction by a page replacement algorithm
- Pinning of pages to lock into memory



Windows

- Uses demand paging with clustering. Clustering brings in pages surrounding the faulting page
- Processes are assigned working set minimum and working set maximum
- Working set minimum is the minimum number of pages the process is guaranteed to have in memory
- A process may be assigned as many pages up to its working set maximum
- When the amount of free memory in the system falls below a threshold, automatic working set trimming is performed to restore the amount of free memory
- Working set trimming removes pages from processes that have pages in excess of their working set minimum

Solaris

- Maintains a list of free pages to assign faulting processes
- Lotsfree threshold parameter (amount of free memory) to begin paging
- Desfree threshold parameter to increasing paging
- Minfree threshold parameter to starting swapping
- Paging is performed by pageout process
- Pageout scans pages using modified clock algorithm
- Scanrate is the rate at which pages are scanned. This ranges from slowscan to fastscan
- Priority paging gives priority to process code pages

