


# DART Tutorial Section 25: A simple 1D advection model: Tracer Data Assimilation





**©UCAR** 



## 1D Simple Advection Model: Overview

models/simple\_advection/work/

## Found in models/simple\_advection

- 1. One dimensional periodic domain.
- 2. Chaotic/stochastic model for wind.
- 3. Single passive tracer advected by wind.
- 4. Stochastic model for tracer source can be added.
- 5. Diurnal cycle for tracer source can be added.
- 6. Model for phase offset of diurnal cycle can be added.

## 1D Simple Advection Model

Model domain, timestepping, and namelist controls (in italics):

- 1. One-dimensional, periodic grid on domain [0, 1].
- 2. Equally-spaced gridpoints, number controlled by num\_grid\_points.
- 3. Location of gridpoints is 0, 1/N, 2/N,..., N-1/N; N=num\_grid\_points.
- 4. Distance between gridpoints is grid\_spacing\_meters.
- 5. Time-stepping controlled by *time\_step\_days*, *time\_step\_seconds*.

# The wind model: Burger's Equation

- 1. Wind equation is:  $\frac{\partial u}{\partial t} = -u \frac{\partial u}{\partial x}$
- 2. Continuous solution forms shocks when u varies with x.
- 3. Use upstream Lagrangian differencing:
  - a. Let  $u_i$  be velocity at gridpoint i located at  $x_i$ ;  $\Delta t$  is timestep.
  - b. Source location for wind is:  $x_s = x_i u_i \Delta t$
  - c. Linearly interpolate u to  $x_s$ ; this is new wind at gridpoint i.
- 4. This is heavy damping.
- 5. Generally won't form shocks, even when analytic solution should.

## Wind Model 2: Namelist controls in italics

- 1. Without something additional, damps to spatially constant.
- 2. Randomly perturb each gridpoint value of u every timestep:

$$u_i = u_i + Normal(0, W\Delta t)$$
 , i = 1,..., N

W = wind\_random\_amp

3. Damp the spatial mean wind field to M = mean\_wind:

$$\overline{u}(t + \Delta t) = \overline{u}(t) - W_D \Delta t \left[ \overline{u}(t) - M \right]$$

W<sub>D</sub> is wind\_damping\_rate

## Trying out the wind model

```
cd models/simple_advection/work
csh workshop setup.csh
```

- 1. Run ./perfect\_model\_obs and use ncview true\_state.nc to check out the winds (ignore the other fields for now).
- Make sure you understand the spatial/temporal behavior of winds.
- 3. Play with mean\_wind, wind\_damping\_rate, wind\_random\_amp to get different types of flows.
- 4. Having winds reverse will be interesting for some tracer cases.

# Tracer field and namelist control (italics)

- 1. A single passive (doesn't affect wind) tracer is advected by the wind.
- 2. Have tracer concentration, C<sub>i</sub>, at each gridpoint.
- 3. Semi-lagrangian upstream time differencing (same as for wind).
- 4. There is a tracer source/sink rate, S<sub>i</sub>, at each gridpoint.
- 5. Also a background D=destruction\_rate (percent / second).  $C_i = C_i + S_i \Delta t D \Delta t C_i$

## An assimilation example

1. Observations (20 altogether):

Ten equally-spaced co-located observations of u and C.

Located halfway between gridpoints (0.05, 0.15,..., 0.95).

Forward observation operator is linear interpolation (mean).

u observations have error variance of 16.01.

C observations have error variance of 1000.2.

(Apparently insignificant decimals make changing these easier)

- 2. Base namelist assimilates both types of observations.
- 3. Run ./perfect\_model\_obs followed by ./filter. (Make sure to use base input.nml, etc.).
- 4. Use Matlab to examine behavior of the assimilation.
- 5. Keep track of errors for concentration and wind fields.

## An assimilation example (2)

- 1. Look at impact of using subsets of the observations.
- 2. Observations being used are controlled in &obs\_kind\_nml. Default is:

Change to assimilating only wind observations:

3. Try assimilating only wind, only concentration and not assimilating anything (delete assimilate\_these\_obs\_types). Record results and understand what's going on.

## Tracer source model and namelist control

- 1. So far, tracer source has been constant in time (not in space).
- 2. Make the source model a damped random walk at each gridpoint.

Add random noise to each gridpoint at each timestep. Also damp to a time mean value.

$$S_i = S_i + N$$
  $al(0, S_R) - S_D(S_i - \overline{S}_i)$ 

where  $S_R = source\_random\_amp\_frac$ ,  $S_D = source\_damping\_rate$  and  $\overline{S_i}$  is time mean value for source at this gridpoint.

 $\overline{S}_i$  is actually a 4th set of state variables (defined at each gridpoint). We will NOT work with this set of variables here.

## Assimilation with time-varying tracer source

#### Use these settings:

```
&model_nml
    source_random_amp_frac = 0.000002

&perfect_model_obs_nml
    input_state_files = 'perfect_input_source_noise.nc'

&filter_nml
    input_state_file_list = 'filter_input_list.txt'

filter_input_list.txt contains a list of input files, for this model, there is only one file in the list. Edit the contents of filter_input_list.txt to contain filter input source noise.nc
```

- Repeat the assimilations with different classes of observations.
   (./perfect\_model\_obs followed by ./filter)
- 2. This time, also keep track of errors for the source field.
- 3. What happens if *source\_random\_amp\_frac* = 0.00001?

Can you find ways to improve filter performance in these cases?

## Diurnal component for tracer source model

- 1. source\_diurnal\_rel\_amp controls amplitude of diurnal component as fraction of source value.
- 2. Turn this on and try assimilation experiments again.

```
&perfect_model_obs_nml
...
    input_state_files = "perfect_input_diurnal.nc"
&model_nml
...
    source_diurnal_rel_amp = 0.05,
```

3. Change contents of filter\_input\_list.txt to filter\_input\_diurnal.nc

# Impact of observation density

#### Try this:

- Repeat the different assimilation cases.
   Run ./perfect\_model\_obs followed by ./filter.
- 2. What happens if observations get even sparser? (You'll have to do your own observation sequence design for this).

It is a good idea to svn revert set\_def.out obs\_seq.in after you are done with your own observation sequence design and experimentation to stay consistent with the tutorial material.

## Using DA to learn about the source model

This is basically parameter estimation. Try this:

```
&model_nml
    source_phase_noise = 0.00001

&perfect_model_obs_nml
    obs_seq_in_file_name = 'obs_seq.in'
    input_state_files = 'perfect_input.nc'

&filter_nml
    input_state_file_list = 'filter_input_list.txt'
```

- 1. Change contents of filter\_input\_list.txt to filter\_input.nc
- 2. Run ./perfect\_model\_obs followed by ./filter

## DA for sources with lots of structure

#### Try this:

No system noise.

```
&model_nml
    source_phase_noise = 0.0

&perfect_model_obs_nml
    obs_seq_in_file_name = 'obs_seq.in'
    input_state_files = 'perfect_input_saw.nc'
```

The source has large mean value at points 1, 3 and 5, small elsewhere.

Can one resolve this spatial structure?

## Problems to explore

- 1. Pick one of the configurations above. Suppose that wind observations cost \$10 and concentration observations cost \$20. If you have \$200 to spend on observations (that MUST be located halfway between the gridpoints), what is the best observing/assimilation system you can design? The error variance of the observations is fixed as in the original cases. You can put multiple observations of any kind at an observing location. The metric of success is the smallest total error for the concentration. What if the metric is the smallest total error for the source?
- 2. Suppose you can only take observations once a day but the source has a fixed diurnal component. Is there any way to learn anything about the diurnal component? You can use as many observations as you want for this. Ask how to change the observation frequency.

# Problems to explore (2)

- 3. For the saw tooth source pattern, what happens as the number of observing locations goes down in this case?
- 4. What happens to the quality of the assimilations in some of the cases above if the *destruction\_rate* is made smaller or bigger (it's already pretty big in some sense)?
- 5. We might be happier if tracer were not created or destroyed by the assimilation. Is the assimilation creating and destroying tracer? Is there any systematic component to this? Can you find ways to reduce creation/destruction by the assimilation scheme?
- 6. What happens if we use a fixed-lag smoother in this problem? How should the smoother be tuned? What happens to tracer destruction/creation in the smoother estimates?

# Problems to explore (3)

7. Can you think of good ways to add model error into this system? If you do, what happens to the quality of the assimilations for various types of experiments? Simulating model error in a meaningful way is essential to predicting what will happen when one switches to real observations.

## DART Tutorial Index to Sections

- 1. Filtering For a One Variable System
- 2. The DART Directory Tree
- 3. DART Runtime Control and Documentation
- 4. How should observations of a state variable impact an unobserved state variable? Multivariate assimilation.
- 5. Comprehensive Filtering Theory: Non-Identity Observations and the Joint Phase Space
- 6. Other Updates for An Observed Variable
- 7. Some Additional Low-Order Models
- 8. Dealing with Sampling Error
- 9. More on Dealing with Error; Inflation
- **10.** Regression and Nonlinear Effects
- 11. Creating DART Executables
- 12. Adaptive Inflation
- 13. Hierarchical Group Filters and Localization
- 14. Quality Control
- 15. DART Experiments: Control and Design
- 16. Diagnostic Output
- 17. Creating Observation Sequences
- 18. Lost in Phase Space: The Challenge of Not Knowing the Truth
- 19. DART-Compliant Models and Making Models Compliant
- 20. Model Parameter Estimation
- 21. Observation Types and Observing System Design
- 22. Parallel Algorithm Implementation
- 23. Location module design (not available)
- 24. Fixed lag smoother (not available)
- 25. A simple 1D advection model: Tracer Data Assimilation