

TBarCode OCX

Barcode ActiveX® Control

Version 11

Developer Manual

9 January 2018

TEC-IT Datenverarbeitung GmbH Hans-Wagner-Str. 6 A-4400 Steyr, Austria

> t ++43 (0)7252 72720 f ++43 (0)7252 72720 77 office@tec-it.com www.tec-it.com



Content

1		Content	2
2		Disclaimer	3
3	3.1 3.2 3.3 3.4 3.5	Introduction What is TBarCode SDK? Important Security Notice What is TBarCode OCX? Scope of this Document Restrictions of the Demo Version	4 4 4 4 5
4	4.1 4.2	Installation Requirements Download and Setup	6 6
5	5.1 5.2 5.2.1 5.2.2 5.3 5.3.1 5.3.2 5.4 5.4.1 5.4.2	Microsoft Development Environments Microsoft Visual Basic 6 Microsoft Visual C++ MFC Applications Non MFC Application Microsoft .NET Use TBarCode OCX as Control Use TBarCode OCX as Library Microsoft Visual FoxPro Inserting TBarCode into a FoxPro-Project Reports & Labels	7 7 7 7 9 10 10 11 12 12
6	6.1	Microsoft ERP Systems Microsoft Navision® / Dynamics® NAV	13
7	7.1 7.2 7.2.1 7.2.2 7.2.3 7.2.4 7.2.5 7.2.6	Borland Delphi / Borland C++ Builder Using TBarCode OCX in Borland Delphi 6/7 Using TBarCode OCX in Borland Delphi 2005 (Delphi for Win32) Create and Save a Package for TBarCode OCX Set the Project Options Import TBarCode Component Add Components to the Package Create and Install Package Create a new VCL Forms Application	14 14 14 14 15 16 16
8	8.1 8.2 8.3 8.4 8.4.1 8.4.2	Sybase PowerBuilder TBarCode OCX in PowerBuilder DataWindow Insert TBarCode OCX Script the Control within PowerBuilder 10 Generate Barcode Images for the DataWindow Generate the Barcode Images (from the Dialog Window) Insert the Barcodes into your DataWindow	17 17 18 18 18 18
9	9.1 9.2	Oracle Forms / Oracle Reports Barcodes in Forms Barcodes in Reports	20 20 20
10	0 10.1 10.2	Redistributing TBarCode OCX Dependencies Redistribution	21 21 21
1	1	Contact and Support Information	22
A	Ppendix A A.1 A.2 A.3 A.3.1 A.4 A.5 A.6 A.7	How to set a specific Module Width (15 mils) in Web Applications? License TBarCode in my Application Clipped Barcode Image (SaveImage) Solution Unreadable Barcodes with PrintForm (VB) Save MaxiCode with a higher Resolution SaveImage does not work Barcodes created with SaveImage are unreadable Additional FAQs on our Web Page	23 23 23 23 23 24 24 24 24



2 Disclaimer

The actual version of this product (document) is available as is. TEC-IT declines all warranties that go beyond applicable rights. The licensee (or reader) bears all risks that might take place during the use of the system (the documentation). TEC-IT and its contractual partner cannot be penalized for direct and indirect damages or losses (this includes non-restrictive, damages through loss of revenues, constriction in the exercise of business, loss of business information or any kind of commercial loss), which is caused by use or inability to use the product (documentation), although the possibility of such damage was pointed out by TEC-IT.



We reserve all rights to this document and the information contained therein. Reproduction, use or disclosure to third parties without express authority is strictly forbidden.



Für dieses Dokument und den darin dargestellten Gegenstand behalten wir uns alle Rechte vor. Vervielfältigung, Bekanntgabe an Dritte oder Verwendung außerhalb des vereinbarten Zweckes sind nicht gestattet.

© 1998-2018 TEC-IT Datenverarbeitung GmbH Hans-Wagner-Str. 6

A-4400 Austria t.: +43 (0)7252 72720 f.: +43 (0)7252 72720 77 http://www.tec-it.com



3 Introduction

3.1 What is TBarCode SDK?

TBarCode SDK is a set of professional tools for the generation of barcodes. More than 100 different symbologies (linear barcodes, 2D barcodes and stacked barcode variants) can be printed or exported as graphics files. All industry formats are supported. The barcodes can be generated in the highest possible resolution and quality.

TBarCode SDK is available in several versions for different operating systems, applications and programming environments. The following versions are included in this setup:

TBarCode OCX	A Microsoft® ActiveX® compliant barcode control. It can be used with Microsoft® Office applications as well as by software developers.
TBarCode .NET	A .NET barcode library for software developers. It includes barcode controls for Windows Forms and ASP.NET 2.0.
TBarCode Library	A DLL for Windows platforms for software developers. (A DLL for Windows CE/Windows Mobile is available on request. Please contact us with your platform details.)

3.2 Important Security Notice

The ActiveX control TBarCode OCX is now a site-locked ActiveX control. This security enhancement was implemented in response to a reported possible security leak in conjunction with Internet Explorer and an installed TBarCode OCX. It is strongly recommended to update all TBarCode installations as soon as possible.

As part of the fix the TBarCode OCX methods SaveImage() and SaveImageEx() now are

restricted to specific internet zones. This happens only if **TBarCode OCX** runs in Microsoft Internet Explorer as part of a web-page. The allowed zones can be specified in the registry. In addition these functions append the correct image filename extension if the file extension specified by the user does not match the supported image formats.

Please refer to the TBarCode OCX Developer Reference for details.

3.3 What is TBarCode OCX?

TBarCode OCX is a Microsoft[®] ActiveX[®] compliant barcode control. Such an ActiveX control is sometimes called OLE control or OCX control. In German it is named "Steuerelement".

You can use TBarCode OCX in:

- Microsoft® Office: barcodes are embedded into documents, forms or databases easily.
- Development environments: integrate barcodes into your own application(s).
- Report-Generators and Reporting Engines: Enhance the output with barcode functionality.
- Web Applications: Use barcode technique as part of browser-based applications.
- Most programming and script languages.

3.4 Scope of this Document

This document shows developers how to use **TBarCode OCX** with various IDEs (integrated development environments) like Visual Studio.



3.5 **Restrictions of the Demo Version**

In the demo version the barcodes will be drawn with a demo-hint. That means that the word "Demo" or the phrase "www.tec-it.com" is drawn partially over the barcode. The demo-hint does not influence the readability of the barcode in a negative way.

- In special cases (e.g. very small or high-resolution barcodes) you may want to test the product without restrictions. To obtain a temporary license key contact sales@tec-it.com.
- For enabling the full-featured version (without the demo hints) you can obtain a license key from TEC-IT (http://www.tec-it.com/order/).
- For more information on licensing **TBarCode**, please refer to section A.2.



4 Installation

4.1 Requirements

The following operating systems are supported:

- Microsoft Windows 10
- Microsoft Windows 8
- Microsoft Windows 7
- Microsoft Windows Server 2012 and 2012 R2
- Microsoft Windows Server 2008 and 2008 R2

4.2 Download and Setup

Download **TBarCode SDK** from http://www.tec-it.com/Download ▶ TBarCode SDK and execute the setup application. Depending on your selection one or more of the following components are installed – along with documentations and sample applications:

TBarCode OCX

A barcode ActiveX control for Microsoft Office users and for software developers. User manual and API reference are included in the setup.

TBarCode Library

A DLL for software developers. Developer manual and API reference are included in the setup.

TBarCode .NET

For software developers. Developer manual and API reference are included in the setup.

- Administrative rights are required to install.
- ▶ TBarCode OCX is an ActiveX control. ActiveX controls must be registered within the Microsoft Windows operating system before they can be used. This registration is executed automatically by the setup application. On demand you can register the OCX file manually with the command line tool "regsvr32.exe".



5 **Microsoft Development Environments**

5.1 Microsoft Visual Basic 6

In order to insert TBarCode OCX in Visual Basic 6, please execute the following steps:

- Open or create your VB Project.
- Right-click the Toolbox and select *Components* from the menu.
- Select TBarCode OCX 11 Type Library from the list (Insertable Objects) and confirm with
- Now you can use **TBarCode** as VB Control (it is shown in the Toolbox).
- Set the characteristics of the barcode in the VB properties window ("Properties TBarCode101").
- In case you prefer the TBarCode "Property Pages" (instead of the VB properties window), right-click the object and select *Properties* from the pop-up menu.

5.2 Microsoft Visual C++

5.2.1 **MFC Applications**

In order to use TBarCode OCX in MFC, please follow these steps:

- Open or create your MFC based application.
- If you create a new project, make sure, that ActiveX Controls 10 is checked (default) on page "Advanced Features" of the "MFC Application Wizard".




Figure 1: Use TBarCode in MSVC++ (MFC Application) (1)

- Open the Toolbox = .
- Right-click General and select Choose Items...




Figure 2: Use TBarCode in MSVC++ 6.0 (MFC Application) (2)

- In the Choose Toolbox Items go to page COM Components.
- Select TBarCode11 from the list, make sure they are checked, and click OK.
- A wrapper class for TBarCode OCX is generated automatically (❷). Click OK to confirm.




Figure 3: Use TBarCode in MSVC++ 6.0 (MFC Application) (3)

The control is thereafter selectable in the control toolbox in the dialog editor (8).

Work with the assistance of the Class Wizard if necessary.




Figure 4: Using TBarCode in MSVC++ 6.0 (MFC Application) (4)

5.2.2 Non MFC Application

For non MFC applications we recommend to use TBarCode DLL.



5.3 Microsoft .NET

5.3.1 Use TBarCode OCX as Control

In order to use **TBarCode OCX** in Visual Studio .NET (e.g. in a "Windows Forms Application" or in an "ASP .NET Web Forms Application"), please follow these steps:

- Open or create a project.
- Right-click inside the Toolbox and select *Choose Items....* A dialog appears.
- In the Choose Toolbox Items go to page COM Components 2.
- Select *TBarCode11* **⑤** (check the checkbox).
- Confirm with OK (4).
- Now TBarCode OCX is added to the Toolbox (6).
- Drag the control from the Toolbox (6) to your form (6).




Figure 5: Using TBarCode in Visual Studio .Net 2005 (as Control)

Microsoft Visual Studio automatically generates a wrapper class for an existing ActiveX control. You can use it like any other control in .NET.



5.3.2 Use TBarCode OCX as Library

In order to use **TBarCode** per code only (without embedding it as ActiveX control in a form), please follow these steps:

- Open or create a project.
- From the menu select Project ➤ Add Reference...
- In the Reference Manager go to page COM ①.
- Select *TBarCode OCX* from the list and check it ②.
- Confirm with OK(⑤).
- Now *TBarCode11Lib* is added to the References of your Project (and can be found in the "Solution Explorer" Window ④).
- The TBarCode class can now be used in your code.




Figure 6: Using TBarCode in Visual Studio .Net 2003 (as Library)

Sample usage of the **TBarCode** class in C#:

```
TBarCode11Lib.TBarCode11Class obj = new TBarCode11Lib.TBarCode11Class();
obj.BarCode = TBarCode11Lib.tag_BarCType.eBC_2OF5IL;
obj.Text = "12345";
```



5.4 Microsoft Visual FoxPro

5.4.1 Inserting TBarCode into a FoxPro-Project

In order to insert TBarCode in Visual FoxPro, please execute the following steps:

- Open or create a FoxPro Project.
- Open or create a Form.
- Select OLE Container from the Standard Toolbox.
- After drawing the outlet of the OLE container, an "Insert object" dialog is opened. Select TBarCode (Insert Control) and confirm with OK.
- The characteristics can be modified in the properties window.
- If you prefer the TBarCode OCX property pages, right-click the control and choose Properties from the pop-up menu.
- Within the Project Manager you can add the newly created form to the project.

5.4.2 Reports & Labels

If you want to print barcodes in reports or labels, you need a table with a specific column, in which **TBarCode** must be stored as OLE Control (data type "general"). This data field must be initialized with the data structure of a barcode object before use. For this purpose you need an instance of a **TBarCode** object as template (e.g. on a form, it may be invisible).

Example code for the initialization of the data fields of a barcode object:

```
FOR n = 1 TO 10
INSERT INTO Table1 FROM MEMVAR
APPEND GENERAL Table1.BC CLASS TBarCode11.TBarCode11
WITH THISFORM.[Name of the TBarCode object instance]
.CONTROLSOURCE = "Table1.BC"
.REFRESH
.barcode = 20 && Barcode-Type = Code128
.TEXT = "000070000041"
.printdatatext = .T.
.BACKCOLOR = 16777215
.FORECOLOR = 0 && 16711680 -> (blue)
.REFRESH
ENDWITH
```

After this code has been executed, an OLE Picture/ActiveX Bound Control can be inserted into a Report or Label Form. In this sample, you have to specify "Table1.BC" as data source (field). Please take a look at our FoxPro-Sample, which can be downloaded from http://www.tec-it.com/Download ► TBarCode.



Microsoft ERP Systems 6

6.1 Microsoft Navision® / Dynamics® NAV

Under Navision TBarCode OCX cannot be inserted into a report directly. So you have to use the following workaround:

- Create or open a report and insert a Picture Box.
- Create a barcode image (per code) using the TBarCode OCX Control.
- Load the image to the Picture Box.

Sample code for creating a barcode image:

```
// this is com object instantiation
COM objBC;
objBC = new COM("TBarCode11.TBarCode11.1"); // create class TBarCode11
objBC.Text = "121212"
                                            // set barcode data
                                            // 20 ... use Code-128
objBC.Barcode = 20;
objBC.SaveImage(DateiNameBmp, 4, pxWidth, pxHeight, nXRes, nYRes); // 4 = eIMBmp (Bitmap)
```

For more detailed information, please take a look at our Navision Tutorial, which can be downloaded under http://www.tec-it.com/Download ► TBarCode or contact our technical support.



7 Borland Delphi / Borland C++ Builder

7.1 Using TBarCode OCX in Borland Delphi 6/7


To insert **TBarCode OCX** in Delphi or Borland C++ Builder, please follow the steps described below:

- Select Components ► Import ActiveX Control from the menu.
- Select TBarCode OCX Type Library from the list.
- Click the *Install* button and confirm the following pop-up windows with *OK*. The TBarCode control can now be used like a standard component (Toolbar ActiveX).

7.2 Using TBarCode OCX in Borland Delphi 2005 (Delphi for Win32)

To insert TBarCode OCX in Delphi 2005, please follow these steps:

7.2.1 Create and Save a Package for TBarCode OCX




Create Package:

 Choose File ► New ► Package – Delphi for Win32 from the menu.

Save Package:

- Choose File ➤ Save All from the menu.
- The Save Package As dialog will open.
- Choose the directory for saving the package.
 Hint: It is recommended to create a separate directory for the package.
- Then assign a name to package-project (e.g. TBarCode11).
- Confirm with OK.

7.2.2 Set the Project Options



- Choose Project ➤ Options... from the menu.
- The Project Options Dialog will open.

Description:


 Select <u>Description</u> in the tree on the left. The description text can be edited on the right.

Output Directory:


- Select <u>Directories/Conditionals</u> in the tree on the left.
- Under Output directory, choose the directory where you have saved your project.
- Confirm with OK.




7.2.3 Import TBarCode Component




- Choose Component ► Import Component... from menu.
- The Import Component wizard will open.
- In the Wizard, choose *Import ActiveX Control*.
- Then click Next.



- Choose TBarCode OCX from the list.
- Click Next.




- On this page leave all default values.
- Click Next.



- This is the last page of the wizard.
- Choose Create Unit.
- Then click Finish.
- You will find TBARCODE11Lib_TLB in the main window of Delphi.
- Save this Unit in the same directory where the package-project is located.




7.2.4 Add Components to the Package



- Choose Project ► Add to Project... from the menu.
- The Add dialog will open.
- Select the "Add Unit" tab.
- Click Browse to look for TBARCODE11Lib TLB.PAS.
- Click OK to add TBarCode.

7.2.5 Create and Install Package



Create the package:

Select Project ➤ Build <ProjectName> from the menu.

Install the created Package:

- Select Component ► Install Packages from the menu.
- Click Add.
- Choose the created package (here TBarCode6.BPL) and click Open.
- The package (TBarCode11 OCX) is now listed in Design Packages.
- Click OK to finish the installation.

7.2.6 Create a new VCL Forms Application



- Choose File ► New ► VCL Forms Application... from the menu.
- In the Tool Palette you can find the new category ActiveX.
- TBarCode OCX was added in this category and is now ready to use.



8 Sybase PowerBuilder

8.1 TBarCode OCX in PowerBuilder DataWindow

In PowerBuilder¹ the use of ActiveX controls (like **TBarCode OCX**) is not possible within so-called DataWindows if the control is bound to the band layer. This limitation is not caused by **TBarCode OCX**.

To get dynamic "data driven" barcodes you have to use the following workaround.

Instead of placing the **TBarCode OCX** control inside the DataWindow, you have to insert it into the dialog Window. Thus it can be programmed for our workaround as follows.

By using this control you can create a bitmap file for each barcode, save it to disk and load it to a picture data field in the DataWindow. That has to be done for each data row/record set.

This workaround is described in detail in the following sections.

8.2 Insert TBarCode OCX

To insert TBarCode OCX into a PowerBuilder dialog window, please execute the following steps:

- Select Controls ➤ OLE from the menu.
- Select the page *Insert Control* from the tab (PowerBuilder 10).
- Select TBarCode from the list.
- If desired, change the properties in the context menu (OCX Properties).
- ▶ In PowerBuilder Version 7, 8, 9 and 10 always insert TBarCode with *Insert Control* because Create New does not work with scripting.




Figure 7: Inserting TBarCode in PowerBuilder

¹ PowerBuilder version 7-10





8.3 Script the Control within PowerBuilder 10

In order to access the properties and methods of the ActiveX control you have to use the following syntax:

```
ControlName.Object.Property
```

Example:

The barcode type (the symbology) is set by assigning a number to the barcode property. Please refer to the "Barcode Reference" (http://www.tec-it.com ➤ Support ➤ Knowledge Base) to learn more.

8.4 Generate Barcode Images for the DataWindow

8.4.1 Generate the Barcode Images (from the Dialog Window)

You need a **TBarCode OCX** object in your dialog window which can be programmed. In our sample it is called "w_barcode_printing".

Open your source code. In the section where you prepare the data for the output you have to do something like the following to save the barcode images:

```
//Image path and filename
ls_image = "C:\_APPS\FeeSystem\bc1.jpg"

//Saves the barcode as a JPEG
w_barcode_printing.ole_barcode.SaveImageEx (0, ls_image, 4, 100, 300, 80, 127, 127)
```

Currently PowerBuilder only supports BMP, JPEG, and GIF. You cannot use the EMF file type.

With the SetItem() function you can finally assign the name of the generated barcode bitmap file to the column used in the DataWindow (bc_pic).

Using this approach will allow you to simulate the data binding inside the DataWindows.

8.4.2 Insert the Barcodes into your DataWindow

Inside your DataWindow you have to create a column with a *STRING* data type. Here we use the name *bc_pic*. This column will contain the path and the name for each barcode bitmap file for each record. Then insert a column control for the created data field.

In the "General" properties of the column control check the *DISPLAY AS PICTURE* box as shown below. This will make the control show the picture and not the filename inside the control frame.

For example: If the column contains the value "c:\picture.jpg", the control will display the picture and not the text "c:\picture.jpg".



Figure 8: PowerBuilder DataWindow "Display As Picture"

Instead of using a column control you may also insert a computed field control and use the <code>BITMAP()</code> function:




Figure 9: PowerBuilder DataWindow Bitmap function



9 Oracle Forms / Oracle Reports

9.1 Barcodes in Forms

In order to use TBarCode OCX in an Oracle Form please execute the following steps:

- Create a new form.
- In the layout editor:
 - a) Draw an ActiveX control.
 - b) Right-click with the mouse and select *Insert Object*.
 - c) Select TBarCode.
- Select Menu ➤ Program OLE Importer from the menu and import the control.

Optional:

- Create a button and add a when-button-pressed trigger on the canvas (where you can call the ActiveX control).
- Close the layout editor (This step is VERY IMPORTANT!).
- Run the form.
- Press the button to run the ActiveX control.

9.2 Barcodes in Reports

Oracle Reports do not support ActiveX controls.

Workaround: The user can call an executable from within a report. For instance you can generate barcode bitmaps with the TEC-IT product **Barcode Studio** which can be executed in command line mode (without a visible window). **Barcode Studio** creates and saves a bitmap whenever it is called. Afterwards the generated bitmap can be loaded into an image inside the report.

Another possibility is to use the **TFORMer** product family (advanced label and form reporting tool).

Use **TFORMer Designer** to design your barcode label or report. Thereafter use **TFORMer Runtime** (or the command line tool *TFPrint.exe*) to generate and print the complete report. **TFORMer** supports direct printer output, PostScript, PDF and HTML output directly (without any additional software).



10 Redistributing TBarCode OCX

This chapter explains what is important when redistributing a custom application that uses the TBarCode OCX control.

Please note that in most cases you need a developer license for re-distribution of TBarCode OCX (except for in-house applications which are bound to one or more sites).

10.1 Dependencies

An application that uses **TBarCode OCX** requires the following files:

- TBarCode11.ocx
 - This is the native Win32 ActiveX component. This file is mandatory.
- TBarCode11_x64.ocx
 - This is the native Win64 (x64) ActiveX component. This file is mandatory.
- TBarCode11.dll
 - This is a native Win32 library that performs barcode generation. This file is mandatory.
- TBarCode11 x64.dll
 - This is a native Win64 (x64) library that performs barcode generation. This file is mandatory for 64-Bit applications.
- zlib1.dll
 - This is a 3rd-party library that performs data compression. This file is optional. It is only required, when data compression in barcodes is enabled.

These files are located in the folder C:\Program Files\Common Files\TEC-IT\TBarCode\11.0 (or in the folder you have chosen during setup).

TBarCode OCX requires also the **Microsoft VC14 CRT and ATL DLLs**. See next section how to distribute them with your application.

10.2 Redistribution

When redistributing a custom application the files described above need to be redistributed together with the application. The DLLs should be located in the same folder as the executable.

Other files than those listed above must not be redistributed.

You may have to redistribute the **Visual C++ 2015 Update 3 runtime components** (MS CRT 14.0 and ATL 14.0 DLLs) with your application and ensure they are installed on the target computer.

- You can install these components with the Microsoft Visual C++ 2015 Redistributable Update 3 RC Packages available at
 - https://www.microsoft.com/en-US/download/details.aspx?id=52685
 The package installs all required runtime DLLs.

Please contact TEC-IT Support if you need help.



11 Contact and Support Information

TEC-IT Datenverarbeitung GmbH

Address: Hans-Wagnerstr. 6

> AT-4400 Steyr Austria/Europe

Phone: +43 / (0)7252 / 72 72 0 Fax: +43 / (0)7252 / 72 72 0 - 77 Email: mailto:support@tec-it.com Web: http://www.tec-it.com

FAQ: http://www.tec-it.com/support/faq/tbarcode/Default.aspx

AIX is a registered trademark of IBM Corporation.

HTML, DHTML, XML, XHTML are trademarks or registered trademarks of W3C, World Wide Web Consortium, Laboratory for Computer Science NE43-358, Massachusetts Institute of Technology, 545 Technology Square, Cambridge, MA 02139. JAVA® is a registered trademark of Sun Microsystems, Inc., 901 San Antonio Road, Palo Alto, CA 94303 USA.

JAVASCRIPT® is a registered trademark of Sun Microsystems, Inc., used under license for technology invented and implemented by Netscape.

Microsoft®, Windows®, Microsoft Word®, Microsoft Excel® are registered trademarks of Microsoft Corporation.

Navision is a registered trademark of Microsoft Business Solutions ApS in the United States and/or other countries.

Oracle® is a registered trademark of Oracle Corporation.

PCL® is a registered trademark of the Hewlett-Packard Company.

PostScript is a registered trademark of Adobe Systems Inc.

SAP, SAP Logo, R/2, R/3, ABAP, and SAPscript are trademarks or registered trademarks of SAP AG in Germany (and in several other countries).

All other products mentioned are trademarks or registered trademarks of their respective companies. If any trademark on our web site or in this document is not marked as trademark (or registered trademark), we ask you to send us a short message (mailto:office@tec-it.com).





Appendix A: FAQ

If you have questions not covered in these FAQ, you can also check our website http://www.tec-it.com/FAQ or contact our support team: mailto:barcode@tec-it.com.

A.1 How to set a specific Module Width (15 mils) in Web Applications?

Please refer to the "Barcode Reference" (http://www.tec-it.com ➤ Support ➤ Knowledge Base) for more information.

A.2 License TBarCode in my Application

Assume you got the following license key:

```
Product ID: 2022 (1D Barcodes in V11)
Licensee: Barcode Inc.
License Kind: 2 (Site)
Licenses: 1
License-Key: 12A3B5C6
```

Now implement a call to the method *LicenseMe* before you draw a barcode (we suggest at startup of your application).

Example in Visual Basic (enumerators are used):

```
TBarCode111.LicenseMe "Barcode Inc.", eLicKindSite, 1, "12A3B5C6", eLicProd1D
```

The Product ID depends on the version of **TBarCode** (see your license data).

A.3 Clipped Barcode Image (SaveImage)

If the *ModuleWidth* property is set to a specific value the barcode may be clipped because it does not fit into the image dimensions specified in *Savelmage*.

A.3.1 Solution

If you need a specific module width for your application (e.g. 3 pixels), use the number of barcode modules (*CountModules* property) and multiply this value with 3 (to get 1 module = 3 Pixels wide). Use this value as horizontal size of the image in *Savelmage*. Using this method, the image size will adapt automatically depending on number of horizontal barcode modules.

For 2D symbologies use *Get2DXCols* and *Get2DXRows* for finding the best horizontal and vertical size values.

A.4 Unreadable Barcodes with PrintForm (VB)

In Visual Basic the form objects (like **TBarCode**) are rendered with (low) screen resolution and not with the (usually high) printer resolution. Therefore the printed barcode may become unreadable.

To work around this problem adjust the module width of the barcode to the resolution of the screen:

- ► This can be achieved by using the *CountModules* property.
- Or use the TBarCode property OptResolution = true



For details please see our Visual Basic Sample Code, which is installed together with the product setup. The samples contain also the PrintForm workaround to get a readable barcode.

A.5 Save MaxiCode with a higher Resolution

You have to set the *ModuleWidth* property to a higher value (as it is by default) – and increase the values for XSize / YSize when saving the barcode.

Example:

```
FlName = "Maxicode.bmp"

TBarCode111.Text = "BarCodeText"

TBarCode111.BarCode = eBC_MAXICODE

'Use nRatio to enlarge or reduce image size

nRatio = 2

TBarCode111.ModuleWidth = 1500 * nRatio

DoEvents

YSize = 208 * nRatio

XSize = 215 * nRatio

TBarCode111.SaveImage "C:\Users\User\Documents\" & FlName, TBarCode11Lib.eIMBmp, XSize,

YSize, 72, 72

'Hint : When printing we recommend using the standardized size of MaxiCode

'Height: ~24.4 mms;

'Width : ~25,2 mms
```

A.6 Savelmage does not work

Please check if you have write permissions to the directory you want to write to (e.g. important in web applications).

Please check if the internet zone was unlocked when using **TBarCode** OCX as part of a web page. See the *TBarCode OCX Developer Reference* for details.

A.7 Barcodes created with Savelmage are unreadable

Please refer to the "Barcode Reference" (http://www.tec-it.com ► Support ► Knowledge Base) for more information.

A.8 Additional FAQs on our Web Page

Please check out the FAQ on our web site http://www.tec-it.com/support/faq/tbarcode/Default.aspx.