


concordance=TRUE

	Environmental Analysis Teaching and Research Laboratory	Date: 7/12/2015	SOP No. 32 v0.1
	Standard Operating Procedure	Title: Soil Loss on Ignition	
	Approved By: Los Huertos	Revised: July 3, 2025	

1. Scope and Application

1.1 Loss on Ignition (LOI) is used to determine organic matter content (OM%) in soil samples. This is important for indirectly estimating soil organic carbon (SOC) in agricultural topsoil.

1.2 The applications implement SFU Soil Science Lab method (Robertson 2011) and Salehi et. al (2011).

2. Summary of Method

2.1 This method will cover how to conduct a LOI procedure in the Pomona College Geology Department Lab. Ignition of the soil samples in a muffled furnace burns off any organic matter, leaving only the mineral content. The weight difference of the samples before and after ignition represents the OM%. This method uses a temperature of 360°C for 2 hours.

Contents

1	Scope and Application	1
2	Summary of Method	1
3	Biases and Interferences	3
4	Health and Safety	3
5	Personnel & Training Responsibilities	3
6	Required Materials and Apparati	4
7	Reagents and Standards	4
8	Estimated Time	4
9	Sample Collection, Preservation, and Storage	4

10 Procedure	4
Preperation	4
Ignition	4
Calculating Soil Sample Mass	5
11 Recording the Results	6
12 Data Analysis and Calculations	6
Calculating effective diameter, D_e	7
Calculating the Percent Finer, PF	7
Graphing and Interpreting the Results	7
13 QC/QA Criteria	7
14 References	7
15 Appendix A. Data Sheet	7
16 Appendix B: R code to calculate parameters for the SOP	8

3. Biases and Interferences

3.1 The following are parameters that might influence the results of the LOI test and thus, we review methods that would best fit the type of soils from our samples.

Clay content Soil texture has many influences, two of which being climate and parent material

Ignition temperature If the temperature is not hot enough, there may be OM remaining in the samples after ignition.

Ignition duration If the samples are not burned for long enough, there may be OM remaining in the samples after ignition.

4. Health and Safety

4.1 The muffled furnace burns up to 3000°C, posing a significant threat to 4th degree burns if precautions aren't taken.

Safety and Personnel Protective Equipment

4.2 Care should be taken to prevent burns. Remove crucibles from the furnace with tongs and heat-proof gloves. Wait at least 1 hour for them to cool down before handling with bare hands. In case of contact, run skin under cold water for 15 minutes and follow lab procedures for emergency.

5. Personnel & Training Responsibilities

5.1 Researchers training is required before the procedures in this method can be used.

5.2 Researchers using this SOP should be trained for the following SOPs:

- SOP01 Laboratory Safety
- SOP07 Using Balances
- SOP15 Using Drying Ovens

6. Required Materials and Apparati

1. Porcelain crucibles
2. Soil samples
3. Muffled furnace
4. Drying oven
5. Tongs
6. Heat-proof gloves
7. Jack stand
8. Metal tin
9. Scoopula
10. Combustion residue mapping sheet

7. Reagents and Standards

8. Estimated Time

8.1 This procedure requires several days to complete.

9. Sample Collection, Preservation, and Storage

10. Procedure

Preperation

10.1 Prepare the soil samples in advance in the EA lab. Samples may be sieved with a 2mm sieve. The following steps use a drying oven to remove moisture content from the soil and the crucibles that may affect the true dry weights. You can collect soil % moisture data while simultaneously prepping for LOI.

1. Weigh and record the weight of a labeled metal tin. Add about 3 scoops fo soil using the scoopula into the tin. Record the soil ID, tin , tin weight, and soil 'wet' mass.
2. Oven-dry tins at 105°C for 24 hours.
3. Once done, open the oven door for about 15 min to cool down. Take samples out of the oven once cool to touch. Weigh and record weigh
4. Oven-dry crucibles in the same manner.

Ignition

10.2 Once ready for ignition, head to the Geo Lab. If the oven is not on already, we can begin heating the oven while preparing the crucibles. Ask the lab technician for help

if needed. The Geology Dept. has multiple muffled furnaces. This SOP instructs how to use the Nabertherm furnace

10.3 We will load the furnace while hot and keep it on continuously and overnight until finished with all samples. Frequent reheating can harm the heating coils.

10.4 Use the dial knob to set the furnace to the correct program preset called "LOI" and assure it is set to the correct temperature of 360°C. Press the start button. The LCD screen will tell you the current temperature inside the furnace.

10.5 Then, for each sample...

1. Record the weight of the crucible on a scale capable of precision to 0.0001. It may have an assigned , if not write one with Sharpie on the side of the crucible.
2. Add oven-dried sample into the crucible.
3. Weigh and record this as the pre-ignition weight.

10.6 As you prepare the crucibles, use the Combustion Residue Mapping Sheet to map to lay out where you'll put each crucible in the furnace. 8 crucibles can fit in the furnace.

10.7 This is important to prevent mixing up samples. Permanent marker will leave a light stain, but shouldn't be relied on. Use the hole on the plate to help you determine direction.

10.8 Arrange the crucibles in order on the furnace plate atop the jack stand. The jack stand should be level with the inside of the furnace for easy loading.

10.9 Once the furnace is ready, use the tongs and heat-proof gloves push the furnace plate in like so.

10.10 Set a timer for 2 hours.

10.11 Find something to do in the meantime like prepping the next batch of crucibles.

Calculating Soil Sample Mass

10.12 We then calculate the "Total Sample Represented" in the hydrometer test as the mass of soil in hydrometer test as the oven dry mass used by the percent passed through 2 mm sieve and multiply by 100.

$$W = \text{ovendrymass} * \text{percentpassing2mmsieve} * 100 \quad (1)$$

$$WB = \frac{M_{air} * 10000}{Per_{No.10} * (100 + Moisture_H)} \quad (2)$$

$$DW_{air} = 50/(1 + DW_c) \quad (3)$$

and for sandy soils,

$$DW_{air} = 100/(1 + DW_c) \quad (4)$$

Determining Proportion of Soil Retained No. 200 Sieve

10.13 Particles retained on the No. 200 sieve are larger are often categorized as sand. As the hydrometer does very little to distinguish between size fractionation of sand – very fine, fine, medium, coarse, and very coarse sand.

10.14 But collecting the particles on the No. 200 sieve, we can use sieves to better understand the soil characteristics. We can do this by analyzing the mass of the soils retained on the No. 200 sieve, which has a mesh size of XX 0.125 mm.

1. Pour the contents of the cylinder through a No. 200 sieve;
2. Using the sink with a sediment trap, wash the soil in the sieve until the water leaving the sieve is clear.
3. Select a soil tin, and record the tin # (Box XX) and tin mass (Box XX).
4. Carefully wash the soil from the tin into the soil, without damaging the sieve screen. The screens are quite delicate, so using a squeeze bottle is probably best. Using a brush or metal device will force particles into the screen, which can get stuck, distort and stretch the mesh openings or otherwise damage them.
5. Weigh the dry soil with the soil tin and record the results in Box Xx.

11. Recording the Results

Record the results in Appendix A, Then enter the data into the data entry form (<http://test>). Other columns calculations will be produced with the R code from Appendix B.

Do not put commas in text fields – if you do the download... it will create extra columns and the data will be misaligned.

12. Data Analysis and Calculations

Once the data has been entered in the online form, you can extract the data as a csv file. This csv file can then be called by R to calculate the data automatically, using the following functions.

Importing Data

Import and check data integrity

```
#hydrometer = import()
#head(hydrometer)
#str(hydrometer)
```

What should you be looking for? We want to make sure the data shown are the same as expected. There are several ways to look at the data to determine this. I have shown two ways. 1) Looking at the header (first six observations), then we evaluate the structure of the dataframe.

Calculating effective diameter, D_e

Calculating the Percent Finer, PF

Graphing and Interpreting the Results

13. QC/QA Criteria

14. References

14.1 D422...

14.2 Wilde, S.A., R.B. Corey, J.G. Iyer, and G.K. Voigt. 1979. Soil and Plant Analysis for Tree Culture. Oxford and IBH Publishing Co., New Delhi. Pp. 12-13.

14.3 Anderson, J.M., and J.S. Ingram, eds. 1993. Tropical Soil Biology and Fertility: A Handbook of Methods. 2nd ed. CAB International, Wallingford, UK. P. 93-94.

15. Appendix A. Data Sheet

16. Appendix B: R code to calculate parameters for the SOP