Methods for Determing the Diurnal Distribution of the Santa Ana Sucker Through Videography

October 2, 2016

1 Materials and Equipment

- 2 Waterproof GoPro Hero 4 Silver cameras with mounts
- 4 64GB microSD SanDisk memory cards
- 4 Waterproof Re-Fuel 6-Hour ActionPack Battery for GoPro HERO by DigiPower
- 2 HOBO Tidbit water temperature data loggers
- \bullet 2 Grey Cinder block cubes open on two parallel sides, $\,$ 8in x 8in x 8in, Home Depot
- 2 Grey Cinder block backs, 8in x 8in
- 1 bottle of Original Sticks to Everything Gorilla Glue

2 Procedures

Preparing the Equipment First, we acquired all the necessary equipment, keeping in mind the length of time we wanted to keep our cameras underwater. We chose the GoPro Hero 4 Silver because of its battery life and recording time. To set up the cameras, we removed them from the packaging, inserted a microSD card into each, and charged them fully by connecting the included USB cables to a computer. The cameras needed to be fully charged before we were able to adjust the settings. Once the cameras were sufficiently charged, we set the filming settings to record in 720p x 30fps. We set the cameras aside and left them charging.

Next, we charged all four of the waterproof Re-Fuel battery packs. As these were charging, we put together our cinder block mounting structures. We took our cinder block cubes and set them up on a clean, stable table. We connected the flat adhesive mounts that were included with the GoPros and connected a GoPro camera to each. Since the cinder blocks were open on two parallel sides,

we were able to see right through the cinder block cube to the other side. One of us stood on one side with the GoPro and mount, and the other stood on the other side of the opening. One of us turned the GoPro on and put the camera with the mount inside the cinder block cube, using the view on the screen to find the best position for the mount inside of the cube, taking care to ensure we could clearly see the other person on the other side. We found an ideal place where the view was mostly unobstructed by the sides of the cube but the cameras were still far enough inside the cube that they wouldnâ $\check{A}\check{Z}t$ be too easily spotted by passersby. This spot was 5 cm from the edge of the cube. We traced the front and the back of the mount so we could glue it in the correct place. We repeated this procedure for the second cube and mount, and standardized the construction by placing the mount in the second cube 5 cm away from the edge of the cube.

In order to securely glue the mount in place, we used Gorilla glue. To activate the Gorilla glue, we first had to moisten one of the surfaces with water. We moistened the mounts on the adhesive side. We did not remove the adhesive backing so we could reutilize the mounts in the future. Once the mount was damp, we put Gorilla glue on the cinder block inside the lines we had drawn around the mount. We then placed the mount on the Gorilla glue, taking care to align the edges of the mount with the lines we had drawn. Next, as per the Gorilla glue instructions, we found a heavy object that could provide significant pressure on the mount and that would fit inside the cube. We left this for three hours to harden.

Upon returning to the lab, we removed the heavy objects from the cube and checked the seal on the mount and cinder block to ensure the bond had successfully cemented. After this, we went to work on attaching the cinder block backs to close up one of the open sides on the cubes. We repeated much of the same process we used when attaching the mounts to the cubes, and followed the Gorilla Glue instructions carefully. First, one of us moistened the cinder block back while the other applied Gorilla Glue to the edge of the cube. Then, we carefully aligned the corners of the back with the cube. We repeated this with the second cube. Seeing that the cinderblock back was heavy enough on itâÁŹs own, we did not place a heavy object on top of this structure and instead simply left it to dry and harden overnight. Finally, we checked on the cameras and battery packs again to ensure they had charged. We left them plugged in overnight. We also packed away the Gorilla Glue, the multiple SD cards, paper towels, and extra mounts in a field kit so we could deal with any emergencies in the field.

Field Work We started our first recording session at 10 am. We drove to the downstream site and found a spot under brush cover in a pool next to a fast moving section of the stream. We first placed the cinderblock squarely on the riverbed and positioned it facing the fast moving water. We then turned the camera on, pressed record, and placed it on the mount in the cinderblock. We let it run for a few seconds, then took it out and watched the video to ensure

it was recording at a good angle. We then pressed record again and replaced it. Before leaving, we marked the area with flags so we would be able to find it again.

Next, we walked approximately 20 minutes upstream to another covered pool next to a fast moving section, and repeated the camera placement procedures. We marked with flags, and then left.

We returned at approximately 2 pm. We took out the camera at the downstream site, replaced the memory card and the battery pack, hit record, and replaced the camera exactly as it was positioned previously. We then walked upstream and did the same thing with the second camera. After returning, we cleared the memory cards and plugged in the battery packs.

Our last recording session was at 8 am the next morning. We replaced the memory cards and battery packs again and returned the cameras to their positions. One of us returned the next day to collect the cameras.