TexVar - Manual

TexVar – LaTeX math calculations

Version: 1.5.8

Sebastian Pech November 20, 2015

Contents

1	Des	Description			
2	2.1 2.2	Allation Prerequisites	2 2 2 2		
3	Getting Started - Hello World				
4	General Information on tVar Enviroment				
5	Tex'	Var - Commands	3		
	5.1	Creating Variables	3		
		5.1.1 Creating Variables in Equation	4		
		5.1.2 Auto-Formatting of variable names	5		
	5.2	Creating Functions	5		
	5.3	Indexing Matrices and Vectors	5		
	5.4	Output	7		
		5.4.1 print()	7		
		5.4.2 outRES()	8		
		5.4.3 Other Output Commands	8		
		5.4.4 LATEX Output	9		
		5.4.5 Precise Manipulation of Output	9		
		5.4.6 Grouping Math Environments	10		
	5.5	Global Parameters	11		
		5.5.1 Details on automatic removal of trailing zeros	11		
	5.6	Plotting with Gnuplot	12		
	0.0	5.6.1 Configuration	12		
		5.6.2 Creating a Plot	12		
	5.7	Mathematical Commands	14		
		5.7.1 General	14		
		5.7.2 Matrices and Vectors	15		
	5.8	The Link Function	15		
_	_				
6		mples	17		
	6.1	U-Value	17		
	6.2	Rotating a Vector	18		
	6.3	Vector Calculations - Custom Function	19		

1 Description

TexVar (short tVar) is a basic IATEX math calculations tool written in Lua. For integration into IATEX it has to be used together with LuaLaTeX. Compared to software like Mathcad TexVar is a lot more flexible. You can fill custom designed tables with results, do calculations within text documents and print beautiful LaTeX equations. The current version also supports 2D-plotting with gnuplot.

2 Installation

2.1 Prerequisites

The following software is needed in order to use TexVar:

- Lua 5.1 or higher
- LuaLaTeX (MikTex or Texlive)
- GnuPlot 5.0 (only needed for plotting)

2.2 Installation

Download TexVar from http://texvar.projectzoo.at/ and copy the folder tVar and the file texvar.sty (subfolder package) to a location that is visible to LATEX. (e.g. the folder your *.tex file is in or global LATEX-folder 1)

2.2.1 Configuration for Gnuplot

In order to use Gnuplot with TexVar you have to allow LuaLaTeX to call external commands during runtime. This works through the command-line switch --shell-escape. Your complete call for LuaLaTeX could look like this: lualatex -synctex=1 -interaction=nonstopmode --shell-escape %.tex.

3 Getting Started - Hello World

To ensure your installation is working test the following code. When using an luacode based environment like tVar it's important that the commands \begin{tVar} \end{tVar} are not indented.

```
\documentclass{article}
2
   %
3
   \usepackage{texvar}
4
  \usepackage[fleqn]{amsmath}
5 %
  \begin{document}
6
   \begin{tVar}
7
8 #Hello World! I'm using TexVar
   tVar.getVersion()
9
10 \ensuremath{\mbox{\mbox{end}{tVar}}}
  \end{document}
```

Output

Hello World! I'm using TexVar Version: 1.5.8

¹You can find information on global IATEX-folders athttps://www.math.hmc.edu/computing/support/tex/installing/

4 General Information on tVar Environment

This section gives a general insight on how commands are interpreted and how this affects the code. Generally, there are two key commands the TexVar interpreter searches for 2 :

```
1. #
```

2. :=

Every other command is directly forwarded to the Lua interpreter. This means you can write any Lua code you want inside the tVar environment.

```
1 \begin{tVar}
2 function mypow(a,b)
3 return a^b
4 end
5 for i=0,4 do
6 tex.print("Step " .. mypow(2,i) .. "\\\")
7 end
8 \end{tVar}
```

Step 1
Step 2
Step 4
Step 8
Step 16

5 TexVar - Commands

5.1 Creating Variables

TexVar knows three types of variables:

tVar is the basic type for scalar values.

tMat is used for matrices.

tVec is used for vectors.

The following code generates a variable of each type. Every assignment is made with :=.

```
1 \begin{tVar}
2 a:=13
3 e:={1,2,4}
4 A:={{1,0},{2,4},{3,9.1}}
5 \end{tVar}
```

Output

a = 13

 $^{^2\}mathrm{Details}$ on these key commands are discussed in Section 5

$$\vec{e} = \begin{pmatrix} 1 \\ 2 \\ 4 \end{pmatrix}$$

$$\mathbf{A} = \begin{pmatrix} 1 & 0 \\ 2 & 4 \\ 3 & 9.1 \end{pmatrix}$$

5.1.1 Creating Variables in Equation

New variables can also be created inside equations. Vectors and matrices can be created as shown in Section 5.1. Lua knows - by default - how to do calculations with numbers. Any mathematical operation with a tVar object and a decimal number results in a tVar value.

```
1
   \begin{tVar}
2
   # Variable a is created from the equation ...
3
   a := 13 * 2^2
   # To preserver the equation some of the ...
   a := tVar : New(13) * 2^2
   # At first Lua calculates $2^2=4$ ...
7
   # To print the whole ...
   a:=13*tVar:New(2)^2
9
   # Matrices and Vectors
  c := \{\{1,2,3\},\{4,2,6\},\{1,3,2\}\} * \{1,2,3\} * a
11 \end{tVar}
```

Output

Variable a is created from the equation $13 \cdot 2^2$. Since all numbers are just decimal values, Lua calculates the result and creates the tVar object afterwards.

$$a = 52$$

To preserver the equation some of the numbers have to be initialized as tVar objects. In this case it's the number 13.

$$a = 13 \cdot 4 = 52$$

At first Lua calculates $2^2 = 4$ and then multiplies the tVar object 13 with 4 which results in a tVar object containing the equation. To print the whole equation, one number from the first calculation has to be transformed into a tVar object.

$$a = 13 \cdot 2^2 = 52$$

Matrices and Vectors

$$\vec{c} = \begin{pmatrix} 1 & 2 & 3 \\ 4 & 2 & 6 \\ 1 & 3 & 2 \end{pmatrix} \cdot \begin{pmatrix} 1 \\ 2 \\ 3 \end{pmatrix} \cdot a = \begin{pmatrix} 1 & 2 & 3 \\ 4 & 2 & 6 \\ 1 & 3 & 2 \end{pmatrix} \cdot \begin{pmatrix} 1 \\ 2 \\ 3 \end{pmatrix} \cdot 52 = \begin{pmatrix} 728 \\ 1352 \\ 676 \end{pmatrix}$$

5.1.2 Auto-Formatting of variable names

The LATEX-representation of a variable is automatically generated from the variable name. The first occurrence of an underline starts the subscript the first occurrence of a double underline starts the superscript. Every other underline becomes a comma.

```
1 \begin{tVar}
2 a_1_3:=13
3 a__10_2:=3
4 b_1_x__y_2:=12
5 \end{tVar}
```

Output

$$a_{1,3} = 13$$

$$a_2^{10} = 3$$

$$b_{1.x}^{y,2} = 12$$

5.2 Creating Functions

Functions can easily be defined with the following syntax. The auto-formatting of function names and attribute names works according to Section 5.1.2.

```
1 \begin{tVar}
2 f(x,y):=x^2+y^2+4
3 a:=f(2,3)+11
4 \end{tVar}
```

Output

$$f(x,y) = x^2 + y^2 + 4$$

$$a = f(2,3) + 11 = 2^2 + 3^2 + 4 + 11 = 28$$

5.3 Indexing Matrices and Vectors

The syntax for indexing a matrix is similar to the Matlab syntax. To access a matrix you have to use square brackets and a string as key. The key has to be formatted according to the following examples.

```
1 \begin{tVar}
2 A:={{1,2,6},{2,4,6},{7,6,9}}
3 # Index one element with syntax [row,column]
4 A["1,2"]:outRES()
5 # Index a range
```

```
6 A["1:2,1:end"]:outRES()
7 # The range 1:end is equal to :
8 A["1:2,:"]:outRES()
9\, # You can also set matrices this way
10 A["1:2,:"]:={{1,2,3},{4,5,6}}
11 A["1:2,:"]:outRES()
12 # Adress vector
13 c := A[":,2"]
14 d:=A["2,:"]
   # The above also applies to vectors
15
16
   {plain
17
     v_1:=\{1,4,3\}
18
19
     v_1["2"]:outRES()
20
     v_1["1"]:=9
21
22
     v_1:outRES()
23
   }
24
   \end{tVar}
```

Output

$$\mathbf{A} = \begin{pmatrix} 1 & 2 & 6 \\ 2 & 4 & 6 \\ 7 & 6 & 9 \end{pmatrix}$$

Index one element with syntax [row,column]

$$A[1,2] = 2$$

Index a range

$$\mathbf{A}[1:2,1:end] = \begin{pmatrix} 1 & 2 & 6 \\ 2 & 4 & 6 \end{pmatrix}$$

The range 1:end is equal to :

$$\mathbf{A}[1:2,:] = \begin{pmatrix} 1 & 2 & 6 \\ 2 & 4 & 6 \end{pmatrix}$$

You can also set matrices this way

$$\mathbf{A}[1:2,:] = \begin{pmatrix} 1 & 2 & 3 \\ 4 & 5 & 6 \end{pmatrix}$$

Adress vector

$$\vec{c} = \begin{pmatrix} 2 \\ 5 \\ 6 \end{pmatrix}$$

$$\vec{d} = \begin{pmatrix} 4 & 5 & 6 \end{pmatrix}$$

The above also applies to vectors

$$\vec{v}_1 = \begin{pmatrix} 1 \\ 4 \\ 3 \end{pmatrix} , \ \vec{v}_1[2] = 4 , \ \vec{v}_1 = \begin{pmatrix} 9 \\ 4 \\ 3 \end{pmatrix}$$

5.4 Output

5.4.1 print()

The [tVar]:print() command creates the output according to the global parameter tVar.outputMode. The following options are supported:

```
Output a = 10 b = 2 c = a + b = 10 + 2 = 12 tVar.outputMode = "RES_EQ_N" c = 12 tVar.outputMode = "RES_EQ" c = 12 tVar.outputMode = "RES" c = 12
```

If you do your calculations inside \begin{tVar} and \end{tVar} the [tVar]:print() command is automatically added to your calculations. This means c:=(a+b) creates an output using the [tVar]: print() command. To suppress the automatic output just add a ";" at the end of the line.

```
1 \begin{tvar}
2 # With output:
3 a:=10
4 b:=3
5 c:=a+b
6 # Without output (Lines 7 and 8 produce no output):
7 a:=10;
8 b:=3;
9 c:=a+b
10 \end{tvar}
```

Output

With output:

$$a = 10$$

$$b = 3$$

$$c = a + b = 10 + 3 = 13$$

Without output (Lines 7 and 8 produce no output):

$$c = a + b = 10 + 3 = 13$$

5.4.2 outRES()

The [tVar]:outRES() command is equal to the combination of [tVar]:print() with tVar.outputMode = "RES". If you do your calculations inside \begin{tVar} and \end{tVar} the [tVar]:outRES() command is automatically added to any assignment of a new variable. That means a:=10 creates and output using the [tVar]:outRES() command.

In some cases you might want to print an equation without assigning a variable. This can be achieved by directly calling the function tVar.outRES([tVar]) (Now with a dot) and passing your equation as argument to the function.

- 1 \begin{tVar}
- 2 a:=2
- 3 b := 13
- 4 tVar.outRES((a+b)/2+b)
- $5 \ \end{tVar}$

Output

$$a = 2$$

$$b = 13$$

$$\frac{a+b}{2} + b = 20.5$$

This method also works for the output commands listed in Section 5.4.3.

5.4.3 Other Output Commands

For every output mode mentioned in Section 5.4.1 there is an equal output function.

RES_EQ_N [tVar]:outRES_EQ_N(numbering,environment)

RES_EQ [tVar]:outRES_EQ(numbering,environment)

RES [tVar]:outRES(numbering,environment)

The attributes numbering and environment are boolean values and define if the output is created with numeration and a math environment. Both parameters are optional and can also be defined via the global parameters tVar.numeration and $tVar.mathEnvironment^3$

Additionally there are the functions [tVar]:out() for printing the result without the variable name and [tVar]:outN() for printing the variable name the equation with numbers and the result.

³In case tVar.mathEnviroment is set to "" no math environment is used.

5.4.4 LATEX Output

Inside \begin{tVar} and \end{tVar} the symbol # can be used to print a text in IATeX. Inside such a text you can use %%[tVar]%% to print a variables name and \$[tVar]\$ to print a variables value.

IFTEX commands used within # have to be escaped. For example \section{} has to be written as \section{}.

```
1 \begin{tVar}
2 #\\section*{First Section}
3 a_1_2:=22.4:setUnit("m")
4 # Linebreaks are a bit confusing \\\
5 # The variable %%a_1_2%% has the value $$a_1_2$$
6 \end{tVar}
```

Output

First Subsection

```
a_{1.2} = 22.4 m
```

Linebreaks are a bit confusing The variable $a_{1,2}$ has the value 22.4 m

5.4.5 Precise Manipulation of Output

The following functions manipulate equations directly and can be used for detailed formatting.

[tVar]:bracR()	Surrounds the [tVar] object with round brackets.
[tVar]:bracB()	Surrounds the [tVar] object with boxed brackets.
[tVar]:bracC()	Surrounds the [tVar] object with curly brackets.
[tVar]:CRLF ([string])	Inserts a line break in N after the [tVar] object and adds the string before and after the line break.
<pre>[tVar]:CRLFb([string])</pre>	Inserts a line break in N before the [tVar] object and adds the string before and after the line break.
<pre>[tVar]:CRLF_EQ ([string])</pre>	Inserts a line break in EQ after the [tVar] object and adds the string before and after the line break.
<pre>[tVar]:CRLFb_EQ([string])</pre>	Inserts a line break in EQ before the [tVar] object and adds the string before and after the line break.
[tVar]:clean()	Removes the calculation history from an object.
[tVar]:setUnit([string])	Sets the unit for a tVar object.

```
1 \begin{tVar}
2 a:=10:setUnit("m")
3 b:=3:setUnit("m")
4 c:=((((a+b):bracR()^2):bracB()*5):bracC()*22):setUnit("m^2")
5 #In case you do a really long calculation you can insert a linebreak
6 c:=((a+a+a+a+b+b):CRLF("+")+b+b+b:CRLF_EQ("+")+b+b+a+a+a):CRLFb("=")
7 \end{tVar}
```

Output

$$a = 10 m$$

 $b = 3 m$
 $c = \left\{ \left[(a+b)^2 \right] \cdot 5 \right\} \cdot 22 = \left\{ \left[(10+3)^2 \right] \cdot 5 \right\} \cdot 22 = 18590 m^2$

In case you do a really long calculation you can insert a linebreak

5.4.6 Grouping Math Environments

By default TexVar creates a new mathematical environment for every output (except plain text-output with #). To group equations into one environment, you can enclose them with curly brackets. The group operator automatically adds an alignment symbol at the beginning of the line and a line-break at the end. If you want to suppress this behavior you can open the group with the command {plain.

```
1
   \begin{tVar}
2
   {
3
     a := 1
 4
     b:=10
5
     c := 3
6
   }
 7
   d:=(a+b):bracR()/c
   #It's also possible to create environments without line-breaks and
       alignment:
9
   {plain
10
   f:=3
11 #,~
12
   g:=f+d
13
14 \end{tVar}
```

Output

$$a = 1$$
 $b = 10$
 $c = 3$

$$d = \frac{(a+b)}{c} = \frac{(1+10)}{3} = 3.667$$

It's also possible to create environments without line-breaks and alignment:

$$f=3$$
 , $g=f+d=3+3.667=6.667$

5.5 Global Parameters

Global parameters can be set during runtime and affect all commands.

Tab. 1: Global parameters with default values and description

tVar.numFormat = "%.3f"	Defines the number format for printing.
tVar.mathEnviroment = "align"	Defines the environment used around equations.
tVar.outputMode = "RES_EQ_N"	Defines the output mode (Section 5.4.1).
tVar.numeration = true	Disables and enables numeration of equations.
tVar.decimalSeparator = "."	Defines the decimal separator.
<pre>tMat.texStyle = "mathbf"</pre>	Defines the style for matrices.
tMat.eqTexAsMatrix = false	Enables and disables output of a matrix as variable name or matrix with variable names
tVec.texStyle = "vec"	Defines the style for vectors.
tVar.calcPrecision = 10	Defines the how many decimal places are used for comparison.
tVar.disableOutput = false	Disables the complete output.
tVar.autocutZero = true	Removes trailing zeros from a decimal number.
tVar.autocutDecimalSep = true	In case tVar.autocutDecimalSep is true remove the decimal separator if all trailing zeros have been removed. Else show number with one decimal zero. (Only works if tVar.autocutZero = true)
tVar.debugMode = "off"	In case debugMode is set to "on" the equations are printed as LATEX code.
tVar.logInterp = false	Enables logging of interpreted commands. Creates a file tVarLog.log
tVar.coloredOutput = false	Prints all variables with value=nil red.

5.5.1 Details on automatic removal of trailing zeros

The following example shows the difference between the global parameters tVar.autocutDecimalSep and tVar.autocutZero. If tVar.autocutZero is disabled the number format from tVar.numFormat get's applied.

```
1 \begin{tVar}
2 #Default settings
3 {
4 a:=2.0
5 b:=3.3
6 c:=tVar.sqrt(a^2+b^2)
7 }
8 #Disable tVar.autocutDecimalSep
9 tVar.autocutDecimalSep = false
10 {
11 a:=2.0
```

```
12  b:=3.3
13  c:=tVar.sqrt(a^2+b^2)
14  }
15  #Disable tVar.autocutZero
16  tVar.autocutZero = false
17  {
18  a:=2.0
19  b:=3.3
20  c:=tVar.sqrt(a^2+b^2)
21  }
22  \end{tVar}
```

Output

Default settings

$$a = 2$$

 $b = 3.3$
 $c = \sqrt{a^2 + b^2} = \sqrt{2^2 + 3.3^2} = 3.859$

Disable tVar.autocutDecimalSep

$$a = 2.0$$

 $b = 3.3$
 $c = \sqrt{a^{2.0} + b^{2.0}} = \sqrt{2.0^{2.0} + 3.3^{2.0}} = 3.859$

 $Disable\ tVar.autocutZero$

$$a = 2.000$$

$$b = 3.300$$

$$c = \sqrt{a^{2.000} + b^{2.000}} = \sqrt{2.000^{2.000} + 3.300^{2.000}} = 3.859$$

5.6 Plotting with Gnuplot

Plotting in TexVar is support via Gnuplot. The code describing the figure is generated in TexVar and is sent to Gnuplot which creates the graphics.

5.6.1 Configuration

For enabling plotting the path to the Gnuplot executable has to be set via a global parameter. By default its set to tPlot.gnuplot_library ="gnuplot". In case you work on a windows system and want to specify the absolute path to your Gnuplot install the command has to be tPlot.gnuplot_library = [==[""WINDOWSPATH"]==].

The Gnuplot terminal is by default tPlot.terminal = "pdf enhanced color font 'Helvetica,12'" and the file extension is tPlot.FileExtension = "pdf".

5.6.2 Creating a Plot


Every parameter set through [tPlot].* is directly translated to a gnuplot command. Actually tPlot is only aware of the following commands

```
Creates a new plot. Present is an optional parameter.
tPlot:New(present[tPlot])
                                     If a value gets passed the configuration of the plot is
                                     used as template for the new plot.
                                     Resolution for functions
[tPlot].steps = 0.1
[tPlot].conf.size = "14cm,8cm"
                                     Size of the plot
[tPlot].xrange = "[0,10]"
                                     Range of the x axis and min and max value for func-
                                     tion creation.
[tPlot]:add(f or
                                      Adds a functions or points to the plot.
\{\{1,2\},\{3,2\}\},"f(x)", "with
line lt 1 lc 2")
[tPlot]:plot()
                                     Generates the plot and returns the includegraphics
                                     command.
```

```
\begin{tVar}
 2
   f(x):=1/x
 3
   plot1=tPlot:New()
 4
   plot1.xlabel = "{/ Symbol e}_c"
   plot1.ylabel = "{/ Symbol s}_c"
 7
   plot1.steps = 0.001
 8
 9
   plot1.xtics = "0.1"
  plot1.xrange = "[0:1]"
10
   plot1.yrange = "[0:16]"
   plot1.conf.size = "6cm ,6cm"
12
   plot1:add(f,"f(x)", "with line lt 1 lc 2")
14 \text{ plot1:add}(\{\{0.2,6\},\{0.5,12\}\}, \text{"pt", "with points lc 1"})
15 #\\begin{center}
16 plot1:plot()
17 #\\end{center}
18 \ \end{tVar}
```

Output

$$f(x) = \frac{1.000}{x}$$




Currently TexVar only supports 2D plots and functions with one attribute. If you want to print a function with more than one attribute you can create a helper function.

```
\begin{tVar}
1
^2
   -- use plot1 as template
3
   plot2=tPlot:New(plot1)
4
5 f(x,z) := (1/x)^z
6
  -- helper functions with fixed z values
7
  f_h_1(x) := f(x,2);
8
  f_h_2(x) := f(x,1);
9
   plot2:add(f_h_1,"z=2","with line lt 1 lc 2")
10
   plot2:add(f_h_2,"z=1","with line lt 1 lc 3")
11
12
13 #\\begin{center}
  plot2:plot()
14
16 \ \end{tVar}
```

Output

$$f(x,z) = \frac{1.000}{x}^z$$



5.7 Mathematical Commands

The following subsections are just a listing of currently implemented mathematical functions.

5.7.1 General

These functions can be used with every tVar object.

- tVar.sqrt([tVar],[tVar])
- tVar.PI
- tVar.abs([tVar])
- tVar.acos([tVar])
- tVar.cos([tVar])
- tVar.cosh([tVar])
- tVar.asin([tVar])
- tVar.sin([tVar])

- tVar.sinh([tVar])
- tVar.atan([tVar])
- tVar.tan([tVar])
- tVar.tanh([tVar])
- tVar.ceil([tVar])
- tVar.floor([tVar])
- tVar.exp([tVar])
- tVar.ln([tVar])
- tVar.log10([tVar])
- tVar.rad([tVar])
- tVar.deg([tVar])
- tVar.atan2(X[tVar],Y[tVar])
- tVar.fact([tVar])

5.7.2 Matrices and Vectors

These functions can only be used with tMat or tVec objects.

- [tMat]:T()
- [tMat]:Det()
- [tMat]:Inv()
- tVec.crossP([tVec],[tVec])

5.8 The Link Function

If you want to use your own functions within TexVar, you can use the Link function to link them to tVar functions. This only applies to functions that don't use TexVar objects for calculation. If you want to write a TexVar function see Section 5.2. The following code shows the implementation of the factorial function with the link function.

```
1
   \begin{tVar}
   function mycalcFactorial(n)
3
     -- no tVar objects here just numbers
     if n \le 1 then return 1 end
4
5
     return n*mycalcFactorial(n-1)
6
   end
7
8
   -- link it
  myfact = tVar.link(mycalcFactorial,"","!")
9
10
  a:=10
11
12
  b:=myfact(a)
13 \end{tVar}
```

```
b = a! = 10.000! = 3628800.000
```

The link function takes as first attribute the function you want to link as second a string to be added before the attributes and as third a string to be added after the attributes.

All Lua math functions are implemented this way.

For example the Lua function math.atan2:

```
1 --- calculates inverse tangens with with appr. quadrant
2 --
3 -- @param opposite (tVar,number) values
4 -- @param adjacent (tVar,number) values
5 -- @return (tVar)
6 tVar.atan2 = tVar.link(math.atan2,"\\text{atan2}\\left(","\\right)")
```

Output

 $c = \operatorname{atan2}(3.000; 4.000) = 0.644$

6 Examples 17

6 Examples

6.1 U-Value

This is a very simple example using only the basic functionality of TexVar.

```
1 \mbox{newcommand{\msKpW}{\tfrac{m^2K}{W}}}
    2 \mbox{ } 1 \mbox{ } 1 \mbox{ } 2 \mbox{ } 1 \mbox{ } 1 \mbox{ } 2 \mbox{ } 1 \mbox{ 
    4 \ \mbox{newcommand} \{\mbox{m}\} \{\mbox{m}\}
    5 Calculating the U-Value for an element with two layers.\\
    6
           \begin{tVar}
                       #\\noindent Resistance of surface
    7
   8
                      R_se:= 0.3:setUnit("\\msKpW")
   9
 10
                       R_si := 0.13 : setUnit("\msKpW")
 11
 12
                      #Parameters for elements
13
             {
14
                      d_1 := 0.2:setUnit("\m")
 15
                       \\lambda_1 := 0.035:setUnit("\\WpmK")
 16
                       d_2 := 0.1:setUnit("\m")
17
                       \\lambda_2 := 0.5:setUnit("\\WpmK")
18
19
                      #Calculate thermal resistance
20
21
                      R := (R_se + d_1/lambda_1 + d_2/lambda_2 + R_si):setUnit("\msKpW")
22
                      #Calculate U-Value
23
                      U := (1/R) : setUnit(" \setminus WpmsK")
24 \ \end{tVar}
```

Output

Calculating the U-Value for an element with two layers. Resistance of surface

$$R_{se} = 0.300 \ \frac{m^2 K}{W}, \ R_{si} = 0.130 \ \frac{m^2 K}{W}$$

Parameters for elements

$$\begin{aligned} d_1 &= 0.200 \ m \\ \lambda_1 &= 0.035 \ \frac{W}{mK} \\ d_2 &= 0.100 \ m \\ \lambda_2 &= 0.500 \ \frac{W}{mK} \end{aligned}$$

Calculate thermal resistance

$$R = R_{se} + \frac{d_1}{\lambda_1} + \frac{d_2}{\lambda_2} + R_{si} = 0.300 + \frac{0.200}{0.035} + \frac{0.100}{0.500} + 0.130 = 6.344 \frac{m^2 K}{W}$$

Calculate U-Value

$$U = \frac{1.000}{R} = \frac{1.000}{6.344} = 0.158 \ \frac{W}{m^2 K}$$

18 6 Examples

6.2 Rotating a Vector

This example shows the usage of the parameter tMat.eqTexAsMatrix as mentioned in Section 5.5.

```
\begin{tVar}
2
   tMat.eqTexAsMatrix = true
3
4 #Rotation angle in degree
5 \land \text{theta:=tVar.rad}(45)
7 #Rotation matrix in R2
8 {
   A := {{tVar.cos(theta),-tVar.sin(theta)},{tVar.sin(theta),tVar.cos(
9
       theta) }}: outRES_EQ()
   e_x := \{1,0\}
10
   }
11
12
13
14 tMat.eqTexAsMatrix = false
15 e := (A * e_x)
16 \ \end{tVar}
```

Output

Rotation angle in degree

$$\theta = \text{rad}(45.000) = 0.785$$

Rotation matrix in R2

$$\mathbf{A} = \begin{pmatrix} \cos\left(\theta\right) & \left(-\sin\left(\theta\right)\right) \\ \sin\left(\theta\right) & \cos\left(\theta\right) \end{pmatrix} = \begin{pmatrix} 0.707 & \left(-0.707\right) \\ 0.707 & 0.707 \end{pmatrix}$$

$$\vec{e}_x = \begin{pmatrix} 1.000 \\ 0.000 \end{pmatrix}$$

$$\vec{e} = \mathbf{A} \cdot \vec{e}_x = \begin{pmatrix} 0.707 & (-0.707) \\ 0.707 & 0.707 \end{pmatrix} \cdot \begin{pmatrix} 1.000 \\ 0.000 \end{pmatrix} = \begin{pmatrix} 0.707 \\ 0.707 \end{pmatrix}$$

6 Examples 19

6.3 Vector Calculations - Custom Function

This example shows how to create a custom TexVar function for calculating the angle between two vectors. The function has an extra parameter for disabling printing.

```
1
   \begin{tVar}
3 tVar.outputMode = "RES_EQ"
 4 function angleBetweenVectors(a,b,disablePrinting)
5
      if disablePrinting then
        tVar.disableOutput = true
6
7
      end
8
9
      #Calculate the length of the vectors
10
11
      len_a:=tVar.sqrt(a*a)
12
      len_b:=tVar.sqrt(b*b)
13
14
      #Normalize the vectors
15
16
      a_n:=(a/len_a)
17
      b_n := (b/len_b)
18
     \\alpha:=tVar.deg(tVar.acos(a_n*b_n)):setUnit("^{\\circ}")
19
20
21
      if disablePrinting then
22
        tVar.disableOutput = false
23
      end
24
25
      return alpha
26
   end
27
28 #With output
29
   {
30
     v_1:=\{1,0.4,0.5\}
31
      v_2 := \{0.3, 1, 0\}
   }
32
33
34
   \\alpha_1:=angleBetweenVectors(v_1,v_2)
35
36 #Without output
37
   {
     v_3:=\{4,0.2,5\}
38
39
      v_4 := \{9.3,8,1\}
40
   \\alpha_2:=angleBetweenVectors(v_3,v_4,true)
41
42 \ \end{tVar}
```

20 6 Examples

Output

With output

$$\vec{v}_1 = \begin{pmatrix} 1.000 \\ 0.400 \\ 0.500 \end{pmatrix}$$

$$\vec{v}_2 = \begin{pmatrix} 0.300 \\ 1.000 \\ 0.000 \end{pmatrix}$$

$$\vec{v}_2 = \begin{pmatrix} 0.300 \\ 1.000 \\ 0.000 \end{pmatrix}$$

Calculate the length of the vectors

$$len_a = \sqrt{\vec{v}_1 \cdot \vec{v}_1} = 1.187$$

$$len_b = \sqrt{\vec{v}_2 \cdot \vec{v}_2} = 1.044$$

Normalize the vectors

$$\vec{a}_n = \frac{\vec{v}_1}{len_a} = \begin{pmatrix} 0.842\\ 0.337\\ 0.421 \end{pmatrix}$$

$$\vec{b}_n = \frac{\vec{v}_2}{len_b} = \begin{pmatrix} 0.287\\ 0.958\\ 0.000 \end{pmatrix}$$

$$\alpha = \deg\left(a\cos\left(\vec{a}_n \cdot \vec{b}_n\right)\right) = 55.622$$
 °

$$\alpha_1 = 55.622$$
 °

Without output

$$\vec{v}_3 = \begin{pmatrix} 4.000 \\ 0.200 \\ 5.000 \end{pmatrix}$$

$$\vec{v}_4 = \begin{pmatrix} 9.300 \\ 8.000 \\ 1.000 \end{pmatrix}$$

$$\vec{v}_4 = \begin{pmatrix} 9.300 \\ 8.000 \\ 1.000 \end{pmatrix}$$

$$\alpha_2 = 56.255$$
 $^{\circ}$