



## A+ LAB SERIES V5

### Lab 10: Sharing Resources - Folders

Document Version: **2026-01-02**

| Material in this Lab Aligns to the Following |                                                                                             |
|----------------------------------------------|---------------------------------------------------------------------------------------------|
| CompTIA A+ (220-1201) Exam Objectives        | 2.4: Explain common network configuration concepts.                                         |
| CompTIA A+ (220-1202) Exam Objectives        | 1.7: Given a scenario, configure Microsoft Windows networking features on a client/desktop. |

## Contents

|                                                                         |    |
|-------------------------------------------------------------------------|----|
| Introduction .....                                                      | 3  |
| Objective .....                                                         | 3  |
| Lab Topology .....                                                      | 4  |
| Lab Settings .....                                                      | 5  |
| 1 Assign a Windows Computer to a Workgroup .....                        | 6  |
| 1.1 Adding Win11-OS to a Workgroup and Modifying Network Settings ..... | 6  |
| 1.2 Adding Win10-OS to a Workgroup and Modifying Network Settings ..... | 13 |
| 2 Configuring Shared Folders .....                                      | 21 |
| 2.1 Creating a Shared Folder in Win10-OS .....                          | 21 |

## Introduction

One of the fundamental purposes of a network is to share resources, such as file folders.


## Objective

In this lab, we will perform tasks related to sharing folders in Windows 10 and Windows 11 and review key concepts of Windows folder sharing.

In this lab, we will be performing the following tasks:

- Assign both Windows 10 and Windows 11 to a workgroup.
- Review Advanced Sharing Settings to enable File and Printer Sharing.
- Create users who will access shared folders.
- Create folders and files to configure for sharing.
- Apply permissions to shared folders and test access.

## Lab Topology



## Lab Settings

The information in the table below is needed to complete the lab. The task sections below provide details on how to use this information.

| Virtual Machine | IP Address        | Account<br>(if needed) | Password<br>(if needed) |
|-----------------|-------------------|------------------------|-------------------------|
| Win10-OS        | 192.168.1.10 / 24 | sysadmin               | NDGLabpass123!          |
| Win11-OS        | 192.168.1.11 / 24 | sysadmin               | NDGLabpass123!          |

## 1 Assign a Windows Computer to a Workgroup

This section of the lab will walk through adding a *Windows-based* computer to a workgroup.


### 1.1 Adding Win11-OS to a Workgroup and Modifying Network Settings

1. Open a console connection to the **Win11-OS** system.




To launch the console for a lab device, you can click on the respective tab in the navigation bar at the top or navigate to the *Topology* section and click the lab device's corresponding image.


2. Select the search bar on the taskbar, type **Control Panel**, and select **Open**.




3. In the *Control Panel* window, change the *View* to **Small icons**. Click on **System**.




4. On the *System* window, locate the *Device name* and select **Domain or workgroup**.



5. On the *System Properties* window, click the **Change** button.




6. Under the *Computer name*, type **Enterprise** to change the name of this computer. Under *Workgroup*, type MYGROUP to change the name of the *Workgroup* of which this computer will be a member. Click **OK**.







7. Click **OK** when the *Welcome to the MYGROUP workgroup* window is displayed.



8. Next, a window will be displayed, reminding you that you need to reboot for the changes to take effect. Click the **OK** button.



9. Click the **Close** button in the *System Properties* window to close the window.




10. When prompted, click on the **Restart Now** button to reboot the computer.




11. The *Win11-OS* system will automatically log back in as **sysadmin**.


12. Once logged in, right-click on the **Network** icon (located in the notification area) and then click on the **Network and Internet settings** menu option.




13. Select **Advanced network settings**.




14. Select the **vEthernet (Default External Switch)** adaptor. Then select **Edit** next to More adaptor options.




15. Ensure the **File and Printer Sharing for Microsoft Networks** and **Internet Protocol Version 4 (TCP/IP)** checkbox is selected. Make sure **Internet Protocol Version 4 (TCP/IPv4)** is highlighted. Select **Properties**.




16. Verify the Static IP Address is set, as you will need this address later in this lab. Select **Ok** to close the IPv4 Properties Window.




17. Select **Close** to close the *vEthernet Properties* window.



18. Click on **Advanced sharing settings**.



19. This window allows you to change the sharing options for various network profiles. Expand *Private networks* by selecting the **drop-down arrow**. Ensure that **Network discovery** is *On* and turn on the **file and printer sharing** radio button. Close the **Advanced sharing settings** window.




20. Close the *Advanced Network Settings* window.

## 1.2 Adding Win10-OS to a Workgroup and Modifying Network Settings


1. Switch to the **Win10-OS** system.




2. Select the search bar on the taskbar, type the command **Control Panel**, and select **Open**.




3. In the *Control Panel* window, ensure that **Small icons** are set for the *View by* and click on **System**.




4. In the right side of the *About* window, scroll down and click on the **Advanced system settings** link.




5. Select the **Computer Name** tab and select **Change**.




6. Type **Client** in the *Computer name* text field to change the name of this computer. In the *Workgroup* text field, type **MYGROUP** to change the name of the *workgroup* of which this computer will be a member. Click **OK**.




7. Click **OK** when the *Welcome to the MYGROUP workgroup* window is displayed.



8. A window will be displayed, reminding you that you need to reboot for the changes to take effect. Click the **OK** button.



9. In the *System Properties* window, click the **Close** button.






10. In the Notification that *You must restart your computer to apply these changes*, click **Restart Now**.




11. Once the computer finishes rebooting, the *Win10-OS* system will automatically log back in as *sysadmin*.


12. Right-click on the **Network** icon (located in the notification area) and then click on the **Open Network and Internet settings** menu option.




13. Under *Advanced network settings*, click **Change adapter options**.




14. Right-click on **Ethernet0** and click on **Properties**.



15. Ensure the **File and Printer Sharing for Microsoft Networks** and **Internet Protocol Version 4 (TCP/IPv4)** checkbox is selected. Make sure **Internet Protocol Version 4 (TCP/IPv4)** is highlighted. Select **Properties**.




16. Verify the Static IPv4 Address Settings. Select **OK** to close IPv4 Properties window.




K


17. On the *Ethernet0 Properties* window, select **Close**.




18. Close the *Network Connections* window.




19. Under *Advanced network Settings*, click on **Network and Sharing Center**.



## 20. Select **Change Advanced Sharing Settings**.



## 21. Select the **Drop Down Arrow** for the Private Network. Ensure that **Turn on network discovery** and **Turn on file and printer sharing** radio buttons are selected. Click **Save changes**.



## 22. Close all open Windows.

## 2 Configuring Shared Folders


This section of the lab will walk you through how to configure a shared folder to be accessed in the same *workgroup*.

### 2.1 Creating a Shared Folder in Win10-OS

1. Verify you are logged into the **Win10-OS** System.




2. Right-click within a space on the desktop and select **New > Folder**.




3. Type **Data** as the name of the new folder, followed by pressing the **Enter** key.




- Double-click the folder you just created to open it and create a new text document by right-clicking in any empty space within the folder, selecting **New**, and then clicking **Text Document**.




- Enter **Test** as the file name and press the **Enter** key.




6. Close the *Windows Explorer* window and return to the Desktop, and right-click the Data folder, selecting **Properties**.




7. Click on the **Sharing** tab and then click the **Advanced Sharing** button.



8. In the *Advanced Sharing* window, check the checkbox next to **Share this folder**. Change the *Share name* to **SharedData** and then click the **Permissions** button.




9. In the *Permissions for SharedData* window, make sure the group **Everyone** is selected and check the checkbox for **Full Control** underneath the *Allow* column. This will check all the checkboxes underneath the *Allow* column. Click **Add**.






10. Type **Client\Users** and click **OK**.



11. Select **Users (CLIENT\Users)** from the list and then check the checkbox for **Full Control** underneath the *Allow* column and click **OK**.



12. Click **OK** to close the *Advanced Sharing* window.

13. Click **Close** to close the *Data Properties* window.


14. Next, you will access the shared folder from the *Win11-OS* system. Change focus to the **Win11-OS** system.




15. Click on the **Windows Explorer** icon in the taskbar.




16. Click on **Network** located in the left navigational pane.



17. Type `\\CLIENT\SharedData` in the address bar. Select **Enter** on your keyboard.



18. The *SharedData* folder opens and you now have access to the *Test* text document.



19. The lab is now complete; you may end the reservation.