ARES INTERNET LOCKDOWN

v1.4.2 | Quick operating and installation guide | Ubuntu / nginx

1. Everyday commands

lockdown-internet --tailscale	Start a five-minute test. Automatically restores firewall behavior unless confirmed.
lockdown-internet --permanent --tailscale	Apply lockdown until manually restored or reboot. Does not by itself survive a reboot.
restore-internet	Remove the lockdown firewall table; does not turn off a previously enabled boot service.
lockdown-internet --tailscale --check	Validate server config and nftables rules without applying them.
ares-anydesk-diagnose	Read-only AnyDesk diagnostic if remote desktop connectivity fails.

These commands request sudo when required. The standard configuration preserves LAN access to ARES applications, SSH/VNC, Tailscale, and the approved AnyDesk exceptions.

2. Test safely before using permanent lockdown

```
lockdown-internet --tailscale --check
lockdown-internet --tailscale
```

- From a separate device, test AnyDesk and Tailscale SSH/VNC.
- From a wireless student client, open http://ares.local/.
- From the server, verify general HTTPS browsing is blocked.
- Restore and confirm AnyDesk reconnects without rebooting:

```
restore-internet
```

Do not enable boot persistence until all of these checks pass. The Tenda MW6 mDNS behavior remains a separate field acceptance test.

INSTALLATION & REBOOT SETUP

Same firewall rules as v1.4.1; only the installer and instructions have been simplified.

3. Install or update in three commands

```
unzip ARES_Internet_Lockdown_Package_v1.4.2.zip
cd ares-lockdown-v1.4.2
bash install.sh
```

The installer detects the local network automatically when there is one suitable IPv4 interface. It reuses an existing valid configuration. If the only interface also carries the internet default route, confirm it really serves student devices. If multiple interfaces exist, select the student-side LAN by number; do not select a modem-only uplink.

Mode A (ARES application server) is the default. The installer backs up changed scripts, preserves compatible command wrappers, and checks firewall syntax. It does not activate lockdown during installation.

It asks "Enable lockdown automatically after every reboot?" The safe default is No. If you answer Yes, it requires explicit confirmation that remote access and restoration have already been tested.

4. Enable or disable lockdown after reboot

After completing the live test, rerun the installer to enable the systemd service:

```
bash install.sh --boot
sudo systemctl is-enabled ares-internet-lockdown.service
```

Enter YES to confirm that AnyDesk, Tailscale SSH/VNC, ARES browser access and restore/reconnect all passed. The service is enabled for the next boot but is not started during installation.

To turn off the next-boot lockdown and restore the current connection:

```
sudo systemctl disable ares-internet-lockdown.service
restore-internet
```

5. Special configurations

Multiple LANs: The installer offers numbered choices. For advanced/manual configuration, use bash install.sh --lan "interface=subnet/CIDR", with actual interface names and networks.

Mode B (ARES gateway): Optional: bash install.sh --mode gateway. This does not configure DHCP, routing, forwarding, NAT, or client gateway addresses.

Network boundary: In Mode A, the firewall controls traffic on the ARES server. It cannot block students accessing the internet through a separate router that does not pass traffic through ARES.

Recovery: If AnyDesk stops working after restore, confirm the firewall table is absent and check/restart the AnyDesk service. A reboot-persistent lockdown should be tested with console or alternate access available.