CS 2110 - Lab 10

Subroutines Review and Recursion

Monday, June 27, 2022



Lab Assignment: Subroutines Quiz

- 1. Go to Quizzes on Canvas
- 2. Select Lab 10, password: recursionrecursion
- 3. Get 100% to get attendance!
 - a) Unlimited attempts
 - b) Collaboration is allowed!
 - c) Ask your TAs for help:)

Homework 5

- Covers basic assembly programming topics
- Released!
- Due today!!! June 27th at 11:59 PM
- Files available on Canvas
- Submit to Gradescope (unlimited submissions)

Homework 6

- Released
- Covers assembly subroutines and calling convention
- Due Thursday, July 7th at 11:59 PM
- Files available on Canvas
- Submit to Gradescope (unlimited submissions)
- Please don't wait until the very last hours before the homework is due to ask for help!

Quiz 3

- Next Wednesday, July 6th
- Quiz opens at your assigned lab time (unless you have already established a different time with your professor)
- Full 75 minutes to take the quiz!
- As usual, you will join back to your lab section after the quiz.
- A topic list will be posted on Canvas

The Stack

- The stack is a location in memory that is useful for storing temporary program data
 - O Subroutine calls parameters, return values
 - O Local variables what if our 8 registers aren't enough
- Grows "downwards" towards smaller memory addresses from a fixed starting location
- The top of the stack is stored in the "stack pointer"
- In the LC-3, we use R6 as the stack pointer

Pushing to the Stack

What we want to do:

- Store 3 variables on the stack (RO on top)
- R0 = 3 R1 = 230 R2 = -684

How do we do it?

Memory	Contents	Pointers
Address		
xEFF7	garbage	
xEFF8	garbage	
xEFF9	garbage	
xEFFA	garbage	
xEFFB	garbage	
xEFFC	garbage	
xEFFD	garbage	
xEFFE	garbage	
xEFFF	garbage	
xF000	Who knows	< R6, stack pointer

Pushing to the Stack

What we want to do:

Store 3 variables on the stack (R0 on top)

 \bullet R0 = 3

R1 = 230

R2 = -684

ADD R6, R6, -3

STR R0, R6, 0

STR R1, R6, 1

STR R2, R6, 2

concise

Which one do you prefer??

ADD R6, R6, -1

STR R2, R6, 0

ADD R6, R6, -1

STR R1, R6, 0

ADD R6, R6, -1

STR R0, R6, 0

thorough

Memory	Contents	Pointers
Address		
xEFF7	garbage	
xEFF8	garbage	
xEFF9	garbage	
xEFFA	garbage	
xEFFB	garbage	
xEFFC	garbage	
xEFFD	3	< R6,
		stack pointer
xEFFE	230	
xEFFF	-684	
xF000	Who knows	

Popping from the Stack

What we want to do (in order):

- Retrieve 1 value from the stack (NOT popping)
 - O unknown $3 \rightarrow R0$
- Pop 2 values from the top stack
 - O (We don't care about the value of unknown2)
 - O unknown1 \rightarrow R1
 - O unknown2 → nowhere

How do we do it?

Memory	Contents	Pointers
Address		
xEFF7	garbage	
xEFF8	garbage	
xEFF9	garbage	
xEFFA	garbage	
xEFFB	garbage	
xEFFC	garbage	
xEFFD	unknown1	< R6,
		stack pointer
xEFFE	unknown2	
xEFFF	unknown3	
xF000	Who knows	

Popping from the Stack

What we want to do (in order):

- unknown3 → R0
- unknown1 \rightarrow R1
- unknown2 → nowhere

LDR R0, R6, 2

LDR R1, R6, 0

ADD R6, R6, 2

OR

concise

LDR R0, R6, 2

LDR R1, R6, 0

ADD R6, R6, 1

ADD R6, R6, 1

thorough

Memory Address	Contents	Pointers
xEFF7	garbage	
xEFF8	garbage	
xEFF9	garbage	
xEFFA	garbage	
xEFFB	garbage	
xEFFC	garbage	
xEFFD	unknown1	< R6, stack pointer
xEFFE	unknown2	
xEFFF	unknown3	
xF000	Who knows	

Which one do you prefer??

To push and pop values onto the stack, we use the ST and LD instructions. True/False?



Calling Convention

- "Subroutine" is another name for "function"; it involves one section of code (the caller) invoking another section of code (the callee)
- We need to figure out a way to communicate important information like parameters and return values between the caller and callee
- This is called a calling convention
- Example of a simple calling convention: "the caller will put the arguments in R0 and R1 and the callee will put the result in R2"
- However, we want a calling convention that is more general and doesn't "clobber" (overwrite) our registers

LC-3 Calling Convention

		_
Who Saves	STACK	
Callee	Saved Regs	← R6
Callee	First local	← R5
Callee	oldFP/old R5	
Callee	RA (callee r7)	
Callee	RV (space)	R5+3
Caller	Arg 1	R5+4
Caller	Arg 2	R5+5

- We create a stack frame (or activation record) on the stack which holds the data we need to save
- We save the old register values so they don't get clobbered by our subroutine
- We use the frame pointer (R5) to have a fixed reference point to access arguments and the return value—how can we compute the address of the nth argument?
- We also save the return address to prevent it from being clobbered by future JSR calls

Why do we have a frame pointer?



Caller – subroutine example (subtract)

		Ī	subtract'
;; MAIN HERE		Lower memory	
LD RO, A	Get A from Memory		
LD R1, B	Get B from Memory		
ADD R6, R6, -2	Make room for args		
STR R0, R6, 0	Store args in reverse order		
STR R1, R6, 1	A goes above B		
JSR subtract	Call subtract		
LDR R2, R6, 0	Get return value off of the stack		
ADD R6, R6, 3	Deallocate space for RV and args		
ST R2, RESULT	Save result in Memory	Higher memory	
;; END MAIN			

	subtract's stack	temp	late
Lower memory		R4	<- SP (R6)
		R3	
		R2	
		R1	
		RØ	
		LV2	
		LV1	<- FP (R5)
		old FP(R5)	
		RA (old R7)	
		RV	
		arg 1	
Higher memory		arg n-1	

Callee (subtract function)

	1	I	subtract's stack	temp	late
;; Stack setup		Lower memory		R4	<- SP (R6)
ADD R6, R6, -4	Make room for RV, RA, old FP, and 1 local			R3	
STR R7, R6, 2	Save RA in the space we made for it			R2 R1	
STR R5, R6, 1	Save R5 in the space for the old FP			RØ	
ADD R5, R6, 0	Set R5 to the FP of this Activation Record				
ADD R6, R6, -5	Make room for saving Registers			LV1	<- FP (R5)
STR R0, R6, 4	Save R0			old FP(R5)	
STR R1, R6, 3	Save R1			RA (old R7)	
STR R2, R6, 2	Save R2			arg 1	
STR R3, R6, 1	Save R3	Higher memory			
STR R4, R6, 0	Save R4			arg n-1	

Callee (subtract function)

;; EXTRACT ARGS	
LDR R0, R5, 4	Read A off stack and into R0
LDR R1, R5, 5	Read B off stack and into R1
;; SUBTRACT	
NOT R1, R1	2's complement negation
ADD R1, R1, 1	R1 <= -B
ADD R2, R0, R1	Perform subtraction, R2 <= A - B
;; STORE RV	
STR R2, R5, 3	Put the result in the space allocated for RV

;	subtract's stack	temp	late
Lower memory		R4	<- SP (R6)
		R3	
		R2	
		R1	
		RØ	
		LV2	
		LV1	<- FP (R5)
		old FP(R5)	
		RA (old R7)	
		RV	
		arg 1	
Higher memory			

arg n-1

Callee (subtract function)

	T	1	subtract's stack	temp	late
;; TEARDOWN		Lower memory		R4	<- SP (R6)
LDR R0, R6, 4	Restore RO			R3	
LDR R1, R6, 3	Restore R1			R2	
EBR RI, Ro, o	Nestore KI			R1	
LDR R2, R6, 2	Restore R2			RØ	
LDD D2 D4 1	Restore R3				
LDR R3, R6, 1	Restore K5			LV2	
LDR R4, R6, 0	Restore R4			LV1	<- FP (R5)
ADD R6, R5, 0	Reset stack pointer to frame pointer			old FP(R5)	
1555504	D	1		RA (old R7)	
LDR R5, R6, 1	Restore old FP into R5			RV	
LDR R7, R6, 2	Restore RA into R7			arg 1	
ADD R6, R6, 3	Deallocate space for local, oldFP, and RA	Higher memory			
7,66 1,70,70	Beandeate space for local, old 1, and 10.	Trigiter memory		arg n-1	
RET	Return to main			arg n	

What values does the caller push onto the stack before calling a function?



Inside the callee function, we can always load the first argument into Ro using LDR Ro, R5, __




Recursion!

- How can we implement subroutines calling themselves in the LC-3?
- Recursion in assembly is the same as other function calls!
- The recursive function will have to act as both the caller and the callee


What if a subroutine calls a subroutine?

- Just push another stack frame above it
- This works normally, and R6 will always point the current stack frame
 - O A stack is a "last-in, first out" data structure
 - O The most recently pushed stack frame will be that corresponding to the current function
 - O Therefore, our current stack frame will always be at the top of the stack!



What if a subroutine calls a subroutine?

 However, there's a problem: R7 can get "clobbered" by the second call to JSR/JSRR, and then we won't know where to return to!



- This is why we save the return address (from R7) in our stack frame
- We simply have to restore R7 by popping the RA off the stack before calling RET

Debugging

Debug pow2.asm

Recursively compute a power of 2 given an input integer n.

```
int pow2 (int n) {
    if (n == 0) {
        return 1;
    }
    return 2 * pow2 (n-1);
}
```

	R4	<- SP (R6)
	R3	
	R2	
	R1	
	RØ	
	LV2	
	LV1	<- FP (R5)
	old FP(R5)	
	RA (old R7)	
	RV	
	arg 1	
	arg n-1	
	arg n	
×F000		

The _____ is stored in the trap vector table.



Review: TRAPs

- Subroutines built into LC-3 to simplify instructions
- Look like normal instructions, but are aliases for TRAP calls
 - o "HALT" is exactly the same as "TRAP x25"
- Each has a corresponding 8-bit Trap Vector
 - The LC-3 will look up the location of the subroutine in the Trap Vector Table
 - o The trap vector table is stored from address x0000 to x00FF

HALT (x25): stops running the program

OUT (x21): takes character (in ASCII) in R0 and prints it on console

PUTS (x22): given mem address in R0, print characters until NULL terminating character ('\0')

GETC (x20): takes character input from console and stores it

in R0