


Reverse Engineering

Class 1


Executable Binaries




Compilation



Executable binaries



EXE (PE)



ELF



MACH-O



.NET assemblies




CLASSFILE

Executable binaries

- Executable instructions
 - by the processor (x86, ARM, etc.)
 - by a virtual machine interpreter (JVM, CPython, etc.)
- Data
 - constants (embedded in instruction opcodes or not)
 - variables
- Debugging information


ELF



- Executable and Linkable Format (ELF)
 - Linux Foundation reference specification
 - ELF headers
 - <glibc>/elf/elf.h (glibc)
 - /usr/include/linux/elf.h (kernel)
 - man elf
 - Specify executable binaries, libraries (shared-objects), objects (.o), kernel modules, the kernel itself
 - Binary format. Why? Could it be different?




ELF




- ELF format is recognized by:
 - kernel
 - when loading modules and drivers
 - sys_execve when launching executable binaries
 - dynamic loader (ld-linux, glibc)
 - when loading shared libraries
 - bootloader
 - when loading the kernel in memory
 - compilers, linkers, assemblers, debuggers and other tools (objdump, readelf, etc.)

ELF




/bin/bash (Linux, x86_64)

ELF




- File header
 - Magic number → “ELF” (0x7F, 0x45, 0x4C, 0x46)
 - 32 or 64 bits
 - Architecture → Linux supports multiple platforms
 - Endianness → Little-endian? Big-endian?
 - ELF version
 - ABI (Application Binary Interface) and ABI version
 - I.e. System V

ELF



- Type (relocatable object, executable binary, shared library)
- Entry point → first executable instruction
- Table offsets (in file)
 - Program Headers
 - Section Headers
- Table sizes (entry size, entries count)
- ELF header size

ELF




typedef struct

```
{  
    unsigned char e_ident[EI_NIDENT]; /* Magic number and other info */  
    Elf64_Half e_type;                  /* Object file type */  
    Elf64_Half e_machine;                /* Architecture */  
    Elf64_Word e_version;                /* Object file version */  
    Elf64_Addr e_entry;                 /* Entry point virtual address */  
    Elf64_Off e_phoff;                  /* Program header table file offset */  
    Elf64_Off e_shoff;                  /* Section header table file offset */  
    Elf64_Word e_flags;                  /* Processor-specific flags */  
    Elf64_Half e_ehsize;                 /* ELF header size in bytes */  
    Elf64_Half e_phentsize;               /* Program header table entry size */  
    Elf64_Half e_phnum;                  /* Program header table entry count */  
    Elf64_Half e_shentsize;               /* Section header table entry size */  
    Elf64_Half e_shnum;                  /* Section header table entry count */  
    Elf64_Half e_shstrndx;                /* Section header string table index */  
} Elf64_Ehdr;
```

file header - elf.h (glibc)


ELF



How to parse an ELF header? (given a stream of bytes and a definition of the header structure)



ELF




How to parse an ELF header? (given a stream of bytes and a definition of the header structure)

```
char* file_buffer = { 0x7F, 0x45, 0x4C, ... };  
Elf64_Ehdr *elf_header = (Elf64_Ehdr*)file_buffer;  
elf_header->e_type; CAST
```

This is what kernel, glibc, objdump, readelf and other tools do for fixed length structures.


Ptr is incremented by sizeof(structure) to continue parsing.

ELF



```
[martin@vmlinwork 1]$ readelf -h main
ELF Header:
  Magic:    7f 45 4c 46 02 01 01 00 00 00 00 00 00 00 00 00
  Class:          ELF64
  Data:           2's complement, little endian
  Version:        1 (current)
  OS/ABI:         UNIX - System V
  ABI Version:   0
  Type:          EXEC (Executable file)
  Machine:       Advanced Micro Devices X86-64
  Version:        0x1
  Entry point address: 0x400400
  Start of program headers: 64 (bytes into file)
  Start of section headers: 6728 (bytes into file)
  Flags:          0x0
  Size of this header: 64 (bytes)
  Size of program headers: 56 (bytes)
  Number of program headers: 9
  Size of section headers: 64 (bytes)
  Number of section headers: 30
  Section header string table index: 27
```


ELF



- **Program headers**

- Table with information to prepare the binary for execution.
Used in runtime too.
 - PT_LOAD → map of virtual memory segments to the executable binary:
 - offset in file
 - Virtual address + alignment
 - permissions (R, W, X)
 - file size
 - memory size
 - completed with 0s if greater than the size on file (i.e. uninitialized global variables)


ELF



- Program headers
 - PT_LOAD
 - What does mapping virtual memory segments to a file mean?
 - If the file offset that we want to map were 0xdf8, what granularity do we have to map it to 0x600000?
 - What happens when segments can be written? Is the file written too?




ELF



- **Program headers**

- PT_LOAD
 - Virtual memory backed by a file. In case of `page_fault`, OS loads the data in memory from the file. Thus, the executable binary is not loaded to memory at once but in chunks as needed.
 - Page granularity (I.e. 4096 bytes). Thus, file is mapped from offset 0 to virtual address `0x600000`.
 - Depends. In this case, file in HDD is not written.


ELF



- Who uses PT_LOAD information from an executable binary?



ELF




- Who uses PT_LOAD information from an executable binary?

Linux kernel: sys_execve maps process virtual address ranges to an executable binary (data, instructions).


Dynamic loader: does the same for dynamic libraries.

ELF



- Note: binaries and dynamic libraries may NOT specify to which virtual addresses have to be mapped
 - Position Independent Executables and Position Independent Code
 - Addresses are randomly chosen
 - In this case, PT_LOAD entry does not specify an absolute virtual address (just offsets, sizes, permissions, alignment, etc.)

ELF



```
static unsigned long elf_map(struct file *filep, unsigned long addr,
    struct elf_phdr *eppnt, int prot, int type,
    unsigned long total_size)

unsigned long map_addr;
unsigned long size = eppnt->p_filesz + ELF_PAGEOFFSET(eppnt->p_vaddr);
unsigned long off = eppnt->p_offset - ELF_PAGEOFFSET(eppnt->p_vaddr);
addr = ELF_PAGESTART(addr);
size = ELF_PAGEALIGN(size);

/* mmap() will return -EINVAL if given a zero size, but a
 * segment with zero filesize is perfectly valid */
if (!size)
    return addr;
```

A screenshot of a debugger interface showing the call stack. The current frame is 'elf_map()' at binfmt_elf.c:346. The stack trace includes: load_elf_binary() at binfmt_elf.c:111, search_binary_handler() at exec.c:1668, exec_binprm() at exec.c:1,668, do_execveat_common() at exec.c:1,668, do_execve() at exec.c:1,834, 0x0, SYSC_execve() at exec.c:1,915, SyS_execve() at exec.c:1,910, 0x0, and do_syscall_64() at common.c:2.


File Tasks Problems Executables Debugger Console Memory Progress Search

[C/C++ Attach to Application] gdb (7.12.1)

0x8048000


**main_32 mapped in Linux kernel (x86_64) using PT_LOAD information –
elf_map – fs/binfmt_elf.c. VirtAddress in PT_LOAD for executable segment is
0x08048000**

ELF



- **PT_INTERP** → binary interpreter (dynamic loader)
 - `/lib64/ld-linux-x86-64.so.2`
 - `<glibc>/elf/` (source code)
 - Executes before the binary and loads libraries to which the binary dynamically links. It may not exist (self-contained binaries), but there is generally one.
- **PT_DYNAMIC** → information for the dynamic linker: in which virtual address is this information available? (according to **PT_LOAD** mapped from the file to a virtual RW segment)
- **PT_PHDR** → location of Program Headers table in virtual memory

ELF



```
[martin@vmlinwork 1]$ readelf -l main
```

```
Elf file type is EXEC (Executable file)
```


```
Entry point 0x400400
```

```
There are 9 program headers, starting at offset 64
```

Program Headers:

Type	Offset	VirtAddr	PhysAddr	Flags	Align
	FileSiz	MemSiz			
PHDR	0x0000000000000040	0x00000000000400040	0x00000000000400040		
	0x000000000000001f8	0x000000000000001f8		R E	8
INTERP	0x00000000000000238	0x00000000000400238	0x00000000000400238		
	0x0000000000000001c	0x0000000000000001c		R	1
[Requesting program interpreter: /lib64/ld-linux-x86-64.so.2]					
LOAD	0x0000000000000000	0x00000000000400000	0x00000000000400000		
	0x000000000000006e4	0x000000000000006e4		R E	200000
LOAD	0x00000000000000e08	0x00000000000600e08	0x00000000000600e08		
	0x0000000000000021c	0x00000000000000238		RW	200000
DYNAMIC	0x00000000000000e20	0x00000000000600e20	0x00000000000600e20		
	0x000000000000001d0	0x000000000000001d0		RW	8


ELF



- **Section headers**

- Map of executable binary sections in HDD (file). Each section is an “information unit”
 - Section name
 - Section type. In example:
 - Symbols table
 - Strings table
 - Relocations table
 - Dynamic symbols table
 - Hashes table
 - Dynamic linking table (referenced from Program Headers)

ELF




- Contains
 - Section offset in file
 - Section size in file (in memory if section were of NOBITS type)
 - Section virtual address
 - Alignment (to be loaded/mapped into the virtual address space; in HDD sections are contiguous)
 - Permissions (Read? Write? Execute?)
 - Entry size, if section were a table

ELF




- This table (in file) is NOT mapped into the created process virtual address space
 - I.e.: `readelf -S main_32`
 - “There are 36 section headers, starting at offset 0x2700:”
 - However, `PT_LOAD` maps a maximum of 0x00124 file bytes starting at offset 0x000f00. That is up to offset 0x1024.
- However, data referenced from this table (sections themselves) may be mapped. Example: `.text` section. See Program Headers table and calculate file offsets overlap.
- This table is used when the binary is loaded. I.e.: Where does memory for `.bss` section with uninitialized global variables have to be allocated?

ELF



```
typedef struct
{
    Elf64_Word    sh_name;          /* Section name (string tbl
index) */
    Elf64_Word    sh_type;          /* Section type */
    Elf64_Xword   sh_flags;         /* Section flags */
    Elf64_Addr   sh_addr;          /* Section virtual addr at
execution */
    Elf64_Off    sh_offset;         /* Section file offset */
    Elf64_Xword   sh_size;          /* Section size in bytes */
    Elf64_Word    sh_link;          /* Link to another section */
    Elf64_Word    sh_info;          /* Additional section
information */
    Elf64_Xword   sh_addralign;     /* Section alignment */
    Elf64_Xword   sh_entsize;        /* Entry size if section
holds table */
} Elf64_Shdr;
```

ELF



```
[martin@vmlinwork 1]$ readelf -S main
There are 35 section headers, starting at offset 0x2270:
```

Section Headers:


[Nr]	Name	Type	Address	Offset
	Size	EntSize	Flags	Link Info Align
[0]		NULL	0000000000000000	00000000
	0000000000000000	0000000000000000		0 0 0
[1]	.interp	PROGBITS	000000000400238	00000238
	00000000000001c	0000000000000000	A	0 0 1
[2]	.note.ABI-tag	NOTE	000000000400254	00000254
	000000000000020	0000000000000000	A	0 0 4
[3]	.note.gnu.build-i	NOTE	000000000400274	00000274
	000000000000024	0000000000000000	A	0 0 4
[4]	.gnu.hash	GNU_HASH	000000000400298	00000298
	00000000000001c	0000000000000000	A	5 0 8
[5]	.dynsym	DYNSYM	0000000004002b8	000002b8
	000000000000060	000000000000018	A	6 1 8
[6]	.dynstr	STRTAB	000000000400318	00000318
	00000000000003d	0000000000000000	A	0 0 1
[7]	.gnu.version	VERSYM	000000000400356	00000356
	000000000000008	000000000000002	A	5 0 2
[8]	.gnu.version_r	VERNEED	000000000400360	00000360
	000000000000020	0000000000000000	A	6 1 8
[9]	.rela.dyn	RELA	000000000400380	00000380
	000000000000030	000000000000018	A	5 0 8
[10]	.rela.plt	RELA	0000000004003b0	000003b0
	000000000000018	000000000000018	AI	5 23 8
[11]	.init	PROGBITS	0000000004003c8	000003c8
	000000000000017	0000000000000000	AX	0 0 4

ELF



- Symbols table and Strings table
 - Symbol name (index in strings table)
 - Symbol type (not specified, function, object, file, section, TLS data, etc.)
 - Symbol visibility (local, global, weak, etc.)
 - Symbol section
 - Symbol value (i.e. offset where symbol is located within the section)
 - Symbol size

ELF




typedef struct

```
{  
Elf64_Word    st_name;  
unsigned char st_info;  
unsigned char st_other;  
Elf64_Section st_shndx;  
Elf64_Addr st_value;  
Elf64_Xword   st_size;  
} Elf64_Sym;
```

```
/* Symbol name (string tbl index) */  
/* Symbol type and binding */  
/* Symbol visibility */  
/* Section index */  
/* Symbol value */  
/* Symbol size */
```

ELF



```
extern int var_a;
```

```
int var_a = 2;
```

```
static int var_b = 1;
```

```
extern int func_a (void);
```


```
static void func_b (void);
```

```
int main (void) {  
    return func_a();  
}
```

```
static void func_b (void) {  
}
```

main.c

ELF




Symbol table '.syms' contains 13 entries:

Num:	Value	Size	Type	Bind	Vis	Ndx	Name
0:	0000000000000000	0	NOTYPE	LOCAL	DEFAULT	UND	
1:	0000000000000000	0	FILE	LOCAL	DEFAULT	ABS	main.c
2:	0000000000000000	0	SECTION	LOCAL	DEFAULT	1	
3:	0000000000000000	0	SECTION	LOCAL	DEFAULT	3	
4:	0000000000000000	0	SECTION	LOCAL	DEFAULT	4	
5:	0000000000000004	4	OBJECT	LOCAL	DEFAULT	3	var_b
6:	000000000000000b	7	FUNC	LOCAL	DEFAULT	1	func_b
7:	0000000000000000	0	SECTION	LOCAL	DEFAULT	6	
8:	0000000000000000	0	SECTION	LOCAL	DEFAULT	7	
9:	0000000000000000	0	SECTION	LOCAL	DEFAULT	5	
10:	0000000000000000	4	OBJECT	GLOBAL	DEFAULT	3	var_a
11:	0000000000000000	11	FUNC	GLOBAL	DEFAULT	1	main
12:	0000000000000000	0	NOTYPE	GLOBAL	DEFAULT	UND	func_a


main.o → gcc -o main.o main.c

ELF



main.o → string table

ELF




```
Symbol table '.symtab' contains 71 entries:
```

Num:	Value	Size	Type	Bind	Vis	Ndx	Name
0:	0000000000000000	0	NOTYPE	LOCAL	DEFAULT	UND	_
57:	0000000000000000	0	FUNC	GLOBAL	DEFAULT	UND	__libc_start_main@@GLIBC_
58:	0000000000601020	0	NOTYPE	GLOBAL	DEFAULT	24	__data_start
59:	0000000000000000	0	NOTYPE	WEAK	DEFAULT	UND	__gmon_start
60:	00000000004005a8	0	OBJECT	GLOBAL	HIDDEN	15	__dso_handle
61:	00000000004005a0	4	OBJECT	GLOBAL	DEFAULT	15	__IO_stdin_used
62:	0000000000400520	101	FUNC	GLOBAL	DEFAULT	13	__libc_csu_init
63:	0000000000601028	0	NOTYPE	GLOBAL	DEFAULT	25	_end
64:	0000000000400400	43	FUNC	GLOBAL	DEFAULT	13	_start
65:	0000000000601024	0	NOTYPE	GLOBAL	DEFAULT	25	bss_start
66:	00000000004004f6	32	FUNC	GLOBAL	DEFAULT	13	main
67:	0000000000000000	0	NOTYPE	WEAK	DEFAULT	UND	__Jv_RegisterClasses
68:	0000000000601028	0	OBJECT	GLOBAL	HIDDEN	24	TMC END

main → linked binary (against glibc)

ELF




- Dynamic table
 - It's a “map” to used by the dynamic linker in run time.
 - Required shared libraries (names)
 - Tables addresses in memory and sizes
 - Hashes, Strings, Symbols, Relocation, etc.
 - GOT and PLT tables addresses in memory
 - Initialization and finalization function addresses
 - Ends in NULL

ELF



- Is information redundant with Sections Table?
 - Sections Table is not mapped to the process memory.
 - Dynamic Table is mapped. Why? I.e.:
 - Kernel loads an executable binary
 - Control is transferred to the interpreter (dynamic loader)
 - Dynamic loader needs to know, among other things, which libraries does the executable binary link and map them to the process memory (example: libc)

ELF



```
typedef struct
{
    Elf64_Sxword d_tag;           /* Dynamic entry type */
    union
    {
        Elf64_Xword d_val;       /* Integer value */
        Elf64_Addr d_ptr;        /* Address value */
    } d_un;
} Elf64_Dyn;
```

d_tag value may be: DT_NULL, DT_NEEDED,
DT_PLTGOT, DT_STRTAB, DT_SYMTAB, DT_RELAT,
DT_RELASZ, etc.

ELF




```
[martin@vmlinwork 1]$ readelf -d main
```

```
Dynamic section at offset 0xe20 contains 24 entries:
```

Tag	Type	Name/Value
0x0000000000000001	(NEEDED)	Shared library: [libc.so.6]
0x000000000000000c	(INIT)	0x4003c8
0x000000000000000d	(FINI)	0x400594
0x0000000000000019	(INIT_ARRAY)	0x600e08
0x000000000000001b	(INIT_ARRAYSZ)	8 (bytes)
0x000000000000001a	(FINI_ARRAY)	0x600e10
0x000000000000001c	(FINI_ARRAYSZ)	8 (bytes)
0x000000006ffffef5	(GNU_HASH)	0x400298
0x0000000000000005	(STRTAB)	0x400318
0x0000000000000006	(SYMTAB)	0x4002b8
0x000000000000000a	(STRSZ)	61 (bytes)
0x000000000000000b	(SYMENT)	24 (bytes)
0x0000000000000015	(DEBUG)	0x0
0x0000000000000003	(PLTGOT)	0x601000
0x0000000000000002	(PLTRELSZ)	24 (bytes)
0x0000000000000014	(PLTREL)	RELA
0x0000000000000017	(JMPREL)	0x4003b0
0x0000000000000007	(RELA)	0x400380
0x0000000000000008	(RELASZ)	48 (bytes)
0x0000000000000009	(RELAENT)	24 (bytes)
0x000000006fffffe	(VERNEED)	0x400360
0x000000006ffffff	(VERNEEDNUM)	1
0x000000006fffff0	(VERSYM)	0x400356
0x0000000000000000	(NULL)	0x0


ELF



If a dynamic loader has to load an executable binary and only knows its base virtual address,
how is it possible to reach the Dynamic Table?




ELF



If a dynamic loader has to load an executable binary and only knows its base virtual address, **how is it possible to reach the Dynamic Table?**


- Starts reading from the base address
- Jumps File Header (64 bytes) to get the Program Headers table
- Parses it and finds the Dynamic Table address
- Then it's possible, for example, to see which libraries are required (DT_NEEDED), locate library names (Symbols and Strings tables) and load them
- Kernel already did the heavy-lifting of mapping all these information in the executable binary file to virtual memory

ELF




- Relocations Table
 - When an object calls an external function, the offset or address is not known until link time
 - Placeholder:
 - CALL ??? → + relocation entry
 - Then same happens for global variables present in external objects
 - When linking, placeholders are updated with the correct location

ELF



- Relocate a binary or a library
 - Libraries are usually PIC nowadays (Position Independent Code)
 - Binaries are usually not PIE in x86 and PIE in x86_64
 - If not PIC/PIE, there may be absolute addresses (i.e. CALL absolute-address). If PIC/PIE, relative addressing is used but relocations for the GOT/PLT tables are needed (after run time symbols resolution)
 - Not every binary is relocatable: depends on relocation information availability

ELF



```
Relocation section '.rela.text' at offset 0x248 contains 1 entries:  
Offset           Info           Type            Sym. Value  Sym. Name  
000000000005  000c00000002 R_X86_64_PC32    0000000000000000 func_a - 4
```


```
0000000000000000 <main>:
```

0:	55	push %rbp
1:	48 89 e5	mov %rsp,%rbp
4:	e8 00 00 00 00	callq 9 <main+0x9>
9:	5d	pop %rbp
a:	c3	retq

main.o

Relocation in .text: in offset 5 insert the value of the func_a symbol, after resolution (link time). Value is 32 bits long (call near).

ELF




```
[martin@mlinwork 1]$ readelf -r main

Relocation section '.rela.dyn' at offset 0x380 contains 2 entries:
  Offset          Info           Type            Sym. Value   Sym. Name + Addend
0000000600ff0  000200000006 R_X86_64_GLOB_DAT 0000000000000000 __libc_start_main@GLIBC_2.2.5 + 0
0000000600ff8  000300000006 R_X86_64_GLOB_DAT 0000000000000000 __gmon_start__ + 0


Relocation section '.rela.plt' at offset 0x3b0 contains 1 entries:
  Offset          Info           Type            Sym. Value   Sym. Name + Addend
0000000601018  000100000007 R_X86_64_JUMP_SLO 0000000000000000 puts@GLIBC_2.2.5 + 0
```

ELF



- Data section
 - .data
 - Initialized global variables
 - .rodata → read-only
 - .bss
 - Uninitialized global variables
 - Not in file, only in memory
 - Initialized with 0s

ELF



```
#include <stdio.h>
```

```
int a;
```

```
int b = 1;
```

```
const int c = 2;
```


```
int main(int argc, char* argv[]){
```

```
    printf("holaln");
```

```
    return 0;
```

```
}
```

ELF



```
[martin@vmlinwork 1]$ readelf -x 25 main
```

Section '.bss' has no data to dump.

```
[martin@vmlinwork 1]$ readelf -x 24 main
```

Hex dump of section '.data':

```
0x00601020 00000000 01000000
```

.....

```
[martin@vmlinwork 1]$ readelf -x 15 main
```


Hex dump of section '.rodata':

```
0x004005a0 01000200 00000000 00000000 00000000 .....
```

```
0x004005b0 02000000 686f6c61 00
```


....hola.

ELF



- Executable instructions: .text
 - Architecture opcodes
 - Functions implementation
 - *glibc* static stubs (if linked)
 - I.e. initialization routines like `_start` (<glibc>/sysdeps/x86_64/start.S) and `__libc_csu_init` (<glibc>/csu/elf-init.c)
 - Readable and executable segment (not writable)


ELF



```
[martin@vmlinwork 1]$ objdump -d main | grep -A 14 -e "<_start>"
```


```
0000000000400400 <_start>:
400400: 31 ed          xor    %ebp,%ebp
400402: 49 89 d1        mov    %rdx,%r9
400405: 5e              pop    %rsi
400406: 48 89 e2        mov    %rsp,%rdx
400409: 48 83 e4 f0        and   $0xfffffffffffffff0,%rsp
40040d: 50              push   %rax
40040e: 54              push   %rsp
40040f: 49 c7 c0 90 05 40 00  mov   $0x400590,%r8
400416: 48 c7 c1 20 05 40 00  mov   $0x400520,%rcx
40041d: 48 c7 c7 f6 04 40 00  mov   $0x4004f6,%rdi
400424: ff 15 c6 0b 20 00        callq *0x200bc6(%rip)      # 600ff0 <_DYNAMIC+0x1d0>
40042a: f4              hlt
40042b: 0f 1f 44 00 00        nopl   0x0(%rax,%rax,1)
```

ELF




- Global Offset Table (GOT)
 - A binary or library may use global variables and functions exported by other libraries
 - Libraries are Position-Independent-Code (PIC) nowadays
 - When a binary or library are compiled, the virtual address of external functions and global variables in not known
 - CALL ??? → how can we fix this?

ELF




- Global Offset Table (GOT)
 - Table in memory for each binary and library
 - Memory address of extern functions and variables (from other libraries)
 - It's filled in *runtime* with absolute values (virtual addresses)
 - MOV *<variable-GOT-entry>
 - Addressing relative to GOT

ELF



- Procedure Linkage Table (PLT)
 - Trampolines to call external functions using the GOT (one trampoline per external function)
 - Executable code (executable segment)
 - Instead of `CALL *<function-GOT-entry>`, it is `CALL/JMP <function-PLT-entry>`

ELF



- Procedure Linkage Table (PLT)
 - Trampoline executes `JMP *<function-GOT-entry>`
 - When GOT entry is resolved, jumps to the function
 - When GOT entry is not resolved (initial state), trampoline invokes the dynamic loader for resolution

ELF



```
int main(void) {
    int ret = -1;
    pthread_t thread_info;
    pthread_attr_t thread_attr;


    printf("Main thread PID: %d\n", getpid());
    printf("Main thread TID: %d\n", syscall(__NR_gettid));
```

0000000000400a59: push %rbp
0000000000400a5a: mov %rsp,%rbp
0000000000400a5d: sub \$0x60,%rsp
51 int ret = -1;
0000000000400a61: movl \$0xffffffff,-0x4(%rbp)
55 printf("Main thread PID: %d\n", getpid)
0000000000400a68: callq 0x4007e0 <getpid@plt>

“main” ELF (x86_64) - getpid call example through PLT

PLT segment

ELF



```

00000000004007ac:    nopl    0x0(%rax)
pthread_create@plt:
00000000004007b0:    jmpq    *0x201862(%rip)      # 0x602018
00000000004007b6:    pushq    $0x0
00000000004007bb:    jmpq    0x4007a0
puts@plt:
00000000004007c0:    jmpq    *0x20185a(%rip)      # 0x602020
00000000004007c6:    pushq    $0x1
00000000004007cb:    jmpq    0x4007a0
sigaction@plt:
00000000004007d0:    jmpq    *0x201852(%rip)      # 0x602028
00000000004007d6:    pushq    $0x2
00000000004007db:    jmpq    0x4007a0
getpid@plt:
00000000004007e0:    jmpq    *0x20184a(%rip)      # 0x602030
00000000004007e6:    pushq    $0x3
00000000004007eb:    jmpq    0x4007a0
printf@plt:

```

Relocation entry number


0x602028

go to dynamic loader


Take the address from GOT PLT entry

Relocation section '.rela.plt' at offset 0x668 contains 12 entries:						
Offset	Info	Type	Sym.	Value	Sym.	Name + Addend
000000602018	000100000007	R_X86_64_JUMP_SLO	0000000000000000		pthread_create@GLIBC_2.2.5	+ 0
000000602020	000300000007	R_X86_64_JUMP_SLO	0000000000000000		puts@GLIBC_2.2.5	+ 0
000000602028	000400000007	R_X86_64_JUMP_SLO	0000000000000000		sigaction@GLIBC_2.2.5	+ 0
000000602030	000500000007	R_X86_64_JUMP_SLO	0000000000000000		getpid@GLIBC_2.2.5	+ 0
000000602038	000600000007	R_X86_64_JUMP_SLO	0000000000000000		printf@GLIBC_2.2.5	+ 0
000000602040	000800000007	R_X86_64_JUMP_SLO	0000000000000000		pthread_attr_init@GLIBC_2.2.5	+ 0
000000602048	000900000007	R_X86_64_JUMP_SLO	0000000000000000		syscall@GLIBC_2.2.5	+ 0
000000602050	000a00000007	R_X86_64_JUMP_SLO	0000000000000000		sigemptyset@GLIBC_2.2.5	+ 0

Dynamic Loader




- Dynamic loader
 - As an interpreter, executes first
 - Then control is transferred to the binary entry point
 - Loads dynamically linked libraries
 - Resolves symbols
 - Loads libraries in runtime (`dlopen`)
 - Fills the GOT table in runtime (uses relocation information to determine where to write memory addresses once symbols are resolved)



Demo 1.1


Kernel parsing ELF format to launch an executable binary (sys_execve)



Demo 1.2

GOT + PLT call (dynamic linker)


ELF




- \$ gcc -o main -g main.c
- \$ echo \$?
- \$ readelf -a ./main
- \$ objdump -d ./main | grep -A 500 -e "<_start>"
- \$ gdb main
 - (gdb) break main
 - (gdb) run
 - (gdb) x/10xb 0x400000
- \$ cat /proc/<PID>/maps

>_


Lab 1.1




- Patch “main” to:
 - return 5 (instead of 0)
 - infinitely loop
 - print “σ” to *stdout*
- Debug with *gdb* each case
- Patch with *gdb* in runtime each of the previous cases



Lab 1.2



- Debug the dynamic loader parsing ELF format when loading a shared library
- Debug the kernel parsing ELF format when a module (.ko) is loaded



References



- <https://refspecs.linuxfoundation.org>
- https://sourceware.org/git/?p=libc.git;a=blob_plain;f=elf/elf.h;hb=HEAD
- <https://linux.die.net/man/5/elf>