« <u>The Scarygliders X11rdp-O-Matic and RDPsesconfig</u>: v1.1 released, V2 now available

<u>ssh – Secure your systems with ssh on Linux a</u> <u>puTTY on Windows – Part 1</u>

Get audio with your xrdp/x11rdp connections, LAN or Remote! Updated! Windows Clients!

By Kevin Cave, on April 6th, 2012

Okay so I did a bit of research, and found a method of forwarding audio from your remote RDP Linux desktops.

The methods work for RDP connections on your local LAN, and also for connections to remote systems via ssh tunnels.

Here's how...

2012-04-19 Article Updated


Changelog:

Added a section for how to get audio on Windows Clients from the linux RDP target

<u>Prerequisites</u>

- The client system needs PulseAudio client and server installed. These days it's installed by default if you've installed a full desktop Debian/Ubuntu distribution. Update: Also works for Windows, which also needs PulseAudio – see new section for Windows below!
- The target system needs the PulseAudio client libraries installed. No need for the PulseAudio server, although this is probably already installed if you've installed the Gnome Desktop and/or Unity.

A) Local LAN RDP connections...



Here's the basic setup; a client system and the target system running Xrdp/X11rdp.

The client system's IP address is 192.168.1.9.

The target systems's IP address is 192.168.1.254.

The system you're going to listen to audio on is the rdp client, but it's the PulseAudio server. The RDP target system will send all audio data to the PulseAudio server running on your client machine.

1) On the Client System

Ensure the PulseAudio TCP native protocol module is set up on your client system.

Open up a terminal window on your local system, and type the following;

```
pacmd list-modules | grep module-native-protocol-tcp
```

If the response is blank, then this module is not loaded. To load it, type the following;

```
pactl load-module module-native-protocol-tcp auth-ip-acl="<ip address or network range>"
```

Where <ip address or network range > can be a single ip address - for example 192.168.1.254 - or a network range such as 192.168.1.0/24. The former will limit access to the PulseAudio server running on your client system. The latter will grant PulseAudio server access to all systems on that network. You can also specify a list of IP addresses separated with a semicolon. For example; "192.168.1.101;192.168.1.102;192.168.1.254", which would limit access to the systems on the LAN with those addresses.

Once you've loaded this module successfully, you'll see a number returned – this is the module ID number. You can unload the module if you wish to try different configurations, by typing pactl unload-module <ID number>.

2) On the Target RDP System

In the user's ~/.xsession file, add this line BEFORE any lines which start your gnome or unity-2D session...

```
export PULSE_SERVER=<ip address of your client machine>
```

So for example, my client machine's address is 192.168.1.9. The line would read export PULSE_SERVER=192.168.1.9 Save the .xsession file.

Here's what my .xsession file looks like;

```
export PULSE_SERVER=192.168.1.9:4713
gnome-session --session=gnome-fallback
```

3) Connect via RDP

From your client machine, use your favorite RDP client to connect to the target RDP system as usual.

Any audio output from programs running in the RDP session should now automatically be heard on your client system.

Also, if you right-click on the audio icon on your desktop (I'm using the gnome-classic desktop for my RDP sessions), then click on Sound Preferences, you can control the audio output of the RDP session, just as if the sound hardware were on the RDP target machine:)



Here's a screenshot of a gnome-classic session running on rdesktop. I brought up the Sound Preferences and clicked the Hardware tab. Thanks to Pulseaudio's magic, the sound card on my client machine appears - as if it's installed on the RDP server.

Magic, I say. Magic!

I'm running RhythmBox in that session as I type this, and the audio's coming through just fine;)

And that's it for audio on RDP for the local LAN. Next up is doing the same on a truly remote system...

B) Audio on RDP on remote connections...


The method is similar to the above for LAN connections, except that we're going to be doing this through ssh tunnels.

Prerequisites

- The client system needs PulseAudio client and server installed. These days it's installed by default if you've installed a full desktop Debian/Ubuntu distribution.
- The target system needs the PulseAudio client libraries installed. No need for the PulseAudio server, although this is probably already installed if you've installed the Gnome Desktop and/or Unity.

1) On the Client System

remote VPS system too.



We'll need an SSH tunnel between the client machine, and your target machine.

If you don't know how that's done, I suggest you read the article I wrote recently on how to do exactly that ;)

For the purposes of this article, I'm going to form an ssh tunnel between my client, and a machine on my LAN at 192.168.1.254 - the principle is exactly the same, and I've tried this on a

I've tried this procedure on a remote machine over the internet (a VPS), and the sound was choppy when playing sound from Google Chrome (a YouTube video. I don't know if that's a result of a bursty connection or what, so, your results may vary your results for this might be brilliant, or just as bad as the result I achieved, so, be warned.

When I ran Rhythmbox though and played a radio station, the sound came through just fine.

Also, when I ran Gnome Terminal and caused an "audible bell" by pressing backspace when no characters were left to delete, the sound was choppy.

So, basically mixed results for remote audio over the internet – Your Mileage May Vary, etc etc

As with the LAN scenario, ensure the PulseAudio TCP native protocol module is set up on your client system.

Open up a terminal window on your local system, and type the following;

```
pacmd list-modules | grep module-native-protocol-tcp
```

If the response is blank, then this module is not loaded. To load it, type the following;

```
pactl load-module module-native-protocol-tcp auth-ip-acl="127.0.0.1"
```

Since we're going to use an SSH tunnel for this, all we need is access allowed on the locahost interface. You can, if you're going to be accessing RDP systems on the local LAN as well as remote, say "127.0.0.1;<ip address or range>" as we did above, though.

2) On the Target RDP System

In the user's ~/.xsession file, add this line BEFORE the line(s) which start your gnome or unity-2D session...

```
export PULSE_SERVER=<localhost:4713>
```

We'll be using SSH to tunnel port 4713 from the target RDP system to your local client system, so audio will play on that local client system.

Save the .xsession file.

Here's what my .xsession file looks like;

```
export PULSE_SERVER=localhost:4713
gnome-session --session=gnome-fallback
```

3) Form the SSH tunnel connection between your client system and the SSH target system.

If your remote ssh target system is also the RDP server;

```
ssh -c arcfour -R localhost:4713:localhost:4713 -L3390:localhost:3389 <ip address of ssh target system>
```

We just set up two tunnels. The first one handles the PulseAudio connection, the second handles the RDP connection.

So in my case;

```
ssh -c arcfour -R localhost:4713:localhost:4713 -L3390:localhost:3389 192.168.1.254
```

If your RDP server sits on a LAN behind your ssh server;

ssh -c arcfour -R localhost:4713:<ip address of RDP server>:4713 -L
localhost:3390:<ip address of RDP server>:3389 <ip address of ssh target
system>

4) Connect to your RDP server via the ssh tunnel

I'm using rdesktop -a16 -g 1820x900 localhost:3390 for my connection as an example.

Sound should now be routed through your SSH tunnel to your PulseAudio server on your local client.:)



Again, here's an RDP screenshot of my LAN session, tunneled via SSH, with Sound Preferences and Rhythmbox running...




And I tried the same with a truly remote system. The same method with a VPS I have. Rhythmbox sent its output via the ssh tunnel to my local PulseAudio server. The sound was perfect.

I guess it's down to how the program in use sends it's output.

And now for Windows clients: D

That's right, you read it right – you can get audio working from your Linux RDP server to your Windows RDP client machine, Like A Boss. Here's how...

A) Local LAN RDP connections...



Same basic scenario as above.

I have a Linux target RDP server on my LAN at 192.168.1.249

I have a Windows client on the LAN at 192.168.1.10

1) On the Windows client system...

You can obtain Windows PulseAudio binaries, from the FreeDesktop website here.

Click on the link saying "A Zipfile containing preview binaries..." and save the file somewhere.






Extract the files in the zip archive to somewhere on your drive. I'm going to extract to C:\PulseAudio.


Edit C:\PulseAudio\etc\pulse\default.pa

Next you have to configure PulseAudio to accept connections on the LAN. Now, you'll need a text editor which can handle Unix newline



characters – Notepad won't. I've installed a free editor called Notepad++ .

Open up the file C:\PulseAudio\etc\pulse\default.pa




Locate the line in the file saying #load-module module-null-sink

Add the following underneath it

load-module module-native-protocol-tcp listen=0.0.0.0 auth-anonymous=1


NOTE: This means the PulseAudio server running on your client machine will accept connections from anywhere on your local LAN. You can reconfigure this by using the options I described above in the Linux Client section to limit who can connect from where.

Save the file.



Open the file C:\PulseAudio\etc\pulse\daemon.conf

Scroll down to the very end of the file.




At the end of the file, add the following line:

exit-idle-time = -1

This will instruct the PulseAudio daemon not to shut down – otherwise by default it would shut down after 20 minutes of no audio being sent to it.

Save the file and exit the editor.



"C:\PulseAudio\etc\pulse\default.pa"


You may have to do this twice, first time around.

Next up, start a Command Line session. Windows 7 users will need to do this as Administrator.

Change to the PulseAudio bin directory: cd c:\PulseAudio\bin


Start PulseAudio with the following parameters:

pulseaudio.exe -p "C:\PulseAudio\lib\pulse1.1\modules" -nF



The very first run of PulseAudio just stopped.

I pressed the Up Arrow key and then tried running the command again, this time the PulseAudio Daemon loaded.



On Windows 7, the Windows Firewall Alert box popped up, asking you what you want to do.

Click on Allow access, because naturally, we need to be able to send sound data to your client machine;)

You now have a PulseAudio server running on your Windows client machine :)

2) On your RDP target machine...



Edit the .xsession file in the home directory of the target user you will log in as, on the target RDP system.

Add the following line at the very top, before any other lines:


export PULSE_SERVER=192.168.1.10:4713

See the screenshot for clarification. Save the file and exit the editor.

3) Connect via Terminal Services Client to your RDP target machine



You don't need to do anything special for the RDP client configuration – just set your ip address and Display settings if you wish, then connect.




After logging in, notice that, if I hover the mouse cursor over the Volume icon in my specially customized Gnome Classic desktop, it says "WaveOut on Microsoft Sound Mapper" !!

Never thought I'd see anything like that on a Linux Desktop – tee hee!

Now go and run something which produces audio, and rejoice when sound is heard from your Windows client machine's loudspeakers :D



I fired up Firefox and started playing something from YouTube – grooving along as I type this;)



And thanks to the magic of PulseAudio, sound preferences work from the RDP server too – you can change volume from there and even sound balance works :)

And that's it for a LAN connection – but what about an RDP session to a remote RDP server? As the Linux section above, this can be achieved via an SSH tunnel...

B) Audio on RDP on remote connections...



We'll need an SSH tunnel between the client machine, and your target machine.

If you don't know how that's done, I suggest you <u>read the article I</u> <u>wrote recently on how to do exactly that</u>;)

For the purposes of this article, I'm going to form an ssh tunnel between my client, and a machine on my LAN at 192.168.1.254 – the principle is exactly the same as if the RDP server was at a remote location over the internet, and I've tried this on a remote VPS system too.


I'm assuming you've installed PulseAudio onto your Windows client system as outlined above, and it's configured as above, so let's skip that bit and go straight for the SSH jugular...


1) Configure puTTY On the Client System...

Load up puTTY and create a new session as follows:

puTTY config session name and host IP address

Configure a Session Name and enter the Host IP address.





Configure the first tunnel for the RDP data;


Make sure the Local radio-button is selected as shown.

Source port is

3391 (Windows uses 3390 already).

Destination is localhost: 3389.

Click Add.



Configure another tunnel for the PulseAudio data.


Make sure Remote radio-button is selected, as shown.

Source should be 4713

Destination Should be localhost: 4713

Click on Add.

Should look something like this




The tunnels configuration should look something like as shown.



Oh, and remember to go back to Session, and save the configuration, otherwise you'll have to do this all over again next time;)

2) On the remote RDP server system...




Edit the .xsession file in the target user's home directory on the target RDP system, such that the first line reads;

export PULSE_SERVER=localhost:4713

Save and exit.

3) Connect via puTTY/SSH...

Connect via puTTY




Connect to the remote system via puTTY, using the session details you saved from above.

The two tunnels should now be active. Let's see...

4) Connect to an RDP session...



This time round, we're connecting to localhost:3391 – that's the RDP tunnel formed by the puTTY connection.




Good, the RDP tunnel is working, so let's log in...

And the PulseAudio tunnel is working :D

And bingo! The PulseAudio tunnel is working!

Play something and it should work – it did for me:)





Lastly, here's the SSH tunnel to my VPS. The above setup worled on that too, and audio was playing fine –

you may get some distortion on a truly remote system if you're running the PulseAudio control panel like I am on the remote machine.

And that's it! :)

Please let me know how you got on with this!

Rate This Article

Rating: 9.0/10 (16 votes cast)

Get audio with your xrdp/x11rdp connections, LAN or Remote! Updated! Windows Clients!, 9.0 out of 10 based on 16 ratings

Share the knowledge :























Related Posts:



X11rdp, Ubuntu 11.10, Gnome 3,



ssh – Secure your systems with ssh



Install xrdp and X11rdp – the



April 6th, 2012 | Tags: <u>Debian</u>, <u>Linux</u>, <u>RDP and Audio</u>, <u>RDP and Linux</u>, <u>Remote Desktop Protocol</u>, <u>tips and tricks</u>, <u>Ubuntu</u>, <u>Windows</u>, <u>Windows 7</u>, <u>x11rdp</u>, <u>xrdp</u> | Category: <u>audio</u>, <u>Linux Tips & Tricks</u>, <u>Pulseaudio</u>, <u>puTTY</u>, <u>RDP</u>, <u>ssh</u>, <u>Technical</u>, <u>Windows 7</u>

25 comments to Get audio with your xrdp/x11rdp connections, LAN or Remote! Updated! Window Clients!

Wilhelm Moser

2012/04/18 at 19:14 · Reply

first of all thank you for your detailed descriptions... GREAT. Do you think there is a way to route audio regularely to mstsc?

Thank you - willi

Rating: 0 (from 0 votes)

Kevin Cave

2012/04/19 at 08:24 · Reply

Wilhelm, greetings!

There probably is a way to do this, I'm working on it – it will probably be by using PulseAudio on the Windows client machine.

I'll update the article if and when I get this working.

Stay tuned;)

Regards.

Rating: 0 (from 0 votes)

Eric

2012/11/18 at 06:46 · Reply

From http://xrdp-devel.766250.n3.nabble.com/Xrdp-devel-audio-redirection-td4015803.html it looks like you'd just have to put –enable-simplesound in the file. Any thoughts?

Rating: +2 (from 2 votes)

Kevin Cave

2012/04/19 at 15:22 · Reply

Willhelm,

I updated the article with all you'll need to hear audio on your Windows client – let me know how you get on :)

Regards

Rating: +1 (from 1 vote)

Wilhelm MOSER

2012/04/23 at 02:00 · Reply

Thank you Kevin for your help but that is not what I really require.

It is no problem to use pulseaudio for rdp-audio on a dedicated client - thanks to your work on it...

My Problem is:

assume there is a blackbox, say on a boat, serving wlan to any clients.

In the charter bizz every skipper nowadays likes to use his own notebook or tablet. Usually they have a notebook with some WindOS in it... and mstsc.exe very well unknown to them on their own box.

How easy it could be to provide them a blackbox.rdp on their desktop having their "marine radio" natively.

On the other hand, a boat is usually small enough to provide audio directly from the "blackbox" i.e. with bluetooth headsets. But providing it really professional....

I think the trick is to clone ms-ts or to patch x11rdp to send audio on the same port ms-ts does..

Anyways.. thank you and do not throw much time in... I can, have to, live with a less professional solution... brgds

Rating: 0 (from 0 votes)

Kevin Cave

2012/04/23 at 08:34 · Reply

Heh:P

Quite possibly, the freerdp project might do what you want – I haven't spent a lot fo time looking into what FreeRDP can do yet – and I don't think I'll have the time for the rest of this year – I am in the middle of a whole load of personal stuff right now which is eating all my time.

Anyway, hope you find the solution you're lookming for – if you do, let me know;)

Regards

Rating: 0 (from 0 votes)

<u>Chaitanya</u>

2012/06/27 at 12:01 · Reply

Dear Kevin,

I have been a quite old fan of you for the work that you have done till now especially for Remote Desktop system with Linux. I have been following all your posts and have tested almost all of them. They were all great to follow.

This time I am writing to you without testing this "Audio Forwarding Over RDP" stuff. Which I would like you to forgive me for Further I have a question about how Audio forwarding will work when there are more than 1 clients attached to an XRDP server. I mean do they all get their separate audio or it is possible for only one client and 1 server.

Following You Chaitanya

Rating: 0 (from 0 votes)

Kevin Cave

2012/06/27 at 15:19 · Reply

Chaitanya, hi and thanks:)

If you have more than 1 client connecting to the target RDP server, then I would think that each client should get its own audio stream:

Alice is using client machine 1

Bob is using client machine 2

Both are connecting to the target RDP server under their own login names (alice, and bob)

If they're on the same LAN, then they should still be okay, as each has "diverted" their Pulseaudio stream from their login session to their client machine. If they're connecting through their own SSH tunnels, then the same is true.

Finally, if you try this out for yourself, please let me know the results!;)

Regards

Rating: +1 (from 1 vote)

Dismayed User

2012/09/17 at 06:44 · Reply

When I run the following command:

pulseaudio.exe -p "C:\PulseAudio\lib\pulse-1.1\modules" -nF
"C:\PulseAudio\etc\pulse\default.pa"

I get:

- W: [(null)] pulsecore/core-util.c: Secure directory creation not supported on Wi n32.
- W: [(null)] pulsecore/core-util.c: Secure directory creation not supported on Wi n32.
- W: [(null)] pulsecore/core-util.c: Secure directory creation not supported on Wi n32.
- W: [(null)] pulsecore/core.c: failed to allocate shared memory pool. Falling back to a normal memory pool.
- W: [(null)] pulsecore/core-util.c: Secure directory creation not supported on Wi n32.
- W: [(null)] pulsecore/core-util.c: Secure directory creation not supported on Wi n32.
- W: [(null)] pulsecore/core-util.c: Secure directory creation not supported on Wi n32.
- W: [(null)] modules/module-waveout.c: Sample spec not supported by WaveIn, falling back to default sample rate.
- E: [(null)] modules/module-waveout.c: Failed to open WaveIn.
- E: [(null)] modules/module-waveout.c: Error: A device ID has been used that is o ut of range for your system.
- E: [(null)] pulsecore/module.c: Failed to load module "module-waveout" (argument : "sink name=output source name=input"): initialization failed.
- E: [(null)] daemon/main.c: Failed to load directory.
- E: [(null)] daemon/main.c: Module load failed.
- E: [(null)] daemon/main.c: Failed to initialize daemon.
- W: [(null)] pulsecore/core-util.c: Secure directory creation not supported on Wi n32.

It appears that the installation fails; how do I remedy?

Rating: 0 (from 0 votes)

Clueless

2012/10/01 at 01:05 · Reply

I'm having similiar error messages. Did you find a solution?

Rating: 0 (from 0 votes)

deagon

2016/02/21 at 00:34 · Reply

i know this post is years old but i just had this problem and there's no other reference showing up in my google searches.

however, for future google searchers....

this appears to be a bug that is caused by disabling microphone input in recording devices on windows. In my case, re-enabling my microphone resolved the issue.

bug links;

https://www.cendio.com/bugzilla/show_bug.cgi?id=4119 https://www.cendio.com/bugzilla/show_bug.cgi?id=2831

Rating: 0 (from 0 votes)

Stan

2013/08/06 at 20:34 · Reply

Hi. can you tell me where exactly I can find the .xsession file please? I am using RDP on XP to connect to Linux Mint using XRDP and can not find .xsession anywhere. Do I have to create this file? If so, how?

Rating: 0 (from 0 votes)

Kevin Cave

2013/08/07 at 07:18 · Reply

Stan,

The .xsession file should be created when you run the RDPsesconfig tool after X11RDP-o-matic. Its location should be in the home directory of all users selected when you run the tool.

Regards.

Rating: 0 (from 0 votes)

Klaus Deiss

2013/08/11 at 13:44 · Reply

@Dismayed User

edit c:\pulseaudio\etc\pulse\default.pa

change the line where waveout module is loaded and add record=0. That fixed it for me.

load-module module-waveout record=0 sink_name=output source_name=input

greetz

Klaus

Rating: +1 (from 1 vote)

Klaus Deiss

2013/08/11 at 21:55 · Reply

In general I've observed that audio is playing good (local server) except one thing: FLASH!!

You can check it if you switch your browser to HTML5 (http://www.youtube.com/html5). Most videos are playing excellent in HTML5.

greetz

Rating: 0 (from 0 votes)

brian mullan

2013/08/27 at 10:26 · Reply

Kevin...

I noticed in your article Sound with xrdp/X11RDP that your writeup describes using TCP?

I checked Pulseaudio and it looks like it only implements TCP and no UDP option

I wonder why they never implemented a UDP connection for audio since audio is generally one-way you are only concerned about dropped pkts causing delays (possibly due to TCP retransmissions). With udp you might drop a few pkts now and then but most people may not hear the difference in the audio. Pulseaudio's site did mention they support RTP for audio.

Rating: 0 (from 0 votes)

Kevin Cave

2013/08/27 at 16:30 · Reply

Brian,

Interesting that. This article is kind of getting a bit redundant, now that xrdp has a pulseaudio sink of it's own. I might do a write-up about it in the near future. It's a little bit involved and I haven't properly read it over, yet.

Regards!

Rating: 0 (from 0 votes)

Alvin Bell

2014/03/25 at 02:42 · Reply

I am trying to get this working with Windows 7 client (my server is Ubuntu 13.04). When I went through the steps, I got the same kind of screen output as that shown here idicating that the PulseAudio daemon loaded. I also checked that the sound settings on the Windows side were for playing sound on the local system rather than the server. On the remote session, I did not see any audio device representing the Windows system in Sound settings and there was no sound. I did see some errors in my syslog as follows:

Mar 24 21:25:47 Pegasus pulseaudio[2553]: [alsa-sink] alsa-sink.c: Error opening PCM device front:0: Device or resource busy

Mar 24 21:25:47 Pegasus pulseaudio[2553]: [pulseaudio] sink-input.c: Failed to create sink input: sink is suspended.

Based on the recent comment concerning the fact that xrdp has a pulseaudio sink of its own, I rebooted, installed PulseAudic Preferences and changed settings by guesswork:

Checked Enable network access to local sound devices

Checked Allow other machines on the LAN to discover local sound devices

Checked Enable Multicast/RTP sender

Checked Create separate audio device for Multicast/RTP

I started remote session but without manually starting pulseaudio daemon as before. Running ps -ef indicated that pulseaudic was already started through startup anyway (perhaps reason for errors above). I didn't get any errors in syslog now but still not audio device shown in Sound settings on remote session and no sound.

From PulseAudio Manager, my server version is 3.0.

Hoping you might be able to help,

Alvin

Rating: 0 (from 0 votes)

Alvin Bell

2014/03/25 at 02:59 · Reply

Just noticed I was getting a little confused over running of PulseAudio. In the last test, I had not started pulseaudio on Windows side so I guess it wouldn't work. I just tried again with starting the daemon on the Windows side and I also checked the Enable Multicast/RTP receiver in PulseAudio Preferences on the linux server in case that applies, but I still get the same symptoms of no audio device listed and no sound in the remote session.

Alvin

Rating: 0 (from 0 votes)

Yahya

2014/04/14 at 15:49 · Reply

Hi,

You are maybe running it on a rdp (a virtual machine it doesn't support input) so the output is your pc (remote). so pulseaudio cannot find a device.

try directly on your host to be sure.

Rating: 0 (from 0 votes)

Alvin Bell

2014/04/15 at 19:18 · Reply

Thanks for replying. I am running RDP in exactly the same way as described in this article with a Windows client. I'm not sure what you mean by a virtual machine in this context.

I certainly have my doubts about pulseaudio capabilities as I ran into problems trying to use Teamviewer as an alternative solution and was not able to get the audio sending for that either. I have the latest version of pulseaudio but I read about so many problems with it and I wonder if I am fighting a losing battle here.

Rating: 0 (from 0 votes)

cyril

2014/05/09 at 11:14 · Reply

Hello and thank's for your work!

(Sorry for my english, i'm french...)

I have installed xrdp on a debian machine and i connect to it with 4 xp machines. It is running fine but i have no sound, so i read your tuto, but i don't find .xsession file. I just find /etc/X11/Xsession. Can you tell me what i have to do? (i'm a beginner in with Linux)

Thank you for your help

cyril

Rating: 0 (from 0 votes)

fire-fly

2015/01/20 at 13:08 · Reply

Hi

Any ideal how to have Macbook pro connected ubuntu with sound?

I install pulseaudio but it wasn't listen to 4713

Thanks

Rating: 0 (from 0 votes)

fire-fly

2015/01/21 at 15:59 · Reply

Got pulseaudio listening to 4713 on macbook pro, ubuntu is connected to it via 4713. But no sound on macbook :(

Rating: 0 (from 0 votes)

RDPを利用したリモート・デスクトップ | あくまで暫定措置としてのブログ

2014/11/08 at 11:25 · Reply

[...] xrdp "Using Windows RDP to Access your Ubuntu Instance | Cloud Services" "xrdp pulseaudio sink and source"なんて記事があるところをみるとデフォルトでは音の送信はサポートされてない模様。"Get audio with your xrdp/x11rdp connections, LAN or Remote! Updated! Windows Clients! – Scaryg..." Windowsホスト側にPulseaudioをインストールして実現する方法。大変そう。[...

This site uses Akismet to reduce spam. Learn how your comment data is processed.