

D365 F&O Warehouse Management Systems (Advance warehouse)-3

This Article is the continuation of the warehouse management system in [D365 F&O Version-41](#)
Before start working with location Directives, wave, work and other related setups there are pre setups which I have described in previous articles.

1.Location Directives

Location directives are rules that help identify pick and put locations for inventory movement. For example, in a sales order transaction, a location directive determines where the items will be picked, and where the picked items will be put. Location directives consist of a header and associated lines. They are created for specific work order types.

Applies to features in the Warehouse management module. It doesn't apply to features in the Inventory management module.

You can use location directives to perform the following tasks:

- Put away incoming items.
- Pick and stage items for outbound transactions.
- Pick and put raw materials for production.
- Replenish locations.

Navigation: Warehouse management > Setup > Location directives.

Finance and Operations | Warehouse management > Setup > Location directives

← Edit + New Delete ↑ Move up ↓ Move down Edit query Copy Acceptance tests Options

Filter

Work order type
Sales orders

Warehouse

Standard view

Location directives

Sequence number	Name
1	24 SO Pick

Location directives

After reaching the page and before creating new first we need to select work order type

D365 F&O Warehouse Management Systems (Advance warehouse)-3

Work order type

▼

Purchase orders

Sales orders

Raw material picking

Finished goods put away

Co-product and by-product put away

Transfer issue

Transfer receipt

Inventory movement

Canceled work

Cycle counting

Replenishment

Return orders

Kanban put away

Kanban picking

Counting discrepancies accepted

Packed container picking

Sorted inventory picking

Cross docking

Quality in quality check

Quality item sampling

Quality order

Location directive for sales order

To process we are first selecting sales order. In sales order the basic process is

Pick – picking material from warehouse

Put – putting the picked material either at packing/ship or staging area.

← ≡ Save + New Delete ↑ Move up ↓ Move down Edit query Copy Acceptance tests Options

Filter

Work order type

Sales orders ▼

Warehouse

▼

Standard view ▼

Location directives


Sequence number	Name
29	Test

Location directives

Sequence number


Enter the sequence in which the location directive is processed for the selected work type. You can also modify the sequence, if needed. It can be changed using Move Up and Move Down on the menu.

D365 F&O Warehouse Management Systems (Advance warehouse)-3



Work type – Select the type of work that must be performed. The available values depend on the type of inventory transaction that you selected in the.

We can choose from drop down as per the process. As we are working on sales order, we will either choose Pick or Put.



Directive codes


Directive code is the link between work template lines and location directives.

Select the directive code to associate with a work template or replenishment template. On the **Directive code** page, you can create new codes that can be used to connect work templates or replenishment templates to location directives. Directive codes can also be used to establish a link between any work template line and a location directive (such as the bay door or stage location).


If a directive code is set, the system won't search location directives by sequence number when work must be generated. Instead, it will search by directive code. In this way, you can be more specific about the location directive that is used for a particular step in a work template, such as the step for staging the materials.

Navigation: Warehouse management > Setup > Directive codes

D365 F&O Warehouse Management Systems (Advance warehouse)-3



Scope – Use this option to specify the scenarios that the location directive will be applied to. This option replaces the Multiple SKU option



Scope setting	Single order with one item	Multiple orders with the same item	Single order with multiple items	Multiple orders with multiple items
Single item	Yes	Yes	No	No
Multiple items	No	No	Yes	Yes
Single item or order	Yes	Yes	Yes	No
All	Yes	Yes	Yes	Yes

The following table describes when the scopes are available, and whether they allow for the **Edit query** function.

D365 F&O Warehouse Management Systems (Advance warehouse)-3

Scope	Supported work type	Supported work order types	Allow for Edit query
Single item	All	All	Yes
Multiple items	All	All	No
Single item or order	Puts	Co-product and by-product put away, finished goods put away, kanban put away, purchase orders, quality orders, replenishment, return orders, sales orders, transfer issue, and transfer receipt	Yes
All	Puts	All	No

when choosing Single item the edit query is available and if selected multiple item it will be greyed out.

The screenshot shows the D365 F&O Warehouse Management System interface. At the top, there is a navigation bar with buttons: Save, New, Delete, Move up, Move down, Edit query (highlighted with a red box), Copy, Acceptance tests, and Options. Below the navigation bar, there is a sidebar with a search filter and dropdown menus for Work order type (Sales orders), Warehouse, and a table with columns Sequen... and Name. The main area is titled 'Location directives' and shows a table with columns Sequence number and Name. Below this, there is a section for 'Location directives' with a table containing columns Work type, Directive code, and Scope. The 'Work type' is set to 'Pick', 'Directive code' is empty, and 'Scope' is set to 'Single item' (highlighted with a red box).

To do puts for both multiple items and single items, you must ensure that location directives exist that cover both scenarios. For example, you might set up one or more Single item or order location directives to cover scenarios that require fine-tuning (such as through edits to the query), and then one or more All location directives to cover the remaining scenarios.

- Although Single item and Multiple items scopes can be used for puts, this approach typically leads to redundant configurations. Consider using Single item or order and All scopes instead, because this approach will produce a cleaner setup.
- When using the Single item or order scope, receiving flows (like purchase orders) will add the order number to the location directive query during work creation. To prevent unexpected behavior, don't add query ranges for the lines in such cases.

D365 F&O Warehouse Management Systems (Advance warehouse)-3

Warehouse selection

Warehouse selection

Warehouse

Warehouse group

All

Site

Warehouse

Move down Restrict by unit

Use the **Warehouse selection** Fast Tab to specify the warehouse and site where the location directive will apply.

- **Warehouse selection** – Select one of the following values:
 - All – Use the location directive for all warehouses where a more specific location directive hasn't been assigned.
 - Warehouse group – Use the location directive for all warehouses in the warehouse group that's selected in the **Warehouse group** field.
 - Warehouse – Use the location directive only for the specific warehouse that's selected in the **Warehouse** field.
- **Site and Warehouse** – If the **Warehouse selection** field is set to Warehouse, select the site and warehouse where the location directive applies. If you select the warehouse first, the site will be filled in automatically. If you select the site first, the warehouse list will be filtered so that it shows only warehouses at that site.
- **Warehouse group** – If the **Warehouse selection** field is set to Warehouse group, select the warehouse group where the location directive applies. For more information about how to set up warehouse groups, see [Warehouse groups](#).

Warehouse selection

Warehouse selection

Warehouse

Site

2

Warehouse

24

Lines Fast Tab to establish conditions for applying the related actions that are specified on the **Location directive actions** Fast Tab. For each line, you can specify the minimum quantity and maximum quantity that the actions should apply to. You can also specify that the actions should apply to a specific inventory unit.

D365 F&O Warehouse Management Systems (Advance warehouse)-3

Lines ⌵										
+ New 🗑 Delete ⬆ Move up ⬇ Move down Restrict by unit										
☐	Sequence ...	From quan...	To quantity	Unit	Locate quantity	Restrict by ...	Round up t...	Locate pac...	Allow split	Immediate replen
☐	1	1.00	99,999.00		None	☒	☐	☐	☐	
☒	2	1.00	99,999.00	▼	None ▼	☐	☐	☐	☒	▼

- **Sequence number** – Enter the sequence that each location directive line should be processed in for the selected work type. You can change the sequence as you require by using the **Move up** and **move down** buttons on the toolbar.
- **From quantity** – Specify the start of the range of quantities that the line applies to. Specify the quantity in the unit of measure that is selected in the **Unit** field.
- **To quantity** – Specify the end of the range of quantities that the line applies to. Specify the quantity in the unit of measure that is selected in the **Unit** field.
- **Unit** – Select the unit of measure for the items. You can specify a minimum quantity and a maximum quantity that the directive should apply to, and you can specify that the directive should be for a specific inventory unit. The **Unit** field is used only for quantity evaluation. To determine whether the location directive line is applicable at all, the system uses the quantity in the unit that is specified on that line. Every time that it reaches a location directive line, the system tries to convert the demand unit to the unit that is specified on the line. If the unit of measure conversion doesn't exist, the system moves on to the next line.
- **Locate quantity** – This field is used only during attempts to put or locate items in the warehouse. (Therefore, it applies only when the **Work type** field is set to Put). Select one of the following values to specify the quantity that is used to evaluate whether a quantity is within the **from quantity** to **To quantity** range:
 - License plate quantity – Use the quantity on the license plate that is being received.
 - Unitized quantity – Use the quantity that is used during the transaction. For example, you receive a quantity of 1,000 in a warehouse and break it into 10 license plates, each of which has a quantity of 100. In this case, you can use a quantity of 1,000 items instead of the license plate quantity of 100.
 - Remaining quantity – Use the quantity that must still be received on the purchase order line that is being processed.
 - Expected quantity – Use the total quantity of the purchase order line, regardless of what has already been received.
- **Restrict by unit** – This check box lets you make the location directive line specific to a unit of measure or multiple units of measure. Select it to restrict the units of measure

D365 F&O Warehouse Management Systems (Advance warehouse)-3

that are considered valid selection criteria for the location directive lines. This functionality works only for location directives where the **Work type** field is set to Pick.

For example, when you reserve quantities, you want to reserve pallets only from a specific set of locations. In this case, the lines will restrict that sequence to pallets in such a way that any quantity that is less than a pallet won't be selected for the location directive.

Note that the **Restrict by unit** check box doesn't control the unit or units that are applied on work lines. The unit restriction applies only to the units that are made available via the unit sequence group. For example, an item is associated with a unit sequence group that includes both the pallets unit and the pcs units. A unit of measure has been defined, where 1 pallet = 100 pcs, and the location directive uses the **Restrict by unit** functionality only for pallets. Furthermore, a work template has been defined that limits the work header creation to 50 pcs. In this case, work lines of 50 pcs will be created. To specify the unit of measure for restriction, follow these steps:

On the **Lines** Fast Tab, select **Restrict by unit** on the toolbar. (This button becomes available only after you select the **Restrict by unit** check box on the line and then select **Save**.)

On the **Restrict by unit's** page, in the **Unit** field, select the unit of measure that you want to restrict by for the pick and put processes.

- **Round up to unit** – This field works together with the **Restrict by unit** check box. For example, if **restrict by unit** and **Round up to unit** are selected on the location directive line, the work that is generated from the directive for raw material picking should be rounded up to a multiple of one of the handling units that's specified on the **Restrict by unit** page.

Note

This **Round up to unit** setup works only for the Raw material picking work order type, and only for location directives where the **Work type** field is set to Pick.

- **Locate Packing Qty** – If you specify a packing quantity on a sales order, transfer order, or production order, this check box lets you restrict the system so that it can select only locations that have at least that packing quantity.


Note

This functionality works only with location directives of the Pick type.

- **Allow Split** – Specify whether the location directive can split the quantity that is being received or reserved across multiple warehouse locations, or whether the whole quantity must be located in a single location or reserved from a single location to create work.

D365 F&O Warehouse Management Systems (Advance warehouse)-3

- **Immediate replenishment template** – Use this field to create a connection to a replenishment template, so that replenishment is started immediately if items aren't allocated. If you leave this field blank, item replenishment won't be started until all lines of the location directive have been processed.



The screenshot shows a table titled "Location Directive Actions". Above the table is a toolbar with buttons: "+ New", "Delete", "Move up", "Move down", "Edit query", and "Copy". The table has a header row with columns: "Sequen..." (with a circular arrow icon), "Name", "Fixed location usage", "Allow nega...", "Batch enab...", and "Strategy".

You can define multiple location directive actions for each line. Once again, a sequence number is used to determine the order that the actions are assessed in. At this level, you can set up a query to define how the best location in the warehouse is found. You can also use predefined **Strategy** values to find an optimal location.

- **Sequence number** – This field shows the sequence that the actions are processed in for the selected work type. You can change the sequence by using the **Move Up** and **Move Down** buttons on the toolbar.
- **Name** – Enter the name of the location directive action. Be specific, so that the action that is performed is clear from the name.
- **Fixed location usage** – Specify which locations the location directive should consider. Select one of the following values:
 - Fixed and non-fixed locations – The location directive will consider all locations.
 - Only fixed locations for the product – The location directive will consider only fixed locations for products.
 - Only fixed locations for the product variant – The location directive will consider only fixed locations for product variants.
- **Allow negative inventory** – Select this check box to allow negative inventory at the specified warehouse location in location directives.
- **Batch Enabled** – Select this check box to use batch strategies for items that are batch-enabled. It's important that you select this check box for processes that use location directives to find locations to pick batch number–tracked items from. In this way, the search for locations that hold batch number–tracked items is included. If this check box is selected, and the **Strategy** field is set to None, the system will move on to the next action line.
- **Strategy** – To more easily and quickly define the actions that are associated with each location directive line, you can select one of the following predefined strategies:
 - None – No strategy will be used.

D365 F&O Warehouse Management Systems (Advance warehouse)-3

- Match packing quantity – This strategy verifies whether a pick location has the specified packing quantity. This strategy is valid only when the **Work type** field is set to Pick.
- Consolidate – This strategy consolidates items in a specific location where similar items are already available. This strategy is valid only when the **Work type** field is set to Put. A typical setup for put tries to consolidate on the first action line and then, on the second line, tries to put without consolidation. Consolidation of goods makes later picking more efficient.
- Consolidate including incoming work – This strategy works like the **Consolidate** strategy, but it also considers locations where items on incoming put-work lines aren't already available. This is beneficial when receiving multiple license plates with the same item and the items should be moved to the same location. A typical example could occur when receiving based on advance shipping notices (ASNs). This strategy also helps the system find locations when it's necessary to split work line quantities due to location stocking limits or other constraints.
- FEFO batch reservation – This strategy uses first expiry, first out (FEFO) batch reservations. Use it when inventory is located by using a batch expiration date and allocated for batch reservation. You can use this strategy only for batch-enabled items. It's valid only when the **Work type** field is set to Pick.
- Round up to the full LP and FEFO batch – This strategy combines the elements of the FEFO batch reservation and round up to a full LP strategies. It's valid only for batch-enabled items and location directives that have a work type of Pick. The line must be batch-enabled to use the FEFO batch reservation strategy, and the Round up to a full LP strategy can be used only for replenishment. If this strategy is configured together with a location stocking limit, it can cause the selected put work location to be overloaded and stocking limits to be ignored.
- Round up to a full LP – This strategy is used to round up the inventory quantity so that it matches the license plate quantity that is assigned to the items that must be picked. You can use this strategy only for replenishment location directives of the Pick type. If this strategy is configured together with a location stocking limit, it can cause the selected put work location to be overloaded and stocking limits to be ignored.
- License plate guided – Use this strategy when you release the order to the warehouse to create the pick-and-put work. You can use this approach for multiple license plates. This strategy will try to reserve and create picking work against the locations that hold the requested license plates that have been associated with the transfer order lines. However, if these actions can't be

D365 F&O Warehouse Management Systems (Advance warehouse)-3

completed, but you still want to create picking work, you should fall back to another strategy for location directive actions. Depending on your business process requirements, you might also want to search for inventory in another area of the warehouse.

- Empty location with no incoming work – Use this strategy to locate empty locations. A location is considered empty if it has no physical inventory and no expected incoming work. You can use this strategy only for location directives that have a work type of Put.
- Location aging FIFO – Use the first in, first out (FIFO) strategy to ship both batch-tracked items and non-batch-tracked items, based on the date when the inventory entered the warehouse. This capability can be especially useful for non-batch-tracked inventory, where no expiration date is available to use for sorting. The FIFO strategy finds the location that contains the oldest aging date, and then allocates picking based on that aging date.
- Location aging LIFO – Use the last in, last out (LIFO) strategy to ship both batch-tracked items and non-batch-tracked items, based on the date when the inventory entered the warehouse. This capability can be especially useful for non-batch-tracked inventory, where no expiration date is available to use for sorting. The LIFO strategy finds the location that contains the newest aging date, and then allocates picking based on that aging date.

Final output for sales pick location directive

Standard view ▾

Location directives

Sequence number

Name

1

Test

Location directives

Pick -- ^

Work type

Directive code

Scope

Pick

Single item

Warehouse selection

Warehouse | 24 ^

Warehouse selection

Site

Warehouse

Warehouse

2

24

Lines

^

+ New

Delete

↑ Move up

↓ Move down

Restrict by unit

	Sequence ...	From quan...	To quantity	Unit	Locate quantity	Restrict by ...	Round up t...	Locate pac...	Allow split	Immediate replen
☒	1	1.00	99,999.00	▼	None	☒	☐	☐	☐	▼
☐	2	1.00	99,999.00		None	☐	☐	☐	☒	

D365 F&O Warehouse Management Systems (Advance warehouse)-3

Lines

Sequence	From quan...	To quantity	Unit	Locate quantity	Restrict by ...	Round up t...	Locate pac...	Allow split	Immediate replen
1	1.00	99,999.00		None	☒	☐	☐	☐	☐
2	1.00	99,999.00		None	☐	☐	☐	☒	☐

Location Directive Actions

Sequence...	Name	Fixed location usage	Allow nega...	Batch enab...	Strategy
1	PL from Bulk	Fixed and non-fixed locations	☐	☐	None

Select query

Query used

Range Sorting Joins

+ Add

Table	Derived table	Field	Criteria
Locations	Locations	Warehouse	24
On-hand inventory	On-hand inventory	Physical inventory	>0
On-hand inventory	On-hand inventory	Item number	
Locations	Locations	Location profile ID	BULK

Lines

Sequence ...	From quan...	To quantity	Unit	Locate quantity	Restrict by ...	Round up t...	Locate pac...	Allow split	Immediate replen
1	1.00	99,999.00		None	☒	☐	☐	☐	☐
2	1.00	99,999.00		None	☐	☐	☐	☒	☐

Location Directive Actions

Sequence...	Name	Fixed location usage	Allow nega...	Batch enab...	Strategy
1	From Floor	Fixed and non-fixed locations	☐	☐	None
2	From Bulk	Fixed and non-fixed locations	☐	☐	None

Select query

Query used

Range Sorting Joins

+ Add

Table	Derived table	Field	Criteria
Locations	Locations	Warehouse	24
On-hand inventory	On-hand inventory	Physical inventory	>0
On-hand inventory	On-hand inventory	Item number	
Locations	Locations	Location profile ID	FLOOR

Note: Location profile ID is the picking location. Explained in previous article.

Similar way final output for sales put location directive.

Location directives

Sequence number Name

3 24 SOPut

Location directives

Put Baydoor

Work type Directive code Scope

Put Baydoor Single item

Warehouse selection

Warehouse Site Warehouse

Warehouse 2 24

Lines

Sequence ...	From quan...	To quantity	Unit	Locate quantity	Restrict by ...	Round up t...	Locate pac...	Allow split
1	1.00	99,999.00		None	☐	☐	☐	☐

D365 F&O Warehouse Management Systems (Advance warehouse)-3

Sequence...	From quan...	To quantity	Unit	Locate quantity	Restrict by ...	Round up t...	Locate pac...	Allow split
1	1.00	99,999.00		None				

Sequence...	Name	Fixed location usage	Allow nega...	Batch enab...	Strategy
1	Generic	Fixed and non-fixed locations			None

Table	Derived table	Field	Criteria
Locations	Locations	Warehouse	24
Locations	Locations	Location profile ID	BAYDOOR

Test location directives with acceptance tests

Acceptance tests let you define a set of given-when-then tests to verify that location directives behave as expected. In this type of test, given a set of conditions, when something happens, then some specified result should occur. This terminology is known from quality assurance in engineering and can be traced back to the [scientific method](#).

Acceptance tests provide two main benefits:


- **Faster initial setup:** You can verify the outcomes of your location directives without having to go through the regular warehouse processes and inspect the work creation history log.
- **Lower maintenance:** You'll be able to have more confidence when you modify your location directives later, because you can have the impact of each change automatically validated by running your defined acceptance tests.

Acceptance tests for location directives have no operational impact on the warehouse.

Note

You can't create acceptance tests for location directives where the **Scope** option is set to Multiple items (or the **Multiple items** option is set to Yes). We recommend that, whenever possible, you use location directive scopes that can be tested with single items, such as Single item or order and All.

D365 F&O Warehouse Management Systems (Advance warehouse)-3



Set up an acceptance test

Follow these steps to set up an acceptance test.

1. Go to **Warehouse management > Setup > Location directives**.
2. On the Action Pane, select **Acceptance tests**.
3. On the **Location directive acceptance tests** page, follow one of these steps:
 - To create a new test, select **New** on the Action Pane.
 - To edit an existing test, select it in the list pane, and then select **Edit** on the Action Pane.
 - To copy an existing test, select the source test in the list pane, and then select **Copy** on the Action Pane. This step can be useful when you must create a new acceptance test that is a variation of an existing test.
4. On the header of the new or selected test, set the following fields:
 - **Name** – Enter a name for the test.
 - **Description** – Enter a short description of the test.
 - **Inactive** – Set this option to Yes to make the test inactive. Set it to No to make the test active. Inactive tests can't be run and will be skipped if you choose to run all tests.
5. On the **Given** Fast Tab, specify the starting conditions for the test. Set the following fields:

D365 F&O Warehouse Management Systems (Advance warehouse)-3

- **Inventory levels** – Specify whether you want to run the test based on your actual inventory or simulate empty inventory. Select one of the following values:
 - Current on-hand inventory – Run the test by using whatever inventory is available when the test is run. This approach can make the test result less predictable and subject to arbitrary failures (for example, if the item that is used by the test isn't available).
 - No inventory – Simulate an empty warehouse. The simulation will clear inventory of the item that is used in the test, and for all locations that are specified under **Additional inventory**.
- **Additional inventory** – Simulate on-hand quantities for one or more items. The test will add these quantities to the inventory that is specified by the **Inventory levels** field.
 - Select **New** on the toolbar to add a row to the grid.
 - Select **Delete** on the toolbar to remove a row from the grid.
 - Select **Display dimensions** to open a dialog box where you can add dimension columns to the grid, or remove them, as you require.
 - For each row, enter values to specify an item, dimension values, location, and quantity.

Important

The settings on the **Given** Fast Tab don't influence the actual inventory levels in the warehouse. Instead, they simulate conditions that are in effect only temporarily, during test execution.

6. On the **When** Fast Tab, specify what you want to test. The values that you enter are the inputs to the location directive engine. This approach is simpler than building manual tests by creating orders. Set the following fields:
 - **Work order type** – Specify the type of order to simulate (for example, Sales orders or Purchase orders).
 - **Work type** – Specify the work type to simulate. Typically, you'll select Pick or Put.
 - **Order number** – Specify the order number to use during the test. This information can be useful if the location directive query has ranges related to the order table.
 - **Disposition code** – Specify the disposition code that is used to handle return orders.
 - **Directive code** – Specify the directive code that drives the location directives.

D365 F&O Warehouse Management Systems (Advance warehouse)-3

- **Item number** – Specify the item to locate.
 - **Quantity** – Specify the quantity to locate.
 - **Unit** – Specify the unit of measure for the **Quantity** field.
 - **Dimensions** – Specify the storage, product, and tracking dimensions for the item to locate.
7. On the **Then** FastTab, specify the expected outcome of the acceptance test. You **must** set one (and only one) of the following fields:
- **Exact location** – Select a precise location. The test will be marked as passed if this location is the result of the location directive.
 - **Location matching regular expression** – Enter a regular expression that will be validated against the resulting location, even if the resulting location is blank (no result). The test will be marked as passed if the regular expression matches the name of the resulting location. **Location with profile** – Select a location profile. The test will be marked as passed if the resulting location has this profile.
 - **Location in zone** – Select a location zone. The test will be marked as passed if the resulting location has this zone.
8. Select **Save** to save your test. The **Results** Fast Tab stores a record of any test results for each test. For information about how to run tests and interpret the results, see the next section.

Run acceptance tests

After you set up your tests, you can run them, either one by one or all at once. To run one or more tests, follow these steps.

1. Go to **Warehouse management > Setup > Location directives**.
2. On the Action Pane, select **Acceptance tests**.
3. On the **Location directive acceptance tests** page, follow one of these steps:
 - To run a single, specific test, select it in the list pane, and then select **Run** on the Action Pane.
 - To run all active tests, select **Run all** on the Action Pane.
4. After the tests have been run, the list pane is updated to indicate the most recent result of each test. To inspect the results of a test, select the test in the list pane, and then select the **Results** Fast Tab. The grid shows the result of each run of the test. For each result, the following information is provided:

D365 F&O Warehouse Management Systems (Advance warehouse)-3

- **Result** – The result of the test: Passed, Failed or Skipped.
 - **Resulting location** – The location that was found by the test. If no location was found, this field is blank.
 - **Duration (ms)** – The duration of the test in milliseconds (ms). This field also indicates how quickly the system will be able to process your directives during daily operation. For efficient warehouse operations, you should design your location directives so that they can be processed as quickly as possible. One typical cause of a slow response is the use of location directive queries where the defined ranges or sort orders don't match an index on the table. (The system will warn you if you try to save a query that is configured in this way.)
 - **Locations evaluated** – The number of locations that were evaluated during the test. For efficient warehouse operations, you should try to have as few locations as possible evaluated. One way to minimize the number of evaluated locations is to have many location directives, the first of which are the most specific and the last of which are the most general. You can also segment your warehouse by keeping certain types of items in dedicated zones. This approach can help you avoid scanning the whole warehouse every time.
 - **Created date and time** – The date and time when the test was run.
 - **Created by** – The name of the person who ran the test.
5. To view more information about any test run, select it in the grid, and then review the **Log** field. The log includes a work creation history that will help you understand the outcome.

Important

To determine the result of the test, the system compares the **Resulting location** value with the **Then** condition. The log for a failing test might indicate that a location directive did find a location, but that location didn't match the expected location that is defined in the **Then** condition.

Troubleshoot location directives and acceptance tests

Definition of acceptance tests is typically an iterative process. If a test fails, you should find out why it failed. Perhaps the test isn't set up correctly, or perhaps a location directive must be adjusted so that it better meets your requirements.

To troubleshoot your location directives and acceptance tests, follow these steps.

1. Go to **Warehouse management > Setup > Location directives**.
2. In the list pane, select a location directive that you've designed an acceptance test for.

D365 F&O Warehouse Management Systems (Advance warehouse)-3

3. Expand the Fact Box pane. This pane is on the right side of the page and is labeled **Related information**.
4. In the Fact Box pane, expand the **Acceptance tests** Fact Box. The grid in this Fact Box lists the acceptance tests that are relevant to the selected location directive. It also shows the most recent result for each of those tests. From this Fact Box, you can perform the following actions:
 - Select **Run all** to run all the listed tests.
 - Select **Coverage** to switch to and from the coverage view. The coverage view uses colored highlighting to indicate which location directives, lines, and actions were used to determine the result of a selected test. Records that are marked yellow were evaluated but didn't find a location. Records that are marked green did find a location. To change the test that coverage is shown for, select the symbol in the **Result** column for the relevant test.
 - Hover over a test to view more information about it, including the log.
 - In the **Name** column, select the name of a test to open that test on the **Location directive acceptance tests** page. There, you can inspect and adjust the test as you require.
 - Select **Run tests after change** to turn on and off the setting that will automatically run all tests each time that you change a location directive. Use this functionality to provide immediate feedback about the impact of changes as you make them.
5. Based on the results indicated by the coverage view and test log, adjust your tests and/or location directives until they produce the expected results for each test.

Note- For other process like purchase , inventory , production I will create separate setups Article once completed with whole module