

D365 F&O Warehouse Management systems (Advance warehouse)-4

In D365 F&O, work templates define the procedures for warehouse transactions, outlining steps like picking, putting away, and more, for specific work order types (e.g., purchase orders, sales orders).

Here's a more detailed explanation:

Work classes

In Dynamics 365 Finance and Operations (D365 F&O), work classes are used to control the type of work order lines that warehouse workers can process on a mobile device and to validate the put location for a work order line.

Here's a more detailed explanation:

- **Purpose:**

Work classes help define which types of work (e.g., picking, putaway, loading) are associated with a specific menu item on a mobile device, ensuring that workers only see and perform tasks that are appropriate for their role and the current process.

- **Functionality:**

- **Linking to Mobile Device Menu Items:** You can link work classes to specific menu items on the mobile device, allowing you to control which work types are accessible through those menus.
- **Work Order Line Validation:** Work classes can be used to validate the put location for a work order line, ensuring that items are placed in the correct locations.
- **Control over Warehouse Work:** By using work classes, you can have more control over the work that is created and processed using mobile devices.

1. Go to Warehouse management > Setup > Work > Work classes.

2. Click New.

3. In the Work class ID field, type a value.

4. In the Description field, type a value.

5. In the Work order type field, select an option.

D365 F&O Warehouse Management systems (Advance warehouse)-4

Standard view ▾

Work classes

Work class ID * Description

Valid put location types

+ New Delete

Location type ↑

Work order type

- Purchase orders
- Sales orders
- Raw material picking
- Finished goods put away
- Co-product and by-product put away
- Transfer issue
- Transfer receipt
- Inventory movement
- Canceled work
- Cycle counting
- Replenishment
- Return orders
- Kanban put away
- Kanban picking
- Counting discrepancies accepted
- Packed container picking
- Sorted inventory picking
- Cross docking
- Quality in quality check

Quality item sampling

6. Click New.

7. In the Location type field, type a value.

8. Close the page.

Standard view ▾

Work classes

Work class ID Description Work order type

Sales Sales Sales orders

Valid put location types

+ New Delete

Location type ↑

PACK

Example:

You might create a work class called "SO Pick" for sales order picking and another called "SO Load" for loading sales orders and then link these work classes to the corresponding menu items on the mobile device.

D365 F&O Warehouse Management systems (Advance warehouse)-4

Work Templates

- **Purpose:**

Work templates are used to define the procedures and steps that should be followed when executing a warehouse transaction.

- **Work Order Types:**

Each work template is associated with a specific work order type, such as purchase orders, sales orders, transfer orders, or cycle counting.

- **Warehouse Automation:**

They help automate warehouse operations by defining the expected workflow for different types of transactions.

- **Example:**

When receiving a purchase order, a work template might define steps like picking items from the truck and putting them away in a bulk storage location.

When selling, a work template will define the steps of picking items from warehouse and putting them either in Pack or Ship location.

When producing, a work template will define the steps of picking items from warehouse and putting them in Production warehouse raw material pallet/supermarket or Bin location

How to Set Up Work Templates:

1. **Navigate to Work Templates:** Go to Warehouse Management > Setup > Work > Work templates.
2. **Create a New Template:** Select "New" to create a new work template.
3. **Define Header Information:**
 - **Sequence Number:** This determines the order in which the work templates are evaluated.
 - **Work Template ID:** This is the unique identifier for the template.
 - **Work Template Description:** A description of the template.

D365 F&O Warehouse Management systems (Advance warehouse)-4

- **Work Order Type:** Select the type of work order this template applies to (e.g., Purchase Order, Sales Order).
- **Work Pool ID:** Allows you to organize work into groups.
- **Work Priority:** Indicates the importance of the work.

Finance and Operations | Warehouse management > Setup > Work > Work templates

Work templates

Standard view * ∨

Work order type
Sales orders ∨

Purchase orders

- Sales orders
- Raw material picking
- Finished goods put away
- Co-product and by-product put away
- Transfer issue
- Transfer receipt
- Inventory movement
- Canceled work

Work order type
Sales orders ∨

Overview | General

Sequen...	Work template	Work template description	Valid	Automatic...	Work pool ID	Work prior...
6	62 Pick to pack	Pick and place at pack sta...	✓			0

Work Template Details

+ New | Delete | Move up | Move down | Work line breaks

Line number	Work type	Custom work type	Mandatory	Stop work	Freeze	Directive code	Work class ID
1.0000000000	Pick		✓			Pack	Sales
2.0000000000	Put		✓				Sales

4. **Edit Query (Optional):** You can use the "Edit Query" button to refine the selection criteria for the work template.
5. **Save:** Save the work template header.
6. **Add Lines:** Add lines to the work template to define the specific steps and actions.
7. **Associate with Location Directives:** Work templates can be associated with location directives to further control the warehouse operations.

D365 F&O Warehouse Management systems (Advance warehouse)-4

Finance and Operations

Warehouse management > Setup > Work > Work templates

← Edit + New Delete ↑ Move up ↓ Move down Edit query Work header breaks Copy Regenerate sequence numbers Options

Work templates

Standard view * ▾

Work order type

Sales orders ▾

Overview General

Sequen... ▾ Work template Work template description Valid Automatic... Work pool ID Work prior...

6 62 Pick to pack Pick and place at pack sta... ✓ 0

Range Sorting Joins

+ Add Remove

	Table	Derived table	Field	Criteria
✓	Locations ▾	Locations ▾	Location profil... ▾	BULK +
	Temporary work t...	Temporary work t...	Warehouse	62

Mobile device Menu Item.

Mobile device menu item is used for performing the work for any type of order. The work class that's associated with the menu item determines which work is valid.

Navigation

Warehouse Management > Setup > Mobile device > Mobile device menu items

Select New.

Finance and Operations

Warehouse management > Setup > Mobile device > Mobile device menu items

← Edit + New Delete Default data Work confirmation setup Cycle counting System directed work sequence queries Edit query Field list Options

In the **Menu item name** field, type a value. Enter a unique value.

In the **Title** field, type a value. This is the title which will be displayed on the mobile device

Standard view ▾

Mobile device menu items

Menu item name Title

SALES PICK BY SO SP Sales pick by SO Sup...

Page. 5

Created By: Abhishek Jindal


D365 F&O Warehouse Management systems (Advance warehouse)-4

Set the **Mode** field to *Work* and select the **Use existing work** option. Some additional options then become available on the **General** tab. You can control access to the menu item by assigning one or more work classes on the **Work class** FastTab. The work classes define the work that the menu item can process. The work class can also be used to grant access to specific user roles or to separate processing for different types of operations. The following table describes the options that are available. The option can be chosen under the **Directed by** field in the **Mobile device menu items** page.

In the **Mode** field, select **Work**.


Select **Yes** in the **Use existing work** field.

- This mobile device menu item is used to perform existing work. Therefore, you must set this value to **Yes**.
- The **Display inventory status** field determines whether the inventory status of the on-hand inventory will be displayed to the warehouse worker on the mobile device.



In the **Directed by** field, either select **System grouping**. When you select something in the **Directed by** field, additional fields appear in the **General** section on this page. The fields that appear depend on what you selected. When you select **System grouping**, two new fields are added.

We are choosing Directed by from the drop down.



D365 F&O Warehouse Management systems (Advance warehouse)-4

Option	Description
None	This default value doesn't process work.
System directed	Supply Chain Management controls the type of work that is assigned to a worker and the order that the worker performs the work in. When you select this option, you can select System-directed work on the Action Pane to open the System-directed sorting order page, where you can set up sorting criteria for the work. The sorting criteria control the order that the worker performs the work in. You can add as many criteria as you require.
User directed	The worker selects the work to perform and the order to perform it in.
User grouping	The worker manually groups work. This option is useful when, for example, a worker can pick multiple items at the same time in a location. After the worker has finished picking all the required items, they can put the items away.
System grouping	Supply Chain Management groups work for the worker, based on a specified field. For example, picking work is grouped when a worker scans a shipment ID, load ID, or any value that can link each work unit. If you select this option, the following fields are required: System grouping field – Select the field that the worker scans to group the work. System grouping label – Enter text to instruct the worker what to scan to group the work.

Validated user directed	The worker selects the work to perform when work is associated with a larger entity, such as a load or shipment. The worker determines the order that the items are picked in. If you select this option, the following fields are required: Validated user directed field – Select the field that the worker scans to group the work. Validated user directed label – Enter text that instructs the worker what to scan when picking work is grouped by the system. This option is useful when, for example, multiple pallets are staged for a load. If you select LoadId in the Validated User Directed field, the worker can pick any pallet that is associated with the load. The worker receives an error message if they scan an item that isn't associated with the load.
Cluster picking	The worker groups work into clusters. Clusters lets workers pick items from a single location for multiple work orders at the same time.
Cycle count grouping	The worker selects a zone, work pool, or location, and Supply Chain Management assigns work, based on the selection. If you select this option, you can click Cycle counting on the Action Pane to specify additional information to display, and you can also specify the number of times that the worker must repeat the count if a difference is found.
Transport loading	This feature allows several warehouse workers to load inventory from the same or different loads onto the same truck, with loads that are fully or partially shipped.

General

Display inventory status
☒ Yes

Anchoring
☐ No

Count total item quantity first
☐ No

Allow over pick
☐ No

Directed by
User directed

Override target license plate
☐ No

Disable cycle count thresholds
☐ No

Group pick
☐ No

Use process guide
☐ No

Override license plate during put
☐ No

Group put away
☐ No

Deferred put processing policy
Respect settings

Barcode data policy

Allow splitting of work
☐ No

Pick oldest batch
None

Fast validation
☐ No

Pick and pack
☐ No

Keep work locked by user
☐ No

Audit template ID

Show work line list
Never show

Generate license plate
☐ No

Display summary of pick screen
☐ No

Handle by license plate
☐ No

Display inventory status

When enabled, the inventory status will be display on the device. Otherwise, the inventory status will be defaulted.

Directed by

Select the option that indicates how work is assigned in the warehouse.

D365 F&O Warehouse Management systems (Advance warehouse)-4

Use process guide

Select this option to use process guide framework when available.

Barcode data policy

Policy for filling multiple fields based on a single barcode scan

Pick and pack

Select this option to allow workers to combine work for a sales order or load into a single work unit. The worker can perform work only for the sales order or load. For example, this is useful when you must increase a quantity for a sales order after the load, shipment, and work has been created for the sales order. This option is available when the menu item uses existing work, and the work is directed by the user or system.

Generate license plate

When enabled, a new license plate will automatically be created as needed; otherwise, the worker will have to select an existing license plate.

Anchoring

Select this option to allow workers to specify a location that will override the suggested staging or loading location. All the remaining put away work is directed to the new location. For example, this is useful when a worker is to put items for order 1 in a staging location by Dock 1 but can't because a previous load hasn't cleared the location. Rather than waiting for the Dock 1 staging location to become available, the worker decides to use the staging location for Dock 2 instead and overrides the suggested staging location. The put location for all remaining items for the work order is updated to the Dock 2 staging location. If you select this option, you must specify whether to anchor by shipment or by load in the Anchor by field.

Override target license plate

Select this option to allow workers to specify a target license plate number that differs from the suggested target license plate. Use this option when the first pick for a work order is for the entire quantity of an item on a license plate. For example, this is useful when reusing a pallet.

Override license plate during put

Select this option to allow users to consolidate the quantity on the license plate already on location. When this option is selected, a new flow is available to the user that lets them add quantities on an existing license plate on location.

Override license plate during put

D365 F&O Warehouse Management systems (Advance warehouse)-4

Select this option to allow users to consolidate the quantity on the license plate already on location. When this option is selected, a new flow is available to the user that lets them add quantities on an existing license plate on location.

Allow splitting of work

This option controls whether workers can use more than one license plate to transport items for a single line of picking work. It also affects the way the "Full" button works on handheld devices. Workers use the "Full" button during picking work to indicate that a target license plate is full. If this option is disabled, workers can only use the "Full" button after each pick line is finished, which means that the full quantity of the current line must be stored at a single target license plate before work can continue. If this option is enabled, workers can select "Full" at any time while picking, and the device will then prompt them to specify the quantity of the current picking line that has already been loaded onto the target license plate. In both cases, after a worker selects "Full", the handheld device will display the put location for the current target license plate and will generate new picking work for the remaining lines (and/or the remaining quantity of a partial line, if permitted).

Keep work locked by user

Select this option to keep work locked by the worker when splitting work. This is useful when, for an example, a target license plate is full, and the worker must add the remaining items to another license plate, and the same worker should be the one to pick up the remaining items once he has dropped off the full target license plate. The remaining picking work stays on the original work order after the splitting of work and will be locked to the worker who did the split.

Display summary of pick screen

When enabled, a summary of picking work for the selected work order is displayed. The summary is displayed until the first work line is processed for the work order.

Count total item quantity first

Select this option to require a worker to count the total quantity first during a count. If a difference is found, the worker must provide additional information, such as the license plate number, batch number, serial numbers, and so on.

Disable cycle count thresholds

Select this option to ignore the cycle count thresholds. If selected, cycle count work isn't created when threshold values are exceeded.

Group put away

D365 F&O Warehouse Management systems (Advance warehouse)-4

Select this option to group the put-away work. This option is available when the work is grouped either by the worker or by the system. When the worker has finished all the picking work in the group, put-away work is created for the same group.

Pick oldest batch

Select the validation level for items that are set to use existing work

Pick oldest batch

None

None

Warn

Force

Audit template ID

Select the work audit template that will interrupt the work process for this menu item so that another operation can be performed. For example, if this menu item is for inbound work, the audit template might require that the worker checks the temperature in the delivery container. The point at which the process is interrupted is specified on the audit template and can be, for example, when work is started or completed, or when its status changes.

Handle by license plate

If selected, the worker can scan the license plate and then move the entire license plate, instead of scanning each item individually.


Allow over pick

When enabled, it is possible to pick a larger quantity than specified on the order. Note, the ability to over pick, is only available for workers that are allowed to over pick.

Group pick


Group together pick lines that have the same dimensions. If multiple units of measure are combined, pick action will be shown in the lowest of these units. For example, if an item has a Unit Sequence Group of Ea. Box PL while there is a line in Box and a line in PL, the pick will be shown in Box.

D365 F&O Warehouse Management systems (Advance warehouse)-4



Deferred put processing policy

This option provides some flexibility on the deferred put processing policy. Select "Respect settings" to use deferred put processing as defined on the work processing policy. Select "Override settings and process put synchronously" to override the setting and process the put synchronously. For the moment work audit templates are not supported. If an audit template id is set on the menu item, deferred put processing policy is ignored and the put operations are processed synchronously.



Fast validation

Fast validation helps improve performance by enabling the mobile app to do validation using local data, without interacting with the server. This is currently supported when you consolidate license plates and validate catch weight tags during sales picking.

Show work line list

Choose when the warehouse app displays a complete list of lines for the current picking work. This feature provides options that replace the standard "Skip" button. Choose one of the following:

"Show only upon request": Workers can choose to see the list by selecting the "Skip to" button.

"Show at the start of every pick": Workers see the list every time they start or complete a pick line and can see it again by selecting the "Skip to" button.

"Show at the start of the first pick only": Workers see the list each time they start new picking work, but not after each line. They can see the list again by selecting the "Skip to" button.

"Never show": Provides the standard "Skip" button, thereby disabling the work lines list display.

D365 F&O Warehouse Management systems (Advance warehouse)-4

Show work line list

Never show

Never show

Show only upon request

Show at the start of the first pick only

Show at the start of every pick


Work classes

+ New Delete

☐	☐	Work class ID	Work order type
☐	☒	Sales	Sales orders
☐	☐	SO Pick	Sales orders

Work confirmation setup


Is used to input fields manually in order to confirm that there is no mismatch between the system generated and user inputted value.



Select **Work confirmation setup**.

1. In the **Work type** field, select **Pick**.
2. Select the **Auto confirm** check box. The work instruction with work type Pick will be auto-confirmed. This instruction will not be presented to the user.
3. Select **New**.
4. In the **Work type** field, select 'Put'.
5. Select the **Location confirmation** check box. The warehouse worker will be asked to perform a confirmation scan of the location, when the item is put down.
6. Select **Save**.

D365 F&O Warehouse Management systems (Advance warehouse)-4




Mobile device Menu

This will help us to setup what all device menu items will be displayed under which module or process

Navigation

Warehouse Management > Setup > Mobile device > Mobile device menu items

Use this to create the module or process related menu



Move the menu items as per the process