



• VST3 • AU • STANDALONE

MOTION SHAPER

EFFECT

MAKE IT MOVE

Creative Motion Shaper: a 16-step motion sequencer, three step-LFOs, beat repeat, drive, noise and an FX rack – all locked to your tempo.



USER MANUAL

1.1.0 VER

PRESETS

145



WHAT'S INSIDE

01	GETTING STARTED	03
	How it works, first sound	
02	MOTION SEQUENCER	04
	MAIN and SEQ 1-3, LEN, swing, glide	
03	RANDOMIZE	06
	Per section, per lane, all at once	
04	TRIGGER	07
	Euclidean, clock, MIDI, transients	
05	DRIVE AND NOISE	10
	Five clip modes, five noise colours	
06	LFOS AND ROUTING	12
	Three generators, 27 targets	
07	BEAT REPEAT	15
	Grid, roll, reverse, pitch glitch	
08	PRESET LIBRARY	17
	145 factory presets by genre	
09	UNDO AND OUTPUT SAFETY	18
	Undo everything, a ceiling for your ears	
10	ACTIVATION	19
	Demo, preferences, serial	

01 — GETTING STARTED

THREE MODULES, FOUR LANES OF MOTION

AudioXL Motion FX applies **three effect modules** – **Filter, Volume, Pan** – in parallel, plus drive/noise, an FX rack, a granular engine and beat repeat. The movement comes from **four independent sequenced lanes**, all synced to the host tempo.

FILTER

SVF (State Variable) filter with a logarithmic sweep – ideal for acid sweeps.

VOLUME

Rhythmic gating – depth sets how far the envelope pulls the volume down.

PAN

Stereo sweep in sync with the rhythm.

FIRST SOUND IN LOGIC PRO

01**INSERT**

Put AudioXL Motion FX on a channel as an Audio Effect Unit.

02**PLAY**

Start playback – the envelope syncs automatically to the project BPM.

03**DRAW**

Shape the envelope by clicking on the 16 bars.

04**SWITCH ON**

Enable the modules with their ON buttons – Filter is on by default.

STEPS

16

LANES

4

MOD TARGETS

27

PRESETS

145

Formats: VST3, AU and Standalone. Works on stereo and mono buses (insert on a mono track or aux). The macOS installer is universal: Intel x86_64 and Apple Silicon arm64 in a single .pkg / .dmg.

02 — MOTION SEQUENCER

FOUR LANES, ONE BIG GRAPH

LANE	WHAT IT IS	DESTINATIONS
MAIN	16-step motion seq	Filter / Volume / Pan
SEQ 1	LF0 1, step mode	Any of the 27 targets of the matrix
SEQ 2	LF0 2, step mode	Any of the 27 targets
SEQ 3	LF0 3, step mode	Any of the 27 targets

All four are edited in the same large graph: the **MAIN / SEQ 1 / SEQ 2 / SEQ 3** tabs at the top right of the MOTION SEQUENCER panel switch the lane on display.

**NOTE**

SEQ RND randomises the lane you are looking at, not always the main one.

CONTROL	RANGE	WHAT IT DOES
STEPS	per bar	Every bar is a step. MAIN is unipolar (0-100 %); the SEQ lanes are bipolar (-100 ... +100 %) and grow from the centre line.
LEN	1 ... 16	Pattern length. A 7-step lane against a 16-step MAIN makes polymeter – the two only come back into phase after 112 steps .
SWING	0 ... 75 %	Delays the odd step of every pair. Each lane has its own, so you can layer different grooves.
LINEAR	MAIN only	Linear interpolation between steps.
GLIDE	SEQ only	Portamento between steps, from hard steps to a full slide.
LANE ON	on / off	Switches the lane on or off without leaving the page.
SYNC	1/32 ... 1/4	Divides every step into time units (1/16 = one step every sixteenth). For SEQ lanes the division is the length of one step, so the cycle lasts LEN × division .

LEN 16 AGAINST LEN 7 · FIRST 32 STEPS

back in phase after **112 steps**

MAIN · 16

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

SEQ 1 · 7

1

2

3

4

5

6

7

1

2

3

4

5

6

7

1

2

3

4

5

6

7

1

2

3

4

5

6

7

1

2

3

4

03 — RANDOMIZE

ROLL THE DICE, KEEP THE SEED

Every section has its own randomiser – Filter, Volume, Pan, Beat Repeat, Drive, Noise, the three LFOs, Reverb, Delay, Chorus, Flanger, Granular – plus a global **ALL RND**. A **Seed Lock** in each section fixes the random seed, to repeat the same result or vary it step by step.

ENVELOPE SEQUENCER

RND SHAPE

A new random curve over the 16 steps, with a uniform or weighted distribution: **Smooth / Sparse / Dense**.

RND SYNC

Picks a random subdivision among 1/32, 1/16, 1/8, 1/4.

RND MODULE

Randomly switches one or more modules on or off (Filter, Volume, Pan).

SEED LOCK

Fixes the random seed – useful to repeat the same result or vary it incrementally.



Illustrative curves of the three RND Shape distributions.

RND IN EVERY SECTION

FILTER **VOLUME** **PAN** **BEAT REPEAT** **DRIVE** **NOISE** **LFO 1**

LFO 2 **LFO 3** **REVERB** **DELAY** **CHORUS** **FLANGER** **GRANULAR** **ALL RND**

04 — TRIGGER • ENVELOPE SEQUENCER

WHEN THE MOTION STARTS

The Trigger module decides when and how the envelope sequencer is started, reset or pulsed. **Four selectable sources**, which can be combined.

01 • EUCLIDEAN

Rhythmic patterns spread euclideanly over N steps.

STEPS (N)	1 ... 32	Total steps of the pattern.
PULSES (K)	$K \leq N$	Hits spread as evenly as possible over N.
ROTATION (R)	offset	Pattern rotation (0 = canonical position).
RATE	1/32 ... 1/4...	How fast the pattern advances.



02 • CLOCK

DIVISION	1/32 ... 1 bar	1/32, 1/16T, 1/16, 1/8T, 1/8, 1/4, 1/2, 1 bar — synced to the host transport.
PHASE OFFSET	0 ... 100 %	Delays the trigger as a percentage of the division.
RESET ON BAR	on / off	Resets the envelope position at the start of every bar.

03 • MIDI

The envelope starts (or is reset) when MIDI notes or CCs arrive.

NOTE ON	channel	Triggers on every Note On on the selected channel.
NOTE FILTER	All / C3 / D#4...	Filters by a specific pitch.
CC TRIGGER	0 ... 127	Triggers on a CC message – CC number and value threshold selectable.
LATCH	on / off	Keeps the envelope looping until a Note Off arrives.
CHANNEL	1 ... 16 / Omni	MIDI listening channel.

04 • TRANSIENT DETECTOR

Analyses the incoming audio and triggers the envelope on the detected attacks.

SENSITIVITY	0 ... 100 %	Transient detection threshold.
ATTACK	fast / med / slow	Response time of the detector.
FILTER BAND	4 bands	Low (kick), Mid (snare/clap), High (hat/perc), Full.
COOLDOWN	ms	Minimum time between two triggers – avoids double triggers.
SIDECHAIN INPUT	self / ext.	Audio source for the detector: the signal itself or an external sidechain bus.

COMBINING THE SOURCES

FIRST

The first source to fire wins – useful for a MIDI override on top of the clock.

AND

Triggers only if two or more sources fire in the same window (± 1 step).

OR • DEFAULT

Any source starts the envelope.

PRIORITY

Manual priority order – drag and drop the sources in the list.

RANDOMIZE – TRIGGER

RND EUCLIDEAN

A new random N/K pair with K between $N/4$ and $N/2$ (musical density) and a random rotation.

RND SOURCE

Randomly enables a combination of trigger sources in OR mode.

RND DIVISION

Clock: picks a random subdivision among the synced ones.

SEED LOCK

Fixes the seed.

RND EUCLIDEAN • K BETWEEN $N/4$ AND $N/2$ • EXAMPLES



N 16 • K 4 • R 0



N 16 • K 6 • R 2



N 12 • K 5 • R 1



N 8 • K 3 • R 0

05 — DISTORTION MODULES

DRIVE AND NOISE

Two independent distortion modules, placeable in the chain **before** or **after** the Filter/Volume/Pan modules.

DRIVE

SOFT CLIP

Soft tape/valve-style saturation.

HARD CLIP

Clean digital clipping.

FOLD

Wavefolder — complex harmonics, great for metallic sounds.

BITCRUSH

Word-length reduction (1-16 bit).

TUBE

Asymmetric triode-style emulation.

MODE • 5 TYPES

DRIVE	0 ... 100 %	Input gain into the saturator.
TONE	Dark ↔ Bright	Post-distortion EQ: cuts the highs or lifts them.
MIX	0 ... 100 %	Dry/wet — allows parallel distortion.
PRE / POST	position	Pre: before the filter, it colours the sweep. Post: after it, it distorts the result.

NOISE

A modulatable noise generator, added to the signal.

WHITE**PINK****BROWN****VINYL · CRACKLE****DIGITAL · BIT
NOISE****LEVEL****-∞ ... 0 dB**

Noise level relative to the signal.

FILTER**20 Hz - 20 kHz,
Q**

A band-pass on the noise.

GATE**on / off**The noise follows the envelope sequencer — **ON** = **rhythmic, synced noise**.**STEREO WIDTH****mono → stereo**

Width of the generated noise.

RANDOMIZE — DISTORTION

RND DRIVERandom Mode, Drive (**30-80 %**) and Tone — avoids extremes that saturate for nothing.**RND NOISE**Random Type, Level (**-30 ... -12 dB**) and filter band.**RND CHAIN**

Randomises the Pre/Post position and the activation of both modules.

SEED LOCK

Fixes the seed.

RECIPES FOR ACID / TECHNO

ACID DIRT

Drive Soft Clip Amt 65 %

Tone Bright Pre-filter

Mix 80 %

**INDUSTRIAL NOISE
LAYER**

Noise White Level -18 dB

Filter 3 kHz / Q 2 Gate ON

LO-FI CRUNCH

Drive Bitcrush 8 bit

Tone Dark Mix 60 %

Noise Vinyl Level -24 dB

06 – LFO / STEP GENERATORS

THREE GENERATORS, 27 DESTINATIONS

Three independent modulation sources, on top of the main envelope sequencer. Each can modulate any parameter through the routing matrix, and each works in two modes: **LFO** (a continuous waveform) or **Step Sequencer** (16 steps, the same engine as the main envelope, set up separately).

LFO PARAMETERS



SHAPE	9 shapes	SINE, TRI, SAW, RSAW, SQR, S&H, BIN, RND, SEQ.
-------	----------	--

RATE	0.001-20 Hz · 1/1-1/32	Free frequency, or synced to the BPM.
------	------------------------	---------------------------------------

SYNC	on / off	Locks the rate to the host transport.
------	----------	---------------------------------------

DEPTH	0 ... 1	Modulation amount, applied to the bipolar signal.
-------	---------	---

SEQ MODE

Choosing SEQ as the shape turns the LFO into a **16-step lane**. Edit it in the large graph of the MOTION SEQUENCER panel (tabs SEQ 1 / SEQ 2 / SEQ 3); the scope on the LFO page shows the pattern with the playing step highlighted.

LEN	1 ... 16	Lane length in steps.
-----	----------	-----------------------

SWING	per lane	Shuffle inside the lane, independent of the others.
-------	----------	---

GLIDE	0 ... 1	Portamento between adjacent steps (0 = steps, 1 = full slide).
-------	---------	--

SYNC DIV	step length	The full cycle lasts LEN × div.
----------	-------------	---------------------------------

STEP VALUES	-1 ... +1	Bipolar: a lane can push the destination above and below the value set by its knob.
-------------	-----------	--

ROUTING MATRIX

Every LFO/Step can be assigned to **one or more destinations at once** – 27 of them, chosen from each LFO's **TARGETS** button. The indices are stable: new ones are only added at the end, never reordered.

00	Filter Cutoff	01	Volume	02	Pan
03	Drive	04	Noise	05	Granular (GRAN LFO DEST)
06	Filter Res	07	Filter Depth	08	Volume Depth
09	Pan Center	10	Pan Depth	11	Drive Mix
12	Drive Output	13	Reverb Size	14	Reverb Damp
15	Reverb Mix	16	Delay Feedback	17	Delay Mix
18	Chorus Rate	19	Chorus Depth	20	Chorus Mix
21	Flanger Rate	22	Flanger Depth	23	Flanger Feedback
24	Flanger Mix	25	Beat Repeat Mix	26	Output Gain
■ FILTER · VOLUME · PAN ■ DRIVE · NOISE · GRANULAR ■ FX RACK ■ BEAT REPEAT · OUTPUT					

LFO 1

Primary modulation – typically the slowest, the global shape.

LFO 2

Secondary modulation, or in quadrature with LFO 1.

LFO 3

Fast / timbral modulation, or a variation step sequencer.

The three LFOs can be phase-synced or run free, independently.

RANDOMIZE – LFO / STEP

RND LFO

Per generator: randomises Shape, Rate (synced), Phase and Depth – keeps Smooth and Retrigger unchanged so the timing stays stable.

RND STEPS

Step mode: a new random N-step sequence with a **Smooth / Sparse / Groove** distribution (random swing between even and odd steps).

RND ROUTE

Randomly assigns each LFO to a destination in the matrix, with an Amount between **-50 % and +50 %**.

RND ALL

Randomises all three generators at once while keeping musical coherence – avoids modulation clashes on the same destination.

SEED LOCK

Fixes the seed – allows incremental variations of the same random patch.

A BIPOLAR LANE PUSHES THE TARGET ABOVE AND BELOW ITS KNOB

SEQ 1

+1 · ABOVE THE KNOB

KNOB VALUE

-1 · BELOW THE KNOB

07 — BEAT REPEAT

CATCH IT, LOOP IT, FLIP IT

An effect module that captures and replays portions of audio in a loop, in real time, **synced to the host BPM**.

PARAMETER	RANGE	WHAT IT DOES
GRID	1/32 ... 1 bar	Size of the capture cell – 1/32, 1/16, 1/8, 1/4, 1/2, 1 bar.
INTERVAL	× grid	How many grids between repeats (e.g. every 2 steps of 1/16).
GATE LENGTH	0 ... 100 %	Length of the repeated portion, as a share of the grid.
PITCH	-12 ... +12 st	Transposes the loop, with a Glitch mode (random jitter).
CHANCE	0 ... 100 %	Probability of the repeat firing – adds random variation.
REVERSE	on / off	Plays the captured cell backwards.
ROLL	2× · 4× · 8×	Subdivide mode – splits the cell into even smaller slices.
MIX	dry ↔ wet	Balance between the original and the repeated signal.

ROLL · ONE CAPTURED CELL, SUBDIVIDED

OFF



2×



4×



8×



RANDOMIZE — BEAT REPEAT

RND GRID

Random Grid and Interval among musically useful values (1/32-1/4).

RND FX

Randomises Pitch (± 7 semitones), Reverse and Roll consistently with each other.

RND CHANCE

Sets Chance to a random value between 20 % and 80 % – avoids the extremes.

SEED LOCK

Fixes the seed for repeatability.

THE STEP GRID

The beat-repeat **step grid** – Roll, Reverse, Pitch, Stretch, Stop – supports drag-to-merge of columns, with ON/OFF, DRY/WET, RATE and RND. It is covered by undo like every knob, and it is reset by every preset.

RECIPES FOR ACID / TECHNO

MICRO-STUTTER 1/32

Grid 1/32

Gate 50 %

Chance 40 %

Roll 4×

Pitch 0

GLITCH DROP

Grid 1/8

Reverse ON

Pitch Glitch

Chance 60 %

Mix 0.7

TAPE LOOP

Grid 1/4

Gate 100 %

Roll OFF

Reverse OFF

Pitch -12

08 — PRESET LIBRARY

145 PRESETS, BY GENRE AND INSTRUMENT

The PRESET menu groups the library by genre and instrument. **Every preset is self-contained**: recalling it resets the whole parameter tree – modules, per-section envelopes, modulation lanes and the beat-repeat grid – so it never inherits anything from the previous patch.

ACID		10	303, ladder LP, high resonance, valve drive
TECHNO		13	gate, pump, tunnel, industrial, modular patchbay
HOUSE		9	disco filter, sidechain pump, garage shuffle
MINIMAL / DUB TECHNO		7	dub delay, click, micro groove
TRANCE / PSY		5	1/16 gate, rolling bass, uplifter
BASS MUSIC		7	neuro morph, wobble, talkbox, sub drop
DRUM & BASS / BREAKS		5	amen chopper, rollers, jungle stutter
IDM / GLITCH		14	polymeters, granular, bit rot, random walk
TRANSITIONS / FX		7	riser, downlifter, tape stop, impact
AMBIENT / DOWNTempo		12	frozen grains, drift, long rooms
DUB / DELAY		3	echo chamber, dub siren, ping-pong
TEXTURE / LO-FI		7	tape, vinyl, metal fold, sub rumble
MODULATION LAB		13	a showcase of the lanes: triple, polymetric, glide, shuffle
LEAD		8	supersaw gate, formant talk, screamer, analogue unison
VOCAL		8	chop gate, formant wobble, telephone, doubler, robotic talk
KEYS		8	classic tremolo, chorus ensemble, auto-wah, vintage flange
PAD		8	slow riser, granular shimmer, breathing filter, choir swell

START FROM MODULATION LAB – the best presets to understand the engine

TRIPLE LANES	One lane per module (cutoff / drive / pan), same 1/16 grid.
POLY LANES 5-7-16	Three lanes of coprime lengths: they don't realign for 560 steps.
GLIDE LANE BASS	The lane is the bass line, glide at 50 %.
SHUFFLE LANES	Three different swings at the same time.
CROSS MOD CHAOS	Every lane hits several destinations at once.

09 — UNDO AND OUTPUT SAFETY

UNDO ANYTHING, HURT NOBODY

UNDO / REDO

Two buttons in the header, between SYNC and PREFERENCES — dimmed when there is nothing to undo or redo, white otherwise. The tooltip says what would be undone or redone.

KNOBS, TOGGLES, MENUS

One step per interaction: **one knob turn = one undo**, not one per pixel of movement.

PRESETS

Factory and user: loading one is a single undo step, even though it changes ~150 parameters and resets the beat-repeat grid. Loading a user preset **keeps the earlier history**.

BEAT REPEAT

The step grid, drag-to-merge, ON/OFF, DRY/WET, RATE, RND — all undoable.

RND

Per module, SEQ RND, ALL RND: one click, one undo — even when ALL RND touches ten modules at once.


The history is cleared only when the host reloads the plugin state — that is, when you open a saved project. Never on a preset change during the session.

OUTPUT SAFETY CEILING

The output goes through a soft limit: **transparent up to 2× full scale**, then a knee that **never exceeds 4×**. It is not an effect and is not meant to be touched — it only makes sure no combination of parameters can slam the monitors of whoever is trying the plugin.

It touches nothing musical: the hottest preset in the library reaches ~3.3× only with an already hot input (the ceiling takes 0.4 dB off that single peak), and every parameter measured on its own from the defaults stays well below.

IN → OUT (× FULL SCALE)



Shape drawn for illustration.

10 – ACTIVATION

TEN MINUTES, THEN ONE SERIAL

The plugin runs for **10 minutes from first launch** – real time, not playback time – then goes into stand-by: the audio comes out muted until a valid serial is entered. The ten minutes are a **single budget tied to the machine**, not a per-session timer: closing and reopening the plugin or the DAW doesn't reset it.

The header shows no countdown and no AUTHORIZE button – only a **PREFERENCES** button, to the left of POWER.

1 • ANY TIME

PREFERENCES > AUTHORIZATION: the demo status (time left, or ACTIVE with the registered serial), the serial field and the **UNLOCK** button.

2 • AT EXPIRY

When the 10 minutes run out the plugin opens the preferences on the AUTHORIZATION tab by itself – **once per session**, so it doesn't keep stealing focus. The window can be closed; the audio stays muted until a serial is entered.

TAB		WHAT'S THERE
GENERAL	folders	The folders the plugin writes to – user presets and authorisation data – each with an OPEN button.
AUTHORIZATION	licence	Demo/licence status, serial field, UNLOCK.
ABOUT	info	Logo, name, version, company and website – the same screen that opens when you click the logo in the sidebar.

SERIAL FORMAT

AXLM-XXXX-XXXX-XXXX

Upper-case letters and digits; case and dashes don't matter when typing it.

ONE ACTIVATION, EVERY FORMAT

Per installed plugin on the machine, not per DAW session: **VST3, AU and Standalone** share the same state. It survives plugin updates as long as **~/Library/AudioXL/MotionFX/** is not deleted.



NOW MAKE IT MOVE

Four lanes, three LFOs, 27 destinations
— all on your tempo.

