


1. Create Secure Gateway Resource

Navigate to the [Secure Gateway page](#) and create a new Gateway. Note that provisioning may take several minutes to complete.



2. Configure Private Application Resource

To enable access to your internal resources, define a new application within the Secure Gateway.

1. Click the **Add application** button.

Secure Gateway

✓ Successfully created your Secure Gateway. Next step is to [add your first application](#) [Learn more](#) [Add your first application](#)

Secure Gateway provides a unified, browser-integrated solution for zero-trust access. It extends Google Cloud's zero-trust architecture directly to Chrome, offering Context-Aware Access to both SaaS and private web applications, eliminating VPN overhead and enhancing security posture, all within Chrome. [Learn more.](#)

Applications (0)

SaaS Egress Hubs (0)

Access policies

Chrome configuration

Applications

+

Add application

Copy all Egress IPs

Filter

Enter property name or value

?

⋮

Type	Name ↑	Domain Matchers	Egress hubs	Access policy	More actions
					

2. Select **Private application** as the application type.

Select application type

What type of application is it?



Public application

Control access to SaaS applications that support IP allowlisting by utilizing customer-specific static egress IPs. The Secure Enterprise Browser extension intercepts traffic to configured URLs, routes these requests to Secure Gateway in Google Cloud, which then evaluates context-aware access policies and routes them to the target destination via dedicated egress IPs. [Learn more](#)



Private application

Securely connect to internal web applications within Google Cloud, on-premise, or other cloud providers without exposing them to the public internet. The Secure Gateway routes Chrome traffic to these private resources while maintaining zero-trust security controls.

Next

3. Enter an application name and define the **Domain matchers**. Valid matchers include VM IP addresses, GKE application endpoints, load balancer IPs, or FQDNs that resolve to internal application IPs.

Note: Only HTTPS endpoints are supported for now.

Add private application

Make sure all fields are correct to continue

Go to issue(s)

1
Add application details
test (*.example.com, 10.0.0.1)

2
Configure VPC network
Specify the corresponding Google Cloud VPC

3
Define egress policy (optional)
Select Google Cloud region from which the private app will be accessible

4
Define app access policy (optional)
Add authorized users or groups

Add application details

Application name *
test

If your application does not have a name, use a display name.

Domain matchers *
*.test.internal:443, 10.1.1.2:443

Domain matchers should follow the format domain:port. Wildcards (*) are allowed. For example: github.com:80, github.com:443, 192.168.1.1:8080, *.google.com:80

Continue

- Configure the **Upstream VPC network**. The target VPC can reside within the Secure Gateway project or a separate project (as shown in this example).

Add private application

Make sure all fields are correct to continue

Add application details
test (*.test.internal, 10.1.1.2)

2
Configure VPC network
Specify the corresponding Google Cloud VPC

3
Define egress policy (optional)
Select Google Cloud region from which the private app will be accessible

4
Define app access policy (optional)
Add authorized users or groups

Configure VPC network

Where is the VPC network?

☐ In current project
VPC network is in current project.

☒ In another project
My VPC network is in a different project, and I have the correct permissions. [Learn more](#)

projects/sg-directvpc-routing-test/global/networks/gc-vpc

E.g. "projects/PROJECT_ID/global/networks/NETWORK"

Back Continue

- Select the appropriate **Egress policy**. This step can be skipped if the backing resource (e.g., VM, Global LB) supports cross-region traffic. Otherwise, specify the region where the application is hosted.

❗ Make sure all fields are correct to continue

✓ Add application details
test (*.test.internal, 10.1.1.2)

✓ Configure VPC network
Specify the corresponding Google Cloud VPC

3 Define egress policy (optional)
Select Google Cloud region from which the private app will be accessible

4 Define app access policy (optional)
Add authorized users or groups

Define egress policy (optional)

Select Google Cloud region(s) from which the private app will be accessible

Choose one or more supported regions: ▼

Back

Continue

6. Define user permissions to grant access to the application.

← Add private application

✓ Add application details
test (*.test.internal, 10.1.1.2)

✓ Configure VPC network
Specify the corresponding Google Cloud VPC

✓ Define egress policy (optional)
Select Google Cloud region from which the private app will be accessible

4 Define app access policy (optional)
Add authorized users or groups

Define app access policy

Add principals
Principals are users, groups, domains, or service accounts. [Learn more](#)

Principal *
teyuchang@google.com X

Role *
Secure Gateway user ▼

Access Levels ▼

X

+ Add Principal

Back

7. Click **Create** to finalize the application setup.

Secure Gateway provides a unified, browser-integrated solution for zero-trust access. It extends Google Cloud's zero-trust architecture directly to Chrome, offering Context-Aware Access to both SaaS and private web applications, eliminating VPN overhead and enhancing security posture, all within Chrome. [Learn more.](#)

Applications (1) SaaS Egress Hubs (0) Access policies Chrome configuration

Applications [Add application](#) [Copy all Egress IPs](#)

Filter Enter property name or value

Type	Name ↑	Domain Matchers	Egress hubs	Access policy	More actions
Private	test	*.test.internal:443, 10.1.1.2:443		1 principal	

2. Locate and copy the **Delegating service account** email address.


← Application details for test [Edit](#) [Remove](#)

test

Application name	test
Domain matchers	*.test.internal:443, 10.1.1.2:443
VPC network	gc-vpc
Delegating service account	security-gateway@tf2bf4240fb40c84fp-tp.iam.gserviceaccount.com
Access policy	user:teyuchang@google.com

Navigate to the [IAM & Admin page](#) in the VPC network project (e.g., *sg-directvpc-routing-test*) and grant the necessary roles to the delegating service


account.



4. Configure Firewall Rules

Ensure the Secure Gateway can communicate with your VPC resources by creating an ingress firewall rule in the VPC project.

1. Navigate to [VPC Firewall](#) and click **Create firewall rule**.



Name: allow-secure-gateway

Network: [Target VPC Network Name]

Targets: All instances in the network

Source IPv4 ranges: 136.124.16.0/20

Protocols/Ports: TCP

Leave other options with their default value.

Create a firewall rule

Firewall rules control incoming and outgoing traffic to an instance. By default, all incoming traffic to your network is blocked. [Learn more](#)

Name *

allow-secure-gateway



Lowercase letters, numbers, hyphens allowed

Description

Logs

Turning on firewall logs can generate a large number of logs which can increase costs in Logging. [Learn more](#)

☐ On

☒ Off

Network *

gc-vpc



Priority *

1000

[Compare](#)



Priority can be 0 - 65535

Direction of traffic 

☒ Ingress

☐ Egress

Action on match 

☒ Allow

☐ Deny

Action on match ?

☒ Allow

☐ Deny

Targets

All instances in the network



Source filter

IPv4 ranges



Source IPv4 ranges *

136.124.16.0/20



for example, 0.0.0.0/0, 192.168.2.0/24



Second source filter

None



Destination filter

None



Protocols and ports ?

☐ Allow all

☒ Specified protocols and ports

☒ TCP

Ports


E.g. 20, 50-60

5. DNS Configuration

Follow these steps to configure internal DNS resolution (e.g., resolving *my-app.example.com* to *10.0.0.1*).

It can be any IPv4 address in the VPC network and any domain name. Replace the IP address and domain name in the following example if needed.

1. Go to the [Cloud DNS page](#), select your project, and click **Create Zone**.



Zone type: Private

Zone name: private-zone

DNS name: example.com

Network: Add the VPC network where the application resides.

Leave other options with their default value and click “Create”

[←](#) Create a DNS zone

Zone type [?](#)

☒ Private

☐ Public

Zone name * [?](#)

private-zone

Lowercase, no spaces.

DNS name * [?](#)

example.com

Example: myzone.example.com

Description

Options * [?](#)

Default (private) ▼

Networks [?](#)

Your managed zone will be visible to the selected networks.

^ New networks 

Project * [?](#)

sg-directvpc-routing-test Select

Networks * [?](#)

gc-vpc ▼

Done

- Once the zone is created, click **Add standard** to create a record set.

[← Zone details](#) [✎ Edit](#) [+ Add networks](#) [🗑 Delete zone](#)

private-zone

DNS name

example.com.

Type

Private

Record sets

In use by

+ Add standard

+ Add with routing policy

🗑 Delete record sets

🔄 Refresh

Filter

Filter record sets

?

☰

☐	DNS name ↑	Type	TTL (seconds)	Record data
☐	example.com.	SOA	21600	ns-gcp-private.googleapis.com. cloud-dns-hostmaster.google.com. 1 21600 3600 ✓ ✎
☐	example.com.	NS	21600	ns-gcp-private.googleapis.com. ✎

[Equivalent REST](#)

DNS name: my-app.example.com

IPv4 Address: 10.0.0.1 (or your application's IP).

Leave other options with their default value. Click “Create”.

←

Create record set

DNS name

my-app .example.com. ?

Resource record type

A ▼ ?

TTL *

5 ?

TTL unit

minutes ▼ ?

IPv4 Address ?

IPv4 Address 1 *

10.0.0.1

Select

Example: 192.0.2.91

+ Add item

Create

Cancel

6. Enable Global Access for Regional Load Balancers

If your application is backed by a Regional Internal Load Balancer, you must either enable Global Access on the load balancer or configure a specific egress policy within the Secure Gateway application settings.

Navigate to the [Load balancing page](#) to verify whether your load balancer type is global or regional.



Monitor + Analyze Load Balanced Traffic

Use VPC Flow Logs and Flow Analyzer to gain flow level insights for your Load Balancers and backends. [Learn more](#)

- ✓ Diagnose connectivity issues
- ✓ Identify top talkers + Analyze network utilization
- ✓ For passthrough load balancers, understand how flows are being distributed among their backends

[Try now](#) [Remind me later](#)

[Load balancers](#) [Backends](#) [Frontends](#) [Service LB policies](#)

i Faster web performance and improved web protection with Cloud CDN and Cloud Armor. [Learn more](#)

Filter Enter property name or value

☐	Name	Load balancer type	Access type	Protocols	Region	Backends	Actions
☐	cross-region	Application	Internal	HTTP		✓ 1 backend service (0 instance groups, 1 network endpoint group)	⋮
☐	test	Application	Internal	HTTP	europa-west1	✓ 1 regional backend service (0 instance groups, 1 network endpoint group)	⋮

To view or delete load balancing resources like forwarding rules and target proxies, go to the [load balancing components view](#).

Cross-region LB

Regional LB

For regional load balancers, click the resource name to view its details. Ensure that at least one frontend has **Global Access** enabled. Additionally, verify that the Secure Gateway Application's endpoint matcher is correctly configured to use the frontend's IP

address and port.

[←](#) Load balancer details [Edit](#) [Delete](#)

test

Regional internal Application Load Balancer

Region
europa-west1

Frontend

Protocol ↑	Subnetwork	IP:Port	Certificate	SSL Policy	DNS name	Global Access	HTTP keepalive timeout ⓘ
HTTP	default (10.132.0.0/20)	10.132.0.2:80	-			Disabled	610 seconds
HTTP	default (10.132.0.0/20)	10.132.0.3:80	-			Enabled	610 seconds

Host and path rules

Hosts ↑	Paths	Backend
All unmatched (default)	All unmatched (default)	test

Backend

Backend services

1. test

Endpoint protocol	HTTPS
IP address selection policy ⓘ	Only IPv4
Health check	—
Logging	Disabled
Backend security policy	default-security-policy-for-backend-service-test

Backends

Name ↑	Type	Scope	Healthy	Autoscaling	Balancing mode	Traffic duration	Capacity	Preference level ⓘ
test	Serverless network endpoint group	europa-west1	N/A	No configuration	N/A	Default (Short)	N/A	None

If Global Access is disabled on all existing frontends, you can enable it by editing the load balancer configuration.

← Load balancer details

Edit

Delete

test

Regional internal Application Load Balancer

Region

europa-west1

Frontend

Protocol ↑	Subnetwork	IP:Port	Certificate	SSL Policy	DNS name	Global Access	HTTP keepalive timeout ⓘ
HTTP	default (10.132.0.0/20)	10.132.0.2:80	-			Disabled	610 seconds
HTTP	default (10.132.0.0/20)	10.132.0.3:80	-			Enabled	610 seconds

Host and path rules

Hosts ↑	Paths	Backend
All unmatched (default)	All unmatched (default)	test

Backend

Backend services

1. test

Endpoint protocol	HTTPS
IP address selection policy ⓘ	Only IPv4
Health check	—
Logging	Disabled
Backend security policy	default-security-policy-for-backend-service-test

Backends

Name ↑	Type	Scope	Healthy	Autoscaling	Balancing mode	Traffic duration	Capacity	Preference level ⓘ
test	Serverless network endpoint group	europa-west1	N/A	No configuration	N/A	Default (Short)	N/A	None

Navigate to the **Frontend configuration** tab and select **Add Frontend IP and Port**. Ensure the **Global access** checkbox is selected before saving your changes.

[←](#) Edit regional internal Application Load Balancer

Load Balancer name
test

Region
europe-west1

Network
default

Proxy-only subnet *
test1 (192.168.2.0/24)



☒ Backend configuration

☒ Routing rules

☒ Frontend configuration

Review and finalize (optional)

Frontend configuration

Specify an IP address, port and protocol. This IP address is the frontend IP for your clients requests. For SSL, a certificate must also be assigned.

✓ Protocol: HTTP, IP: 10.132.0.2, Port: 80



✓ Protocol: HTTP, IP: 10.132.0.3, Port: 80



^ New Frontend IP and port



Name (Optional)

global-access



Lowercase, no spaces.

✓ Description

Protocol

HTTP



Subnetwork *

default



Port *

80

Application load balancing supports all TCP ports. [Learn more](#)

IP address *

Ephemeral (Automatic)



Global access



☐ Disable

☒ Enable

Service label (Optional)



✓ Show Advanced Features

Done

Add Frontend IP and port