



FEM for 2D problems

Heat conduction: Finite element formulation



Global basis functions

Simplest approach: Triangle mesh and piecewise linear functions




Nodes $\underline{x}_n, n=1, \dots, N_n$

Elements $\Omega_e, e=1, \dots, N_e$

$\Omega_e \subset \Omega, \underline{x}_n \in \Omega$

Basis functions: $\varphi_i : \Omega \rightarrow \mathbb{R}, i = 1, \dots, N$

- Piecewise linear
 - Function value one at node i and zero for all other nodes $\rightarrow \varphi_i(\underline{x}_j) = \delta_{ij}$
- \rightarrow As in 1D



Linear system

Approximate solution

$$\theta_h = \sum_{i=1}^N \varphi_i \cdot \hat{\theta}_i, \quad \hat{\theta}_i \in \mathbb{R}$$

As before

$$\underline{K} \hat{\underline{\theta}} = \underline{f}$$

where

$$k_{ij} = a(\varphi_i, \varphi_j) = \int_{\Omega} \lambda \cdot \nabla \varphi_i \cdot \nabla \varphi_j \, dA + \int_{\Gamma_R} h \cdot \varphi_i \cdot \varphi_j \, ds$$

$$f_i = b(\varphi_i) = \int_{\Omega} \omega \cdot \varphi_i \, dA + \int_{\Gamma_R} h \cdot \theta^* \cdot \varphi_i \, ds$$




→ Compute element-wise

$$a(\theta, \delta\theta) = \int_{\Omega} \lambda \cdot \nabla \theta \cdot \nabla \delta\theta \, dA + \int_{\Gamma_R} h \cdot \theta \cdot \delta\theta \, ds$$




$$b(\delta\theta) = \int_{\Omega} \omega \cdot \delta\theta \, dA + \int_{\Gamma_R} h \cdot \theta^* \cdot \delta\theta \, ds$$

Linear element functions on triangle


In one dimension



In two dimensions



Element $\Omega_e \subset \Omega$






Nodes x_1^e, x_2^e, x_3^e

Area A_e

We omit e when we consider a single element

Element functions



$$N_i^e : \Omega_e \rightarrow \mathbb{R} \quad \text{with} \quad N_i^e(x_j^e) = \delta_{ij} = \begin{cases} 1 & \text{if } i=j \\ 0 & \text{otherwise} \end{cases}, \quad i,j=1,2,3$$

N_i^e are functions of planes


$$N_i^e(x, y) = a_i + b_i \cdot x + c_i \cdot y$$

$$\nabla N_i^e(x, y) = \begin{pmatrix} b_i \\ c_i \end{pmatrix}$$

→ Gradient is element-wise constant

Milestones

1. Verification with analytical solution




$$\theta(x_1, x_2) = \frac{\omega}{4 \cdot \lambda} (r^2 - x_1^2 - x_2^2)$$

$$\theta_{\max} = \frac{\omega \cdot r^2}{4 \cdot \lambda}$$

Required

- Element conductivity matrix \underline{K}^e and source vector \underline{f}^e
- Dirichlet BCs
- Mesh with triangle elements

2. Application to practical problem



Required

- Robin and Neumann BCs
- Varying values for λ

Element conduction matrix and source vector

Global bilinear and linear forms

$$a(\theta, \delta\theta) = \int_{\Omega} \lambda \cdot \nabla \theta \cdot \nabla \delta\theta \, dA + \int_{\Gamma_R} h \cdot \theta \cdot \delta\theta \, ds$$
$$b(\delta\theta) = \int_{\Omega} w \cdot \delta\theta \, dA + \int_{\Gamma_R} h \cdot \theta^* \cdot \delta\theta \, ds$$

later

Element bilinear and linear forms

$$a_e(\theta, \delta\theta) = \int_{\Omega_e} \lambda \cdot \nabla \theta \cdot \nabla \delta\theta \, dA$$

$$b_e(\delta\theta) = \int_{\Omega_e} w \cdot \delta\theta \, dA$$

Element stiffness matrix

$$\delta(\theta, \delta\theta) = \int_{\Omega_e} \lambda \cdot \nabla \theta \cdot \nabla \delta\theta \, dA$$

$$K_{ij}^e = a^e(N_i^e, N_j^e) = \int_{\Omega_e} \lambda \cdot \nabla N_i^e \cdot \nabla N_j^e \, dA$$

For linear triangle

$$\begin{aligned} &= \lambda \cdot \nabla N_i^e \cdot \nabla N_j^e \int_{\Omega_e} 1 \, dA \\ &= \lambda \cdot A_e \cdot \nabla N_i^e \cdot \nabla N_j^e \end{aligned}$$

$$K^e = \lambda \cdot A_e \cdot \begin{pmatrix} \nabla N_1^e \cdot \nabla N_1^e & \nabla N_1^e \cdot \nabla N_2^e & \nabla N_1^e \cdot \nabla N_3^e \\ \nabla N_2^e \cdot \nabla N_1^e & \nabla N_2^e \cdot \nabla N_2^e & \nabla N_2^e \cdot \nabla N_3^e \\ \nabla N_3^e \cdot \nabla N_1^e & \nabla N_3^e \cdot \nabla N_2^e & \nabla N_3^e \cdot \nabla N_3^e \end{pmatrix}$$

Sym

Element matrix with the B-matrix

$$\underline{N}^e = (N_1^e \ N_2^e \ N_3^e), \text{ Vector of shape functions}$$

$$\underline{D} = \nabla = \begin{pmatrix} \partial / \partial x_1 \\ \partial / \partial x_2 \end{pmatrix}, \text{ Differential-operator}$$

$$\underline{B}^e = \underline{D} \underline{N}^e = (\nabla N_1^e \ \nabla N_2^e \ \nabla N_3^e)$$

$$K^e = A_e \cdot \lambda \cdot \underline{B}^e \underline{B}^{eT}$$

Exercise