

## Creating a System Rescue USB

### Required Materials

-  1x USB drive (32 GB or 64 GB)
  -  1x Folder with the rescue script and ISO file [Folder](#)
- 

### Step 1 — Prepare the Files

1. Download the provided `.zip` file containing the rescue utility.
  2. Unzip the file. A folder will be extracted (e.g., `systemrescueUSB`).
  3. Inside this folder, ensure you have:
    - `comando.txt`
    - `gen.sh`
    - `systemrescue-9.06-amd64.iso`
- 

### Step 2 — Format the USB Drive

 This process will **erase** all contents of the USB.

1. Plug the USB into your **Linux** PC.
2. Run the following to identify the USB device:

```
lsblk
```

Look for your USB device (e.g., `sda` , `sdb` ) based on size.

3. Launch a partition tool such as **GParted**:

```
sudo gparted
```

- Delete all existing partitions on the USB.
  - Create a **single partition** formatted as **ext4**.
  - Apply changes and close the tool.
4. Unplug and replug the USB.
  5. Run `lsblk` again to confirm the correct device name (e.g., `/dev/sdb` ).
- 

### Step 3 — Generate the Rescue USB

1. Open a terminal.

2. Navigate to the extracted folder:

```
cd /path/to/systemrescueUSB
```



3. Run the generation script (replace `sda` with your USB device name):

```
sudo ./gen.sh sda systemrescue-9.06-amd64.iso 906
```



This may take a few minutes.

When it finishes, your **System Rescue USB** will be ready.

---

#### Step 4 — Modify GRUB Configuration (Optional)

After creation, you may need to edit the GRUB configuration:

1. Mount the first partition of the USB:

```
sudo mount /dev/sda1 /mnt
```

2. Navigate to the GRUB directory and edit the relevant config file as needed:

```
sudo nano /mnt/boot/grub/grub.cfg
```

Remove all the content, then paste the next one:

```
1 # Global options
2 set timeout=30
3 set default=0
4 set fallback=1
5 set pager=1
6
7 # Display settings
8 if loadfont /boot/grub/font.pf2 ; then
9     set gfxmode=640x480
10     set color_normal=black/cyan
11     set color_highlight=black/light-gray
12     set menu_color_normal=black/cyan
13     set menu_color_highlight=black/light-gray
14     insmod efi_gop
15     insmod efi_uga
16     insmod gfxterm
17     insmod all_video
18     insmod videotest
19     insmod videoinfo
20     terminal_output gfxterm
21 fi
22
```

```

23 # enable serial console with common settings (ttyS0, 115200 Baud, 8n1)
24 # this works in parallel to regular console
25 serial --unit=3 --speed=115200 --word=8 --parity=no --stop=1
26 terminal_input --append serial
27 terminal_output --append serial
28
29 menuentry "SystemRescue EQX" {
30     set gfxpayload=keep
31     linux /sysresccd/boot/x86_64/vmlinuz archisobasedir=sysresccd archisolabel=RESCUE906
32     iomem=relaxed console=ttyS3,115200n8 copytoram
33     initrd /sysresccd/boot/intel_ucose.img /sysresccd/boot/amd_ucose.img
34     /sysresccd/boot/x86_64/sysresccd.img
35 }
36
37 menuentry "SystemRescue P100" {
38     set gfxpayload=keep
39     linux /sysresccd/boot/x86_64/vmlinuz archisobasedir=sysresccd archisolabel=RESCUE906
40     iomem=relaxed console=ttyS0,115200n8 copytoram
41     initrd /sysresccd/boot/intel_ucose.img /sysresccd/boot/amd_ucose.img
42     /sysresccd/boot/x86_64/sysresccd.img
43 }
44
45 menuentry "Boot SystemRescue using default options" {
46     set gfxpayload=keep
47     linux /sysresccd/boot/x86_64/vmlinuz archisobasedir=sysresccd archisolabel=RESCUE906
48     iomem=relaxed
49     initrd /sysresccd/boot/intel_ucose.img /sysresccd/boot/amd_ucose.img
50     /sysresccd/boot/x86_64/sysresccd.img
51 }
52
53 menuentry "Boot SystemRescue and copy system to RAM (copytoram)" {
54     set gfxpayload=keep
55     linux /sysresccd/boot/x86_64/vmlinuz archisobasedir=sysresccd archisolabel=RESCUE906
56     iomem=relaxed copytoram
57     initrd /sysresccd/boot/intel_ucose.img /sysresccd/boot/amd_ucose.img
58     /sysresccd/boot/x86_64/sysresccd.img
59 }
60
61 menuentry "Boot SystemRescue and verify integrity of the medium (checksum)" {
62     set gfxpayload=keep
63     linux /sysresccd/boot/x86_64/vmlinuz archisobasedir=sysresccd archisolabel=RESCUE906
64     iomem=relaxed checksum
65     initrd /sysresccd/boot/intel_ucose.img /sysresccd/boot/amd_ucose.img
66     /sysresccd/boot/x86_64/sysresccd.img
67 }
68
69 menuentry "Boot SystemRescue using basic display drivers (nomodeset)" {
70     set gfxpayload=keep
71     linux /sysresccd/boot/x86_64/vmlinuz archisobasedir=sysresccd archisolabel=RESCUE906
72     iomem=relaxed nomodeset
73     initrd /sysresccd/boot/intel_ucose.img /sysresccd/boot/amd_ucose.img
74     /sysresccd/boot/x86_64/sysresccd.img
75 }
76
77 menuentry "Boot SystemRescue with serial console (ttyS0,115200n8)" {
78     set gfxpayload=keep
79     linux /sysresccd/boot/x86_64/vmlinuz archisobasedir=sysresccd archisolabel=RESCUE906
80     iomem=relaxed console=tty0 console=ttyS0,115200n8
81     initrd /sysresccd/boot/intel_ucose.img /sysresccd/boot/amd_ucose.img
82     /sysresccd/boot/x86_64/sysresccd.img
83 }
84
85 menuentry "Boot SystemRescue, do not activate md raid or lvm (nomdlvm)" {
86     set gfxpayload=keep
87     linux /sysresccd/boot/x86_64/vmlinuz archisobasedir=sysresccd archisolabel=RESCUE906
88     iomem=relaxed nomdlvm

```

```
74     initrd /sysresccd/boot/intel_ucose.img /sysresccd/boot/amd_ucose.img
75     /sysresccd/boot/x86_64/sysresccd.img
76 }
77 menuentry "Boot a Linux operating system installed on the disk (findroot)" {
78     set gfxpayload=keep
79     linux /sysresccd/boot/x86_64/vmlinuz archisobasedir=sysresccd archisolabel=RESCUE906
80     iomem=relaxed findroot
81     initrd /sysresccd/boot/intel_ucose.img /sysresccd/boot/amd_ucose.img
82     /sysresccd/boot/x86_64/sysresccd.img
83 }
84 menuentry "Stop during the boot process before mounting the root filesystem" {
85     set gfxpayload=keep
86     linux /sysresccd/boot/x86_64/vmlinuz archisobasedir=sysresccd archisolabel=RESCUE906
87     iomem=relaxed break
88     initrd /sysresccd/boot/intel_ucose.img /sysresccd/boot/amd_ucose.img
89     /sysresccd/boot/x86_64/sysresccd.img
90 }
91 menuentry "Memtest86+ memory tester for UEFI" {
92     insmod fat
93     set gfxpayload=800x600,1024x768
94     linux /EFI/memtest.efi keyboard=both
95 }
96 menuentry "Start EFI Shell" {
97     insmod fat
98     insmod chain
99     terminal_output console
100     chainloader /EFI/shell.efi
101 }
102 menuentry "EFI Firmware setup" {
103     fwsetup
104 }
105 menuentry "Reboot" {
106     reboot
107 }
108 menuentry "Power off" {
109     halt
110 }
```