

Crew 1.0 - Configuration Reference

This document has two parts. The first is short and hand-written: how crew's two config files combine, how to see what is in force, and the common setups. The second is generated from the code and lists every key.

How the Two Files Combine

crew reads two JSON files:

- `~/.claude/crew/config.json` - the **machine-global** file. Your personal defaults for every repo on this machine: providers and models, notifications, auto-clear, the guards, how far autopilot may go.
- `.crew/config.json` - the **repo** file. Facts about one checkout: the tracker, the board, scope enforcement, production declarations.

The repo file wins over the machine file, which wins over crew's defaults. Four exceptions, each named in the Layer column below:

- A **repo-only** key in the machine file takes effect nowhere. It is pruned on read and refused on write.
- A **ratcheted** key (`install.policy`, every `guards.*`, `change.requireForProduction`, `environments.prodUnattended`) resolves to the narrower of the two values, so a cloned repo cannot widen what your machine allows.
- A **machine-armed** key (`resume.auto`, `context.autoClear.enabled`) can be turned on only in the machine file. A repo can only switch it off.
- A **personal** key (the five `autopilot.*` keys) resolves per key to the stricter of the layers that set it; a layer that says nothing imposes nothing. A machine value is your default for every repo, which a repo may narrow and never widen.

A `null` in the repo file over a machine value inherits the machine value. The `/crew:init` template writes every key except the personal ones, so it does not shadow your machine defaults for those; a repo `/crew:init` set up before that still spells `autopilot.mode: "off"`, which holds a machine plan down until you remove it (`--explain --all` names it as a shadow:).

Seeing What Is in Force

- `/crew:config --show` prints every machine-settable key, its value and the layer it came from, and names any key that takes effect nowhere.
- `/crew:config` with no argument is a menu that writes either file through the validated path. It shows a dry run first, refuses unknown keys and out-of-range values, and marks a widening with `!`.
- From a shell: `python3 plugin/crew/hooks/scripts/crew_config.py --explain` is the same table, `--explain --all` adds every repo-only key and names each shadowing repo value, and `--models` is the per-role provider table.

Backups and Rebuilding a Lost Config

Every write a crew script makes to either file first copies the old bytes to `~/.claude/crew/backups/` (the newest 20 per file kept) and is refused when that copy fails; a hand edit is not backed up. `crew_config.py --backups` lists the machine file's (add `--repo` for the repo file's) and `--restore <stamp> --apply` puts one back. Your non-default values are kept in `~/.claude/crew/profile.json` (and in your vault when `memory.vaultPath` is set), so `--rebuild --repo` or `--rebuild --global` regenerates a lost or corrupt file from the template plus that profile, as a dry run until `--apply`.

Common Setups

- **Personal defaults once, for every repo.** Put providers, models, `notify.*`, the guards and the `autopilot.*` keys in `~/.claude/crew/config.json`. Leave repo files to repo facts.
- **Self-approval under autopilot.** Set `autopilot.mode: "plan"` and choose `autopilot.approval` (human, self or risk) in either file, and set `scope.allowCliApproval: true` in the repo file, which is the only file that key is read from. Review acceptance and production deploys still stop for you.
- **Notifications.** In the machine file, set `notify.provider` and the environment variable names in `notify.urlEnv / notify.tokenEnv`. The secret stays in your environment, never in the file. Those two are machine-only: a repo file's value is ignored with a notice.

The reasoning behind each key is in `plugin/crew/CONFIG.md`, which ships with the plugin.

Reference (Generated)

Generated from the code by `python3 docs/guides/crew/src/config_reference.py --write`. Do not edit by hand: `python3 scripts/check-marketplace.py` fails when this file is stale.

156 keys: 88 settable in the machine-global file, 68 repo-only.

Columns:

- **Layer:** which file may set the key.
- **Default:** what `default_config()` returns. Where the machine default differs, both are shown.
- **Values:** the values crew accepts, read from the same tuple the validator reads. "not validated" means crew checks nothing and names the file that reads the key.
- **Since:** the first crew version whose template declared the key. Keys in the first template (crew 0.11.0) read "0.11.0 or earlier".

Layers

- **repo:** only `.crew/config.json` may set it; the global file's value is pruned on read and refused on write.
- **both:** either file may set it; the repo value wins over the machine one.
- **both, ratchet:** either file may set it, and the NARROWER of the two wins (`crew_guards.RATCHETED_KEYS`). A repo can tighten what the machine allows, never loosen it.
- **both, widening warned:** either file may set it and the repo wins, but a write that widens it is flagged (`crew_config._RATCHETED`).
- **both, stricter wins:** a personal key (`crew_guards.PERSONAL_KEYS`): either file may set it, and where both do the STRICTER value wins; a layer that is silent (absent or `null`) imposes nothing, so a machine value is your default for every repo and a repo may only narrow it.
- **machine-arms:** only the global file can turn it on (exactly `true`); a repo may only veto it with `false` (`crew_config.REPO_VETO_ONLY`).
- **machine-only:** read from the global file alone; a repo's own value is never consulted.

Top-Level Keys

Setting	Layer	Default	Values	Since	Summary
schema	repo	7	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects integer)	0.11.0 or earlier	Config schema version; /crew:migrate upgrades an older one.
tier	repo	0	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects integer)	0.11.0 or earlier	Setup tier recorded by /crew:init.
roles	repo	["explorer", "reviewer"]	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects list of role names)	0.11.0 or earlier	Optional roles installed in this repo.
tracker	repo	"files"	files obsidian jira sdp	0.11.0 or earlier	Where tickets live; crew_tracker.resolve answers could not tell when two configs disagree.
verifyGate	repo	true	not validated - read by plugin/crew/hooks/scripts/verify-gate.sh (expects boolean)	0.11.0 or earlier	Run the Stop verify gate.

Setting	Layer	Default	Values	Since	Summary
qa.provider	both	"auto"	auto claude codex copilot kimi	0.11. 0 or earlier	Who reviews: auto walks qa.order; a named provider is used as-is.
qa.order	both	["codex", "kimi", "copilot", "claude"]	list of: claude codex copilot kimi	0.14. 6	The reviewers auto tries, in order. A list is one leaf, replaced wholesale.
qa.fallback	both	"claude- sonnet-5"	not validated - read by plugin/crew/c ommands/revie w.md (expects model id)	0.16. 6	Model a gone pin falls back to, on its family's provider (L-0712).
qa.codex.model	both	null	not validated - read by plugin/crew/c ommands/revie w.md (expects string or null)	0.14. 6	Codex model for review; null passes no flag.
qa.codex.reasoningEffort	both	null	none minimal low medium high xhigh max (listed in plugin/crew/c ommands/revie w.md; not	0.14. 6	Codex reasoning effort for review; null passes no flag.

Setting	Layer	Default	Values	Since	Summary
			validated)		
qa.copilot.model	both	null	not validated - read by plugin/crew/commands/review.md (expects string or null)	0.14.6	Copilot model for review; null uses the CLI default.
qa.kimi.model	both	null	not validated - read by plugin/crew/commands/review.md (expects string or null)	1.0.39	Kimi Code model id for review (k3, kimi-for-coding, ...); null uses the CLI's own default.
qa.roles	both	{}	object of role pins; each pin's provider is checked (checked in plugin/crew/hooks/scripts/crew_config.py)	0.16.6	Per-role reviewer pins, qa.roles.<role>.provider / .model; a pin beats the provider block for that role.

Dev

Setting	Layer	Default	Values	Since	Summary
dev.provider	both	"claude"	claude codex copilot kimi	0.14.6	Who implements.
dev.fallback	both	"claude-sonnet-5"	not validated - read by plugin/crew/sk	0.16.6	Model a gone dev pin falls back to, on its

Setting	Layer	Default	Values	Since	Summary
			ills/crew-providers/SKILL.md (expects model id)		family's provider.
dev.codex.model	both	null	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string or null)	0.14.6	Codex model for implementation.
dev.codex.reasoningEffort	both	null	none minimal low medium high xhigh max (listed in plugin/crew/commands/review.md; not validated)	0.14.6	Codex reasoning effort for implementation.
dev.copilot.model	both	null	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string or null)	0.14.6	Copilot model for implementation.
dev.kimi.model	both	null	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string or null)	1.0.39	Kimi Code model id for implementation, as qa.kimi.model.

Setting	Layer	Default	Values	Since	Summary
dev.roles	both	{}	object of role pins; each pin's provider is checked (checked in plugin/crew/hooks/scripts/crew_config.py)	0.16.6	Per-role dev pins, as qa.roles.

Worktree

Setting	Layer	Default	Values	Since	Summary
worktree.root	both	null	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects path or null)	0.16.27	Where crew creates linked worktrees; null uses the default.

secondOpinion

Setting	Layer	Default	Values	Since	Summary
secondOpinion.provider	both	"none"	not validated - read by plugin/crew/commands/plan.md (expects string)	0.11.0 or earlier	Second-opinion provider for plans; none is off.
secondOpinion.mode	both	"cli"	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects	0.11.0 or earlier	How the second opinion is reached.

Setting	Layer	Default	Values	Since	Summary
			string)		
secondOpinion.model	both	null	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string or null)	0.11.0 or earlier	Second-opinion model.
secondOpinion.keyEnv	both	"GEMINI_API_KEY"	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string)	0.11.0 or earlier	Environment variable holding the provider's API key.
secondOpinion.sendsCode	both	false	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects boolean)	0.11.0 or earlier	Whether code may be sent to the second-opinion provider.

Jira

Setting	Layer	Default	Values	Since	Summary
jira.project	repo	null	not validated - read by plugin/crew/commands/jira-sync.md (expects string or null)	0.11.0 or earlier	Jira project key. No consumer found (CONFIG.md section 9).

Setting	Layer	Default	Values	Since	Summary
jira.cloudId	repo	null	not validated - read by plugin/crew/commands/jira-sync.md (expects string or null)	0.19.10	Jira cloud id, cached by /crew:jira-sync; read by nothing.

Sdp

Setting	Layer	Default	Values	Since	Summary
sdp.portal	repo	null	not validated - read by plugin/crew/commands/sdp-sync.md (expects string or null)	0.11.0 or earlier	ServiceDesk Plus portal.
sdp.noteVisibility	repo	"private"	not validated - read by plugin/crew/commands/sdp-sync.md (expects string)	0.11.0 or earlier	Visibility of notes crew writes to SDP.
sdp.closeOnDone	repo	false	not validated - read by plugin/crew/commands/sdp-sync.md (expects boolean)	0.11.0 or earlier	Close the SDP request when the ticket is done.

Obsidian

Setting	Layer	Default	Values	Since	Summary
obsidian.vaultPath	repo	null	not validated - read by	0.11.0 or	Vault holding the board; falls back

Setting	Layer	Default	Values	Since	Summary
			plugin/crew/hooks/scripts/crew_tracker.py (expects path or null)	earlier	to memory.vaultPath and must hold .obsidian/.
obsidian.boardDir	repo	null	not validated - read by plugin/crew/hooks/scripts/crew_tracker.py (expects path or null)	0.11.0 or earlier	Board folder inside the vault (relative, no ..).
obsidian.board	repo	"Board.md"	not validated - read by plugin/crew/hooks/scripts/crew_tracker.py (expects file name)	0.11.0 or earlier	Board file name.
obsidian.columns.backlog	repo	"Backlog"	not validated - read by plugin/crew/hooks/scripts/crew_tracker.py (expects string)	0.11.0 or earlier	Board column for backlog tickets (direction, ready, needs-owner).
obsidian.columns.ready	repo	"Ready"	not validated - read by plugin/crew/hooks/scripts/crew_tracker.py (expects string)	0.11.0 or earlier	Board column for ready tickets.
obsidian.columns.inProgress	repo	"In Progress"	not validated -	0.11.	Board column for

Setting	Layer	Default	Values	Since	Summary
			read by plugin/crew/hooks/scripts/crew_tracker.py (expects string)	0 or earlier	tickets in progress.
obsidian.columns.review	repo	"Review"	not validated - read by plugin/crew/hooks/scripts/crew_tracker.py (expects string)	0.11.0 or earlier	Board column for tickets in review.
obsidian.columns.done	repo	"Done"	not validated - read by plugin/crew/hooks/scripts/crew_tracker.py (expects string)	0.11.0 or earlier	Board column for closed tickets (done, cancelled, superseded; each checked).

Memory

Setting	Layer	Default	Values	Since	Summary
memory.mode	both	"repo"	not validated - read by plugin/crew/skills/crew-memory/SKILL.md (expects string)	0.11.0 or earlier	Where memory lives (repo, or a vault).
memory.vaultPath	both	null	not validated - read by plugin/crew/hooks/scripts/crew_recalls.py (expects	0.11.0 or earlier	The Obsidian vault used for memory.

Setting	Layer	Default	Values	Since	Summary
			path or null)		
<code>memory.inject</code>	repo	true	not validated - read by plugin/crew/hooks /scripts/crew_con text.py (expects boolean)	1.0.25	Inject the handoff and recall at session start; only an explicit false stops it.
<code>memory.recall.vaults</code>	repo	[]	not validated - read by plugin/crew/hooks /scripts/crew_rec all.py (expects list of vault names)	1.0.25	This repo's vault priority for recall; empty uses the obsidian config's roles.
<code>memory.recall.maxChars</code>	repo	800	positive integer (coerced in plugin/crew/hooks /scripts/crew_rec all.py)	1.0.25	Recall output budget; a non- positive or non- integer value reads as 800.
<code>memory.recall.projects</code>	repo	[]	not validated - read by plugin/crew/hooks /scripts/crew_rec all.py (expects list of project names)	1.1.11	Project names sent to vault recall as - - project so this repo's notes rank first; empty sends the main checkout's directory name.

Context

Setting	Layer	Default	Values	Since
context.enabled	repo	true	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects boolean)	0.11.0 or earlier
context.warnAt	repo	0.5	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects number)	0.11.0 or earlier
context.budgetTokens	repo	null	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects integer or null)	0.11.0 or earlier
context.reserveTokens	repo	0	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects integer or null)	0.11.0 or earlier
context.handoffPath	repo	".work/ HANDOFF.m d"	not validated - read by plugin/crew/hooks/scripts/crew_autocycle.py (expects path)	0.11.0 or earlier

Setting	Layer	Default	Values	Since
<code>context.keepTranscripts</code>	repo	5	not validated - read by plugin/crew/hooks/scripts/handoff-write.sh (expects integer)	0.11.0 or earlier
<code>context.autoClear.enabled</code>	machine- arms	null	null true false (checked in plugin/crew/hooks/scripts/crew_autocycle.py)	0.19.1 0
<code>context.autoClear.method</code>	both	"auto"	auto none notify tmux xdotool wtype sendkeys; per OS: linux: auto, none, notify, tmux, xdotool, wtype; macos: auto, none, notify, tmux; windows: auto, none, notify, sendkeys; windows-bash: auto, none, notify, tmux, sendkeys	0.19.1 0
<code>context.autoClear.windowTitle</code>	both	null	not validated - read by plugin/crew/hooks/scripts/auto-	0.19.1 0

Setting	Layer	Default	Values	Since
			<code>clear.ps1</code> (expects string or null)	
<code>context.autoClear.command</code>	both	<code>"/clear"</code>	not validated - read by plugin/crew/hooks/scripts/crew_autocycle.py (expects string)	0.19.10
<code>context.autoClear.delaySeconds</code>	both	3	number (coerced in plugin/crew/hooks/scripts/crew_autocycle.py)	0.19.10
<code>context.autoClear.minHandoffLines</code>	both	5	number (coerced in plugin/crew/hooks/scripts/crew_autocycle.py)	0.19.10
<code>context.autoClear.unsafeFocus</code>	repo	false	not validated - read by plugin/crew/hooks/scripts/auto-clear.sh (expects boolean)	0.19.11
<code>context.autoClear.onlyRepos</code>	machine-only	null	list of absolute	1.0.25

Setting	Layer	Default	Values	Since
			repo paths, or null (coerced in plugin/crew/hooks/scripts/crew_autocycle.py)	
context.autoClear.onlySessions	machine-only	null	list of session ids, or null (coerced in plugin/crew/hooks/scripts/crew_autocycle.py)	1.0.25
context.autoClear.wrapUp	machine-arms	null	null true false (checked in plugin/crew/hooks/scripts/crew_autocycle.py)	1.0.334

Setting	Layer	Default	Values	Since
<code>context.autoWrapUp</code>	repo	true	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects boolean)	0.19.10
<code>context.autoResume</code>	repo	true	not validated - read by plugin/crew/commands/migrate.md (expects boolean)	0.19.10
<code>context.staleHandoff.maxAgeHours</code>	repo	72	not validated - read by plugin/crew/hooks/scripts/crew_stale.py (expects integer)	0.16.33
<code>context.staleHandoff.maxCommitsBehind</code>	repo	3	not validated - read by plugin/crew/hooks/scripts/crew_stale.py (expects integer)	0.16.33

Resume

Setting	Layer	Default	Values	Since	Summary
<code>resume.auto</code>	machine-arms	null	null true false (checked in plugin/crew/hooks/scripts/crew_resume.py)	1.0.40	Auto-resume after /clear or a manual /compact. Only the

Setting	Layer	Default	Values	Since	Summary
					machine file can arm it (exactly true); a repo false vetoes it.
<code>resume.typeDelaySeconds</code>	both	2	whole seconds; fraction cut, negative or non-number reads as the default (coerced in <code>plugin/crew/hooks/scripts/crew_autocycle.py</code>)	1.0.32 1	Wait before auto-resume types its command: before the tmux ready probe, and the only wait on Windows. Read from the machine file only.
<code>resume.readyTimeoutSeconds</code>	both	15	whole seconds; fraction cut, negative or non-number reads as the default (coerced in <code>plugin/crew/hooks/scripts/crew_autocycle.py</code>)	1.0.32 1	How long the tmux ready probe waits for an idle, empty input line before it types nothing. Read from the machine file only.

Emergency

Setting	Layer	Default	Values	Since	Summary
emergency.standDown	repo	true	not validated - read by plugin/crew/hooks/scripts/_common.sh (expects boolean)	0.11.0 or earlier	Whether a declared incident may stand gates down; false forbids it.
emergency.ttlMinutes	repo	120	integer (coerced in plugin/crew/hooks/scripts/crew_incident.py)	0.11.0 or earlier	Default incident lifetime; a non-integer reads as the default.
emergency.maxTtlMinutes	repo	480	integer (coerced in plugin/crew/hooks/scripts/crew_incident.py)	0.11.0 or earlier	Longest incident lifetime; never below ttlMinutes.

Notify

Setting	Layer	Default	Values	Since	Summary
notify.provider	both	null	telegram, teams, none or null; any other value sends nothing (coerced in plugin/crew/hooks/scripts/crew_notify.py)	0.11.0 or earlier	Where notification telegram, teams or A repo null inherits machine provider; none opts this repo

Setting	Layer	Default	Values	Since	Summary
<code>notify.urlEnv</code>	machine-only	null	not validated - read by plugin/crew/hooks/scripts/crew_notify.py (expects string or null)	0.11.0 or earlier	Name of the environment variable holding the webhook URL. Honor the machine's repo's is ignored with notice.
<code>notify.tokenEnv</code>	machine-only	null	not validated - read by plugin/crew/hooks/scripts/crew_notify.py (expects string or null)	0.11.0 or earlier	Name of the environment variable holding the Telegram bot token. Can be filled from the machine's <code>bot_token_env</code> . Honor the machine's
<code>notify.chatId</code>	both	null	not validated - read by plugin/crew/hooks/scripts/crew_notify.py (expects string or null)	0.11.0 or earlier	Telegram chat id; must be filled from the notice's <code>chat_id</code> , and the string is not unset. example value could be
<code>notify.events</code>	both	<code>["blocker", "deploy", "question"]</code>	list of event names; an unknown name is dropped with a notice (coerced in plugin/crew/hooks/scripts/crew_notify.py)	0.11.0 or earlier	Events that notify: blocker, question, and blocker (T-0060's four blockers reasons). The pre-emptive, waiting, phase, and done are mapped to a notice. A list is one
<code>notify.realertHours</code>	both	6	number of hours; negative or non-number	1.0.350	The same event + reason is sent once every many hours; a que

Setting	Layer	Default	Values	Since	Summary
			reads as the default (coerced in plugin/crew/hooks/scripts/crew_notify.py)		once per waiting e
			list of notification_type strings, or null; a non-list reads as null and a non-string entry is dropped (coerced in plugin/crew/hooks/scripts/crew_notify.py)		The Claude Code notification_type that count as a qu uses the built-in fi (crew_notify.QUES).
notify.questionTypes	both	null		1.0.350	

Platform

Setting	Layer	Default	Values	Since	Summary
platform.os	repo	null	not validated - read by plugin/crew/hooks/scripts/crew_platform.py (expects string or null)	0.11.0 or earlier	Detected OS, stamped by platform-sync.
platform.wsl	repo	null	not validated - read by plugin/crew/hooks/scripts/crew_platform.py (expects	0.11.0 or earlier	Detected WSL, stamped by platform-sync.

Setting	Layer	Default	Values	Since	Summary
			boolean or null)		
platform.shell	repo	null	not validated - read by plugin/crew/hooks/scripts/crew_platform.py (expects string or null)	0.11.0 or earlier	Detected shell, stamped by platform-sync.
platform.windowsHostIp	repo	null	not validated - read by plugin/crew/hooks/scripts/crew_platform.py (expects string or null)	0.11.0 or earlier	Windows host IP seen from WSL.

shellRoute

Setting	Layer	Default	Values	Since	Summary
shellRoute.mode	both	null (repo), "auto" (machine)	auto wsl powershell gitbash	1.0.54	The shell long-running jobs use on native Windows; null inherits, and an unknown value reads as auto and is named.
shellRoute.distro	both	null	not validated - read by plugin/crew/hooks/scripts/crew_shell.py (expects string or null)	1.0.54	WSL distro to route to; null takes the default distro.

Setting	Layer	Default	Values	Since	Summary
<code>pm.enabled</code>	both	true	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects boolean)	0.11.0 or earlier	Run the PM brief.
<code>pm.mode</code>	both	"adaptive"	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects string)	0.11.0 or earlier	How the PM brief adapts its length.
<code>pm.quietLines</code>	both	8	integer (coerced in plugin/crew/hooks/scripts/crew_state.py)	0.11.0 or earlier	PM brief length when nothing changed.
<code>pm.maxLines</code>	both	40	integer (coerced in plugin/crew/hooks/scripts/crew_state.py)	0.11.0 or earlier	Longest PM brief.
<code>pm.authority</code>	both, widening warned	"report-only"	report-only act autonomous	0.11.0 or earlier	How much the PM may do unasked. A widening is warned about; the two layers combine by precedence.

Setting	Layer	Default	Values	Since	Summary
pm.ticketGranularity	both	"system"	session system change	0.16.34	How big a ticket the PM cuts.
pm.maxDispatches	both	3	integer (coerced in plugin/crew/hooks/scripts/crew_state.py)	0.11.0 or earlier	Roles the PM may dispatch in one pass.

Graph

Setting	Layer	Default	Values	Since	Summary
graph.enabled	repo	true	not validated - read by plugin/crew/skills/crew-graph/SKILL.md (expects boolean)	0.11.0 or earlier	No consumer found (CONFIG.md section 9).
graph.tool	repo	"graphify"	not validated - read by plugin/crew/skills/crew-graph/SKILL.md (expects string)	0.11.0 or earlier	No consumer found (CONFIG.md section 9).
graph.out	repo	"graphify-out"	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects path)	0.11.0 or earlier	Where the code graph is written.
graph.mode	repo	"code-only"	not validated - read by plugin/crew/skills/crew-graph/SKILL	0.11.0 or earlier	No consumer found (CONFIG.md

Setting	Layer	Default	Values	Since	Summary
			L.md (expects string)		section 9).
graph.commitHook	repo	false	not validated - read by plugin/crew/skills/crew-graph/SKILL.md (expects boolean)	0.11.0 or earlier	No consumer found (CONFIG.md section 9).

Docs

Setting	Layer	Default	Values	Since	Summary
docs.theme	both	null	not validated - read by plugin/crew/skills/crew-house-style/SKILL.md (expects string or null)	0.16.33	House-style theme for built documents; null uses the skill's own choice.
docs.reportTheme	both	null	not validated - read by plugin/crew/skills/crew-house-style/SKILL.md (expects string or null)	0.16.33	Theme for findings reports.

Bitbucket

Setting	Layer	Default	Values	Since	Summary
bitbucket.mergeGate.enabled	both	false	not validated - read by plugin/crew/commands/promote.md (expects	0.16.33	Let /crew:promote drive the Bitbucket merge gate.

Setting	Layer	Default	Values	Since	Summary
			boolean)		
bitbucket.mergeGate.branch	both	null	not validated - read by plugin/crew/ commands/promote.md (expects string or null)	0.16.33	Branch the Bitbucket merge gate protects.
bitbucket.mergeGate.preset	both	"standard"	not validated - read by plugin/crew/ commands/promote.md (expects string)	0.16.33	Selects nothing today (CONFIG.md section 9).

GitHub

Setting	Layer	Default	Values	Since	Summary
github.mergeGate.enabled	both	false	not validated - read by plugin/crew/com mands/promote.m d (expects boolean)	0.19.30	Let /crew:promot e drive the GitHub merge gate.
github.mergeGate.branch	both	null	not validated - read by plugin/crew/com mands/promote.m d (expects string or null)	0.19.30	Branch the GitHub merge gate protects.

Install

Setting	Layer	Default	Values	Since	Summary
install.policy	both, ratchet	"manual"	manual ask auto (ratchet: narrower layer wins; listed narrowest first)	0.19.18	Whether crew may install a missing prerequisite.

Guards

Setting	Layer	Default	Values	Since	Summary
guards.terraformApply	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	0.19.30	terraform apply and friends.
guards.forcePush	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	0.19.30	git push --force.
guards.adminMerge	both, ratchet	"block"	block ask	0.19.3	gh pr merge --admin.

Setting	Layer	Default	Values	Since	Summary
			allow (ratchet: narrower layer wins; listed narrowest first)	0	
<code>guards.mergeGate</code>	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	0.19.3 0	Taking a live repo's merge gate down (read by <code>/crew:gate</code>).
<code>guards.cloudDestructive</code>	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	1.0.25	Destructive cloud CLI commands.
<code>guards.sqlDestructive</code>	both, ratchet	"block"	block ask allow	1.0.25	Destructive SQL.

Setting	Layer	Default	Values	Since	Summary
			(ratchet: narrower layer wins; listed narrowest first)		
<code>guards.deployWorkflow</code>	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	1.1.16	A gh workflow run or gh api .../dispatches of a workflow <code>environments.workflows</code> lists.
<code>guards.prodDatabase</code>	both, ratchet	"none"	none read full (ratchet: narrower layer wins; listed narrowest first)	0.19.30	How much of a declared production database crew may reach.
<code>guards.prodServer</code>	both, ratchet	"none"	none read full (ratchet:	0.19.30	How much of a declared production host crew may reach.

Setting	Layer	Default	Values	Since	Summary
guards.roleWrites	both, ratchet	"off"	narrower layer wins; listed narrowest first)	0.19.9 2	Enforce each role's write scope. Default off; a malformed value reads as block.
			block report off (ratchet: narrower layer wins; listed narrowest first)		
guards.cloudGuard	both, ratchet	"off"	block report off (ratchet: narrower layer wins; listed narrowest first)	1.0.25	Whether the cloud guard judges commands at all. Default off; report logs only.

Production

Setting	Layer	Default	Values	Since	Summary
production.databases	repo	[]	not validated - read	0.19.30	Globs

Setting	Layer	Default	Values	Since	Summary
			by plugin/crew/hooks/scripts/crew_config.py (expects list of globs)		naming production databases.
production.hosts	repo	[]	not validated - read by plugin/crew/hooks/scripts/crew_config.py (expects list of globs)	0.19.30	Globs naming production hosts.

Cloud

Setting	Layer	Default	Values	Since	Summary
cloud.awsProfiles	repo	[]	not validated - read by plugin/crew/hooks/scripts/cloud_guard.py (expects list of names)	1.0.25	AWS profiles this repo may use.
cloud.awsRegions	repo	[]	not validated - read by plugin/crew/hooks/scripts/cloud_guard.py (expects list of names)	1.0.25	AWS regions this repo may use.

Setting	Layer	Default	Values	Since	Summary
cloud.azureSubscriptions	repo	[]	not validated - read by plugin/crew/hooks/scripts/cloud_guard.py (expects list of names)	1.0.25	Azure subscriptions this repo may use.

Environments

Setting	Layer	Default	Values	Since	Summary
environments.nonProd	repo	[]	not validated - read by plugin/crew/hooks/scripts/crew_config.py (expects list of globs)	1.0.37	Terraform targets that are not production and may run unattended.
environments.prodUnattended	both, ratchet	false	false true (ratchet: narrower layer wins; listed narrowest first)	1.0.37	Whether production terraform may run unattended; true only when both layers say so.
environments.workflows	repo	{}	not validated - read by plugin/crew/hooks/scripts/crew_config.py (expects object of glob to string)	1.1.16	Deploy workflow globs, each mapped to its environment or

Setting	Layer	Default	Values	Since	Summary
					input:<name>.
Change					
Setting	Layer	Default	Values	Since	Summary
change.requester	both	null	not validated - read by plugin/crew/hooks/scripts/crew_change.py (expects string or null)	0.19.3 1	Who requests the change.
change.implementor	both	null	not validated - read by plugin/crew/hooks/scripts/crew_change.py (expects string or null)	0.19.3 1	Who implements the change.
change.requireForProduction	both, ratchet	false	true false (ratchet: narrower layer wins; listed narrowest first)	0.19.3 1	Require an approved change request before /crew:promote production: a repo may turn it on, never off.
change.sdpTemplate	both	"Change Management	not validated - read by	0.19.3	SDP template

Setting	Layer	Default	Values	Since	Summary
		Request"	plugin/crew/hooks/scripts/crew_change.py (expects string)	1	for a change request.
change.jiraIssueType	both	"Change"	not validated - read by plugin/crew/hooks/scripts/crew_change.py (expects string)	0.19.3 1	Jira issue type for a change request.
change.category	both	null	not validated - read by plugin/crew/hooks/scripts/crew_change.py (expects string or null)	0.19.3 1	Change category.

Git

Setting	Layer	Default	Values	Since	Summary
git.forbiddenTrailers	both	[]	list of trailer tokens (letters, digits and -, no :) (checked in plugin/crew/hooks/scripts/crewtrailers.py)	1.0.328	Commit trailer tokens the owner forbids, reported by /crew:done. The two layers combine by union, so a repo can add a token and never remove the

Setting	Layer	Default	Values	Since	Summary
					machine owner's; a value that is not a list of tokens makes the list unknown, never empty (CONFIG.md section 22).

Scope

Setting	Layer	Default	Values	Since	Summary
scope.mode	repo	"off"	off report block auto	1.0.25	Whether the scope guard enforces a ticket's Touch list; a value outside these fails closed to block.
scope.allowCliApproval	repo	false	false true (checked in plugin/crew/hooks/scripts/crew_ticket.py)	1.0.25	Whether a CLI-written approval receipt counts; only exactly true allows it.

Autopilot

Setting	Layer	Default	Values	Since	Summary
autopilot.mode	both, stricter wins	"off"	off plan backlog (checked in plugin/crew/hooks/scripts /crew_autopilot.py); personal: listed strictest first, the stricter wins	1.0.41	Only the strings plan, ticket pending, backlog (checked in goal's ticket), and dependencies inside the ticket's /crew:autopilot are anything other than as off, with a warning.
autopilot.maxPhases	both, stricter wins	12	positive integer (checked in plugin/crew/hooks/scripts /crew_autopilot.py); personal: the smaller wins	1.0.41	Phases of work to take; any number greater than positive integer reads as a warning.
autopilot.deploy	both, stricter wins	"none"	none nonprod all; personal: listed strictest first, the stricter wins	1.0.42	Where a ticket is run without a deployment as none.
autopilot.approval	both, stricter wins	"risk"	human risk self; personal: listed strictest first, the stricter wins	1.0.42	Who approves a ticket unless the autopilot approves else read as none.
autopilot.questions	both, stricter wins	"risk"	human risk self; personal: listed strictest first, the stricter wins	1.0.42	Who answers a ticket's open questions unless the autopilot answers else read as none.

Setting	Layer	Default	Values	Since	Summary
<code>autopilot.maxAutoReplans</code>	repo	0	non-negative integer (checked in <code>plugin/crew/hooks/scripts/crew_autopilot.py</code>)	1.0.339	Successful autopilot runs are terminated by rejecting the current plan. The number of rounds of round-trip planning (including review iterations) is limited by <code>maxAutoReplans</code> and any further iterations are rejected. <code>maxAutoReplans</code> is a non-negative integer. The default reads as 0, which means that there is no limit above 5 seconds. If the limit is reached, a warning is issued.
<code>autopilot.ship</code>	repo	"merge"	<code>pr merge</code>	1.0.349	After a successful run, the autopilot pushes a commit to the repository. The commit message is the PR; merged PRs are merged into the main branch. The commit message is <code>pr merge</code> (where <code>pr</code> is the PR number). The commit is required to be a merge commit. The default reads as "merge", which means that a merge is required. If the limit is reached, a warning is issued.
<code>autopilot.knownFailures</code>	repo	[]	list of check names (checked in <code>plugin/crew/hooks/scripts/crew_autopilot.py</code>)	1.0.349	Required for the autopilot to run. The list whose failures are known. The autopilot will block a new plan if a failure is matched. The list is a list of strings. The default reads as [], which means that no failures are known. If the limit is reached, a warning is issued.
<code>autopilot.ciTimeoutMinutes</code>	repo	60	positive integer (checked in <code>plugin/crew/hooks/scripts/crew_autopilot.py</code>)	1.0.349	Minutes for the autopilot to run checks; set to 0 for no timeout or green.

Setting	Layer	Default	Values	Since	Summary
					stops. Any positive input reads as a warning.
					A nightly HH:MM-HH:MM machine (may cross midnight the two sides overrides Anything could not stricter o applies.
autopilot.sleep.schedule	repo	null	HH:MM-HH:MM or null (checked in plugin/crew/hooks/scripts /crew_sleep.py)	1.0.332	autopilot inside the window; the day v anything as human strictest, warning.
autopilot.sleep.approval	repo	null	null human self risk (checked in plugin/crew/hooks/scripts /crew_sleep.py)	1.0.332	autopilot inside the window; the day v anything as human strictest, warning.
autopilot.sleep.questions	repo	null	null human self risk (checked in plugin/crew/hooks/scripts /crew_sleep.py)	1.0.332	autopilot inside the window; the day v anything as human strictest,

Setting	Layer	Default	Values	Since	Summary
					warning.
					autopilot
					inside the
					window (
					keeps the
					nonprod c
					replaces
autopilot.sleep.deploy	repo	null	null nonprod none (checked in plugin/crew/hooks/scripts /crew_sleep.py)	1.1.21	else, all refused v warning. effective nonprod: never run unattend
					Inside the
					window (
					true hold
					that only
					attention
					Approval
					Review o
					rounds) a
autopilot.sleep.notifyHold	repo	null	null true (checked in plugin/crew/hooks/scripts /crew_notify_hold.py)	1.1.21	them; the summary count. A deploy re refused S stalled la held. Onl armed an the sched manual s

Setting	Layer	Default	Values	Since	Summary
					outside it (nothing); but null or nothing, warning.
<code>autopilot.maxTicketsPerRun</code>	repo	3	positive integer (checked in <code>plugin/crew/hooks/scripts/crew_autopilot_backlog.py</code>)	1.1.21	Tickets on a session (one session starts; the session stops the session. Anything more than a positive integer reads as a warning.
<code>autopilot.maxTokensPerSession</code>	repo	2000000	positive integer (checked in <code>plugin/crew/hooks/scripts/crew_autopilot_backlog.py</code>)	1.1.21	Input plugin reads tokens on a session before the session a transcript cannot be too. Anything more than a positive integer reads as a warning.
<code>autopilot.maxLanes</code>	repo	null	positive integer or null (checked in <code>plugin/crew/hooks/scripts/crew_wave.py</code>)	1.1.6	Lanes on a session (<code>/crew:autopilot</code>) wave runs. null is the default (<code>pm.maxDisplacement</code>). Larger values are capped to anything

Setting	Layer	Default	Values	Since	Summary
					positive i reads as a warning
					What aut with a re A wave la ends at t verdict, c takes a C on to the checks, f rereview the ledge
autopilot.reviewPolicy	repo	"stop"	stop clean-only fix-and-rereview	1.1.6	A single-t (T-0067): and-rere fixing a n FINDING BLOCK a itself (the and re-re Anything as stop, v warning; accepts a

Tickets

Setting	Layer	Default	Values	Since	Summary
tickets.baseBranch	repo	null	branch name or null (checked in plugin/crew/hoo	1.0.158	The branch ticket branches are cut

Setting	Layer	Default	Values	Since	Summary
			ks/scripts/scope_base.py)		from; null tries origin/HEAD's target, then origin/main, then main. A value that is not a branch name, or names no commit, makes the scope base could not tell.

Route

Setting	Layer	Default	Values	Since	Summary
route.enabled	both	false	false true (checked in plugin/crew/hooks/scripts/crew_route.py)	1.0.42	Route plain-text prompts to /crew: commands; only the JSON value true arms it.

unattendedCloud

Setting	Layer	Default	Values	Since	Summary
unattendedCloud.aws.readOnly.profile	machine-only	null	profile name, or null (coerced in plugin/crew/hooks/scripts/crew_unattended.py)	1.1.10	T u e fr e it to c

Setting	Layer	Default	Values	Since
<code>unattendedCloud.aws.readOnly.identity</code>	machine-only	<code>null</code>	ARN prefix ending in <code>/</code> , or null (coerced in <code>plugin/crew/hooks/scripts/crew_unattended.py</code>)	1.1.10
<code>unattendedCloud.aws.readOnly.region</code>	machine-only	<code>null</code>	region, or null (coerced in <code>plugin/crew/hooks/scripts/crew_unattended.py</code>)	1.1.10
<code>unattendedCloud.aws.nonProd</code>	machine-only	<code>{}</code>	None (checked in <code>plugin/crew/hooks/scripts/crew_unattended.py</code>)	1.1.10

Coming (Not in Code Yet)

Keys from approved tickets that have not landed. Each moves into the table above when its ticket lands, because it is then in the code; a test fails until it does (`test_no_coming_key_is_in_code`).

T-0030

Setting	Change	Layer	Default	Values	Summary
coord.ttlMinutes	new key	set when T-0030 lands	30		Lifetime of a cross-session coordination claim (1-10080).
coord.channel	new key	set when T-0030 lands	set when T-0030 lands		Where sessions coordinate.

T-0050

Setting	Change	Layer	Default	Value	Summary
scope.allowCliApproval	change s layer	both, stricter wins	false		Becomes settable in the global file, the stricter layer winning, once its reader (crew_ticket.cli_approval_allowed) reads the global layer in a harness-only follow-up to T-0050.