

Crew 1.0 - Configuration Reference

This document has two parts. The first is short and hand-written: how crew's two config files combine, how to see what is in force, and the common setups. The second is generated from the code and lists every key.

How the Two Files Combine

crew reads two JSON files:

- `~/.claude/crew/config.json` - the **machine-global** file. Your personal defaults for every repo on this machine: providers and models, notifications, auto-clear, the guards.
- `.crew/config.json` - the **repo** file. Facts about one checkout: the tracker, the board, scope enforcement, autopilot, production declarations.

The repo file wins over the machine file, which wins over crew's defaults. Three exceptions, each named in the Layer column below:

- A **repo-only** key in the machine file takes effect nowhere. It is pruned on read and refused on write.
- A **ratcheted** key (`install.policy`, every `guards.*`, `change.requireForProduction`, `environments.prodUnattended`) resolves to the narrower of the two values, so a cloned repo cannot widen what your machine allows.
- A **machine-armed** key (`resume.auto`, `context.autoClear.enabled`) can be turned on only in the machine file. A repo can only switch it off.

A `null` in the repo file over a machine value inherits the machine value. The `/crew:init` template writes every key, which would otherwise shadow your machine defaults.

Seeing What Is in Force

- `/crew:config --show` prints every machine-settable key, its value and the layer it came from, and names any key that takes effect nowhere.
- `/crew:config` with no argument is a menu that writes either file through the validated path. It shows a dry run first, refuses unknown keys and out-of-range values, and marks a widening with `!`.
- From a shell: `python3 plugin/crew/hooks/scripts/crew_config.py --explain` is the same table, and `--models` is the per-role provider table.

Common Setups

- **Personal defaults once, for every repo.** Put providers, models, notify.* and the guards in ~/.claude/crew/config.json. Leave repo files to repo facts.
- **Self-approval under autopilot.** In the repo file, set scope.allowCliApproval: true and autopilot.mode: "plan", then choose autopilot.approval (human, self or risk). Review acceptance and production deploys still stop for you.
- **Notifications.** In the machine file, set notify.provider and the environment variable names in notify.urlEnv / notify.tokenEnv. The secret stays in your environment, never in the file.

The reasoning behind each key is in plugin/crew/CONFIG.md, which ships with the plugin.

Reference (Generated)

Generated from the code by `python3 docs/guides/crew/src/config_reference.py --write`.
Do not edit by hand: `python3 scripts/check-marketplace.py` fails when this file is stale.

138 keys: 76 settable in the machine-global file, 62 repo-only.

Columns:

- **Layer:** which file may set the key.
- **Default:** what default_config() returns. Where the machine default differs, both are shown.
- **Values:** the values crew accepts, read from the same tuple the validator reads. "not validated" means crew checks nothing and names the file that reads the key.
- **Since:** the first crew version whose template declared the key. Keys in the first template (crew 0.11.0) read "0.11.0 or earlier".

Layers

- **repo:** only .crew/config.json may set it; the global file's value is pruned on read and refused on write.
- **both:** either file may set it; the repo value wins over the machine one.
- **both, ratchet:** either file may set it, and the NARROWER of the two wins (crew_guards.RATCHETED_KEYS). A repo can tighten what the machine allows, never loosen it.
- **both, widening warned:** either file may set it and the repo wins, but a write that widens it is flagged (crew_config._RATCHETED).

- **machine-arms:** only the global file can turn it on (exactly true); a repo may only veto it with false (crew_config.REPO_VETO_ONLY).
- **machine-only:** read from the global file alone; a repo's own value is never consulted.

Top-Level Keys

Setting	Layer	Default	Values	Since	Summary
schema	repo	7	not validated - read by plugin/crew/hooks /scripts/crew_sta te.py (expects integer)	0.11.0 or earlier	Config schema version; /crew:upgrade migrates an older one.
tier	repo	0	not validated - read by plugin/crew/hooks /scripts/crew_sta te.py (expects integer)	0.11.0 or earlier	Setup tier recorded by /crew:init.
roles	repo	["explorer" , "reviewer"]	not validated - read by plugin/crew/hooks /scripts/crew_sta te.py (expects list of role names)	0.11.0 or earlier	Optional roles installed in this repo.
tracker	repo	"files"	files obsidian jira sdp	0.11.0 or earlier	Where tickets live; crew_tracker.resol ve answers could not tell when two configs disagree.
verifyGate	repo	true	not validated - read by plugin/crew/hooks /scripts/verify- gate.sh (expects boolean)	0.11.0 or earlier	Run the Stop verify gate.

Setting	Layer	Default	Values	Since	Summary
qa.provider	both	"auto"	auto claude codex copilot kimi	0.11.0 or earlier	Who reviews: auto walks qa.order; a named provider is used as-is.
qa.order	both	["codex", "kimi", "copilot", "claude"]	list of: claude codex copilot kimi	0.14.6	The reviewers auto tries, in order. A list is one leaf, replaced wholesale.
qa.fallback	both	"claude-sonnet-5"	not validated - read by plugin/crew/commands/review.md (expects model id)	0.16.6	Claude model used when no other reviewer is available.
qa.codex.model	both	null	not validated - read by plugin/crew/commands/review.md (expects string or null)	0.14.6	Codex model for review; null passes no flag.
qa.codex.reasoningEffort	both	null	none minimal low medium high	0.14.6	Codex reasoning effort for review; null passes no flag.

Setting	Layer	Default	Values	Since	Summary
			xhigh max (listed in plugin/crew/commands/review .md; not validated)		
qa.copilot.model	both	null	not validated - read by plugin/crew/commands/review .md (expects string or null)	0.14.6	Copilot model for review; null uses the CLI default.
qa.kimi.model	both	null	not validated - read by plugin/crew/commands/review .md (expects string or null)	1.0.39	Kimi Code model id for review (k3, kimi-for-coding, ...); null uses the CLI's own default.
qa.roles	both	{}	object of role pins; each pin's provider is checked (checked in	0.16.6	Per-role reviewer pins, qa.roles.<role> .provider / .model; a pin beats the provider block for that role.

Setting	Layer	Default	Values	Since	Summary
			plugin/crew/hooks/scripts/crew_config.py)		
Dev					
Setting	Layer	Default	Values	Since	Summary
dev.provider	both	"claude"	claude codex copilot kimi	0.14.6	Who implements.
dev.fallback	both	"claude-sonnet-5"	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects model id)	0.16.6	Claude model used when the dev provider is unavailable.
dev.codex.model	both	null	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string or null)	0.14.6	Codex model for implementation
dev.codex.reasoningEffort	both	null	none minimal low medium high xhigh max (listed in plugin/crew/commands/review.md; not validated)	0.14.6	Codex reasoning effort for implementation
dev.copilot.model	both	null	not validated - read by plugin/crew/sk	0.14.6	Copilot model for

Setting	Layer	Default	Values	Since	Summary
			ills/crew-providers/SKILL.md (expects string or null)		implementation
dev.kimi.model	both	null	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string or null)	1.0.39	Kimi Code model id for implementation as qa.kimi.model.
dev.roles	both	{}	object of role pins; each pin's provider is checked (checked in plugin/crew/hooks/scripts/crew_config.py)	0.16.6	Per-role dev pins, as qa.roles.

Worktree

Setting	Layer	Default	Values	Since	Summary
worktree.root	both	null	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects path or null)	0.16.27	Where crew creates linked worktrees; null uses the default.

secondOpinion

Setting	Layer	Default	Values	Since	Summary
secondOpinion.provider	both	"none"	not validated - read by	0.11.0 or	Second-opinion provider for

Setting	Layer	Default	Values	Since	Summary
			plugin/crew/commands/plan.md (expects string)	earlier	plans; none is off.
secondOpinion.mode	both	"cli"	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string)	0.11.0 or earlier	How the second opinion is reached.
secondOpinion.model	both	null	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string or null)	0.11.0 or earlier	Second-opinion model.
secondOpinion.keyEnv	both	"GEMINI_API_KEY"	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string)	0.11.0 or earlier	Environment variable holding the provider's API key.
secondOpinion.sendsCode	both	false	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects boolean)	0.11.0 or earlier	Whether code may be sent to the second-opinion provider.

Jira

Setting	Layer	Default	Values	Since	Summary
jira.project	repo	null	not validated -	0.11.0	Jira project key.

Setting	Layer	Default	Values	Since	Summary
			read by plugin/crew/commands/jira-sync.md (expects string or null)	or earlier	No consumer found (CONFIG.md section 9).
jira.cloudId	repo	null	not validated - read by plugin/crew/commands/jira-sync.md (expects string or null)	0.19.10	Jira cloud id, cached by /crew:jira-sync; read by nothing.

Sdp

Setting	Layer	Default	Values	Since	Summary
sdp.portal	repo	null	not validated - read by plugin/crew/commands/sdp-sync.md (expects string or null)	0.11.0 or earlier	ServiceDesk Plus portal.
sdp.noteVisibility	repo	"private"	not validated - read by plugin/crew/commands/sdp-sync.md (expects string)	0.11.0 or earlier	Visibility of notes crew writes to SDP.
sdp.closeOnDone	repo	false	not validated - read by plugin/crew/commands/sdp-sync.md (expects boolean)	0.11.0 or earlier	Close the SDP request when the ticket is done.

Obsidian

Setting	Layer	Default	Values	Since	Summary
obsidian.vaultPath	repo	null	not validated - read by plugin/crow/hooks/scripts/crow_tracker.py (expects path or null)	0.11.0 or earlier	Vault holding the board; falls back to memory.vaultPath and must hold .obsidian/.
obsidian.boardDir	repo	null	not validated - read by plugin/crow/hooks/scripts/crow_tracker.py (expects path or null)	0.11.0 or earlier	Board folder inside the vault (relative, no ..).
obsidian.board	repo	"Board.md"	not validated - read by plugin/crow/hooks/scripts/crow_tracker.py (expects file name)	0.11.0 or earlier	Board file name.
obsidian.columns.backlog	repo	"Backlog"	not validated - read by plugin/crow/hooks/	0.11.0 or earlier	Board column for backlog tickets.

Setting	Layer	Default	Values	Since	Summary
obsidian.columns.ready	repo	"Ready"	scripts/c rew_track er.py (expects string) not validated - read by plugin/cr ew/hooks/ scripts/c rew_track er.py (expects string)	0.11. 0 or earlie r	Board column for ready tickets.
obsidian.columns.inProgress	repo	"In Progress "	not validated - read by plugin/cr ew/hooks/ scripts/c rew_track er.py (expects string)	0.11. 0 or earlie r	Board column for tickets in progress.
obsidian.columns.review	repo	"Review"	not validated - read by plugin/cr ew/hooks/ scripts/c rew_track er.py (expects string)	0.11. 0 or earlie r	Board column for tickets in review.
obsidian.columns.done	repo	"Done"	not validated - read by	0.11. 0 or earlie	Board column for done tickets.

Setting	Layer	Default	Values	Since	Summary
			plugin/crew/hooks/scripts/crew_tracker.py (expects string)	r	

Memory

Setting	Layer	Default	Values	Since	Summary
memory.mode	both	"repo"	not validated - read by plugin/crew/skills/crew-memory/SKILL.md (expects string)	0.11.0 or earlier	Where memory lives (repo, or a vault).
memory.vaultPath	both	null	not validated - read by plugin/crew/hooks/scripts/crew_recall.py (expects path or null)	0.11.0 or earlier	The Obsidian vault used for memory.
memory.inject	repo	true	not validated - read by plugin/crew/hooks/scripts/crew_context.py (expects boolean)	1.0.25	Inject the handoff and recall at session start; only an explicit false stops it.
memory.recall.vaults	repo	[]	not validated - read by plugin/crew/hooks/scripts/crew_recall.py (expects list of vault names)	1.0.25	This repo's vault priority for recall; empty uses

Setting	Layer	Default	Values	Since	Summary
			ew_recall.py (expects list of vault names)		the obsidian config's roles.
memory.recall.maxChars	repo	800	positive integer (coerced in plugin/crew/hooks/scripts/crew_recall.py)	1.0.25	Recall output budget; a non-positive or non-integer value reads as 800.

Context

Setting	Layer	Default	Values	Since
context.enabled	repo	true	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects boolean)	0.11.0 or earlier
context.warnAt	repo	0.5	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects number)	0.11.0 or earlier
context.budgetTokens	repo	null	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects integer or null)	0.11.0 or earlier
context.reserveTokens	repo	0	not validated - read by	0.11.0 or

Setting	Layer	Default	Values	Since
			plugin/crew/hooks/scripts/context-watch.sh (expects integer or null)	earlier
context.handoffPath	repo	".work/HANDOFF.mind"	not validated - read by plugin/crew/hooks/scripts/crew_autocycle.py (expects path)	0.11.0 or earlier
context.keepTranscripts	repo	5	not validated - read by plugin/crew/hooks/scripts/handoff-write.sh (expects integer)	0.11.0 or earlier
context.autoClear.enabled	machine-arms	null	null true false (checked in plugin/crew/hooks/scripts/crew_autocycle.py)	0.19.10
context.autoClear.method	both	"auto"	auto none notify tmux xdotool wtype sendkeys; per OS: linux: auto, none, notify, tmux, xdotool, wtype; macos: auto, none, notify, tmux;	0.19.10

Setting	Layer	Default	Values	Since
			windows: auto, none, notify, sendkeys; windows-bash: auto, none, notify, tmux, sendkeys	
context.autoClear.windowTitle	both	null	not validated - read by plugin/crew/hooks/scripts/auto-clear.ps1 (expects string or null)	0.19.10
context.autoClear.command	both	"/clear"	not validated - read by plugin/crew/hooks/scripts/crew_autocycle.py (expects string)	0.19.10
context.autoClear.delaySeconds	both	3	number (coerced in plugin/crew/hooks/scripts/crew_autocycle.py)	0.19.10
context.autoClear.minHandoffLines	both	5	number (coerced in plugin/crew/hooks/scripts/crew_autocycle.py)	0.19.10
context.autoClear.unsafeFocus	repo	false	not validated - read by plugin/crew/hooks/scripts/auto	0.19.11

Setting	Layer	Default	Values	Since
			-clear.sh (expects boolean)	
context.autoClear.onlyRepos	machine-only	null	list of absolute repo paths, or null (coerced in plugin/crew/hoo ks/scripts/crew _autocycle.py)	1.0.25
context.autoClear.onlySessions	machine-only	null	list of session ids, or null (coerced in plugin/crew/hoo ks/scripts/crew _autocycle.py)	1.0.25
context.autoClear.wrapUp	machine- arms	null	null true false (checked in plugin/crew/hoo ks/scripts/crew _autocycle.py)	1.0.33 4

Setting	Layer	Default	Values	Since
<code>context.autoWrapUp</code>	repo	true	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects boolean)	0.19.10
<code>context.autoResume</code>	repo	true	not validated - read by plugin/crew/commands/migrate.m d (expects boolean)	0.19.10
<code>context.staleHandoff.maxAgeHours</code>	repo	72	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects integer)	0.16.33
<code>context.staleHandoff.maxCommitsBehind</code>	repo	3	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects integer)	0.16.33

Resume

Setting	Layer	Default	Values	Since	Summary
resume.auto	machine-arms	null	null true false (checked in plugin/crew/hooks/scripts/crew_resume.py)	1.0.40	Auto-resume after /clear or a manual /compact. Only the machine file can arm it (exactly true); a repo false vetoes it.
resume.typeDelaySeconds	both	2	whole seconds; fraction cut, negative or non-number reads as the default (coerced in plugin/crew/hooks/scripts/crew_autocycle.py)	1.0.32 1	Wait before auto-resume types its command: before the tmux ready probe, and the only wait on Windows. Read from the machine file only.
resume.readyTimeoutSeconds	both	15	whole seconds; fraction cut, negative or non-number reads as the default (coerced in plugin/crew	1.0.32 1	How long the tmux ready probe waits for an idle, empty input line before it types nothing. Read from the machine

Setting	Layer	Default	Values	Since	Summary
			/hooks/scripts/crew_autocycle.py)		file only.

Emergency

Setting	Layer	Default	Values	Since	Summary
emergency.standDown	repo	true	not validated - read by plugin/crew/hooks/scripts/_common.sh (expects boolean)	0.11.0 or earlier	Whether a declared incident may stand gates down; false forbids it.
emergency.ttlMinutes	repo	120	integer (coerced in plugin/crew/hooks/scripts/crew_incident.py)	0.11.0 or earlier	Default incident lifetime; a non-integer reads as the default.
emergency.maxTtlMinutes	repo	480	integer (coerced in plugin/crew/hooks/scripts/crew_incident.py)	0.11.0 or earlier	Longest incident lifetime; never below ttlMinutes.

Notify

Setting	Layer	Default	Values	Since	Summary
notify.provider	both	"none"	not validated - read by plugin/crew/hooks/scripts/notify.sh (expects	0.11.0 or earlier	Where notifications go; none is off.

Setting	Layer	Default	Values	Since	Summary
			string)		
notify.urlEnv	both	null	not validated - read by plugin/crew/ho oks/scripts/no tify.sh (expects string or null)	0.11.0 or earlier	Environment variable holding the webhook URL.
notify.tokenEnv	both	null	not validated - read by plugin/crew/ho oks/scripts/no tify.sh (expects string or null)	0.11.0 or earlier	Environment variable holding the token.
notify.chatId	both	null	not validated - read by plugin/crew/ho oks/scripts/no tify.sh (expects string or null)	0.11.0 or earlier	Chat id for chat providers.
notify.events	both	["phase", "gate", "waiting"]	not validated - read by plugin/crew/ho oks/scripts/no tify.sh (expects list of event names)	0.11.0 or earlier	Events that notify. A list is one leaf.

Platform

Setting	Layer	Default	Values	Since	Summary
platform.os	repo	null	not validated - read by plugin/crew/ho	0.11.0 or earlier	Detected OS, stamped by platform-sync.

Setting	Layer	Default	Values	Since	Summary
			oks/scripts/crew_platform.py (expects string or null)		
platform.wsl	repo	null	not validated - read by plugin/crew/oks/scripts/crew_platform.py (expects boolean or null)	0.11.0 or earlier	Detected WSL, stamped by platform-sync.
platform.shell	repo	null	not validated - read by plugin/crew/oks/scripts/crew_platform.py (expects string or null)	0.11.0 or earlier	Detected shell, stamped by platform-sync.
platform.windowsHostIp	repo	null	not validated - read by plugin/crew/oks/scripts/crew_platform.py (expects string or null)	0.11.0 or earlier	Windows host IP seen from WSL.

shellRoute

Setting	Layer	Default	Values	Since	Summary
shellRoute.mode	both	null (repo), "auto" (machine)	auto wsl powershell gitbash	1.0.54	The shell long-running jobs use on native Windows; null inherits, and an unknown value reads as auto and

Setting	Layer	Default	Values	Since	Summary
					is named.
shellRoute.distro	both	null	not validated - read by plugin/crew/h ooks/scripts/ crew_shell.py (expects string or null)	1.0.54	WSL distro to route to; null takes the default distro.

Pm

Setting	Layer	Default	Values	Since	Summary
pm.enabled	both	true	not validated - read by plugin/crew/ hooks/script s/crew_state .py (expects boolean)	0.11.0 or earlier	Run the PM brief.
pm.mode	both	"adaptive"	not validated - read by plugin/crew/ hooks/script s/crew_state .py (expects string)	0.11.0 or earlier	How the PM brief adapts its length.
pm.quietLines	both	8	integer (coerced in plugin/crew/ hooks/script s/crew_state .py)	0.11.0 or earlier	PM brief length when nothing changed.
pm.maxLines	both	40	integer (coerced in plugin/crew/ hooks/script	0.11.0 or earlier	Longest PM brief.

Setting	Layer	Default	Values	Since	Summary
			s/crew_state.py)		
pm.authority	both, widening warned	"report-only"	report-only act autonomous	0.11.0 or earlier	How much the PM may do unasked. A widening is warned about; the two layers combine by precedence.
pm.ticketGranularity	both	"system"	session system change	0.16.34	How big a ticket the PM cuts.
pm.maxDispatches	both	3	integer (coerced in plugin/crew/hooks/scripts/crew_state.py)	0.11.0 or earlier	Roles the PM may dispatch in one pass.

Graph

Setting	Layer	Default	Values	Since	Summary
graph.enabled	repo	true	not validated - read by plugin/crew/skills/crew-graph/SKILL.md (expects boolean)	0.11.0 or earlier	No consumer found (CONFIG.md section 9).
graph.tool	repo	"graphify"	not validated - read by plugin/crew/skills/crew-graph/SKILL.md (expects string)	0.11.0 or earlier	No consumer found (CONFIG.md section 9).

Setting	Layer	Default	Values	Since	Summary
graph.out	repo	"graphify-out"	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects path)	0.11.0 or earlier	Where the code graph is written.
graph.mode	repo	"code-only"	not validated - read by plugin/crew/skills/crew-graph/SKILL.md (expects string)	0.11.0 or earlier	No consumer found (CONFIG.md section 9).
graph.commitHook	repo	false	not validated - read by plugin/crew/skills/crew-graph/SKILL.md (expects boolean)	0.11.0 or earlier	No consumer found (CONFIG.md section 9).

Docs

Setting	Layer	Default	Values	Since	Summary
docs.theme	both	null	not validated - read by plugin/crew/skills/crew-house-style/SKILL.md (expects string or null)	0.16.33	House-style theme for built documents; null uses the skill's own choice.
docs.reportTheme	both	null	not validated - read by plugin/crew/skills/crew-house-style/SKILL.md (expects string or null)	0.16.33	Theme for findings reports.

Bitbucket

Setting	Layer	Default	Values	Since	Summary
bitbucket.mergeGate.enabled	both	false	not validated - read by plugin/crew /commands/promote.md (expects boolean)	0.16.33	Let /crew:promote drive the Bitbucket merge gate.
bitbucket.mergeGate.branch	both	null	not validated - read by plugin/crew /commands/promote.md (expects string or null)	0.16.33	Branch the Bitbucket merge gate protects.
bitbucket.mergeGate.preset	both	"standard"	not validated - read by plugin/crew /commands/promote.md (expects string)	0.16.33	Selects nothing today (CONFIG.md section 9).

GitHub

Setting	Layer	Default	Values	Since	Summary
github.mergeGate.enabled	both	false	not validated - read by plugin/crew /commands/promote.md (expects boolean)	0.19.30	Let /crew:promote drive the GitHub merge gate.

Setting	Layer	Default	Values	Since	Summary
github.mergeGate.branch	both	null	not validated - read by plugin/crew/commands/promote.md (expects string or null)	0.19.30	Branch the GitHub merge gate protects.

Install

Setting	Layer	Default	Values	Since	Summary
install.policy	both, ratchet	"manual"	manual ask auto (ratchet: narrower layer wins; listed narrowest first)	0.19.18	Whether crew may install a missing prerequisite.

Guards

Setting	Layer	Default	Values	Since	Summary
guards.terraformApply	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	0.19.30	terraform apply and friends.
guards.forcePush	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest	0.19.30	git push --force.

Setting	Layer	Default	Values	Since	Summary
			first)		
<code>guards.adminMerge</code>	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	0.19.30	gh pr merge --admin.
<code>guards.mergeGate</code>	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	0.19.30	Taking a live repo's merge gate down (read by /crew:gate).
<code>guards.cloudDestructive</code>	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	1.0.25	Destructive cloud CLI commands.
<code>guards.sqlDestructive</code>	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	1.0.25	Destructive SQL.
<code>guards.prodDatabase</code>	both, ratchet	"none"	none read full	0.19.30	How much of a declared

Setting	Layer	Default	Values	Since	Summary
	t		(ratchet: narrower layer wins; listed narrowest first)		production database crew may reach.
guards.prodServer	both, ratchet	"none"	none read full (ratchet: narrower layer wins; listed narrowest first)	0.19.30	How much of a declared production host crew may reach.
guards.roleWrites	both, ratchet	"off"	block report off (ratchet: narrower layer wins; listed narrowest first)	0.19.92	Enforce each role's write scope. Default off; a malformed value reads as block.
guards.cloudGuard	both, ratchet	"off"	block report off (ratchet: narrower layer wins; listed narrowest first)	1.0.25	Whether the cloud guard judges commands at all. Default off; report logs only.

Production

Setting	Layer	Default	Values	Since	Summary
production.databases	repo	[]	not validated -	0.19.30	Globs

Setting	Layer	Default	Values	Since	Summary
			read by plugin/crew/hooks/scripts/crew_config.py (expects list of globs)		naming production databases.
production.hosts	repo	[]	not validated - read by plugin/crew/hooks/scripts/crew_config.py (expects list of globs)	0.19.30	Globs naming production hosts.

Cloud

Setting	Layer	Default	Values	Since	Summary
cloud.awsProfiles	repo	[]	not validated - read by plugin/crew/hooks/scripts/cloud_guard.py (expects list of names)	1.0.25	AWS profiles this repo may use.
cloud.awsRegions	repo	[]	not validated - read by plugin/crew/hooks/scripts/cloud_guard.py (expects list of names)	1.0.25	AWS regions this repo may use.
cloud.azureSubscriptions	repo	[]	not validated - read by plugin/crew/hooks/scripts/cloud_guard.py (expects	1.0.25	Azure subscriptions this repo may use.

Setting	Layer	Default	Values	Since	Summary
			list of names)		

Environments

Setting	Layer	Default	Values	Since	Summary
environments.nonProd	repo	[]	not validated - read by plugin/crew/hooks/scripts/crew_config.py (expects list of globs)	1.0.37	Terraform targets that are not production and may run unattended.
environments.prodUnattended	both, ratchet	false	false true (ratchet: narrower layer wins; listed narrowest first)	1.0.37	Whether production terraform may run unattended; true only when both layers say so.

Change

Setting	Layer	Default	Values	Since	Summary
change.requester	both	null	not validated - read by plugin/crew/hooks/scripts/crew_change.py (expects string or	0.19.31	Who requests the change.

Setting	Layer	Default	Values	Since	Summary
change.implementor	both	null	null) not validated - read by plugin/crew/hooks/scripts/crew_change.py (expects string or null)	0.19.31	Who implements the change.
change.requireForProduction	both, ratchet	false	true false (ratchet: narrower layer wins; listed narrowest first)	0.19.31	Require an approved change request before /crew:promote production: a repo may turn it on, never off.
change.sdpTemplate	both	"Change Management Request"	not validated - read by plugin/crew/hooks/scripts/crew_change.py (expects string)	0.19.31	SDP template for a change request.
change.jiraIssueType	both	"Change"	not validated - read by plugin/crew/hooks/scripts/crew	0.19.31	Jira issue type for a change request.

Setting	Layer	Default	Values	Since	Summary
change.category	both	null	_change.py (expects string) not validated - read by plugin/crew/ w/hooks/scripts/ crew_change.py (expects string or null)	0.19.3 1	Change category.

Git

Setting	Layer	Default	Values	Since	Summary
git.forbiddenTrailers	both	[]	list of trailer tokens (letters, digits and -, no :) (checked in plugin/crew/ hooks/scripts/ crew_trailers.py)	1.0.328	Commit trailer tokens the owner forbids, reported by /crew:done. The two layers combine by union, so a repo can add a token and never remove the machine owner's; a value that is not a list of tokens makes the list unknown, never empty (CONFIG.md)

Setting	Layer	Default	Values	Since	Summary
					section 22).

Scope

Setting	Layer	Default	Values	Since	Summary
scope.mode	repo	"off"	off report block auto	1.0.25	Whether the scope guard enforces a ticket's Touch list; a value outside these fails closed to block.
scope.allowCliApproval	repo	false	false true (checked in plugin/crew/ hooks/scripts/crew_tickets.py)	1.0.25	Whether a CLI-written approval receipt counts; only exactly true allows it.

Autopilot

Setting	Layer	Default	Values	Since	Summary
autopilot.mode	repo	"off"	off plan (checked in plugin/crew/ hooks/scripts/crew_autopilot.py)	1.0.41	Only the exact string plan arms /crew:autopilot; anything else reads as off, with a warning.
autopilot.maxPhases	repo	12	positive integer (checked in plugin/crew/ hooks/scripts/crew_autopilot.py)	1.0.41	Phases one run may take; anything but a positive integer reads as

Setting	Layer	Default	Values	Since	Summary
			s/crew_autopilot.py)		12, with a warning.
autopilot.deploy	repo	"none"	none nonprod all	1.0.42	Where a deploy may run without asking; anything else reads as none.
autopilot.approval	repo	"risk"	human self risk	1.0.42	Who approves a ticket under autopilot; anything else reads as human.
autopilot.questions	repo	"risk"	human self risk	1.0.42	Who answers a ticket's open questions under autopilot; anything else reads as human.
autopilot.maxAutoReplans	repo	0	non-negative integer (checked in plugin/crew/hooks/scripts/crew_autopilot.py)	1.0.40 2	Successor plans autopilot may start by rejecting an out-of-rounds BLOCK review itself; 0 is off, and anything but a non-negative integer reads as 0, and above 5 as 5, with a warning.
autopilot.sleep.schedule	repo	null	HH:MM-HH:MM or null (checked in plugin/crew/hooks/scripts/crew_sleep.py)	1.0.33 2	A nightly window, HH:MM-HH:MM in machine local time (may cross midnight); inside it the two sleep overrides apply. Anything else is could not tell: only a stricter override

Setting	Layer	Default	Values	Since	Summary
					applies.
autopilot.sleep.approval	repo	null	null human self risk (checked in plugin/crew/hooks/scripts/crew_sleep.py)	1.0.332	autopilot.approval inside the sleep window; null keeps the day value; anything else counts as human, the strictest, with a warning.
autopilot.sleep.questions	repo	null	null human self risk (checked in plugin/crew/hooks/scripts/crew_sleep.py)	1.0.332	autopilot.questions inside the sleep window; null keeps the day value; anything else counts as human, the strictest, with a warning.

Tickets

Setting	Layer	Default	Values	Since	Summary
tickets.baseBranch	repo	null	branch name or null (checked in plugin/crew/hooks/scripts/scope_base.py)	1.0.158	The branch ticket branches are cut from; null tries origin/HEAD's target, then origin/main, then main. A value that is not a branch name, or names no commit, makes the scope base could not tell.

Route

Setting	Layer	Default	Values	Since	Summary
route.enabled	both	false	false true (checked in plugin/crew/hooks/scripts/crew_route.py)	1.0.42	Route plain-text prompts to /crew: commands; only the JSON value true arms it.

Coming (Not in Code Yet)

Keys from approved tickets that have not landed. Each moves into the table above when its ticket lands, because it is then in the code; a test fails until it does (test_no_coming_key_is_in_code).

T-0009

Setting	Change	Layer	Default	Values	Summary
guards.deployWorkflow	new key	both, ratchet	block		Whether crew may dispatch a deploy workflow.
environments.workflows	new key	repo	{}		Deploy workflows per environment.

T-0011

Setting	Change	Layer	Default	Values	Summary
autopilot.ship	new key	repo	merge	pr merge	After /crew:done, open a PR (pr) or also merge it once required checks are green (merge).
autopilot.knownFailures	new	repo	[]		Required checks

Setting	Change	Layer	Default	Values	Summary
	key				that may fail without blocking a merge, matched by exact name.
autopilot.ciTimeoutMinutes	new key	repo	60		How long ship waits for CI; still pending at the timeout stops.

T-0012

Setting	Change	Layer	Default	Values	Summary
autopilot.maxTicketsPerRun	new key	repo	3		Tickets one goal run may work before it stops.
autopilot.maxTokensPerSession	new key	repo	200000 0		Token cap for one goal session.
autopilot.mode	changes values	repo	off	off plan backlog	Adds backlog: work a goal's tickets one at a time.

T-0029

Setting	Change	Layer	Default	Values	Summary
autopilot.maxLanes	new key	repo	the resolved pm.maxDispatches		Parallel lanes one autopilot wave may run; may only lower

Setting	Change	Layer	Default	Values	Summary
					the limit.
autopilot.reviewPolicy	new key	repo	stop	stop clean-only fix-and-rereview	What a lane does with review findings.

T-0030

Setting	Change	Layer	Default	Values	Summary
coord.ttlMinutes	new key	set when T-0030 lands	30		Lifetime of a cross-session coordination claim (1-10080).
coord.channel	new key	set when T-0030 lands	set when T-0030 lands		Where sessions coordinate.

T-0050

Setting	Change	Layer	Default	Values	Summary
autopilot.mode	changes layer	both, stricter wins	off		The personal autopilot keys become settable in the global file; the stricter layer wins.
scope.allowCliApproval	changes layer	both, stricter wins	false		Becomes settable in the global file; the stricter layer wins.