Crew 1.0 - Configuration Reference

This document has two parts. The first is short and hand-written: how crew's two config files combine, how to see what is in force, and the common setups. The second is generated from the code and lists every key.

How the Two Files Combine

crew reads two JSON files:

- `~/.claude/crew/config.json` - the **machine-global** file. Your personal defaults for every repo on this machine: providers and models, notifications, auto-clear, the guards, how far autopilot may go.
- `.crew/config.json` - the **repo** file. Facts about one checkout: the tracker, the board, scope enforcement, production declarations.

The repo file wins over the machine file, which wins over crew's defaults. Four exceptions, each named in the Layer column below:

- A **repo-only** key in the machine file takes effect nowhere. It is pruned on read and refused on write.
- A **ratcheted** key (`install.policy`, each guard `guards.profile` and `guards.overrides` expand to, `change.requireForProduction`, `environments.prodUnattended`) resolves to the narrower of the two values, so a cloned repo cannot widen what your machine allows.
- A **machine-armed** key (`resume.auto`, `context.autoClear.enabled`) can be turned on only in the machine file. A repo can only switch it off.
- A **personal** key (the five `autopilot.*` keys) resolves per key to the stricter of the layers that set it; a layer that says nothing imposes nothing. A machine value is your default for every repo, which a repo may narrow and never widen.

A `null` in the repo file over a machine value inherits the machine value. The `/crew:init` template writes every key except the personal ones, so it does not shadow your machine defaults for those; a repo `/crew:init` set up before that still spells `autopilot.mode: "off"`, which holds a machine `plan` down until you remove it (`--explain --all` names it as a `shadow:`).

Seeing What Is in Force

- `/crew:config --show` prints every machine-settable key, its value and the layer it came from, and names any key that takes effect nowhere.
- `/crew:config` with no argument is a menu that writes either file through the validated path. It shows a dry run first, refuses unknown keys and out-of-range values, and marks a widening with `!`.
- From a shell: `python3 plugin/crew/hooks/scripts/crew_config.py --explain` is the same table, `--explain --all` adds every repo-only key and names each shadowing repo value, and `--models` is the per-role provider table.

Backups and Rebuilding a Lost Config

Every write a crew script makes to either file first copies the old bytes to `~/.claude/crew/backups/` (the newest 20 per file kept) and is refused when that copy fails; a hand edit is not backed up. `crew_config.py --backups` lists the machine file's (add `--repo` for the repo file's) and `--restore <stamp> --apply` puts one back. Your non-default values are kept in `~/.claude/crew/profile.json` (and in your vault when `memory.vaultPath` is set), so `--rebuild --repo` or `--rebuild --global` regenerates a lost or corrupt file from the template plus that profile, as a dry run until `--apply`.

Common Setups

- **Personal defaults once, for every repo.** Put providers, models, `notify.*`, the guards and the `autopilot.*` keys in `~/.claude/crew/config.json`. Leave repo files to repo facts.
- **Self-approval under autopilot.** Set `autopilot.mode: "plan"` and choose `autopilot.approval` (`human`, `self` or `risk`) in either file, and set `scope.allowCliApproval: true` in the repo file, which is the only file that key is read from. Review acceptance and production deploys still stop for you.
- **Notifications.** In the machine file, set `notify.provider` and the name of the environment variable holding the token in `notify.tokenEnv`. The secret stays in your environment, never in the file. `tokenEnv` is machine-only: a repo file's value is ignored with a notice.

The key list is `plugin/crew/CONFIG.md`, which ships with the plugin; the reasoning behind the

keys is in `docs/crew/config-rationale.md`.

Reference (Generated)

Generated from the code by `python3 docs/guides/crew/src/config_reference.py --write`. Do not edit by hand: `python3 scripts/check-marketplace.py` fails when this file is stale.

87 keys: 50 settable in the machine-global file, 37 repo-only.

Columns:

- **Layer**: which file may set the key.
- **Default**: what `default_config()` returns. Where the machine default differs, both are shown.
- **Values**: the values crew accepts, read from the same tuple the validator reads. "not validated" means crew checks nothing and names the file that reads the key.
- **Since**: the first crew version whose template declared the key. Keys in the first template (crew 0.11.0) read "0.11.0 or earlier".

Layers

- **repo**: only `.crew/config.json` may set it; the global file's value is pruned on read and refused on write.
- **both**: either file may set it; the repo value wins over the machine one.
- **both, ratchet**: either file may set it, and the NARROWER of the two wins (`crew_guards.RATCHETED_KEYS`). A repo can tighten what the machine allows, never loosen it.
- **both, widening warned**: either file may set it and the repo wins, but a write that widens it is flagged (`crew_config._RATCHETED`).
- **both, stricter wins**: a personal key (`crew_guards.PERSONAL_KEYS`): either file may set it, and where both do the STRICTER value wins; a layer that is silent (absent or `null`) imposes nothing, so a machine value is your default for every repo and a repo may only narrow it.
- **machine-arms**: only the global file can turn it on (exactly `true`); a repo may only veto it with `false` (`crew_config.REPO_VETO_ONLY`).

- **machine-only**: read from the global file alone; a repo's own value is never consulted.

Top-Level Keys

Setting	Layer	Default	Values	Since	Summary
`schema`	repo	`8`	not validated - read by `plugin/crew/hooks/scripts/crew_state.py` (expects integer)	0.11.0 or earlier	Config schema version; `/crew:migrate` upgrades an older one.
`tracker`	repo	`"files"`	`files` | `obsidian` | `jira` | `sdp`	0.11.0 or earlier	Where tickets live; `crew_tracker.resolve` answers `could not tell` when two configs disagree.
`verifyGate`	repo	`true`	not validated - read by `plugin/crew/hooks/scripts/verify-gate.sh` (expects boolean)	0.11.0 or earlier	Run the Stop verify gate.

Qa

Setting	Layer	Default	Values	Since	Summary
`qa.provider`	both	`"auto"`	`auto` | `claude` | `codex` | `copilot` | `kimi`	0.11.0 or earlier	Who reviews: `auto` walks `qa.order`; a named provider is used as-is.
`qa.order`	both	`["codex", "kimi",`	list of: `claude` | `codex` |	0.14.	The reviewers `auto` tries, in

Setting	Layer	Default	Values	Since	Summary
		`"copilot", "claude"]`	`copilot` | `kimi`	6	order. A list is one leaf, replaced wholesale.
`qa.fallback`	both	`"claude-sonnet-5"`	not validated - read by `plugin/crew/commands/review.md` (expects model id)	0.16.6	Model a gone pin falls back to, on its family's provider (L-0712).
`qa.codex.model`	both	`null`	not validated - read by `plugin/crew/commands/review.md` (expects string or null)	0.14.6	Codex model for review; null passes no flag.
`qa.codex.reasoningEffort`	both	`null`	`none` | `minimal` | `low` | `medium` | `high` | `xhigh` | `max` (listed in `plugin/crew/commands/review.md`; not validated)	0.14.6	Codex reasoning effort for review; null passes no flag.
`qa.copilot.model`	both	`null`	not validated - read by `plugin/crew/commands/review.md` (expects string or null)	0.14.6	Copilot model for review; null uses the CLI default.
`qa.kimi.model`	both	`null`	not validated - read by	1.0.3	Kimi Code model id for review (`k3`,

Setting	Layer	Default	Values	Since	Summary
			`plugin/crew/commands/review.md` (expects string or null)	9	`kimi-for-coding`, ...); null uses the CLI's own default.
`qa.roles`	both	`{}`	object of role pins; each pin's provider is checked (checked in `plugin/crew/hooks/scripts/crew_config.py`)	0.16.6	Per-role reviewer pins, `qa.roles.<role>.provider` / `.model`; a pin beats the provider block for that role.

Dev

Setting	Layer	Default	Values	Since	Summary
`dev.provider`	both	`"claude"`	`claude` | `codex` | `copilot` | `kimi`	0.14.6	Who implements.
`dev.fallback`	both	`"claude-sonnet-5"`	not validated - read by `plugin/crew/skills/crew-providers/SKILL.md` (expects model id)	0.16.6	Model a gone dev pin falls back to, on its family's provider.
`dev.codex.model`	both	`null`	not validated - read by `plugin/crew/skills/crew-providers/SKILL.md` (expects	0.14.6	Codex model for implementation.

Setting	Layer	Default	Values	Since	Summary
			string or null)		
`dev.codex.reasoningEffort`	both	`null`	`none` | `minimal` | `low` | `medium` | `high` | `xhigh` | `max` (listed in `plugin/crew/commands/review.md`; not validated)	0.14.6	Codex reasoning effort for implementation.
`dev.copilot.model`	both	`null`	not validated - read by `plugin/crew/skills/crew-providers/SKILL.md` (expects string or null)	0.14.6	Copilot model for implementation.
`dev.kimi.model`	both	`null`	not validated - read by `plugin/crew/skills/crew-providers/SKILL.md` (expects string or null)	1.0.39	Kimi Code model id for implementation, as `qa.kimi.model`.
`dev.roles`	both	`{}`	object of role pins; each pin's provider is checked (checked in `plugin/crew/hooks/scripts/crew_config.py`)	0.16.6	Per-role dev pins, as `qa.roles`.

secondOpinion

Setting	Layer	Default	Values	Since	Summary
`secondOpinion.provider`	both	`"none"`	not validated - read by `plugin/crew/commands/plan.md` (expects string)	0.11.0 or earlier	Second-opinion provider for plans; `none` is off.
`secondOpinion.mode`	both	`"cli"`	not validated - read by `plugin/crew/skills/crew-providers/SKILL.md` (expects string)	0.11.0 or earlier	How the second opinion is reached.
`secondOpinion.model`	both	`null`	not validated - read by `plugin/crew/skills/crew-providers/SKILL.md` (expects string or null)	0.11.0 or earlier	Second-opinion model.

Jira

Setting	Layer	Default	Values	Since	Summary
`jira.project`	repo	`null`	not validated - read by `plugin/crew/commands/jira-sync.md` (expects string or null)	0.11.0 or earlier	Jira project key. No consumer found (docs/crew/config-rationale.md).
`jira.cloudId`	repo	`null`	not validated - read by `plugin/crew/commands/jira-`	0.19.10	Jira cloud id, cached by `/crew:jira-sync`; read by nothing.

Setting	Layer	Default	Values	Since	Summary
			`sync.md` (expects string or null)		

Obsidian

Setting	Layer	Default	Values	Since	Summary
`obsidian.vaultPath`	repo	`null`	not validated - read by `plugin/crew/hooks/scripts/crew_tracker.py` (expects path or null)	0.11.0 or earlier	Vault holding the board; falls back to `memory.vaultPath` and must hold `.obsidian/`.
`obsidian.boardDir`	repo	`null`	not validated - read by `plugin/crew/hooks/scripts/crew_tracker.py` (expects path or null)	0.11.0 or earlier	Board folder inside the vault (relative, no `..`).

Memory

Setting	Layer	Default	Values	Since	Summary
`memory.mode`	both	`"repo"`	not validated - read by `plugin/crew/skills/crew-memory/SKILL.md` (expects string)	0.11.0 or earlier	Where memory lives (`repo`, or a vault).
`memory.vaultPath`	both	`null`	not validated - read by `plugin/crew/hooks/scripts/crew_recall.py` (expects path or null)	0.11.0 or earlier	The Obsidian vault used for memory.

Context

Setting	Layer	Default	Values	Since	Sum
`context.enabled`	repo	`true`	not validated - read by `plugin/crew/hooks/scripts/context-watch.sh` (expects boolean)	0.11.0 or earlier	Run t cont watc
`context.warnAt`	repo	`0.4`	not validated - read by `plugin/crew/hooks/scripts/context-watch.sh` (expects number)	0.11.0 or earlier	Fract the b at wh watc warn wrap and a clear defa since (was expli value kept.
`context.reserveTokens`	repo	`0`	not validated - read by `plugin/crew/hooks/scripts/context-watch.sh` (expects integer or null)	0.11.0 or earlier	Toke back the b `null` off.
`context.autoClear.enabled`	machine-arms	`null`	`null` | `true` | `false` (checked in `plugin/crew/hooks/scripts/crew_a`	0.19.10	Auto after wrap Only

Setting	Layer	Default	Values	Since	Sum
			`utocycle.py`)		mach can a (exac `true` `fals` it.
`context.autoClear.method`	both	`"auto"`	`auto` | `none` | `notify` | `tmux` | `xdotool` | `wtype`; per OS: linux: auto, none, notify, tmux, xdotool, wtype; macos: auto, none, notify, tmux; windows: auto, none, notify; windows-bash: auto, none, notify, tmux	0.19.10	How is typ `auto` per platf meth OS la stand clear
`context.autoClear.delaySeconds`	both	`3`	number (coerced in `plugin/crew/hooks/scripts/crew_autocycle.py`)	0.19.10	Dela befo typin unus value and as 3.
`context.autoClear.minHandoffLines`	both	`5`	number (coerced in `plugin/crew/hooks/scripts/crew_autocycle.py`)	0.19.10	Shor hand may clear after

Setting	Layer	Default	Values	Since	Sum
					num read
`context.autoClear.onlyRepos`	machine-only	`null`	list of absolute repo paths, or null (coerced in `plugin/crew/hooks/scripts/crew_autocycle.py`)	1.0.25	Narr only, mach only: narr noth list a only repo a no arms noth
`context.autoClear.onlySessions`	machine-only	`null`	list of session ids, or null (coerced in `plugin/crew/hooks/scripts/crew_autocycle.py`)	1.0.25	As `onlyR` for s ids; w both both matc
`context.autoClear.wrapUp`	machine-arms	`null`	`null` | `true` | `false` (checked in `plugin/crew/hooks/scripts/crew_autocycle.py`)	1.0.334	Auto up b auto (T-00 warn beco the w proc and clear

Setting	Layer	Default	Values	Since	Sum
					for it resul the r file a (exac `true` when enab arme repo veto

Resume

Setting	Layer	Default	Values	Since	Summary
`resume.auto`	machine-arms	`null`	`null` | `true` | `false` (checked in `plugin/crew/hooks/scripts/crew_resume.py`)	1.0.40	Auto-resume after `/clear` or a manual `/compact`. Only the machine file can arm it (exactly `true`); a repo `false` vetoes it.

Emergency

Setting	Layer	Default	Values	Since	Summary
`emergency.standDown`	repo	`true`	not validated - read by `plugin/crew/hooks/scripts/_common.sh`	0.11.0 or earlier	Whether a declared incident may stand gates

Setting	Layer	Default	Values	Since	Summary
			(expects boolean)		down; `false` forbids it.
`emergency.maxTtlMinutes`	repo	`480`	integer (coerced in `plugin/crew/hooks/scripts/crew_incident.py`)	0.11.0 or earlier	Longest incident lifetime; never below `ttlMinutes`.

Notify

Setting	Layer	Default	Values	Since	Summary
`notify.provider`	both	`null`	telegram, teams, none or null; any other value sends nothing (coerced in `plugin/crew/hooks/scripts/crew_notify.py`)	0.11.0 or earlier	Where notifications go: `telegram`, `teams` or `none` (off). A repo null inherits the machine provider; a repo `none` opts this repo out.
`notify.tokenEnv`	machine-only	`null`	not validated - read by `plugin/crew/hooks/scripts/crew_notify.py` (expects string or null)	0.11.0 or earlier	Name of the environment variable holding the Telegram bot token; null may be filled from the notify skill's `bot_token_env`. Honoured from the machine file

Setting	Layer	Default	Values	Since	Summary
					only.
`notify.chatId`	both	`null`	not validated - read by `plugin/crew/hooks/scripts/crew_notify.py` (expects string or null)	0.11.0 or earlier	Telegram chat id; null may be filled from the notify skill's `chat_id`, and the skill's example value counts as unset.
`notify.events`	both	`["blocker", "deploy", "question"]`	list of event names; an unknown name is dropped with a notice (coerced in `plugin/crew/hooks/scripts/crew_notify.py`)	0.11.0 or earlier	Events that notify: `deploy`, `question`, and `blocker` (T-0060's four blocker reasons). The pre-1.0 names `gate`, `waiting`, `phase`, `review` and `done` are mapped with a notice. A list is one leaf.

Platform

Setting	Layer	Default	Values	Since	Summary
`platform.os`	repo	`null`	not validated - read by `plugin/crew/hooks/scripts/crew_platform.py` (expects	0.11.0 or earlier	Detected OS, stamped by platform-sync.

Setting	Layer	Default	Values	Since	Summary
			string or null)		
`platform.wsl`	repo	`null`	not validated - read by `plugin/crew/hooks/scripts/crew_platform.py` (expects boolean or null)	0.11.0 or earlier	Detected WSL, stamped by platform-sync.
`platform.shell`	repo	`null`	not validated - read by `plugin/crew/hooks/scripts/crew_platform.py` (expects string or null)	0.11.0 or earlier	Detected shell, stamped by platform-sync.
`platform.windowsHostIp`	repo	`null`	not validated - read by `plugin/crew/hooks/scripts/crew_platform.py` (expects string or null)	0.11.0 or earlier	Windows host IP seen from WSL.

Pm

Setting	Layer	Default	Values	Since	Summary
`pm.authority`	both, widening warned	`"report-only"`	`report-only` | `act` | `autonomous`	0.11.0 or earlier	How much the PM may do unasked. A widening is warned about; the two layers combine by precedence.
`pm.maxDispatches`	both	3	integer (coerced	0.11.0	Roles the PM

Setting	Layer	Default	Values	Since	Summary
			in `plugin/crew/hooks/scripts/crew_state.py`)	or earlier	may dispatch in one pass.

Graph

Setting	Layer	Default	Values	Since	Summary
`graph.out`	repo	`"graphify-out"`	not validated - read by `plugin/crew/hooks/scripts/crew_state.py` (expects path)	0.11.0 or earlier	Where the code graph is written.

Install

Setting	Layer	Default	Values	Since	Summary
`install.policy`	both, ratchet	`"manual"`	`manual` | `ask` | `auto` (ratchet: narrower layer wins; listed narrowest first)	0.19.18	Whether crew may install a missing prerequisite.

Guards

Setting	Layer	Default	Values	Since	Summary
`guards.profile`	both, ratchet	`"off"`	`off` | `standard` | `strict`	1.2.62	One word for the twelve guards: `off` (today's defaults), `standard` or `strict`. Expands per layer; each guard's ratchet then runs on the expanded values.
`guards.overrides`	both,	`{}`	object of guard	1.2.62	`guards.overrides.<gua`

Setting	Layer	Default	Values	Since	Summary
	ratchet		name to tier (checked in `plugin/crew/hooks/scripts/crew_guards.py`)		`rd>`: one guard's tier, replacing the profile's value for it. Each entry is checked against that guard's own tiers; a bad one reads as the floor.

Production

Setting	Layer	Default	Values	Since	Summary
`production.databases`	repo	`[]`	not validated - read by `plugin/crew/hooks/scripts/crew_config.py` (expects list of globs)	0.19.30	Globs naming production databases.
`production.hosts`	repo	`[]`	not validated - read by `plugin/crew/hooks/scripts/crew_config.py` (expects list of globs)	0.19.30	Globs naming production hosts.

Cloud

Setting	Layer	Default	Values	Since	Summary
`cloud.awsProfiles`	repo	`[]`	not validated - read by `plugin/crew/hooks/scripts/cloud_guard.py` (expects list	1.0.25	AWS profiles this repo may use.

Setting	Layer	Default	Values	Since	Summary
			of names)		
`cloud.awsRegions`	repo	`[]`	not validated - read by `plugin/crew/hooks/scripts/cloud_guard.py` (expects list of names)	1.0.25	AWS regions this repo may use.
`cloud.azureSubscriptions`	repo	`[]`	not validated - read by `plugin/crew/hooks/scripts/cloud_guard.py` (expects list of names)	1.0.25	Azure subscriptions this repo may use.

Environments

Setting	Layer	Default	Values	Since	Summary
`environments.nonProd`	repo	`[]`	not validated - read by `plugin/crew/hooks/scripts/crew_config.py` (expects list of globs)	1.0.37	Terraform targets that are not production and may run unattended.
`environments.prodUnattended`	both, ratchet	`false`	`false` | `true` (ratchet: narrower layer wins; listed narrowest first)	1.0.37	Whether production terraform may run unattended; `true` only when both

Setting	Layer	Default	Values	Since	Summary
					layers say so.
`environments.workflows`	repo	`{}`	not validated - read by `plugin/crew/hooks/scripts/crew_config.py` (expects object of glob to string)	1.1.16	Deploy workflow globs, each mapped to its environment or `input:<name>`.

Change

Setting	Layer	Default	Values	Since	Summary
`change.requireForProduction`	both, ratchet	`false`	`true` | `false` (ratchet: narrower layer wins; listed narrowest first)	0.19.31	Require an approved change request before `/crew:promote production`: a repo may turn it on, never off.

Git

Setting	Layer	Default	Values	Since	Summary
`git.forbiddenTrailers`	both	`[]`	list of trailer tokens (letters, digits and `-`, no `:`) (checked in `plugin/crew/hooks/scripts/crew`	1.0.328	Commit trailer tokens the owner forbids, reported by `/crew:done`. The two layers combine by union, so a repo can

Setting	Layer	Default	Values	Since	Summary
			`_trailers.py`)		add a token and never remove the machine owner's; a value that is not a list of tokens makes the list unknown, never empty (docs/crew/config-rationale.md).

Scope

Setting	Layer	Default	Values	Since	Summary
`scope.mode`	repo	`"off"`	`off` | `report` | `block` | `auto`	1.0.25	Whether the scope guard enforces a ticket's Touch list; a value outside these fails closed to `block`.
`scope.allowCliApproval`	repo	`false`	`false` | `true` (checked in `plugin/crew/hooks/scripts/crew_ticket.py`)	1.0.25	Whether a CLI-written approval receipt counts; only exactly `true` allows it.

Autopilot

Setting	Layer	Default	Values	Since	Summar
`autopilot.mode`	both, stricter wins	`"off"`	`off` | `plan` | `backlog` (checked in `plugin/crew/hooks/scripts/crew_autopilot.py`); personal: listed strictest first, the stricter wins	1.0.41	Only the strings `p` ticket per `backlog` (goal's tic depende inside th `/crew:au` anything as off, wi warning.
`autopilot.maxPhases`	both, stricter wins	`12`	positive integer (checked in `plugin/crew/hooks/scripts/crew_autopilot.py`); personal: the smaller wins	1.0.41	Phases o take; any positive i reads as warning.
`autopilot.deploy`	both, stricter wins	`"none"`	`none` | `nonprod` | `all`; personal: listed strictest first, the stricter wins	1.0.42	Where a run witho anything as `none`.
`autopilot.approval`	both, stricter wins	`"risk"`	`human` | `risk` | `self`; personal: listed strictest first, the stricter wins	1.0.42	Who app ticket un autopilot else read
`autopilot.questions`	both, stricter wins	`"risk"`	`human` | `risk` | `self`; personal: listed strictest first, the stricter wins	1.0.42	Who ans ticket's o question autopilot else read

Setting	Layer	Default	Values	Since	Summar
`autopilot.maxAutoReplans`	repo	`0`	non-negative integer (checked in `plugin/crew/hooks/scripts/crew_autopilot.py`)	1.0.339	Successo autopilot by rejecti of-round review its and anyt non-nega reads as above 5 a warning.
`autopilot.ship`	repo	`"merge"`	`pr` | `merge`	1.0.349	After `/cr` pushes a the PR; `m` merges i commit) required allow. An reads as warning.
`autopilot.sleep.schedule`	repo	`null`	HH:MM-HH:MM or null (checked in `plugin/crew/hooks/scripts/crew_sleep.py`)	1.0.332	A nightly `HH:MM-HH` machine (may cro midnight the two s overrides Anything could no stricter o applies.
`autopilot.sleep.approval`	repo	`null`	`null` | `human` | `self` | `risk`	1.0.33	`autopilo`

Setting	Layer	Default	Values	Since	Summar
			(checked in `plugin/crew/hooks/scripts/crew_sleep.py`)	2	inside th window; the day v anything as huma strictest, warning.
`autopilot.sleep.questions`	repo	`null`	`null` | `human` | `self` | `risk` (checked in `plugin/crew/hooks/scripts/crew_sleep.py`)	1.0.33 2	`autopilo` inside th window; the day v anything as huma strictest, warning.
`autopilot.sleep.deploy`	repo	`null`	`null` | `nonprod` | `none` (checked in `plugin/crew/hooks/scripts/crew_sleep.py`)	1.1.21	`autopilo` inside th window (keeps th `nonprod` replaces else, `all` refused v warning. effective `nonprod`: never ru unattend
`autopilot.maxTicketsPerRun`	repo	`3`	positive integer (checked in `plugin/crew/hooks/scripts/crew_autopilot_backlog.p`	1.1.21	Tickets o (one sess start; the

Setting	Layer	Default	Values	Since	Summar
			y)		stops the Anything positive i reads as warning.
autopilot.maxTokensPerSession	repo	2000000	positive integer (checked in plugin/crew/hooks/scripts/crew_autopilot_backlog.py)	1.1.21	Input plu tokens o session r each assi message once, bef stops; a t that cann stops too but a pos reads as with a wa
autopilot.maxLanes	repo	null	positive integer or null (checked in plugin/crew/hooks/scripts/crew_wave.py)	1.1.6	Lanes on /crew:au wave runs null is the pm.maxDi larger va capped t anything positive i reads as a warnin
autopilot.reviewPolicy	repo	"stop"	stop | clean-only | fix-and-rereview	1.1.6	What aut with a re A wave la

Setting	Layer	Default	Values	Since	Summar
					ends at t verdict, c takes a C on to the checks, f `rereview` the ledge A single-t (T-0067): `and-rere` fixing a r FINDING BLOCK ar itself (the and re-re Anything as `stop`, `v` warning; accepts a

Tickets

Setting	Layer	Default	Values	Since	Summary
`tickets.baseBranch`	repo	`null`	branch name or null (checked in `plugin/crew/hooks/scripts/scope_base.py`)	1.0.158	The branch ticket branches are cut from; null tries origin/HEAD's target, then origin/main, then main. A value that is not a branch name, or names

Setting	Layer	Default	Values	Since	Summary
					no commit, makes the scope base could not tell.

Route

Setting	Layer	Default	Values	Since	Summary
`route.enabled`	both	`false`	`false` | `true` (checked in `plugin/crew/hooks/scripts/crew_route.py`)	1.0.42	Route plain-text prompts to `/crew:` commands; only the JSON value `true` arms it.

unattendedCloud

Setting	Layer	Default	Values	Since	S
`unattendedCloud.aws.readOnly.profile`	machine-only	`null`	profile name, or null (coerced in `plugin/crew/hooks/scripts/crew_unattended.py`)	1.1.10	T u e f e it te c fi
`unattendedCloud.aws.readOnly.identity`	machine-only	`null`	ARN prefix ending in `/`, or null (coerced in `plugin/crew/hooks/scripts/crew_una`	1.1.10	T A r e r

Setting	Layer	Default	Values	Since	S
			`ttended.py`)		M
`unattendedCloud.aws.readOnly.region`	machine-only	`null`	region, or null (coerced in `plugin/crew/hooks/scripts/crew_unattended.py`)	1.1.10	T u n M
`unattendedCloud.aws.nonProd`	machine-only	`{}`	None (checked in `plugin/crew/hooks/scripts/crew_unattended.py`)	1.1.10	E { r e u r e a o

Coming (Not in Code Yet)

Keys from approved tickets that have not landed. Each moves into the table above when its ticket lands, because it is then in the code; a test fails until it does (`test_no_coming_key_is_in_code`).

T-0030

Setting	Change	Layer	Default	Values	Summary
`coord.ttlMinutes`	new key	set when T-0030 lands	30		Lifetime of a cross-session coordination claim (1-10080).
`coord.channel`	new key	set when	set when T-0030		Where sessions coordinate.

Setting	Change	Layer	Default	Values	Summary
		T-0030 lands	lands		

T-0050

Setting	Change	Layer	Default	Values	Summary
`scope.allowCliApproval`	changes layer	both, stricter wins	false		Becomes settable in the global file, the stricter layer winning, once its reader (`crew_ticket.cli_approval_allowed`) reads the global layer in a harness-only follow-up to T-0050.