

Crew 1.0 - Configuration Reference

This document has two parts. The first is short and hand-written: how crew's two config files combine, how to see what is in force, and the common setups. The second is generated from the code and lists every key.

How the Two Files Combine

crew reads two JSON files:

- `~/.claude/crew/config.json` - the **machine-global** file. Your personal defaults for every repo on this machine: providers and models, notifications, auto-clear, the guards, how far autopilot may go.
- `.crew/config.json` - the **repo** file. Facts about one checkout: the tracker, the board, scope enforcement, production declarations.

The repo file wins over the machine file, which wins over crew's defaults. Four exceptions, each named in the Layer column below:

- A **repo-only** key in the machine file takes effect nowhere. It is pruned on read and refused on write.
- A **ratcheted** key (`install.policy`, `every guards.*`, `change.requireForProduction`, `environments.prodUnattended`) resolves to the narrower of the two values, so a cloned repo cannot widen what your machine allows.
- A **machine-armed** key (`resume.auto`, `context.autoClear.enabled`) can be turned on only in the machine file. A repo can only switch it off.
- A **personal** key (the five `autopilot.*` keys) resolves per key to the stricter of the layers that set it; a layer that says nothing imposes nothing. A machine value is your default for every repo, which a repo may narrow and never widen.

A `null` in the repo file over a machine value inherits the machine value. The `/crew:init` template writes every key except the personal ones, so it does not shadow your machine defaults for those; a repo `/crew:init` set up before that still spells `autopilot.mode: "off"`, which holds a machine plan down until you remove it (`--explain --all` names it as a shadow:).

Seeing What Is in Force

- `/crew:config --show` prints every machine-settable key, its value and the layer it came

from, and names any key that takes effect nowhere.

- `/crew:config` with no argument is a menu that writes either file through the validated path. It shows a dry run first, refuses unknown keys and out-of-range values, and marks a widening with `!`.
- From a shell: `python3 plugin/crew/hooks/scripts/crew_config.py --explain` is the same table, `--explain --all` adds every repo-only key and names each shadowing repo value, and `--models` is the per-role provider table.

Backups and Rebuilding a Lost Config

Every write a crew script makes to either file first copies the old bytes to `~/.claude/crew/backups/` (the newest 20 per file kept) and is refused when that copy fails; a hand edit is not backed up. `crew_config.py --backups` lists the machine file's (add `--repo` for the repo file's) and `--restore <stamp> --apply` puts one back. Your non-default values are kept in `~/.claude/crew/profile.json` (and in your vault when `memory.vaultPath` is set), so `--rebuild --repo` or `--rebuild --global` regenerates a lost or corrupt file from the template plus that profile, as a dry run until `--apply`.

Common Setups

- **Personal defaults once, for every repo.** Put providers, models, `notify.*`, the guards and the `autopilot.*` keys in `~/.claude/crew/config.json`. Leave repo files to repo facts.
- **Self-approval under autopilot.** Set `autopilot.mode: "plan"` and choose `autopilot.approval` (human, self or risk) in either file, and set `scope.allowCliApproval: true` in the repo file, which is the only file that key is read from. Review acceptance and production deploys still stop for you.
- **Notifications.** In the machine file, set `notify.provider` and the environment variable names in `notify.urlEnv / notify.tokenEnv`. The secret stays in your environment, never in the file. Those two are machine-only: a repo file's value is ignored with a notice.

The reasoning behind each key is in `plugin/crew/CONFIG.md`, which ships with the plugin.

Reference (Generated)

Generated from the code by `python3 docs/guides/crew/src/config_reference.py --write`. Do not edit by hand: `python3 scripts/check-marketplace.py` fails when this file is stale.

156 keys: 88 settable in the machine-global file, 68 repo-only.

Columns:

- **Layer:** which file may set the key.
- **Default:** what `default_config()` returns. Where the machine default differs, both are shown.
- **Values:** the values crew accepts, read from the same tuple the validator reads. "not validated" means crew checks nothing and names the file that reads the key.
- **Since:** the first crew version whose template declared the key. Keys in the first template (crew 0.11.0) read "0.11.0 or earlier".

Layers

- **repo:** only `.crew/config.json` may set it; the global file's value is pruned on read and refused on write.
- **both:** either file may set it; the repo value wins over the machine one.
- **both, ratchet:** either file may set it, and the NARROWER of the two wins (`crew_guards.RATCHETED_KEYS`). A repo can tighten what the machine allows, never loosen it.
- **both, widening warned:** either file may set it and the repo wins, but a write that widens it is flagged (`crew_config._RATCHETED`).
- **both, stricter wins:** a personal key (`crew_guards.PERSONAL_KEYS`): either file may set it, and where both do the STRICTER value wins; a layer that is silent (absent or `null`) imposes nothing, so a machine value is your default for every repo and a repo may only narrow it.
- **machine-arms:** only the global file can turn it on (exactly `true`); a repo may only veto it with `false` (`crew_config.REPO_VETO_ONLY`).
- **machine-only:** read from the global file alone; a repo's own value is never consulted.

Top-Level Keys

Setting	Layer	Default	Values	Since	Summary
schema	repo	7	not validated - read by plugin/crew/hooks /scripts/crew_sta te.py (expects integer)	0.11.0 or earlier	Config schema version; /crew:migrate upgrades an older one.

Setting	Layer	Default	Values	Since	Summary
tier	repo	0	not validated - read by plugin/crew/hooks /scripts/crew_sta te.py (expects integer)	0.11.0 or earlier	Setup tier recorded by /crew:init.
roles	repo	["explorer" , "reviewer"]	not validated - read by plugin/crew/hooks /scripts/crew_sta te.py (expects list of role names)	0.11.0 or earlier	Optional roles installed in this repo.
tracker	repo	"files"	files obsidian jira sdp	0.11.0 or earlier	Where tickets live; crew_tracker.resolv e answers could not tell when two configs disagree.
verifyGate	repo	true	not validated - read by plugin/crew/hooks /scripts/verify- gate.sh (expects boolean)	0.11.0 or earlier	Run the Stop verify gate.

Qa

Setting	Layer	Default	Values	Since	Summary
qa.provider	both	"auto"	auto claude codex copilot kimi	0.11.0 or earlier	Who reviews: auto walks qa.order; a named provider is used as-is.
qa.order	both	["codex", "kimi", "copilot", "claude"]	list of: claude codex	0.14. 6	The reviewers auto tries, in order. A list is

Setting	Layer	Default	Values	Since	Summary
			copilot kimi		one leaf, replaced wholesale.
qa.fallback	both	"claude- sonnet-5"	not validated - read by plugin/cr ew/comm nds/review .md (expects model id)	0.16. 6	Claude model used when no other reviewer is available.
qa.codex.model	both	null	not validated - read by plugin/cr ew/comm nds/review .md (expects string or null)	0.14. 6	Codex model for review; null passes no flag.
qa.codex.reasoningEffort	both	null	none minimal low medium high xhigh max (listed in plugin/cr ew/comm nds/review .md; not validated)	0.14. 6	Codex reasoning effort for review; null passes no flag.
qa.copilot.model	both	null	not	0.14.	Copilot model for

Setting	Layer	Default	Values	Since	Summary
			validated - read by plugin/crow/ command s/review .md (expects string or null)	6	review; null uses the CLI default.
qa.kimi.model	both	null	not validated - read by plugin/crow/ command s/review .md (expects string or null)	1.0.3 9	Kimi Code model id for review (k3, kimi-for-coding, ...); null uses the CLI's own default.
qa.roles	both	{}	object of role pins; each pin's provider is checked (checked in plugin/crow/ hooks/ scripts/ crow_conf ig.py)	0.16. 6	Per-role reviewer pins, qa.roles.<role> .provider / .mod el; a pin beats the provider block for that role.

Setting	Layer	Default	Values	Since	Summary
dev.provider	both	"claude"	claude codex copilot kimi	0.14.6	Who implements.
dev.fallback	both	"claude-sonnet-5"	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects model id)	0.16.6	Claude model used when the dev provider is unavailable.
dev.codex.model	both	null	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string or null)	0.14.6	Codex model for implementation.
dev.codex.reasoningEffort	both	null	none minimal low medium high xhigh max (listed in plugin/crew/commands/review.md; not validated)	0.14.6	Codex reasoning effort for implementation.
dev.copilot.model	both	null	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string or null)	0.14.6	Copilot model for implementation.
dev.kimi.model	both	null	not validated - read by plugin/crew/skills/crew-	1.0.39	Kimi Code model id for implementation,

Setting	Layer	Default	Values	Since	Summary
			providers/SKILL.md (expects string or null)		as qa.kimi.model.
dev.roles	both	{}	object of role pins; each pin's provider is checked (checked in plugin/crew/hooks/scripts/crew_config.py)	0.16.6	Per-role dev pins, as qa.roles.

Worktree

Setting	Layer	Default	Values	Since	Summary
worktree.root	both	null	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects path or null)	0.16.27	Where crew creates linked worktrees; null uses the default.

secondOpinion

Setting	Layer	Default	Values	Since	Summary
secondOpinion.provider	both	"none"	not validated - read by plugin/crew/commands/plan.md (expects string)	0.11.0 or earlier	Second-opinion provider for plans; none is off.
secondOpinion.mode	both	"cli"	not validated - read by plugin/crew/skills/crew-	0.11.0 or earlier	How the second opinion is reached.

Setting	Layer	Default	Values	Since	Summary
			providers/SKILL.md (expects string)	r	
secondOpinion.model	both	null	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string or null)	0.11.0 or earlier	Second-opinion model.
secondOpinion.keyEnv	both	"GEMINI_API_KEY"	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects string)	0.11.0 or earlier	Environment variable holding the provider's API key.
secondOpinion.sendsCode	both	false	not validated - read by plugin/crew/skills/crew-providers/SKILL.md (expects boolean)	0.11.0 or earlier	Whether code may be sent to the second-opinion provider.

Jira

Setting	Layer	Default	Values	Since	Summary
jira.project	repo	null	not validated - read by plugin/crew/commands/jira-sync.md (expects string or null)	0.11.0 or earlier	Jira project key. No consumer found (CONFIG.md section 9).
jira.cloudId	repo	null	not validated - read	0.19.10	Jira cloud id,

Setting	Layer	Default	Values	Since	Summary
			by plugin/crew/commands/jira-sync.md (expects string or null)		cached by /crew:jira-sync; read by nothing.

Sdp

Setting	Layer	Default	Values	Since	Summary
sdp.portal	repo	null	not validated - read by plugin/crew/commands/sdp-sync.md (expects string or null)	0.11.0 or earlier	ServiceDesk Plus portal.
sdp.noteVisibility	repo	"private"	not validated - read by plugin/crew/commands/sdp-sync.md (expects string)	0.11.0 or earlier	Visibility of notes crew writes to SDP.
sdp.closeOnDone	repo	false	not validated - read by plugin/crew/commands/sdp-sync.md (expects boolean)	0.11.0 or earlier	Close the SDP request when the ticket is done.

Obsidian

Setting	Layer	Default	Values	Since	Summary
obsidian.vaultPath	repo	null	not validated - read by plugin/crew/hooks/scripts/crew	0.11.0 or earlier	Vault holding the board; falls back to memory.vaultPath and must hold

Setting	Layer	Default	Values	Since	Summary
			_tracker.py (expects path or null)		.obsidian/.
obsidian.boardDir	repo	null	not validated - read by plugin/crew/hooks/scripts/crew_tracker.py (expects path or null)	0.11.0 or earlier	Board folder inside the vault (relative, no ..).
obsidian.board	repo	"Board.md"	not validated - read by plugin/crew/hooks/scripts/crew_tracker.py (expects file name)	0.11.0 or earlier	Board file name.
obsidian.columns.backlog	repo	"Backlog"	not validated - read by plugin/crew/hooks/scripts/crew_tracker.py (expects string)	0.11.0 or earlier	Board column for backlog tickets (direction, ready, needs-owner).
obsidian.columns.ready	repo	"Ready"	not validated - read by plugin/crew/hooks/sc	0.11.0 or earlier	Board column for ready tickets.

Setting	Layer	Default	Values	Since	Summary
obsidian.columns.inProgress	repo	"In Progress"	not validated - read by plugin/crews/hooks/scripts/crew_tracker.py (expects string)	0.11.0 or earlier	Board column for tickets in progress.
obsidian.columns.review	repo	"Review"	not validated - read by plugin/crews/hooks/scripts/crew_tracker.py (expects string)	0.11.0 or earlier	Board column for tickets in review.
obsidian.columns.done	repo	"Done"	not validated - read by plugin/crews/hooks/scripts/crew_tracker.py (expects string)	0.11.0 or earlier	Board column for closed tickets (done, cancelled, superseded; each checked).

Memory

Setting	Layer	Default	Values	Since	Summary
memory.mode	both	"repo"	not validated -	0.11.0	Where memory

Setting	Layer	Default	Values	Since	Summary
			read by plugin/crew/skills/crew-memory/SKILL.m d (expects string)	or earlier	lives (repo, or a vault).
memory.vaultPath	both	null	not validated - read by plugin/crew/hooks/scripts/crew_recall.py (expects path or null)	0.11.0 or earlier	The Obsidian vault used for memory.
memory.inject	repo	true	not validated - read by plugin/crew/hooks/scripts/crew_context.py (expects boolean)	1.0.25	Inject the handoff and recall at session start; only an explicit false stops it.
memory.recall.vaults	repo	[]	not validated - read by plugin/crew/hooks/scripts/crew_recall.py (expects list of vault names)	1.0.25	This repo's vault priority for recall; empty uses the obsidian config's roles.
memory.recall.maxChars	repo	800	positive integer (coerced in plugin/crew/hooks/scripts/crew_recall.py)	1.0.25	Recall output budget; a non- positive or non- integer value reads as 800.
memory.recall.projects	repo	[]	not validated - read by plugin/crew/ho	1.1.11	Project names sent to vault recall as - -

Setting	Layer	Default	Values	Since	Summary
			oks/scripts/crew_recall.py (expects list of project names)		project so this repo's notes rank first; empty sends the main checkout's directory name.

Context

Setting	Layer	Default	Values	Since
context.enabled	repo	true	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects boolean)	0.11.0 or earlier
context.warnAt	repo	0.5	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects number)	0.11.0 or earlier
context.budgetTokens	repo	null	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects integer or null)	0.11.0 or earlier
context.reserveTokens	repo	0	not validated - read by plugin/crew/hooks/scripts/context-watch.sh	0.11.0 or earlier

Setting	Layer	Default	Values	Since
			(expects integer or null)	
<code>context.handoffPath</code>	repo	<code>".work/HANDOFF.m d"</code>	not validated - read by <code>plugin/crew/hoo ks/scripts/crew _autocycle.py</code> (expects path)	0.11.0 or earlier
<code>context.keepTranscripts</code>	repo	5	not validated - read by <code>plugin/crew/hoo ks/scripts/hand off-write.sh</code> (expects integer)	0.11.0 or earlier
<code>context.autoClear.enabled</code>	machine- arms	null	null true false (checked in <code>plugin/crew/hoo ks/scripts/crew _autocycle.py</code>)	0.19.1 0
<code>context.autoClear.method</code>	both	"auto"	auto none notify tmux xdotool wtype sendkeys; per OS: linux: auto, none, notify, tmux, xdotool, wtype; macos: auto, none, notify, tmux; windows: auto, none, notify, sendkeys;	0.19.1 0

Setting	Layer	Default	Values	Since
			windows-bash: auto, none, notify, tmux, sendkeys	
<code>context.autoClear.windowTitle</code>	both	null	not validated - read by plugin/crew/hoo ks/scripts/auto -clear.ps1 (expects string or null)	0.19.1 0
<code>context.autoClear.command</code>	both	"/clear"	not validated - read by plugin/crew/hoo ks/scripts/crew _autocycle.py (expects string)	0.19.1 0
<code>context.autoClear.delaySeconds</code>	both	3	number (coerced in plugin/crew/hoo ks/scripts/crew _autocycle.py)	0.19.1 0
<code>context.autoClear.minHandoffLines</code>	both	5	number (coerced in plugin/crew/hoo ks/scripts/crew _autocycle.py)	0.19.1 0
<code>context.autoClear.unsafeFocus</code>	repo	false	not validated - read by plugin/crew/hoo ks/scripts/auto -clear.sh (expects boolean)	0.19.11

Setting	Layer	Default	Values	Since
<code>context.autoClear.onlyRepos</code>	machine-only	null	list of absolute repo paths, or null (coerced in plugin/crew/hooks/scripts/crew_autocycle.py)	1.0.25
<code>context.autoClear.onlySessions</code>	machine-only	null	list of session ids, or null (coerced in plugin/crew/hooks/scripts/crew_autocycle.py)	1.0.25
<code>context.autoClear.wrapUp</code>	machine-arms	null	null true false (checked in plugin/crew/hooks/scripts/crew_autocycle.py)	1.0.33 4

Setting	Layer	Default	Values	Since
context.autoWrapUp	repo	true	not validated - read by plugin/crew/hooks/scripts/context-watch.sh (expects boolean)	0.19.10
context.autoResume	repo	true	not validated - read by plugin/crew/commands/migrate.m d (expects boolean)	0.19.10
context.staleHandoff.maxAgeHours	repo	72	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects integer)	0.16.33
context.staleHandoff.maxCommitsBehind	repo	3	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects integer)	0.16.33

Resume

Setting	Layer	Default	Values	Since	Summary
resume.auto	machine-arms	null	null true false (checked in	1.0.40	Auto-resume after /clear or a manual

Setting	Layer	Default	Values	Since	Summary
					/compact. Only the machine file can arm it (exactly true); a repo false vetoes it.
<code>resume.typeDelaySeconds</code>	both	2	whole seconds; fraction cut, negative or non-number reads as the default (coerced in <code>plugin/crew/hooks/scripts/crew_autocycle.py</code>)	1.0.32 1	Wait before auto-resume types its command: before the tmux ready probe, and the only wait on Windows. Read from the machine file only.
<code>resume.readyTimeoutSeconds</code>	both	15	whole seconds; fraction cut, negative or non-number reads as the default (coerced in <code>plugin/crew/hooks/scripts/crew_autocycle.py</code>)	1.0.32 1	How long the tmux ready probe waits for an idle, empty input line before it types nothing. Read from the machine file only.

Emergency

Setting	Layer	Default	Values	Since	Summary
emergency.standDown	repo	true	not validated - read by plugin/crew/hooks/scripts/_common.sh (expects boolean)	0.11.0 or earlier	Whether a declared incident may stand gates down; false forbids it.
emergency.ttlMinutes	repo	120	integer (coerced in plugin/crew/hooks/scripts/crew_incident.py)	0.11.0 or earlier	Default incident lifetime; a non-integer reads as the default.
emergency.maxTtlMinutes	repo	480	integer (coerced in plugin/crew/hooks/scripts/crew_incident.py)	0.11.0 or earlier	Longest incident lifetime; never below ttlMinutes.

Notify

Setting	Layer	Default	Values	Since	Summary
notify.provider	both	null	telegram, teams, none or null; any other value sends nothing (coerced in plugin/crew/hooks/scripts/crew_notify.py)	0.11.0 or earlier	Where notifications go: telegram, teams or none (off). A repo null inherits the machine provider; a repo none opts this repo out.
notify.urlEnv	machine-only	null	not validated -	0.11.0 or	Name of the environment

Setting	Layer	Default	Values	Since	Summary
			read by plugin/crew/hooks/scripts/crew_notify.py (expects string or null)	earlier	variable holding the Teams webhook URL. Honoured from the machine file only; a repo's is ignored with a notice.
notify.tokenEnv	machine-only	null	not validated - read by plugin/crew/hooks/scripts/crew_notify.py (expects string or null)	0.11.0 or earlier	Name of the environment variable holding the Telegram bot token; null may be filled from the notify skill's bot_token_env. Honoured from the machine file only.
notify.chatId	both	null	not validated - read by plugin/crew/hooks/scripts/crew_notify.py (expects string or null)	0.11.0 or earlier	Telegram chat id; null may be filled from the notify skill's chat_id, and the skill's example value counts as unset.
notify.events	both	["blocker", "deploy", "question"]	list of event names; an unknown name is dropped with a notice (coerced in	0.11.0 or earlier	Events that notify: deploy, question, and blocker (T-0060's four blocker reasons). The pre-1.0 names gate,

Setting	Layer	Default	Values	Since	Summary
			plugin/crew/hooks/scripts/crew_notify.py)		waiting, phase, review and done are mapped with a notice. A list is one leaf.
notify.realertHours	both	6	number of hours; negative or non-number reads as the default (coerced in plugin/crew/hooks/scripts/crew_notify.py)	1.0.350	The same event + ticket + reason is sent once per this many hours; a question pings once per waiting episode.
notify.questionTypes	both	null	list of notification_type strings, or null; a non-list reads as null and a non-string entry is dropped (coerced in plugin/crew/hooks/scripts/crew_notify.py)	1.0.350	The Claude Code notification_type values that count as a question; null uses the built-in five (crew_notify.QUESTION_TYPES).

Platform

Setting	Layer	Default	Values	Since	Summary
platform.os	repo	null	not validated - read by plugin/crew/hooks/scripts/crew_ _platform.py (expects string or null)	0.11.0 or earlier	Detected OS, stamped by platform-sync.
platform.wsl	repo	null	not validated - read by plugin/crew/hooks/scripts/crew_ _platform.py (expects boolean or null)	0.11.0 or earlier	Detected WSL, stamped by platform-sync.
platform.shell	repo	null	not validated - read by plugin/crew/hooks/scripts/crew_ _platform.py (expects string or null)	0.11.0 or earlier	Detected shell, stamped by platform-sync.
platform.windowsHostIp	repo	null	not validated - read by plugin/crew/hooks/scripts/crew_ _platform.py (expects string or null)	0.11.0 or earlier	Windows host IP seen from WSL.

shellRoute

Setting	Layer	Default	Values	Since	Summary
shellRoute.mode	both	null (repo), "auto"	auto wsl powershell	1.0.54	The shell long- running jobs use on native

Setting	Layer	Default	Values	Since	Summary
		(machine)	gitbash		Windows; null inherits, and an unknown value reads as auto and is named.
shellRoute.distro	both	null	not validated - read by plugin/crew/hooks/scripts/crew_shell.py (expects string or null)	1.0.54	WSL distro to route to; null takes the default distro.

Pm

Setting	Layer	Default	Values	Since	Summary
pm.enabled	both	true	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects boolean)	0.11.0 or earlier	Run the PM brief.
pm.mode	both	"adaptive"	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects string)	0.11.0 or earlier	How the PM brief adapts its length.
pm.quietLines	both	8	integer (coerced in plugin/crew/hooks/scripts/crew_state.py)	0.11.0 or earlier	PM brief length when nothing changed.
pm.maxLines	both	40	integer	0.11.0	Longest PM

Setting	Layer	Default	Values	Since	Summary
			(coerced in plugin/crew/hooks/scripts/crew_state.py)	or earlier	brief.
pm.authority	both, widening warned	"report-only"	report-only act autonomous	0.11.0 or earlier	How much the PM may do unasked. A widening is warned about; the two layers combine by precedence.
pm.ticketGranularity	both	"system"	session system change	0.16.34	How big a ticket the PM cuts.
pm.maxDispatches	both	3	integer (coerced in plugin/crew/hooks/scripts/crew_state.py)	0.11.0 or earlier	Roles the PM may dispatch in one pass.

Graph

Setting	Layer	Default	Values	Since	Summary
graph.enabled	repo	true	not validated - read by plugin/crew/skills/crew-graph/SKILL.md (expects boolean)	0.11.0 or earlier	No consumer found (CONFIG.md section 9).
graph.tool	repo	"graphify"	not validated - read by plugin/crew/skills/crew-graph/SKILL.md (expects	0.11.0 or earlier	No consumer found (CONFIG.md section 9).

Setting	Layer	Default	Values	Since	Summary
			string)		
graph.out	repo	"graphify-out"	not validated - read by plugin/crew/hooks/scripts/crew_state.py (expects path)	0.11.0 or earlier	Where the code graph is written.
graph.mode	repo	"code-only"	not validated - read by plugin/crew/skills/crew-graph/SKILL.md (expects string)	0.11.0 or earlier	No consumer found (CONFIG.md section 9).
graph.commitHook	repo	false	not validated - read by plugin/crew/skills/crew-graph/SKILL.md (expects boolean)	0.11.0 or earlier	No consumer found (CONFIG.md section 9).

Docs

Setting	Layer	Default	Values	Since	Summary
docs.theme	both	null	not validated - read by plugin/crew/skills/crew-house-style/SKILL.md (expects string or null)	0.16.33	House-style theme for built documents; null uses the skill's own choice.
docs.reportTheme	both	null	not validated - read by plugin/crew/skills/crew-house-style/SKILL.md (expects string or null)	0.16.33	Theme for findings reports.

Bitbucket

Setting	Layer	Default	Values	Since	Summary
bitbucket.mergeGate.enabled	both	false	not validated - read by plugin/crew/ commands/promote.md (expects boolean)	0.16.33	Let /crew:promote drive the Bitbucket merge gate.
bitbucket.mergeGate.branch	both	null	not validated - read by plugin/crew/ commands/promote.md (expects string or null)	0.16.33	Branch the Bitbucket merge gate protects.
bitbucket.mergeGate.preset	both	"standard"	not validated - read by plugin/crew/ commands/promote.md (expects string)	0.16.33	Selects nothing today (CONFIG.md section 9).

GitHub

Setting	Layer	Default	Values	Since	Summary
github.mergeGate.enabled	both	false	not validated - read by plugin/crew/commands/promote.md (expects boolean)	0.19.30	Let /crew:promote drive the GitHub merge gate.
github.mergeGate.branch	both	null	not validated - read by plugin/crew/commands/promote.m	0.19.30	Branch the GitHub merge gate

Setting	Layer	Default	Values	Since	Summary
			d (expects string or null)		protects.

Install

Setting	Layer	Default	Values	Since	Summary
install.policy	both, ratchet	"manual"	manual ask auto (ratchet: narrower layer wins; listed narrowest first)	0.19.18	Whether crew may install a missing prerequisite.

Guards

Setting	Layer	Default	Values	Since	Summary
guards.terraformApply	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	0.19.30	terraform apply and friends.
guards.forcePush	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest	0.19.30	git push --force.

Setting	Layer	Default	Values	Since	Summary
			first)		
			block ask allow		
guards.adminMerge	both, ratchet	"block "	(ratchet: narrower layer wins; listed narrowest first)	0.19.3 0	gh pr merge --admin.
			block ask allow		
guards.mergeGate	both, ratchet	"block "	(ratchet: narrower layer wins; listed narrowest first)	0.19.3 0	Taking a live repo's merge gate down (read by /crew:gate).
			block ask allow		
guards.cloudDestructive	both, ratchet	"block "	(ratchet: narrower layer wins; listed narrowest first)	1.0.25	Destructive cloud CLI commands.
			block ask allow		
guards.sqlDestructive	both, ratchet	"block "	block ask allow	1.0.25	Destructive SQL.

Setting	Layer	Default	Values	Since	Summary
			(ratchet: narrower layer wins; listed narrowest first)		
<code>guards.deployWorkflow</code>	both, ratchet	"block"	block ask allow (ratchet: narrower layer wins; listed narrowest first)	1.1.16	A gh workflow run or gh api .../dispatches of a workflow environments.workflows lists.
<code>guards.prodDatabase</code>	both, ratchet	"none"	none read full (ratchet: narrower layer wins; listed narrowest first)	0.19.3 0	How much of a declared production database crew may reach.
<code>guards.prodServer</code>	both, ratchet	"none"	none read full (ratchet: narrower layer wins; listed	0.19.3 0	How much of a declared production host crew may reach.

Setting	Layer	Default	Values	Since	Summary
			narrowest first)		
guards.roleWrites	both, ratchet	"off"	block report off (ratchet: narrower layer wins; listed narrowest first)	0.19.9 2	Enforce each role's write scope. Default off; a malformed value reads as block.
guards.cloudGuard	both, ratchet	"off"	block report off (ratchet: narrower layer wins; listed narrowest first)	1.0.25	Whether the cloud guard judges commands at all. Default off; report logs only.

Production

Setting	Layer	Default	Values	Since	Summary
production.databases	repo	[]	not validated - read by plugin/crew/hooks/scripts/crew_config.py (expects list of globs)	0.19.30	Globs naming production databases.
production.hosts	repo	[]	not validated - read by	0.19.30	Globs naming production

Setting	Layer	Default	Values	Since	Summary
			plugin/crew/hooks/scripts/crew_config.py (expects list of globs)		hosts.

Cloud

Setting	Layer	Default	Values	Since	Summary
cloud.awsProfiles	repo	[]	not validated - read by plugin/crew/hooks/scripts/cloud_guard.py (expects list of names)	1.0.25	AWS profiles this repo may use.
cloud.awsRegions	repo	[]	not validated - read by plugin/crew/hooks/scripts/cloud_guard.py (expects list of names)	1.0.25	AWS regions this repo may use.
cloud.azureSubscriptions	repo	[]	not validated - read by plugin/crew/hooks/scripts/cloud_guard.py (expects list of names)	1.0.25	Azure subscriptions this repo may use.

Environments

Setting	Layer	Default	Values	Since	Summary
environments.nonProd	repo	[]	not validated	1.0.37	Terraform

Setting	Layer	Default	Values	Since	Summary
			- read by plugin/crew/ hooks/scripts/crew_config.py (expects list of globs)		targets that are not production and may run unattended.
environments.prodUnattended	both, ratchet	false	false true (ratchet: narrower layer wins; listed narrowest first)	1.0.37	Whether production terraform may run unattended; true only when both layers say so.
environments.workflows	repo	{}	not validated - read by plugin/crew/hooks/scripts/crew_config.py (expects object of glob to string)	1.1.16	Deploy workflow globs, each mapped to its environment or input:<name>.

Change

Setting	Layer	Default	Values	Since	Summary
change.requester	both	null	not validated - read by plugin/crew/hooks/scripts/crew_change.py (expects	0.19.31	Who requests the change.

Setting	Layer	Default	Values	Since	Summary
change.implementor	both	null	string or null) not validated - read by plugin/crew/hooks/scripts/crew_change.py (expects string or null)	0.19.31	Who implements the change.
change.requireForProduction	both, ratchet	false	true false (ratchet: narrower layer wins; listed narrowest first)	0.19.31	Require an approved change request before /crew:promote production: a repo may turn it on, never off.
change.sdpTemplate	both	"Change Management Request"	not validated - read by plugin/crew/hooks/scripts/crew_change.py (expects string)	0.19.31	SDP template for a change request.
change.jiraIssueType	both	"Change"	not validated - read by plugin/crew/hooks/scripts/crew	0.19.31	Jira issue type for a change request.

Setting	Layer	Default	Values	Since	Summary
change.category	both	null	_change.py (expects string) not validated - read by plugin/crew/ w/hooks/scripts/crew _change.py (expects string or null)	0.19.31	Change category.

Git

Setting	Layer	Default	Values	Since	Summary
git.forbiddenTrailers	both	[]	list of trailer tokens (letters, digits and -, no :) (checked in plugin/crew/ hooks/scripts/ crew_trailers.py)	1.0.328	Commit trailer tokens the owner forbids, reported by /crew:done. The two layers combine by union, so a repo can add a token and never remove the machine owner's; a value that is not a list of tokens makes the list unknown, never empty (CONFIG.md section 22).

Scope

Setting	Layer	Default	Values	Since	Summary
scope.mode	repo	"off"	off report block auto	1.0.25	Whether the scope guard enforces a ticket's Touch list; a value outside these fails closed to block.
scope.allowCliApproval	repo	false	false true (checked in plugin/crew/hooks/scripts/crew_tickets.py)	1.0.25	Whether a CLI-written approval receipt counts; only exactly true allows it.

Autopilot

Setting	Layer	Default	Values	Since	Summary
autopilot.mode	both, stricter wins	"off"	off plan backlog (checked in plugin/crew/hooks/scripts/crew_autopilot.py); personal: listed strictest first, the stricter wins	1.0.41	Only the exact strings plan (one ticket per run) and backlog (L-0541: a goal's tickets in dependency order, inside the caps) arm /crew:autopilot; anything else reads as off, with a warning.
autopilot.maxPhases	both, stricter wins	12	positive integer (checked in plugin/crew/hooks/scripts/crew_autopilot.py); personal: the	1.0.41	Phases one run may take; anything but a positive integer reads as 12, with a warning.

Setting	Layer	Default	Values	Since	Summary
			smaller wins		
<code>autopilot.deploy</code>	both, stricter wins	"none"	none nonprod all; personal: listed strictest first, the stricter wins	1.0.42	Where a deploy may run without asking; anything else reads as none.
<code>autopilot.approval</code>	both, stricter wins	"risk"	human risk self; personal: listed strictest first, the stricter wins	1.0.42	Who approves a ticket under autopilot; anything else reads as human
<code>autopilot.questions</code>	both, stricter wins	"risk"	human risk self; personal: listed strictest first, the stricter wins	1.0.42	Who answers a ticket's open questions under autopilot; anything else reads as human
<code>autopilot.maxAutoReplans</code>	repo	0	non-negative integer (checked in plugin/crew/hooks/scripts/crew_autopilot.py)	1.0.339	Successor plans autopilot may start by rejecting an out-of-rounds BLOCK review itself; 0 is off and anything but a non-negative integer reads as 0, and above 5 as 5, with a warning.
<code>autopilot.ship</code>	repo	"merge"	pr merge	1.0.349	After /crew:done: pr pushes and opens the PR; merge also merges it (a merge commit) once the required checks allow. Anything else reads as pr, with a

Setting	Layer	Default	Values	Since	Summary
					warning.
<code>autopilot.knownFailures</code>	repo	<code>[]</code>	list of check names (checked in <code>plugin/crew/hooks/scripts/crew_autopilot.py</code>)	1.0.349	Required checks whose fail does not block a merge, matched by exact name; anything but list of strings reads as <code>[]</code> , with a warning.
<code>autopilot.ciTimeoutMinutes</code>	repo	<code>60</code>	positive integer (checked in <code>plugin/crew/hooks/scripts/crew_autopilot.py</code>)	1.0.349	Minutes ship waits for the required checks; still pending or green only after stops. Anything but a positive integer reads as <code>60</code> , with a warning.
<code>autopilot.sleep.schedule</code>	repo	<code>null</code>	<code>HH:MM-HH:MM</code> or null (checked in <code>plugin/crew/hooks/scripts/crew_sleep.py</code>)	1.0.332	A nightly window, <code>HH:MM-HH:MM</code> in machine local time (may cross midnight); inside it the two sleep overrides apply. Anything else is could not tell: only a stricter override applies.
<code>autopilot.sleep.approval</code>	repo	<code>null</code>	<code>null human self risk</code> (checked in <code>plugin/crew/hooks/scripts/crew_sleep.py</code>)	1.0.332	<code>autopilot.approval</code> inside the sleep window; null keeps the day value; anything else counts as human, the

Setting	Layer	Default	Values	Since	Summary
					strictest, with a warning.
autopilot.sleep.questions	repo	null	null human self risk (checked in plugin/crew/hooks/scripts/crew_sleep.py)	1.0.32	autopilot.questions inside the sleep window; null keeps the day value; anything else counts as human, the strictest, with a warning.
autopilot.sleep.deploy	repo	null	null nonprod none (checked in plugin/crew/hooks/scripts/crew_sleep.py)	1.1.16	autopilot.deploy inside the sleep window (L-0654): null keeps the day value, nonprod or none replaces it; anything else, all included, is refused with a warning. Asleep, an effective all reads as nonprod: production never runs unattended asleep.
autopilot.sleep.notifyHold	repo	null	null true (checked in plugin/crew/hooks/scripts/crew_notify_hold.py)	1.1.16	Inside the sleep window (L-0656): true holds the ping that only ask for attention (questions Approval waiting, Review out of rounds) and counts them; the morning summary carries the count. A failure (a

Setting	Layer	Default	Values	Since	Summary
					deploy result, a refused Stop gate, a stalled lane) is never held. Only while armed and asleep before the schedule (a manual sleep outside it holds nothing); anything but null or true holds nothing, with a warning.
<code>autopilot.maxTicketsPerRun</code>	repo	3	positive integer (checked in <code>plugin/crew/hooks/scripts/crew_autopilot_backup.py</code>)	1.1.16	Tickets one goal run (one session) may start; the next one stops the run. Anything but a positive integer reads as 3, with a warning.
<code>autopilot.maxTokensPerSession</code>	repo	2000000	positive integer (checked in <code>plugin/crew/hooks/scripts/crew_autopilot_backup.py</code>)	1.1.16	Input plus output tokens one goal session may spend before the run stops a transcript that cannot be read stops too. Anything but a positive integer reads as 2000000, with a warning.
<code>autopilot.maxLanes</code>	repo	null	positive integer or null (checked in <code>plugin/crew/hooks/scripts/crew</code>	1.1.6	Lanes one /crew:autopilot wave runs at once; null is the resolved <code>pm.maxDispatches</code>, a

Setting	Layer	Default	Values	Since	Summary
			<code>_wave.py)</code>		larger value is capped to it and anything but a positive integer reads as it, each with a warning.
<code>autopilot.reviewPolicy</code>	repo	"stop"	stop clean-only fix-and-rereview	1.1.6	What autopilot does with a review verdict. A wave lane stop ends at the first verdict, clean-only takes a CLEAN round on to the done checks, fix-and-rereview fixes within the ledger's rounds. A single-ticket run (T-0067): only fix-and-rereview acts, fixing a non-final FINDINGS round's BLOCK and FIX line itself (the fix phase) and re-reviewing. Anything else reads as stop, with a warning; no setting accepts a review.

Tickets

Setting	Layer	Default	Values	Since	Summary
<code>tickets.baseBranch</code>	repo	null	branch name or null (checked in	1.0.158	The branch ticket branches are cut from; null tries

Setting	Layer	Default	Values	Since	Summary
			plugin/crew/hooks/scripts/scope_base.py)		origin/HEAD's target, then origin/main, then main. A value that is not a branch name, or names no commit, makes the scope base could not tell.

Route

Setting	Layer	Default	Values	Since	Summary
route.enabled	both	false	false true (checked in plugin/crew/hooks/scripts/crew_route.py)	1.0.42	Route plain-text prompts to /crew: commands; only the JSON value true arms it.

unattendedCloud

Setting	Layer	Default	Values	Since	Summary
unattendedCloud.aws.readOnly.profile	machine-only	null	profile name, or null (coerced in plugin/crew/hooks/scripts/crew_unattended.py)	1.1.10	The AWS unattended exports from (aws export- it must tempora credentials file only
unattendedCloud.aws.readOnly.identity	machine-only	null	ARN prefix ending in /, or null	1.1.10	The ass ARN pre report f

Setting	Layer	Default	Values	Since	Summary
			(coerced in plugin/crew/hooks/scripts/crew_unattended.py)		ending refuses Machine
unattendedCloud.aws.readOnly.region	machine-only	null	region, or null (coerced in plugin/crew/hooks/scripts/crew_unattended.py)	1.1.10	The AWS unattended null is Machine
unattendedCloud.aws.nonProd	machine-only	{}	None (checked in plugin/crew/hooks/scripts/crew_unattended.py)	1.1.10	Environment {profile region} environ usable c repo's environ agrees. only.

Coming (Not in Code Yet)

Keys from approved tickets that have not landed. Each moves into the table above when its ticket lands, because it is then in the code; a test fails until it does (test_no_coming_key_is_in_code).

T-0030

Setting	Change	Layer	Default	Values	Summary
coord.ttlMinutes	new key	set when T-0030 lands	30		Lifetime of a cross-session coordination claim (1-10080).

Setting	Change	Layer	Default	Values	Summary
coord.channel	new key	set when T-0030 lands	set when T-0030 lands		Where sessions coordinate.

T-0050

Setting	Change	Layer	Default	Values	Summary
scope.allowCliApproval	changes layer	both, stricter wins	false		Becomes settable in the global file, the stricter layer winning, once its reader (crew_ticket.cli_approval_allowed) reads the global layer in a harness-only follow-up to T-0050.