Computer Systems

Muchang Bahng

Spring 2024

Contents

1	Priı	mitive Types	2
	1.1	Booleans and Characters	3
	1.2	Integer Family	3
		1.2.1 Arithmetic Operations on Binary Numbers	7
	1.3	Float Family	7
2	Mei	mory	7
	2.1	Type Casting	1
	2.2	Pointers	1
	2.3	Arrays and Pointer Arithmetic	
	2.4	Call by Value vs Call by Reference	
	2.5	Global, Stack, and Heap Memory	
	2.6	Dynamic Memory Allocation	
	2.7	Structs	
3	Cen	ntral Processing Unit	_
	3.1	Circuits	_
	3.2	Registers	
	3.3	Addressing Modes	
	3.4	Instructions	5
		3.4.1 Moving Instructions	
		3.4.2 Control Transfer on Stack	8
		3.4.3 Arithmetic Operations	3
		3.4.4 Condition Codes	5
		3.4.5 Conditional Move and Jumps	7
		3.4.6 If Statements	8
		3.4.7 Loops	0
		3.4.8 Functions	0
		3.4.9 Recursion	6
		3.4.10 Arrays	6
		3.4.11 Matrices	7
		3.4.12 Structs	
4	Con	npilers 5'	7

Before we do any coding, we must learn the theory behind how computer systems work, which all starts from memory management and CPU architecture. We will use C with the gcc compiler, along with MIPS and NASM assembler. It is imperative to learn these two since given that you know a high level language pretty well (Python in my case), you want to learn C to appreciate the things Python does for you, and you want to learn Assembly to appreciate the things C does for you.¹.

To start off, we want a big overall picture of high a computer works. We introduce this with the simplest model of the computer, the Von Nuemann architecture. It consists of a **central processing unit** (CPU), **memory**, and an **input/output** (I/O) system. We show a diagram of this first for conciseness in Figure 1.




Figure 1: von Neumann Architecture

We will go through these one by one, touching on C and Assembly along the way, but the implementation of these things can differ by the **computer architecture**, so let's list some of the basic ones.

Definition 0.1 (Computer Architecture)

The **computer architecture** is the design of the computer, which includes the CPU, memory, and I/O system. There are many different architectures, but we will focus on the most common ones.

We first go over some basic theoretical properties of basic data types, focusing on C, and then we cover all the stuff about memory and then all the stuff about the CPU. This is a natural progression since to work with data, you must first know where to store the data and how it is stored (the memory), and then you want to know how data is manipulated (the CPU).

1 Primitive Types

Let's first define some basic terms.

Definition 1.1 (Collections of Bits)

There are many words that are used to talk about values of different data types:

- 1. A **bit** (b) is either 0 or 1.
- 2. A **Hex** (x) is a collection of 4 bits, with a total of $2^4 = 16$ possible values, and this is used since it is easy to read for humans.
- 3. A Byte (B) is a collection of 8 bits or 2 hex, with a total of $2^8 = 256$ possible values, and most computers will work with Bytes as the smallest unit of memory.

¹https://www.youtube.com/watch?v=XlvfHOrF26M

Definition 1.2 (Collections of Bytes)

Sometimes, we want to talk about slightly larger collections, so we group them by how many bytes they have. However, note that these may not always be the stated size, depending on what architecture or language you are using. This is more of a general term, and they may have different names in different languages. If there is a difference, we will state it explicitly.

- 1. A word (w) is 2 Bytes.
- 2. A long (l) is 4 Bytes.
- 3. A quad (q) is 8 Bytes.

Try to know which letter corresponds to which structure, since that will be useful in both C and Assembly.

1.1 Booleans and Characters

Definition 1.3 (Booleans in C)

The most basic type is the boolean, which is simply a bit. In C, it is represented as bool, and it is either true (1) or false (0).

We can manually check the size of the boolean type in C with the following code.

```
1 #include<stdio.h>
2 #include<stdbool.h>
3
4 int main() {
5 printf("%lu\n", sizeof(bool));
6 return 0;
7 }
1 1
2 .
3 .
4 .
5 .
```

Figure 2: We can verify the size of various primitive data types in C with the sizeof operator.

1.2 Integer Family

The most primitive things that we can store are integers. Let us talk about how we represent some of the simplest primitive types in C: unsigned short, unsigned int, unsigned long, unsigned long long.

Definition 1.4 (Unsigned Integer Types in C)

In C, there are several integer types. We use this hierarchical method to give flexibility to the programmer on the size of the integer and whether it is signed or not.

- 1. An **unsigned short** is 2 bytes long and can be represented as a 4-digit hex or 16 bits, with values in [0:65,535]. Therefore, say that we have
- 2. An **unsigned int** is 4 bytes long and can be represented as an 8-digit hex or 32 bits, with values in [0:4,294,967,295].
- 3. An **unsigned long** is 8 bytes and can be represented as an 16-digit hex or 64 bits, but they are only guaranteed to be stored in 32 bits in other systems.
- 4. An **unsigned long long** is 8 bytes and can be represented as an 16-digit hex or 64 bits, and they are guaranteed to be stored in 64 bits in other systems.

Theorem 1.1 (Bit Representation of Unsigned Integers in C)

To encode a signed integer in bits, we simply take the binary expansion of it.




Figure 3: Unsigned encoding of 4-bit integers in C.

Example 1.1 (Bit Representation of Unsigned Integers in C)

We can see for ourselves how these numbers are represented in bits. Printing the values out in binary requires to make new functions, but we can easily convert from hex to binary.

```
8 int main() {
9
10    unsigned short x = 13;
11    unsigned int y = 256;
12
13    printf("%x\n", x);
14    printf("%x\n", y);
15
16    return 0;
17 }
8 d
9 100
10 .
11 .
12 .
12 .
13 .
14 .
15 .
16 .
17 .
```

So far, the process of converting unsigned numbers to bits seemed simple. Now let's introduce signed integers.

Definition 1.5 (Signed Integer Types in C)

In C, there are several signed integer types. We use this hierarchical method to give flexibility to the programmer on the size of the integer and whether it is signed or not.

- 1. A **signed short** is 2 bytes long and can be represented as a 4-digit hex or 16 bits, with values in [-32,768:32,767].
- 2. A **signed int** is 4 bytes long and can be represented as an 8-digit hex or 32 bits, with values in [-2, 147, 483, 648 : 2, 147, 483, 647].
- 3. A **signed long** is 8 bytes and can be represented as an 16-digit hex or 64 bits, but they are only guaranteed to be stored in 32 bits in other systems.
- 4. A **signed long long** is 8 bytes and can be represented as an 16-digit hex or 64 bits, and they are guaranteed to be stored in 64 bits in other systems.

To store signed integers, it is intuitive to simply take the first (left-most) bit and have that be the sign. Therefore, we lose one significant figure but gain information about the sign. However, this has some problems: first, there are two representations of zeros: -0 and +0. Second, the continuity from -1 to 0 is not natural. It is best explained through an example, which doesn't lose much insight into the general case.

Example 1.2 (Problems with the Signed Magnitude)

Say that you want to develop the signed magnitude representation for 4-bit integers in C. Then, you can imagine the following diagram to represent the numbers.




Figure 4: Signed magnitude encoding of 4-bit integers in C.

You can see that there are some problems:

- 1. There are two representations for 0, which is 0000 and 1000.
- 2. -1 (1001) plus 1 becomes -2 (1010).
- 3. The lowest number -7 (1111) plus 1 goes to 0 (0000) when it should go to -6 (1100).
- 4. The highest number 7 (0111) plus 1 goes to 0 (1000).

An alternative way is to use the two's complement representation, which solves both problems and makes it more natural.

Theorem 1.2 (Bit Representation of Signed Integers in C)

The **two's complement** representation is a way to represent signed integers in binary. It is defined as follows. Given that you want to store a decimal number p in n bits,

- 1. If p is positive, then take the binary expansion of that number, which should be at most n-1 bits (no overflow), pad it with 0s on the left.
- 2. If p is negative, then you can do two things: First, take the binary expansion of the positive number, flip all the bits, and add 1. Or second, represent $p = q 2^n$, take the binary representation of q in n 1 bits, and add a 1 to the left.

If you have a binary number $b = b_n b_{n-1} \cdots b_1$ then to convert it to a decimal number, you simply calculate

$$q = -b_n 2^{n-1} + b_{n-1} 2^{n-2} + \dots + b_1 \tag{1}$$




Figure 5: Two's complement encoding of 4-bit integers in ${\bf C}.$

Example 1.3 (Bit Representation of Signed Integers in C)

We can see for ourselves how these numbers are represented in bits.

```
int main() {
                                                   d
                                                19 ffe7
19
                                                   100
     short short_pos = 13;
     short short_neg = -25;
                                                   ffffffe00
     int int_pos = 256;
     int int_neg = -512;
     printf("%x\n", short_pos);
     printf("%x\n", short_neg);
     printf("%x\n", int_pos);
     printf("%x\n", int_neg);
30
     return 0;
   }
```

```
32  #include<stdio.h>
33  #include<stdbool.h>
34  4
35  int main() {
36    printf("%lu\n", sizeof(bool));
37    printf("%lu\n", sizeof(short));
38    printf("%lu\n", sizeof(int));
39    printf("%lu\n", sizeof(long));
40    printf("%lu\n", sizeof(long long));
41    return 0;
42  }
```

Figure 6: Size of various integer types in C with the sizeof.

1.2.1 Arithmetic Operations on Binary Numbers

Theorem 1.3 (Inversion of Binary Numbers)

Given a binary number p, to compute -p, simply invert the bits and add 1.

Theorem 1.4 (Addition and Subtraction of Binary Numbers)

Given two binary numbers p and q.

- 1. To compute p + q, simply add the numbers together as you would in base 10, but carry over when the sum is greater than 1.
- 2. To compute p-q, you can invert q to -q and compute p+(-q).

1.3 Float Family

Definition 1.6 (Floating Point Types in C)

In C, there are several floating point types. We use this hierarchical method to give flexibility to the programmer on the size of the integer and whether it is signed or not.

- 1. A **float** is 4 bytes long and can be represented as an 8-digit hex or 32 bits, with values in $[1.2 \times 10^{-38} : 3.4 \times 10^{38}]$.
- 2. A **double** is 8 bytes long and can be represented as an 16-digit hex or 64 bits, with values in $[2.3 \times 10^{-308} : 1.7 \times 10^{308}]$.
- 3. A **long double** is 8 bytes and can be represented as an 16-digit hex or 64 bits, but they are only guaranteed to be stored in 80 bits in other systems.

Theorem 1.5 (Bit Representation of Floating Point Types in C)

Floats are actually like signed magnitude. We have

$$(-1)^n \times 2^{e-127} \times 1.s$$
 (2)

where

Doubles encode 64 bits, so not we have exponent having 11 bits (so bias is not 1023) and 52 bits for mantissa.

2 Memory

Definition 2.1 (Memory)

The **memory** is where the computer stores data and instructions, which can be though of as a giant array of memory addresses, with each containing a byte. This data consists of graphical things or even instructions to manipulate other data. It can be visualized as a long array of boxes that each have an **address** (where it is located) and **contents** (what is stored in it).

Memory simply works as a bunch of bits in your computer with each bit having some memory address, which is also a bit. For example, the memory address 0b0010 (2) may have the bit value of 0b1 (1) stored in it.

Addresses	Values
060010	1
060011	1
060100	D
060101	I
060110	0
060111	O
061000	0
061001	1
0 9 1 010	ı

Figure 7: Visualization of memory as a long array of boxes of bits.

However, computers do not need this fine grained level of control on the memory, and they really work at the Byte level rather than the bit level. Therefore, we can visualize the memory as a long array of boxes indexed by Bytes, with each value being a byte as well. In short, the memory is **byte-addressable**. In certain arthitectures, some systems are **word-addressable**, meaning that the memory is addressed by words, which are 4 bytes. a

Byte Address	Values	Values	Word Address
0×120	10010010 = 0×92		0x48
0×121	0 0 0 0 0 0 0 0 = 0 × 0 0	0x92006FBO	
0×122	01101111 = 0x6F		
0 x 123	1011 0000 = 0xB0		
0×124	10010110 =0×96		0×49
0 x125	10010111 = 0× 97	Dx 96971199	
0x126	00010001 = 0 >11		
0×127	10011001 = 0x99		
0×128	11111110 = 0xFE	0×FE	0×4A

Figure 8: Visualization of memory as a long array of boxes of bytes. Every address is a byte and its corresponding value at that address is also a byte, though we represent it as a 2-digit hex.

In the examples above, I listed the memory addresses as a 3 hex character (1.5 bytes) for brevity. In reality,

 $[^]a$ Note that in here the size of a word is 2 bytes rather than 4 as stated above. This is just how it is defined in some x86 architectures.

the number of bytes that a memory address takes is much longer.

Definition 2.2 (32 and 64 Bit Machines)

There are two types of machines that tend to format these boxes very differently: 32-bit and 64-bit machines.

- 1. 32 bit machines store addresses in 32 bits, so they can have 2^{32} addresses, which is about 4 GB of memory.
- 2. 64 bit machines store addresses in 64 bits, so they can have 2^{64} addresses, which is about 16 EB of memory. This does not mean that the actual RAM is 16 EB, but it means that the machine can *handle* that much memory.

The numbers typically mean the size of the type that the machine works best with, so all memory addresses will be 32 or 64 bits wide. Most machines are 64-bits, and so everything in this notes will assume that we are working with a 64 bit machine. As we will later see, this is why pointers are 8 bytes long, i.e. 64 bits. This is because the memory addresses are 64 bits long, though all of them are not used.

With this structure in mind and knowing the size of some primitive types, we can now focus on how declaring them works in the backend.

Definition 2.3 (Declaration, Initialization)

Assigning a value to a variable is a two step process, which is often not distinguished in high level languages like Python.

- 1. You must first **initialize** the variable by setting aside the correct number of bytes in memory.
- 2. You must then **assign** that variable to be some actual value.

The two step process is often called declaration.

This is the reason why C is statically, or strongly, typed. In order to set aside some memory for a variable, you must know how big that variable will be, which you know by its type. This makes sense. We can first demonstrate how to both initialize and declare a variable.

Figure 9: How to declare variables in C. As you can see, by initializing y, the memory address is already assigned and it doesn't change when you assign it. The address is only shown to be 9 hex digits long, but it is actually 16 hex digits long and simply 0 padded on the left.

One question that may come to mind is, what is the value of the variable if you just initialize it? After all the value at that address that is initialized must be either 0s or 1s. Let's find out.

```
56 int main() {
57   int y;
58   printf("%d\n", y);
59   y = 3;
60   printf("%d\n", y);
61
62   return 0;
63 }
56 6298576
57  3
58  .
59  .
60  .
61  .
62  .
63  .
```

Figure 10: The value of an uninitialized variable is some random number.


It may be interesting to see how this random unititialized value is generated. It is simply the value that was stored in that memory address before, and it is not cleared when you initialize it, so you should not use this as a unifom random number generator.

It is intuitive to think that given some multi-byte object like an int (4 bytes), the beginning of the int would be the lowest address and the end of the int would be the highest address, like how consecutive integers are stored in an array. However, this is not always the case (almost always not the case since most computers are little-endian).

Definition 2.4 (Endian Architecture)

Depending on the machine architecture, computers may store these types slightly differently in their byte order. Say that we have an integer of value 0xA1B2C3D4 (4 bytes). Then,

- 1. A **big-endian architecture** (e.g. SPARC, z/Architecture) will store it so that the least significant byte has the highest address.
- 2. A little-endian architecture (e.g. x86, x86-64, RISC-V) will store it so that the least significant byte has the lowest address.
- 3. A bi-endian architecture (e.g. ARM, PowerPC) can specify the endianness as big or little.



We can simply print out the hex values of primitive types to see how they are stored in memory, but it does not provide the level of details that we want on which bytes are stored where. At this point, we must use certain **debuggers** to directly look at the memory. For x86 architectures, we can use gdb and for ARM architectures, we can use lldb. At this point, we need to understand assembly to look through debuggers, so we will provide the example here.

Example 2.1 (Endianness of C Int in x86) To do.

2.1 Type Casting

2.2 Pointers

We have learned how to declare/initialize a variable, which frees up some space in the memory and possibly assigns a value to it. One great trait of C is that we can also store the memory address of a variable in another variable called a pointer. You access both the memory and the value at that memory with this pointer variable.

Definition 2.5 (Pointer Variable)

A **pointer** variable/type is a variable that stores the memory address of another variable.

- 1. You can declare a pointer in the same way that you declare a variable, but you must add a asterisk in front of the variable name.
- 2. The size of this variable is the size of the memory address, which is 8 bytes in a 64-bit architecture
- 3. To get the value of the variable that the pointer points to, called **dereferencing**, you simply put a asterisk in front of the pointer. This is similar to how you put a ampersand in front of a variable to get its memory address.

```
int main() {
                                                   x = 4
     // declare an integer
                                                    &x = 0x16d49ae68
                                                   p = 0x16d49ae68
     int x = 4;
     printf("x = %d\n", x);
     printf("&x = p\n, &x);
                                                    q = 0x16d49ae68
     // declare pointer
     int *p = &x;
     printf("p = p \in p, p);
     printf("*p = %d\n", *p);
     // initialize pointer
76
     int *q;
     q = &x;
     printf("q = p\n, q);
     printf("*q = %d\n", *q);
     return 0;
  }
```

Figure 12

Since the size of addresses are predetermined by the architecture, it may not seem like we need to know the underlying data type of what it points to, so why do we need to write strongly type the underlying data type? Remember that to do pointer arithmetic, you need to know how large the underlying data type is so that you can know how many bytes to move when traversing down an array.

Just like for regular variables, you may be curious on the value of an unassigned pointer. Let's take a look.

Example 2.2 (Uninitialized Pointers)

```
83 int main() {
84    int x = 4;
85    int *p;
86    printf("p = %p\n", p);
87    printf("*p = %x\n", *p);
88    return 0;
90 }
82    p = 0x10249ff20
83    *p = d100c3ff
84    .
85    .
85    .
86    .
87    .
88    .
89    return 0;
90 }
```

Figure 13: The value of an uninitialized pointer is some random address and at a random address it would be some random byte.

This is clearly not good, especially since the program compiles correctly and runs without any errors. This kind of pointer that hasn't been initialized is called a wild pointer.

```
Definition 2.6 (Wild Pointer)
```

A wild pointer is a pointer that has not been initialized to a known value.

To fix this, we must always initialize a pointer to a known value. This may come at a disadvantage, since now we can't reap the benefits of initializing first and assigning later. A nice compromise is to initialize the pointer to a null pointer.

Definition 2.7 (Null Pointer)

A **null pointer** is a pointer that has been initialized to a known value, which is the address 0x0. You can set the type of the pointer and then initialize it to NULL.

```
int main() {
    int *p = NULL;
    printf("p = %p\n", p);

// the code below gives seg fault

/* printf("*p = %d\n", *p); */

int x = 4;
    p = &x;

printf("p = %p\n", p);

printf("p = %p\n", p);

printf("p = %p\n", p);

return 0;

// the code below gives seg fault

/* p = 0x16da72e5c

/* p = 4

/* p = 0x16da72e5c

/* p = 4

/* p = 4

/* p = 0x16da72e5c

/* p = 0x16da7e

/* p =
```

Figure 14: Initializing a null pointer. It is a good practice to initialize a pointer to a null value.

Therefore, the null pointer allows you to set the type of the underlying data type, but the actual address will be 0x0. You cannot dereference a null pointer, and doing so will give you a segmentation fault. There may be times when you do not even know the data type of the pointer, and for this you can use the void pointer, which now doesn't know the type of the variable that it points to but it does allocate address.

Definition 2.8 (Void Pointer)

A **void pointer** is a pointer that does not know the type of the variable that it points to. We can initialize it by simply setting the underlying type to be void. This initializes the address, which should always be 8 bytes, but trying to access the value of the variable is not possible.

```
ind int main() {
    void *p;
    printf("p = %p\n", p);
    int x = 4;
    pe &x;
    printf("%d", *((int*)p));
    return 0;
    int }
```

Figure 15: Initialize a void pointer and then use typecasting to access the value of the variable that it points to.

2.3 Arrays and Pointer Arithmetic

With pointers out of the way, we can talk about how arrays are stored in memory.

Definition 2.9 (Array)

A C array is a collection of elements of the same type, which are stored in contiguous memory locations. You can initialize and declare arrays in many ways, and access their elements with the

index, e.g. arr[i].

1. You declare an array of some constant number of elements n with the elements themselves.

```
int arr[5] = {1, 2, 3, 4, 5};
```

2. You declare an array with out its size n and simply assign them. Then n is automatically determined.

```
int arr[] = {1, 2, 3, 4, 5};
```

3. You initialize an array of some constant size c, and then you assign each element of the array.

```
int arr[5];
for (int i = 0; i < 5; i++) {
   arr[i] = i + 1;
}</pre>
```

Unfortunately, C does not provide a built-in way to get the size of the array (like len in Python), so we must keep track of the size of the array ourselves. Furthermore, the address of the array is the address of where it begins at, i.e. the address of the first element.

You can literally see that the elements of the array are contiguous in memory by iterating through each element and printing out its address.

```
int main(void) {
                                                      Value at position 0 : 1
     // initialize array
                                                      Address at position 0 : 0x7ffd8636b0d0
                                                   112
     int arr[5];
                                                  Value at position 1: 4
     for (int val = 1; val < 6; val++) {</pre>
                                                  114 Address at position 1 : 0x7ffd8636b0d4
115
       arr[val-1] = val * val;
                                                  Value at position 2: 9
16
                                                  Address at position 2 : 0x7ffd8636b0d8
17
118
                                                   Value at position 3 : 16
     int* p = &arr[0];
                                                  Address at position 3 : 0x7ffd8636b0dc
19
     for (int i = 0; i < 5; i++) {</pre>
                                                   19 Value at position 4: 25
                                                   Address at position 4 : 0x7ffd8636b0e0
       printf("Value at position %d : %d\n", i,
21
        arr[i]);
       printf("Address at position %d : %p\n",
        i, p + i);
     return 0;
125
   }
```

Figure 16: Ints are 4 bytes long, so the address of the next element is 4 bytes away from the previous element, making this a contiguous array.

The most familiar implementation of an array is a string in C.

Definition 2.10 (String)

A string is an array of characters, which is terminated by a null character $\setminus 0$. You can initialize them in two ways:

1. You can declare a string with the characters themselves, which you must make sure to end with the null character.

```
char str[6] = {'H', 'e', 'l', 'l', 'o', '\0'};
```

2. You can declare them with double quotes, which automatically adds the null character.

```
1 char str[] = "Hello";
```

Note that for whatever string we initialize, the size of the array is the number of characters plus 1.

To access elements of an array, you simply use the index of the element, e.g. arr[i], but in the backend, this is implemented with *pointer arithmetic*.

Definition 2.11 (Pointer Arithmetic)

Pointer arithmetic is the arithmetic of pointers, which is done by adding or subtracting an integer to a pointer.

- 1. If you add an integer n to a pointer p, e.g. p + n, then the new pointer will point to the nth element after the current element, with the next element being sizeof(type) bytes away from the pervious element.
- 2. If you subtract an integer n from a pointer, then the pointer will point to the nth element before the current element.

This is why you can access the elements of an array with the index, since the index is simply the number of elements away from the first element.

Example 2.3 (Pointer Arithmetic with Arrays of Ints and Chars)

Ints have a size of 4 bytes and chars 1 byte. You can see that using pointer arithmetic, the addresses of the elements of ints increment by 4 and those of the char array increment by 1.

```
int main() {
                                                     Array of Integers
     int integers[3] = {1, 2, 3};
                                                     0x16d39ee58
     char characters[3] = {'a', 'b', 'c'};
                                                     0x16d39ee5c
                                                 130
     int *p = &integers[0];
                                                     0x16d39ee60
30
                                                 131
     char *q = &characters[0];
31
                                                 132
                                                 133 Array of Characters
32
     printf("Array of Integers\n");
                                                 134 0x16d39ee50
33
     for (int i = 0; i < 3; i++) {</pre>
                                                 135 0x16d39ee51
34
       printf("%p\n", integers+i); }
                                                 136 0x16d39ee52
     printf("Array of Characters\n");
     for (int i = 0; i < 3; i++) {</pre>
        printf("%p\n", characters+i); }
39
     return 0;
                                                 141
40
   }
                                                  42
```

Therefore, we can think of accessing the elements of an array as simply pointer arithmetic.

Theorem 2.1 (Bracket Notation is Pointer Arithmetic)

The bracket notation is simply pointer arithmetic in the backend.

```
int main() {
    int arr[3] = {1, 2, 3};
    int *p = &arr[0];

i
```

Figure 17: Accessing the elements of the list using both ways is indeed the same.

2.4 Call by Value vs Call by Reference

When you call by reference, you are essentially modifying the value at a memory address, so it persists.

2.5 Global, Stack, and Heap Memory

Everything in a program is stored in memory, variables, functions, and even the code itself. However, we will find out that they are stored in different parts of the memory. When a program runs, its application memory consists of four parts, as visualized in the Figure 18.

- 1. The **code** is where the code text is stored.
- 2. The **global memory** is where all the global variables are stored.
- 3. The **stack** is where all of the functions and local variables are stored.
- 4. The **heap** is variable and can expand to as much as the RAM on the current system. We can specifically store whatever variables we want in the heap.

We provide a visual of these four parts first, and we will go into them later.




Figure 18: The four parts of memory in a C program.

Definition 2.12 (Code Memory)

This is where the code text is stored. It is read-only and is not modifiable.

In high level languages, we always talk about local and global scope. That is, variables defined within functions have a local scope in the sense that anything we modify in the local scope does not affect the global scope. We can now understand what this actually means by examining the backend. The global scope variables are stored in the global memory, and all local variables (and functions) are stored in the stack.

Definition 2.13 (Global Memory)

This is where all the global variables are stored.

Definition 2.14 (Stack Memory)

This is where all of the functions and local variables are stored. As we will see later, the compiler will always run the main function, which must exist in your file. By the main function is a function itself, and therefore it has its own local scope.

Then, when you initialize any functions or local variables within those functions (which will be the majority of your code), all these will be stored in the stack, which is an literally an implementation of the stack data structure. It is LIFO, and the first thing that goes in is the main function and its local variables, which is referred to as the **stack frame**. You can't free memory in the stack unless its in the top of the stack.

To see what happens in the stack, we can go through an example.

Example 2.4 (Going through the Stack)

Say that you have the following code:

```
int total;
int Square(int x) {
    return x*x;
}
int SquareOfSum(int x, int y) {
    int z = Square(x + y);
    return z;
}
int main() {
    int a = 4, b = 8;
    total = SquareOfSum(a, b);
    printf("output = %d", total);
    return 0;
}
```

The memory allocation of this program will run as such:

- 1. The total variable is initialized and is put into global memory.
- 2. main is called. It is put into the stack.
- 3. The local variables a=4 and b=8 are initialized and are put into the stack.
- 4. The SquareOfSum function is called and put into the stack.
- 5. The input local variables x=4, y=8, z are initialized and put into the stack.
- 6. x + y=12 is computed and put into the stack.
- 7. The Square function is called and put into the stack.
- 8. The x=12 local variable of Square is initialized and put into the stack.
- 9. The CPU computes x*x=144 and returns the output. The Square function is removed from the stack.
- 10. We assign z=144 and SquareOfSum returns it. Now SquareOfSum is removed from the stack.
- 11. total=144 is assigned in the global memory still.

- 12. The printf function is called and put into the stack.
- 13. The printf function prints the output and is removed from the stack.
- 14. The main function returns 0 and is removed from the stack, ending our application.

One limitation of the stack is that its total available memory is fixed from the start, ranging from 1MB to 8MB, and so you can't initialize arrays of billions of integers in the stack. It will cause a memory overflow. In fact, the memory of the stack, along with the global and text memory, are assigned at compile time, making it a **static memory**.

Since the stack is really just a very small portion of available memory, the heap comes into rescue, which is the pool of memory available to you in RAM.

Definition 2.15 (Heap Memory)

The **heap memory** (nothing to do with the heap data structure) is a variable length (meaning it can grow at runtime) and **dynamically allocated** (meaning that we can assign memory addresses during runtime) memory that is limited to your computer's hardware. Unlike simply initializing variables to allocate memory as in the stack, we must use the **malloc** and **free** functions in C, and **new** and **delete** operations in C++.

Definition 2.16 (malloc)

Definition 2.17 (free)

The stack can store pointer variables that point to the memory address in the heap. So the only way to access variables in the heap is through pointer reference, and the stack provides you that window to access that big pool of heap memory.

One warning: if you allocate another address, the previous address does not get deallocated off the memory.

Definition 2.18 (Memory Leak)

On the other hand, if you free an address but have a pointer still pointing to that address, this is also a problem called the dangling pointer.

Definition 2.19 (Dangling Pointer)

At this point, we might be wondering why we need both a stack and a heap. Well the benefits of heaps are clearer since you can dynamically allocate memory, and you don't have the LIFO paradigm that is blocking you from deallocating memory that has been allocated in the beginning of your program. A problem with just having heap is that stacks can be orders of magnitude times faster when allocating/deallocating from it than the heap, and the sequence of function calls is naturally represented as a stack.

2.6 Dynamic Memory Allocation

Let's talk about how malloc and free are implemented in C. If you make a for loop and simply print all the addresses that you allocate to. You will find that they can be quite random. After a program makes some calls to malloc and free, the heap memory can becomes fragmented, meaning that there are chunks of free heap space interspersed with chunks of allocated heap space. The heap memory manager typically

keeps lists of different ranges of sizes of heap space to enable fast searching for a free extent of a particular size. In addition, it implements one or more policies for choosing among multiple free extents that could be used to satisfy a request.

The free function may seem odd in that it only expects to receive the address of the heap space to free without needing the size of the heap space to free at that address. That's because malloc not only allocates the requested memory bytes, but it also allocates a few additional bytes right before the allocated chunk to store a header structure. The header stores metadata about the allocated chunk of heap space, such as the size. As a result, a call to free only needs to pass the address of heap memory to free. The implementation of free can get the size of the memory to free from the header information that is in memory right before the address passed to free.

2.7 Structs

3 Central Processing Unit

Now let's talk about how functions work on a deeper level. When we write a command, like int x = 4, we are manually looking for an address (in the stack, global, or heap) and rewriting the bits that are at that address. Functions are just an automated way to do this, and all these modifications and computations are done by the CPU.

Definition 3.1 (Central Processing Unit)

The CPU is responsible for taking instructions (data) from memory and executing them.

- 1. The CPU is composed of **registers** (different from the cache), which are small, fast storage locations. These registers can either be **general purpose** (can be used with most instructions) or **special purpose** (can be accessed through special instructions, or have special meanings/uses, or are simply faster when used in a specific way).
- 2. The CPU also has an **arithmetic unit** and **logic unit**, which is responsible for performing arithmetic and logical operations.
- 3. The CPU also has a **control unit**, which is responsible for fetching instructions from memory through the **databus**, which is literally a wire connecting the CPU and RAM, and executing them.

It executes instructions from memory one at a time and executes them, known as the **fetch-execute cycle**. It consists of 4 main operations.

- 1. **Fetch**: The **program counter**, which holds the memory address of the next instruction to be executed, tells the control unit to fetch the instruction from memory through the databus.
- 2. **Decode**: The fetched data is passed to the **instruction decoder**, which figures out what the instruction is and what it does and stores them in the registers.
- 3. **Execute**: The arithmetic and logic unit then carries out these operations.
- 4. **Store**: Then it puts the results back on the databus, and stores them back into memory.

The CPU's **clock cycle** is the time it takes for the CPU to execute one instruction. More specifically, the clock cycle refers to a single oscillation of the clock signal that synchronizes the operations of the processor and the memory (e.g. fetch, decode, execute, store), and decent computers have clock cycles of at least 2.60GHz (2.6 billion clock cycles per second).

Therefore, in order to actually do computations on the data stored in the memory, the CPU must first fetch the data, perform the computations, and then store the results back into memory. This can be done in two ways.

- 1. Load and Store Operations: CPUs use load instructions to move data from memory to registers (where operations can be performed more quickly) and store instructions to move the modified data back into memory.
- 2. If the data is too big to fit into the registers, the CPU will use the cache to store the data, and in

worse cases, the actual memory itself. Compilers optimize code by maximizing the use of registers for operations to minimize slow memory access. This is why you often see assembly code doing a lot in registers.

To clarify, let us compare registers and memory. Memory is addressed by an unsigned integer while registers have names like **%rsi**. Memory is much bigger at several GB, while the total register space is much smaller at around 128 bytes (may differ depending on the architecture). The memory is much slower than registers, which is usually on a sub-nanosecond timescale. The memory is dynamic and can grow as needed while the registers are static and cannot grow.

The specific structure/architecture of the CPU is determined by the instruction set architecture (ISA), which can be thought of as a subset of the general computer architecture.

Definition 3.2 (Instruction Set Architecture)

The **ISA** or just **architecture** of a CPU is a high level description of what it can do. Some differences are listed here:

- 1. What instructions it can execute.
- 2. The instruction length and decoding, along with its complexity.
- 3. The performance vs power efficiency.

ISAs can be classified into two types.

- 1. The **complex instruction set computer** (CISC) is characterized by a large set of complex instructions, which can execute a variety of low-level operations. This approach aims to reduce the number of instructions per program, attempting to achieve higher efficiency by performing more operations with fewer instructions.
- 2. The **reduced instruction set computer** (RISC) emphasizes simplicity and efficiency with a smaller number of instructions that are generally simpler and more uniform in size and format. This approach facilitates faster instruction execution and easier pipelining, with the philosophy that simpler instructions can provide greater performance when optimized.

Just like how memory addressing is different between 32 and 64 bit machines, CPUs also use these schemes. While 32-bit processors have 2^{32} possible addresses in their cache, it turns out that 64-bit processors have a 48-address space. This is because CPU manufacturers took a shortcut. They use an instruction set which allows a full 64-bit address space, but current CPUs just only use the last 48-bits. The alternative was wasting transistors on handling a bigger address space which wasn't going to be needed for many years (since 48-bits is about 256TB). Just a bit of history for you. Finally, just to briefly mention, the input/output device, as the name suggests, processes inputs and displays outputs, which is how you can see what the program does.

Example 3.1 (x86 Architecture)

The x86 architecture is a CISC architecture, which is the most common architecture for personal computers. Here are important properties:

- 1. It is a complex instruction set computer (CISC) architecture, which means that it has a large set of complex instructions^a.
- 2. Byte-addressing is enabled and words are stored in little-endian format.
- 3. In the x86_64 architecture, registers are 8 bytes long (and 4 bytes in x86_32) and there are 16 total general purpose registers, for a total of only 128 bytes (very small compared to many GB of memory). Other special purpose registers are also documented in the wikipedia page, but it is not fully documented.

Example 3.2 (ARM Archiecture)

Mainly in phones, tablets, laptops.

^ahttps://en.wikipedia.org/wiki/X86 instruction listings

Example 3.3 (MIPS Architecture)

MIPS is a RISC architecture, which is used in embedded systems such as digital home and networking equipment.

Definition 3.3 (Input/Output Device)

The input device can read/load/write/store data from the outside world. The output device, which has **direct memory address**, can display data to the outside world.

One final note to mention, there are many assembly languages out there and various syntaxes.

Example 3.4 (Assembly Syntax)

The two most popular syntaxes are AT&T and Intel.

- 1. **Intel Syntax**: Specifies memory operands without any special prefixes. Square brackets [] are used to denote memory addresses. For example, mov eax, [ebx] means move the contents of the memory location pointed to by ebx into eax.
- 2. AT&T Syntax: Memory operands are denoted with parentheses () and include the % prefix for registers. An instruction moving data from a memory location into a register might look like movl (%ebx), %eax, with additional prefixes for immediate values and segment overrides.

Example 3.5 (Assembly Languages)

The various assembly languages are as follows:

- 1. **x86 Assembly**: The assembly language for Intel and AMD processors using the x86 architecture. Both AT&T and Intel syntax are available. Tools or environments often allow switching between the two, with AT&T being the default in GNU tools like GDB.
- 2. **ARM Assembly**: The assembly language for ARM processors. Has its own unique syntax, not categorized as AT&T or Intel. ARM syntax is closely tied to its instruction set architecture and is distinct from the x86 conventions.
- 3. MIPS Assembly: The assembly language for MIPS processors. MIPS uses its own assembly language syntax, which is neither AT&T nor Intel. MIPS syntax is designed around the MIPS instruction set architecture.
- 4. **PowerPC Assembly**: The assembly language for PowerPC processors. PowerPC has its own syntax style, tailored to its architecture and instruction set, distinct from the AT&T and Intel syntax models.
- 5. **6502** Assembly: Used in many early microcomputers and gaming consoles. Utilizes a syntax unique to the 6502 processor, not following AT&T or Intel conventions.
- 6. **AVR Assembly**: The assembly language for Atmel's AVR microcontrollers. AVR assembly follows its own syntax style, designed specifically for AVR microcontrollers and not based on AT&T or Intel syntax.
- 7. **Z80** Assembly: Associated with the Z80 microprocessor, used in numerous computing devices in the late 20th century. Z80 assembly language has its own syntax that does not adhere to AT&T or Intel syntax guidelines.

The most common one is the x86 64, which is the one that we will be focusing on, with the AT%T syntax.

3.1 Circuits

Let's go over some common logic gates.

Definition 3.4 (AND, NOT, OR)

Definition 3.5 (XOR, NAND, NOR)

Definition 3.6 (NAND)

3.2 Registers

To understand anything that the CPU does, we must understand assembly language. In here, everything is done within registers, and we can see how the CPU fetches, decodes, and executes instructions. So what exactly are these registers?

Definition 3.7 (Register)

A register is a small, fast storage location within the CPU. It is used to store data that is being used immediately, and is the only place where the CPU can perform operations, which is why it must move data from memory to registers before it can perform operations on it. Everything in a register is in binary, at most 8 bytes, or 64 bits.

The specific type of registers that are available to a CPU depends on the computer architecture, or more specifically, the ISA, but here is a list of common ones for the x86-64. We have %rax, %rbx, %rcx, %rdx, %rsi, %rdi, %rbp, %rsp, %r8, %r9, %r10, %r11, %r12, %r13, %r14, %r15. Therefore, the x86-64 Intel CPU has a total of 16 registers for storing 64 bit data. However, it is important to know which registers are used for what.

Definition 3.8 (Parameter Registers)

Compilers typically store the first six parameters of a function in registers

respectively.

Definition 3.9 (Return Register)

The return value of a function is stored in the

register.

Definition 3.10 (Stack and Frame Pointers)

The %rsp register is the stack pointer, which points to the top of the stack. The %rbp register is the frame pointer, or base pointer, which points to the base of the current stack frame. In a typical function prologue, %rbp is set to the current stack pointer (%rsp) value, and then %rsp is adjusted to allocate space for the local variables of the function. This establishes a fixed point of reference (%rbp) for accessing those variables and parameters, even as the stack pointer (%rbp) moves.

Definition 3.11 (Instruction Pointer)

The %rip register is the instruction pointer, which points to the next instruction to be executed. Unlike all the registers that we have shown so far, programs cannot write directly to %rip.

Definition 3.12 (Notation for Accessing Lower Bytes of Registers)

Sometimes, we need a more fine grained control of these registers, and x86-64 provides a way to access the lower bits of the 64 bit registers. We can visualize them with the diagram below.




Figure 19: The names that refer to subsets of register %rax.

A complete list is shown below.

64-bit Register	32-bit Register	Lower 16 Bits	Lower 8 Bits
%rax	%eax	%ax	%al
%rbx	%ebx	%bx	%bl
%rcx	%ecx	%cx	%cl
%rdx	%edx	%dx	%dl
%rdi	%edi	%di	%dil
%rsi	%esi	%si	%sil
%rsp	%esp	%sp	%spl
%rbp	%ebp	%bp	%bpl
%r8	%r8d	%r8w	%r8b
%r9	%r9d	%r9w	%r9b
%r10	%r10d	%r10w	%r10b
%r11	%r11d	%r11w	%r11b
%r12	%r12d	%r12w	%r12b
%r13	%r13d	%r13w	%r13b
%r14	%r14d	%r14w	%r14b
%r15	%r15d	%r15w	%r15b

Table 1: Register mapping in x86-64 architecture

3.3 Addressing Modes

Registers being 8 bytes mean that we can store memory addresses, and if we can store memory addresses, we can access memory, i.e. the values at those memory addresses. There are 4 ways to do this, called **addressing modes**: immediate, normal, displacement, and indexed. When we parse an instruction, its operands are either

1. Constant (literal) values

- 2. Registers
- 3. Memory forms

Definition 3.13 (Immediate Addressing)

Immediate addressing is when the operand is a constant value, used with a \$ sign.

Example 3.6 (Immediate Addressing)

movq \$0x4, %rax

Definition 3.14 (Normal Addressing)

Normal addressing is when the operand is a register, used with a % sign and the following syntax. The parentheses are used to dereference the memory address like dereferencing a pointer in C.

$$(R) = Mem[Reg[R]]$$
 (6)

where R is the register name, Reg[R] is the value in the register, and Mem[Reg[R]] is the value in the memory address pointed to by the register.

Example 3.7 (Normal Addressing)

The following example shows the source operand being a memory address, with normal addressing, and the destination operand being a register.

movq (%rax), %rbx

Definition 3.15 (Displacement Addressing)

When we have a memory address stored in a register, we can add an offset to it to access a different memory address.

$$D(R) = Mem[Reg[R] + D]$$
 (7)

where R is the register name and D is a constant displacement that specifies offset.

Example 3.8 (Displacement Addressing)

The following example shows the source operand being a memory address and the destination operand being a register. They are both addressed normally.

movq 8(%rdi), %rdx

Definition 3.16 (Indexed Addressing)

Indexed addressing gives us more flexibility, allowing us to multiply the value in the register by a constant and add it to the value in another register. The general formula is shown as the top, but there are special cases:

where D is a constant displacement of 1, 2, or 4 bytes, Rb is the base register (can be any of 8 integer registers), Ri is the index register (can be any register except rsp), and S is the scale factor (1, 2, 4, or 8).

Example 3.9 (Indexed Addressing)

The following shows the source operand being a memory address and the destination operand being a register. Say that %rdx = 0xf000 and %rcx = 0x0100. Then

$$0x80(,%rdx,2) = Mem[2*0xF000 + 0x80] = Mem[0x1E080]$$
 (8)

We see that

```
movq 0x100(%rdi, %rsi, 8), %rdx
```

3.4 Instructions

Now that we've gotten a sense of what these registers are and some commonalities between them, let's do some operations on them with instructions.

Definition 3.17 (Instruction)

An instruction is a single line of assembly code. It consists of some instruction followed by its (one or more) operands. The instruction is a mnemonic for a machine language operation (e.g. mov, add, sub, jmp, etc.). The size specifier can be appended to this instruction mnemonic to specify the size of the operands.

- 1. **b** (byte) for 1 byte
- 2. w (word) for 2 bytes
- 3. I (long) for 4 bytes
- 4. **q** (quad word) for 8 bytes

Note that due to backwards compatibility, word means 2 bytes in instruction names. Furthermore, the maximum size is 8 bytes since that is the size of each register in x86_64. An operand can be of 3 types, determined by their **mode of access**:

- 1. Immediate addressing is denoted with a \$ sign, e.g. a constant integer data \$1.
- 2. Register addressing is denoted with a % sign with the following register name, e.g. %rax.
- 3. Memory addressing is denoted with the hexadecimal address in memory, e.g. 0x034AB.

Like higher level programming languages, we can perform operations, do comparisons, and jump to different parts of the code. Instructions can be generally categorized into three types:

1. **Data Movement**: These instructions move data between memory and registers or between the registery and registery. Memory to memory transfer cannot be done with a single instruction.

```
1 %reg = Mem[address] # load data from memory into register
2 Mem[address] = %reg # store register data into memory
```

2. Arithmetic Operation: Perform arithmetic operation on register or memory data.

```
""" # add memory data to register
""" # subtract memory data from register
""" # subtract memory data from register
""" # subtract memory data from register
""" # multiply memory data to register
""" # divide memory data from register
```

3. **Control Flow**: What instruction to execute next both unconditional and conditional (if statements) ones. With if statements, loops can then be defined.

```
jmp label  # jump to label
je label  # jump to label if equal
jne label  # jump to label if not equal
jg label  # jump to label if greater
jl label  # jump to label if less
call label  # call a function
ret  # return from a function
```

Now unlike compiled languages, which are translated into machine code by a compiler, assembly code is translated into machine code through a two-step process. First, we **assemble** the assembly code into an **object file** by an **assembler**, and then we **link** the object file into an executable by a **linker**. Some common assemblers are **NASM** (Netwide Assembler) and **GAS/AS** (GNU Assembler), and common linkers are **ld** (GNU Linker) and **lld** (LLVM Linker), both installable with **sudo pacman -S nasm ld**.

3.4.1 Moving Instructions

Definition 3.18 (mov)

Let's talk about the mov instruction which copies data from the source to the destination (the data in the source still remains!) and has the syntax

$$mov_src, dest$$
 (9)

- 1. The source can be a register (%rsi), a value (\$0x4), or a memory address (0x4).
- 2. The destination can be a register or a memory address.
- 3. The _ is defined to be one of the size operands, which determine how big the data is. For example, we can call movq to move 8 bytes of data (which turns about to be the maximum size of a register).

A good diagram to see is the following:

Imm	Source	Dest	Src, Dest	C Analog
		-		
Mem Reg movq (%rax), %rdx var_d = *p_a;				var_d = var_a; *p_d = var_a;
	Mem	Reg	movq (%rax), %rdx	var_d = *p_a;

Even with just the mov instruction, we can look at a practical implementation of a C program in Assembly.

Example 3.10 (Swap Function)

Let us take a look at a function that swaps two integers. Let's see what they do.

- 1. In C, we dereference both xp and yp (note that they are pointers to longs, so they store 8 bytes), and assign these two values to two temporary variables. Then, we assign the value of yp to xp and the value of xp to yp.
- 2. In Assembly, we first take the registers %rdi and %rsi, which are the 1st and 2nd arguments of the function, dereference them with the parantheses, and store them in the temporary registers %rax and %rdx. Then, we store the value of %rdx into the memory address of %rdi and the value of %rax into the memory address of %rsi. Note that the input values (the actual of)

Definition 3.19 (movz and movs)

The movz and movs instructions are used to move data from the source to the destination, but with zero and sign extension, respectively. It is used to copy from a smaller source value to a larger destination, with the syntax

```
movz__ src, dest
movs__ src, dest
```

where the first _ is the size of the source and the second _ is the size of the destination.

- 1. The source can be from a memory or register.
- 2. The destination must be a register.

Example 3.11 (Simple example with movz)

Take a look at the code below.

```
n movzbq %al, %rbx
```

The %al represents the last byte of the %rax register. It is 1 byte long. The %rbx register is 8 bytes long, so we can fill in the rest of the 7 bytes with zeros.

```
0x??|0x??|0x??|0x??|0x??|0x??|0x?F| ←%rax

0x00|0x00|0x00|0x00|0x00|0x00|0xFF ←%rbx
```

Example 3.12 (Harder example with movs)

Take a look at the code below.

```
1 movsbl (%rax), %ebx
```

You want to move the value at the memory address in %rax into %ebx. Since the source size is set to 1 byte, you take that byte, say it is 0x80, from the memory, and then sign extend it (by a size of 4 bytes!) into %ebx. Note that therefore, the first four bytes of %rbx will not be affected since it's not a part of %ebx. An exception to this is that in x86-64, any instruction that generates a 32-bit long word value for a register also sets the high-order 32 bits of the register to 0, so this ends up clearing the first 4 bytes to 0.

```
0x00 0x00 0x7F 0xFF 0xC6 0x1F 0xA4 0xE8 ←%rax

... 0x?? 0x?? 0x80 0x?? 0x?? 0x?? ... ← MEM

0x00 0x00 0x00 0x00 0xFF 0xFF 0xFF 0x80 ←%rbx
```

3.4.2 Control Transfer on Stack

Say that you have the following C and Assembly code.

```
int add(int x) {
                                                         add:
     return x + 2;
                                                           movq %rdi, %rax
   }
                                                           addq $2, %rax
60
                                                           ret
   int main() {
                                                         main:
     int a = 2;
                                                           movq $3, $rdi
     int b = add(a);
                                                           call add
     return 0;
                                                           movq $0, %rax
```

Figure 20: A simple function.

If you go through the instructions, you see that in main, you first move \$3 into the %rdi register. Then, you call the add function, and within it you also have the %rdi register. This is a conflict in the register, and we don't want to simply overwrite the value of %rdi in the main function. Simply putting it to another register isn't a great idea since we can't always guarantee that it will be free. Therefore, we must use the memory itself.

Recall the stack, which we can think of as a giant array in which data gets pushed and popped in a last-in-first-out manner. The stack is used to store data and return addresses, and is used to manage function calls. Visually, we want to think of the elements getting pushed in from the bottom (upside down) towards lower memory addresses.

Definition 3.20 (Stack Pointer)

Note that every time we want to push or pop something from the stack, we must know *where* to push or pop it. This is where the **stack pointer** comes in. It is a special register that always points to the top of the stack, and is used to keep track of the stack.

Definition 3.21 (Push and Pop)

The push and pop instructions are used to push and pop data onto and off the stack, respectively.

- 1. When we push the source, we fetch the value at the source and store it at the memory address pointed to by the stack pointer **%rsp**. Then, we decrement **%rsp** by 8.
- 2. When we pop from the stack, we fetch the value at the memory address pointed to by the stack pointer **%rsp** and store it in the destination. Then, we increment **%rsp** by 8.

Note that no matter what the size of the operand, we always subtract 8 from the stack pointer. This is because the stack grows downwards, and we want to make sure that the next element is pushed into the next available space.

Note that the register **%rsp** is the stack pointer, which points to the top of the stack. The stack is used to store data and return addresses, and is used to manage function calls.

Definition 3.22 (Push and Pop)

The push and pop instructions are used to push and pop data onto and off the stack, respectively.

The is a size operand, which determines how big the data is.

Definition 3.23 (Call and Ret)

The call instruction pushes the return address onto the stack and jumps to the function. The ret instruction pops the return address from the stack and jumps to it.

We also talked about how there is instruction code that is even below the stack that is stored. This is where all the machine code/assembly is stored, and we want to find out where we are currently at in this code. This is done with the program counter.

Definition 3.24 (Program Counter, Instruction Pointer)

The **program counter**, or **instruction pointer**, is a special register **rip** that points to the current instruction in the program. It is used to keep track of the next instruction to be executed.

Let's go through one long example to see in detail how this is calculated.

Example 3.13 (Evaluating a Function)

Say that we have the following C code.

```
int adder2(int a) {
   return a + 2;
}

int main() {
   int x = 40;
   x = adder2(x);
   printf("x is: %d\n", x);
   return 0;
}
```


When we compile this program, we can view its full assembly code by calling objdump -d a.out. The output is quite long, so we will focus on the instruction for the adder2 function.

```
0000000000400526 <adder2>:
400526:
               55
                                                %rbp
                                         push
400527:
               48 89 e5
                                         mov
                                                %rsp,%rbp
40052a:
               89 7d fc
                                         mov
                                                %edi,-0x4(%rbp)
40052d:
               8b 45 fc
                                                -0x4(%rbp), %eax
                                        mov
400530:
               83 c0 02
                                                $0x2, %eax
                                         add
400533:
               5d
                                                %rbp
                                         pop
400534:
               сЗ
                                         retq
```

Figure 21: The output of objdump for the adder2 function. The leftmost column represents the addresses (in hex) of where the actual instructions lie. The second column represents the machine code that is being executed. The third column represents the assembly code.

Note some things. Since adder2 is taking in an integer input value, we want to load it into the lower 32 bits (4 bytes) of the %rdi register, which is the first parameter. So we use %edi. Likewise for the return value, we want to output an int so we use %eax rather than %rax. Let's go through some of the steps.


1. By the time we get into calling adder2, we can take a look at the relevant registers.




- (a) First, the **%eax** is filled with garbage, which are leftovers from previous programs that haven't been overwritten yet.
- (b) Second, the %edi=0x28 since we have set x=40 in main, before calling adder2, so it lingers on.
- (c) %rsp=0xd28 since that is where the top of the stack is.
- (d) %rbp=0xd40
- (e) %rip=0x526 since that is where we are currently at in our instruction (we are about to do

it, but haven't done it yet).


2. When we execute the first line of code, we simply push the value at %rbp into the stack. The top of the stack gets decremented by 8 and the value at %rbp is stored there. This means that the top of the stack is at %rsp=0xd20 and the next instruction will be at %rip=0x527.




3. The reason we have pushed %rbp onto the stack is that we want to save it before it gets overwritten by this next execution. We basically move the value of %rsp into %rbp, and the %rip advances to the next instruction. %rip moves to the next instruction.




4. Now we want to take our first argument %edi and store it in memory. Note that since this is 4 bytes, we can move this value into memory that is 4 bytes below the stack (-0x4(%rbp)). Note that the storing the value of %edi into memory doesn't affect the stack pointer %rsp. As far as the program is concerned, the top of this stack is still address 0xd20.




5. The next instruction simply goes into memory 4 bytes below the stack pointer, takes the value there, and stores it into %eax. This is the value of %edi that we just stored. This may seem redundant since we are making a round trip to memory and back to ultimately move the value of %edi into %eax, but compilers are not smart and just follow these instructions.



6. Finally, we add the value \$0x2 to %eax and store it back into %eax.



7. Finally, we pop the value at the top of the stack and store it into %rbp. Note that this is not the value 0x28. It is simply the value that is stored at %rsp=0xd20, which is (%rsp)=0xd40.



Note that the final values in the registers %rsp and %rip are 0xd28 and 0x534, respectively, which are the same values as when the function started executing! This is normal and expected behavior with the call stack, which just stores temporary variable sand data of each function as it executes a program. Once a function completes executing, the stack returns to the state it was in prior to the function call. Therefore, it is common to see the following two instructions at the beginning of a function:

```
push %rbp
mov %rsp, %rbp
```

and the following two at the end of a function

```
pop %rbp retq
```

3.4.3 Arithmetic Operations

Definition 3.25 (Add, Subtract, Multiply)

The add and sub instructions are used to add and subtract data from the destination.

```
add_ src, dest dest = dest + src
sub_ src, dest dest = dest - src
```

The **imul** instruction is used to multiply data between the source and destination and store it in the destination.

Again the _ is a size operand, which determines how big the data is.

Definition 3.26 (Increment, Decrement)

The inc and dec instructions are used to increment and decrement the value in the destination.

inc_ dest
$$dest = dest + 1$$

 $dec_ dest = dest - 1$

Definition 3.27 (Negative)

The **neg** instruction is used to negate the value in the destination.

```
neg_ dest = -dest
```

Example 3.14 (Basic Arithmetic Function)

The following represents the same program in C and in assembly. Let's go through each one:

- 1. In C, we first initialize a = 4, then b = 8, add them together to get c, and then return c.
- 2. In Assembly, we move the value 4 to the **%rax** register, then move the value 8 to the **%rbx** register, add the two values together to store it into **%rax**, and then return the value in the **%rax** register.

```
int main() {

int a = 4, b = 8;

int c = a + b;

return c;

int a = 4, b = 8;

return c;

return c;
```

It is slightly different in Assembly since rather than storing 4 in some intermediate register, we immediately store it in the return register. In a way it is more optimized, and this is what the compiler does for you so that as few registers are used.

A shorthand way to do this is with lea, which stands for load effective address.

Definition 3.28 (Load Effective Address)

The **lea** instruction is used to load the effective address of the source into the destination. For now, we will focus on the arithmetic operations that it can do

This is useful for doing arithmetic operations on the address of a variable.

Definition 3.29 (Bitwise)

The **and**, **or**, **xor**, and **not** instructions are used to perform bitwise operations on the source and destination.

```
and src, dest dest = dest & src or src, dest dest = dest | src xor src, dest dest = dest \hat{s}rc neg dest dest = -dest not dest dest = \simdest
```

Definition 3.30 (Arithmetic and Logical Bit Shift)

The sal arithmetic instruction is used to shift the bits of the destination to the left by the number of bits specified in the source. The shr instruction is used to shift the bits of the destination to the right by the number of bits specified in the source.

The sar instruction is used to shift the bits of the destination to the right by the number of bits specified in the source, and fill the leftmost bits with the sign bit. The shl instruction is used to shift the bits of the destination to the left by the number of bits specified in the source, and fill the rightmost bits with zeros.

Example 3.15 (Harder Arithmetic Example)

The following two codes are equivalent.

```
long arith(long x, long y, long z) {
                                                    arith:
                                                      \# rax/t1 = x + y
     long t1 = x + y;
     long t2 = z + t1;
                                                      leaq (%rdi, %rsi), %rax
74
     long t3 = x + 4;
                                                      \# rax/t2 = z + t1
     long t4 = y * 48;
                                                      addq %rdx, %rax
     long t5 = t3 + t4;
                                                      \#rdx = 3 * y
                                                      leaq (%rsi, %rsi, 2), %rdx
     long rval = t2 * t5;
     return rval;
                                                      \#rdx/t4 = (3*y) * 16
   }
                                                      salq $4, %rdx
                                                      \#rcx/t5 = x + t4 + 4
                                                      leag 4(%rdi, %rdi), %rcx
                                                      \# rax/rval = t5 * t2
                                                      imulg %rcx, %rax
                                                      ret
```

3.4.4 Condition Codes

Sometimes, we want to move (really copy) some value to another register if some condition is met. This is where we use conditional moves. These conditions are met by the flags register, which is a special register that stores the status of the last operation. It is the value of these flags that determine whether all future conditional statements are met in assembly.

Definition 3.31 (Condition Code Flags)

The flags register in the x86 CPU keeps 4 condition code flag bits internally. Think of these as status flags that are *implicitly* set by the most recent arithmetic operation (think of it as side effects). Note that condition codes are NOT set by lea or mov instructions!

- 1. **Zero Flag**: if the last operation resulted in a zero value.
- 2. Sign Flag: if the last operation resulted in a negative value (i.e. the most significant bit is 1).
- 3. Overflow Flag: if the last operation resulted in a signed overflow.
- 4. Carry Flag: if the last operation resulted in a carry out of the most significant bit, i.e. an unsigned overflow.

Every operation may or may not changes these flags to test for zero or nonzero, positive or negative, or overflow conditions, and combinations of these flags express the full range of conditions and cases, e.g. for signed and unsigned values.

Example 3.16 (Zero Flag)

If the code below was just run, then ZF would be set to 1.

```
1 movq $2, %rax
2 subq $2, %rax
```

Example 3.17 (Sign Flag)

If the code below was just run, then SF would be set to 1.

```
1 movq $2, %rax
2 subq $4, %rax
```

Example 3.18 (Overflow Flag)

If either code below was just run, then OF would be set to 1.

```
movq $0x7fffffffffffffff, %rax soldq $1, %rax soldq $1, %rax
```

Example 3.19 (Carry Flag)

If the code below was just run, then CF would be set to 1.

```
movq $0xffffffffffffff, %rax addq $1, %rax
```

This is because the result is 0x0, which is a carry out of the most significant bit and an unsigned overflow.

It would be tedious to always set these flags manually, so there are two methods that can be used to *explicitly* set these flags.

Definition 3.32 (Compare)

The **cmp** instruction is used to perform a subtraction between the source and destination, and set the flags accordingly, but it does not store the result.

The following flags are set if the conditions are met:

```
1. \mathbf{ZF} = \mathbf{1} if dest == src
```

2. SF = 1 if dest < src (MSB is 1)

- 3. $\mathbf{OF} = \mathbf{1}$ if signed overflow
- 4. $\mathbf{CF} = \mathbf{1}$ if unsigned overflow

Definition 3.33 (Test)

The **test** instruction is used to perform a bitwise AND operation between the source and destination, and set the flags accordingly.

dest & src

The following flags are set if the conditions are met. Note that you can't have carry out (CF) or overflow (OF) if these flags are set.

- 1. $\mathbf{ZF} = \mathbf{1}$ if dest & src == 0
- 2. SF = 1 if dest & src < 0 (MSB is 1)

Example 3.20 (Compare)

Assuming that %al = 0x80 and %bl = 0x81, which flags are set when we execute cmpb %al, %bl? Well we must first compute

%bl - %al =
$$0x81 - 0x80 = 0x81 + \sim 0x80 + 1 = 0x81 + 0x7F + 1 = 0x101 = 0x01$$
 (10)

- 1. CF=1 since the result is greater than 0xFF (i.e. larger than byte)
- 2. ZF=0 since the result is not 0
- 3. SF=0 since the MSB is 0, i.e. there is unsigned overflow
- 4. OF=0 since there is no signed overflow

For conditional moves and jumps later shown, it basically uses these explicit sets and always compares them to 0. We will see what this means later.

Finally, we can actually set a byte in a register to 1 or 0 based on the value of a flag.

Definition 3.34 (Set)

3.4.5 Conditional Move and Jumps

Definition 3.35 (Equality with 0)

The test instruction is used to perform a bitwise AND operation between the source and destination, and set the flags accordingly.

dest & src

The sete instruction is used to set the destination to 1 if the zero flag is set, and 0 otherwise.

$$dest = (ZF == 1) ? 1 : 0$$

The cmovne instruction is used to move the source to the destination if the zero flag is not set.

$$dest = (ZF == 0)$$
 ? $src : dest$

Definition 3.36 (Jump)

There are several jump instructions, but essentially they are used to jump to another part of the code. We can use the following mnemonic to jump to a label.

Letter	Word
j	jump
n	not
е	equal
S	signed
g	greater (signed interpretation)
1	less (signed interpretation)
a	above (unsigned interpretation)
b	below (unsigned interpretation)

Table 2: Letter to Word Mapping

Figure 22: Mnemonic for Jump Instructions

For completeness, we include all the jump instructions.

Signed Comparison	Unsigned Comparison	Description
je (jz)		jump if equal (==) or jump if zero
jne (jnz)		jump if not equal (!=)
js		jump if negative
jns		jump if non-negative
jg (jnle)	ja (jnbe)	jump if greater (>)
jge (jnl)	jae (jnb)	jump if greater than or equal (>=)
jl (jnge)	jb (jnae)	jump if less (<)
jle (jng)	jbe (jna)	jump if less than or equal (<=)

Table 3: Comparison Instructions in Assembly

Figure 23: All jump instructions

Definition 3.37 (int)

The int instruction is used to generate a software interrupt. It is often used to invoke a system call.

Definition 3.38 (ret)

The ret instruction is used to return from a function. It returns the value in the %rax register.

3.4.6 If Statements

Now we can have a basic idea of how if statements can be used as a sequence of conditionals and jump operators. Let's first look at the **goto** version of C.

Definition 3.39 (Goto Syntax)

The goto version processes instructions sequentially as long as there is no jump. This is useful because compilers translating code into assembly designate a jump when a condition is true. Contrast this behavior with the structure of an if statement, where a "jump" (to the else) occurs when conditions are not true. The goto form captures this difference in logic.

```
int getSmallest(int x, int y) {
                                                         int getSmallest(int x, int y) {
      int smallest;
                                                           int smallest;
                                                     90
     if (x > y ) { //if (conditional)
                                                     91
                                                           if (x \le y) \{ //if (!conditional) \}
        smallest = y; //then statement
      }
                                                             goto else_statement;
      else {
        smallest = x; //else statement
                                                           smallest = y; //then statement
                                                           goto done;
     return smallest;
96
   }
                                                         else_statement:
                                                           smallest = x; //else statement
98
                                                         done:
00
                                                     202
                                                           return smallest;
201
                                                         }
```

Figure 24: C vs GoTo code of the same function. While GoTo code allows us to view C more like assmebly, it is generally not readable and is not considered best practice.

Now let's see how if statements are implemented by taking a look at this function straight up in assembly.

```
int getSmallest(int x, int y) {
                                             Dump of assembler code for function getSmallest:
                                                                      %edi,-0x14(%rbp)
     int smallest;
                                             0x40059a <+4>:
                                                               mov
204
     if (x > y ) { //if (conditional)
                                             0x40059d <+7>:
                                                                      %esi,-0x18(%rbp)
                                                               mov
205
        smallest = y; //then statement
                                             0x4005a0 <+10>: mov
                                                                      -0x14(%rbp), %eax
06
     }
                                                                      -0x18(%rbp), %eax
                                             0x4005a3 <+13>: cmp
     else {
                                             0x4005a6 <+16>:
                                                               jle
                                                                      0x4005b0 <getSmallest+26>
                                                                      -0x18(%rbp), %eax
        smallest = x; //else statement
                                             0x4005a8 <+18>:
                                             0x4005ae <+24>:
                                                                      0x4005b9 <getSmallest+35>
10
                                                               jmp
                                                                      -0x14(%rbp), %eax
     return smallest;
                                             0x4005b0 <+26>:
                                                               mov
11
                                          12
                                             0x4005b9 <+35>:
                                                                      %rbp
   }
                                                               pop
212
                                             0x4005ba <+36>: retq
13
```

Figure 25: Assembly code of a simple if statement

Again, note that since we are working with int types, the respective parameter registers are %edi and %esi, the respective lower 32-bits of the registers %rdi and %rsi. Let's walk through this again.

- 1. The first mov instruction copies the value located in register %edi (the first parameter, x) and places it at memory location %rbp-0x14 on the call stack. The instruction pointer (%rip) is set to the address of the next instruction, or 0x40059d.
- 2. The second mov instruction copies the value located in register %esi (the second parameter, y) and places it at memory location %rbp-0x18 on the call stack. The instruction pointer (%rip) updates to point to the address of the next instruction, or 0x4005a0.

- 3. The third mov instruction copies x to register %eax. Register %rip updates to point to the address of the next instruction in sequence.
- 4. The cmp instruction compares the value at location %rbp-0x18 (the second parameter, y) to x and sets appropriate condition code flag registers. Register %rip advances to the address of the next instruction, or 0x4005a6.
- 5. The jle instruction at address 0x4005a6 indicates that if x is less than or equal to y, the next instruction that should execute should be at location <getSmallest+26> and that %rip should be set to address 0x4005b0. Otherwise, %rip is set to the next instruction in sequence, or 0x4005a8.

With the cmov instruction, this can be a lot shorter. With the gcc compiler with level 1 optimizations turned on, we can see that a lot of redundancies are turned off.

Figure 26: Compiled with gcc -O1 -o getSmallest getSmallest.c

3.4.7 Loops

Like if statements, loops in assembly can be implementing using jump functions that revisit some instruction address based on the result on an evaluated condition. Let's take a look at a basic loop function.

```
int sumUp(int n) {
                                                          Dump of assembler code for function sumUp:
      int total = 0;
                                                      16
                                                          0x400526 <+0>:
                                                                            push
                                                                                    %rbp
215
      int i = 1;
                                                          0x400527 <+1>:
                                                                            mov
                                                                                    %rsp,%rbp
216
                                                          0x40052a <+4>:
                                                                                    %edi,-0x14(%rbp)
                                                                            mov
117
                                                                                    $0x0,-0x8(%rbp)
      while (i <= n) {
                                                          0x40052d <+7>:
218
                                                                            mov
                                                          0x400534 <+14>:
                                                                                    $0x1,-0x4(%rbp)
        total += i;
219
                                                                            mov
                                                          0x40053b <+21>:
                                                                                    0x400547 < sumUp+33>
20
     }
                                                          0x40053d <+23>:
                                                                                    -0x4(\%rbp), %eax
221
                                                          0x400540 <+26>:
                                                                                    %eax,-0x8(%rbp)
      return total;
                                                                            add
222
   }
                                                          0x400543 <+29>:
                                                                                    $0x1,-0x4(%rbp)
                                                                            add
223
                                                          0x400547 <+33>:
                                                                                    -0x4(%rbp), %eax
224
                                                                            mov
                                                          0x40054a <+36>:
                                                                                    -0x14(%rbp), %eax
225
                                                                            cmp
                                                          0x40054d <+39>:
                                                                                    0x40053d < sumUp+23>
226
                                                                            jle
                                                          0x40054f <+41>:
                                                                                    -0x8(%rbp),%eax
                                                          0x400552 <+44>:
                                                                            pop
                                                                                    %rbp
228
                                                          0x400553 <+45>:
                                                                            retq
```

Figure 27: Simple loop function in C and assembly.

3.4.8 Functions

So far, we've traced through simple functions in assembly. n this section, we discuss the interaction between multiple functions in assembly in the context of a larger program. We also introduce some new instructions involved with function management.

Let's begin with a refresher on how the call stack is managed. Recall that **%rsp** is the stack pointer and always points to the top of the stack. The register **%rbp** represents the base pointer (also known as the frame pointer) and points to the base of the current stack frame. The stack frame (also known as the activation

frame or the activation record) refers to the portion of the stack allocated to a single function call. The currently executing function is always at the top of the stack, and its stack frame is referred to as the active frame. The active frame is bounded by the stack pointer (at the top of stack) and the frame pointer (at the bottom of the frame). The activation record typically holds local variables for a function.




Figure 28: The current active frame belongs to the callee function (fname). The memory between the stack pointer and the frame pointer is used for local variables. The stack pointer moves as local values are pushed and popped from the stack. In contrast, the frame pointer remains relatively constant, pointing to the beginning (the bottom) of the current stack frame. As a result, compilers like GCC commonly reference values on the stack relative to the frame pointer. In Figure 1, the active frame is bounded below by the base pointer of fname, which is stack address 0x418. The value stored at address 0x418 is the "saved" "rbp value (0x42c), which itself is an address that indicates the bottom of the activation frame for the main function. The top of the activation frame of main is bounded by the return address, which indicates where in the main function program execution resumes once the callee function fname finishes executing.

In here, we introduce three common instructions that are used to manage the call stack.

Definition 3.40 (Leave)

The **leave** instruction is used to deallocate the current stack frame. For example, the leaveq instruction is a shorthand that the compiler uses to restore the stack and frame pointers as it prepares to leave a function. When the callee function finishes execution, leaveq ensures that the frame pointer is restored to its previous value. It is equivalent to the following two instructions:

Definition 3.41 (Call and Return)

The **call** instruction is used to call a function and the **ret** to return from a function. The callq and retq instructions play a prominent role in the process where one function calls another. Both instructions modify the instruction pointer (register %rip).

1. When the caller function executes the callq instruction, the current value of %rip is saved on the stack to represent the return address, or the program address at which the caller resumes executing once the callee function finishes. The callq instruction also replaces the value of %rip with the address of the callee function.

2. The retq instruction restores the value of %rip to the value saved on the stack, ensuring that

the program resumes execution at the program address specified in the caller function. Any value returned by the callee is stored in %rax or one of its component registers (e.g., %eax). The retq instruction is usually the last instruction that executes in any function.

retq pop %rip

Let's work through an example to solidify our knowledge.

Example 3.21 (Calling Functions in Assembly)


Let's take the following code and trace through main.

```
#include <stdio.h>
                              0000000000400526 <assign>:
231
                                400526:
                                               55
                                                                                 %rbp
                                                                          push
    int assign(void) {
                                400527:
                                                                                 %rsp,%rbp
                                               48 89 e5
232
                                                                         mov
                                               c7 45 fc 28 00 00 00
        int y = 40;
                                40052a:
                                                                                 $0x28,-0x4(%rbp)
233
                                                                         movl
        return y;
                                400531:
                                               8b 45 fc
                                                                                 -0x4(\%rbp), \%eax
34
                                                                          mov
35
                                400534:
                                               5d
                                                                         pop
                                                                                 %rbp
                                400535:
                                               с3
                                                                         retq
236
    int adder(void) {
        int a;
                              0000000000400536 <adder>:
238
        return a + 2;
                                400536:
                                               55
                                                                                 %rbp
239
                                                                          push
240
   }
                                400537:
                                               48 89 e5
                                                                          mov
                                                                                 %rsp,%rbp
241
                                40053a:
                                               8b 45 fc
                                                                         mov
                                                                                 -0x4(%rbp), %eax
242
    int main(void) {
                                40053d:
                                               83 c0 02
                                                                          add
                                                                                 $0x2, %eax
243
        int x;
                                400540:
                                               5d
                                                                          pop
                                                                                 %rbp
        assign();
                                400541:
                                               с3
244
                                                                         retq
        x = adder();
45
        printf("x is:
                              0000000000400542 <main>:
246
        %d\n", x);
                                400542:
                                               55
                                                                          push
                                                                                 %rbp
        return 0;
                                400543:
                                               48 89 e5
                                                                         mov
                                                                                 %rsp,%rbp
   }
                                400546:
                                               48 83 ec 10
                                                                                 $0x10, %rsp
                                                                          sub
48
                                40054a:
                                               e8 e3 ff ff ff
                                                                          callq
                                                                                 400526 <assign>
                                40054f:
                                               e8 d2 ff ff ff
                                                                                 400536 <adder>
                                                                          callq
50
                                400554:
                                               89 45 fc
                                                                                 %eax,-0x4(%rbp)
                                                                         mov
                                400557:
                                               8b 45 fc
                                                                                 -0x4(\%rbp), %eax
                                                                         mov
                                40055a:
                                               89 c6
                                                                         mov
                                                                                 %eax,%esi
254
                                40055c:
                                               bf 04 06 40 00
                                                                         mov
                                                                                 $0x400604, %edi
                                               ъ8 00 00 00 00
                                                                                 $0x0, %eax
255
                                400561:
                                                                         mov
                                400566:
                                               e8 95 fe ff ff
                                                                                 400400
                                                                          callq
                                   <printf@plt>
                                               ъ8 00 00 00 00
                                                                                 $0x0, %eax
                                40056b:
                                                                          mov
                                400570:
                                               с9
                                                                          leaveq
                                400571:
                                               сЗ
                                                                         retq
```


Figure 29: C code and its assembly equivalent. Main function calls two other functions.

Let's trace through what happens here in detail. This will be long.


1. %rbp is the base pointer that is initialized to something. Before we even begin main, say that we have the following initializations, where %eax, %edi is garbage. %rsp denotes where on the stack we are right before calling to main, %rbp is the base pointer to the current program, and %rip should be the address of the first instruction in main. Again since we work with integers we use the lower 32-bits of the registers. %rip now points to the next instruction.




2. Now we start the main function. By calling main, the base pointer **%rbp** of the stack outside of the main frame will be overwritten by the base of the main stack frame, so we must save it for when main is done. Therefore, we push it onto the stack where **%rsp** is pointing. **%rip** now points to the next instruction.




3. Then we actually change the location of the base pointer to the top of the stack, which now includes the first instruction in main.




4. Now we manually change the stack pointer and have it grow by two bytes (0x10). Therefore, %rsp is decremented by 0x10 and %rip points to the next instruction at 0x54a.




5. Now the next instruction pointed at by "rip is the callq instruction, which tells to go to the address of the assign function. We by default first update "rip to point to the next instruction at 0x55f. However, this should not be the actual next instruction that we execute since we are calling another function. Rather, we want to update "rip to address 0x526 where assign is located at, but after completion we also want to know that we want to execute the instruction after it at address 0x55f. Therefore, we should save address 0x55f onto the stack and then update "rip to point to 0x526. This is what we refer to as a return address.




6. %rip is incremented to the next address. We step into the assign function, which is now a new stack frame, so the first thing we do is save the base pointer of the main stack frame onto the stack since we must immediately update it with the base pointer of the assign stack frame, which is where %rsp is pointing to.




7. %rip is incremented to the next address. We then update the base pointer to the top of the stack.




8. Now we want to move the number 0x28 (40) into the memory location -0x4(%rbp) of the stack, which is 4 bytes above the frame pointer, which is also the stack pointer. It is common that the frame pointer is used to reference locations on the stack. Note that this does not update the stack pointer.



9. Now we take the same address where we stored 0x28 to and move it into %eax, effectively loading 40 onto the return value.




10. We see that we will return this value soon, but before we do, we want to make sure that when the assign stack frame gets deleted (not really, but overwritten), we want to restore the base pointer of the main stack frame. We have already saved this before at "rsp, which hasn't changed since we only worked with displacements from the base pointer. We retrieve the main stack pointer data and load it back into "rbp. Note that this increments "rsp by 8 bytes, shrinking the stack, and we are technically out of the assign stack frame.




11. Note that at this point, since **%rbp** was popped off, the next value that is at the top of the stack


is the address %rip that we store earlier, which points to the next execution in main. When retq executes, this value at the top of the stack is popped into %rip, allowing main to continue executing within the main stack frame. Note that the return value is stored in %eax.




12. Now we execute the next instruction in %rip which is a call to the adder function. %rip is automatically updated to the next address at 0x554, but since this is a callq instruction, we first want to store this %rip into the stack so we can come back to it, and then update %rip to the first instruction in adder, which is address 0x536.




13. Since we are in the adder function, this creates a new stack frame and we must update %rbp. Again, we don't want to overwrite the base pointer of main, so we save it onto the stack by pushing %rbp.




14. Then we update %rbp to the current stack pointer.




15. This part is a bit tricky. Note that the value of 0x28 still lives at 0xd1c, which is conveniently at address -0x4(%rbp). Therefore, when we call int a; in that corresponding line in adder, we can actually add 2 to it, though it seems like there was no value assigned to it. This is just a trick though. So, we can take these remnant value and store it into %eax.




17. Now we are almost done, so we pop the base pointer of the main stack frame, at 0xd40, back into %rbp.




18. We now return the value in <code>%eax</code> and pop the base pointer of the adder stack frame, which simply updates the instruction pointer <code>%rip</code> back to the next instruction in main. This is equivalent to pop <code>%rip</code>, which is equivalent to moving the stack pointer <code>%rsp</code> into <code>%rip</code> and then shrinking the stack by 8 bytes <code>subq \$8, %rsp</code>.




19. Now it is relatively straightforward since we do the rest in main (except for the print statement). The current value in <code>%eax</code> represents the return value of adder. We want to put this in the variable x, which we have already allocated some memory for right above the base pointer in the main stack frame. We move it there. Note that right after, it places this right back into




20. the mov instruction at address 0x55a copies the value in %eax (or 0x2A) to register %esi, which is the 32-bit component register associated with %rsi and typically stores the second parameter to a function. We can see why since this will be put into a print statement, which is a function, and x = %esi is the second argument of printf.




21. Now we want to retrieve the first argument of the print function. The address at \$0x400604 is some address in the code segment memory that holds the string "x is %d\n".






24. The print function might have returned something, but we don't care. We want to main function to return 0, so we move 0 into %eax.



25. Finally we execute leaveq, which prepares the stack for returning from the function call. It essentially moves the base pointer back to the stack pointer and then pops the base pointer off the stack. The new %rbp is the original base pointer of whatever was outside the main function, 0x830.



There is a bit of a concern here from the previous example. The main function had two functions that returned two values. As the subfunction stack frame is removed from the stack, the return value is stored in the %rax register. If another function is called right after, then the return value of the second function will overwrite that of the previous one. This was not a problem in the previous example since the return value of the assign function was not used. However, if it was, then the return value of the adder function would have overwritten it. This is known as register saving.

1. For **caller-saved registers**, the caller function is responsible for saving the value of the register before calling a function and restoring it after the function returns. The caller should save values in its stack frame before calling the callee function, e.g. by pushing all the return values of each callee in the caller stack frame. Then it will restore values after the call.

Therefore, if we have a set of registers {%reg}, the caller must take everything and push them in the caller stack frame. Then it will restore them after the call.

2. For **callee-saved registers**, it is the callee's repsonsibility to save any data in these registers before using the registers.

Therefore, if we have a set of registers {%reg}, then inside the callee stack frame, the callee must take everything and push them in the callee stack frame. Once it computes the final return value, then it will restore all the saved register values from the callee stack frame back into the registers for the caller to use.

Ideally, we want *one* calling convention to simply separate implementation details between caller and callee. In general, however, neither is best. If the caller isn't using a register, then caller-save is better, and if callee doesn't need a register, then callee-save is better. If we do need to save, then callee save generally makes smaller programs, so we compromise and use a combination of both caller-save and callee-save. The compiler tries to pick these registers, and by convention in x86, we have the following.




Figure 30: Caller save and callee save registers.

3.4.9 Recursion

3.4.10 Arrays

For arrays, there's not anything new here. Let's go over some code and follow through it.

```
int sumArray(int *array, int length) {
   int i, total = 0;
   for (i = 0; i < length; i++) {
      total += array[i];
   }
   return total;
}</pre>
```

This function takes the address of an array and the length of it and sums up all the elements in the array.

```
1 0x400686 <+0>: push %rbp
                                            # save %rbp
                                            # update %rbp (new stack frame)
2 0x400687 <+1>: mov %rsp,%rbp
3 0x40068a <+4>: mov %rdi,-0x18(%rbp)
                                            # copy array to %rbp-0x18
4 0x40068e <+8>: mov %esi,-0x1c(%rbp)
                                            # copy length to %rbp-0x1c
5 \text{ 0x400691} < +11>: \text{movl } $0x0, -0x4(\%rbp)
                                               # copy 0 to %rbp-0x4 (total)
6 0x400698 <+18>: movl $0x0,-0x8(%rbp)
                                               # copy 0 to %rbp-0x8 (i)
7  0x40069f <+25>: jmp  0x4006be <sumArray+56> # goto <sumArray+56>
8 0x4006a1 <+27>:
                                               # copy i to %eax
                    mov -0x8(%rbp),%eax
9 0x4006a4 <+30>:
                   cltq
                                               # convert i to a 64-bit integer
0x4006a6 <+32>: lea 0x0(,%rax,4),%rdx
                                               # copy i*4 to %rdx
0x4006ae <+40>: mov -0x18(%rbp),%rax
                                               # copy array to %rax
12 0x4006b2 <+44>: add %rdx,%rax
                                               # compute array+i*4, store in %rax
0x4006b5 <+47>: mov (%rax), %eax
                                               # copy array[i] to %eax
0x4006b7 <+49>: add %eax,-0x4(%rbp)
                                               # add %eax to total
0x4006ba <+52>: addl $0x1,-0x8(%rbp)
                                               # add 1 to i (i+=1)
16 0x4006be <+56>: mov -0x8(%rbp), %eax
                                               # copy i to %eax
0x4006c1 < +59>: cmp -0x1c(%rbp),%eax
                                               # compare i to length
18 0x4006c4 <+62>:
                    jl
                         0x4006a1 <sumArray+27> # if i<length goto <sumArray+27>
                    mov -0x4(%rbp),%eax
19 0x4006c6 <+64>:
                                               # copy total to %eax
20 0x4006c9 <+67>:
                    pop %rbp
                                               # prepare to leave the function
0x4006ca <+68>:
                                               # return total
                    retq
```

3.4.11 Matrices

3.4.12 Structs

4 Compilers

Now let's talk about how this compiling actually happens. To actually turn a C file into an executable file, we need to go through a series of steps.

- 1. Source Code: We start off with the C code, which are the .c, .cpp, or .h files.
- 2. **Preprocessing**: The first step is to preprocess the code. We often include header file, global variables, and other things like #include, #define, and #ifdef. The preprocessor will replace these macros with the actual code. This results in a .i or .ii file.
- 3. Compiling: We take these and generate assembly code. This results in a .asm or .s file.
- 4. **Assembler**: We take the assembly code and generate machine code in the form of object files. This results in a .o or .obj file.
- 5. **Linking**: We take these object files and link them together to form an executable file. This results in a .exe or .out file.

The GCC compiler automates this process for us. For example, gcc -c hello.c generates an object file, taking care of the preprocessing, compiling, and assembling code. Then, gcc hello.o links the object file to generate an executable file. At this point, we may ask two questions. Why is there a separate linking phase? And why are the differences between hello.o and a.out if they are both machine code? To answer these questions, we need to understand the ELF format.

Now when create an executable file, we must link perhaps multiple object files. The problem is that each object file is created independently and does not know that the other object files exist. This can mean that stuff like memory addresses can overlap between these object files. To solve this, we use the linker.

Definition 4.1 (ELF)

The **Executable and Linkable Format** (ELF) is a common standard file format for executables, object code, shared libraries, and core dumps. It is analogous to a book, with the following parts:

- 1. **Sections**, which are like chapters. Each section contains the content for some given purpose or use wthin the program. e.g. .binary is just a block of bytes, .text contains the machine code, .data contains initialized data, and .bss contains uninitialized data.
- 2. **Header**, which is like the cover of the book. It contains metadata about the file, such as the architecture, the entry point, and the sections.
- 3. **Symbol Table**, is like a detailed table of contents of all defined symbols such as functions, external (global) variables, local maps, etc.
- 4. **Relocation records**, which is like the index of the book that lists references to symbols. The format is generally as such when you run objdump -d -r hello.o (d represents disassembly and r represents relocation entries).

```
ELF header # file type

1 .text section
2 .code goes here
5 .rodata section
7 - read only data
8 .data section
10 - initialized global variables
```

```
.bss section
     - uninitialized global variables
13
   .symtab section
     - symbol table (symbol name, type, address)
18
   .rel.text section
     - relocation entries for .text section
19
     - addresses of instructions that will need to be modified in the executable.
  .rel.data section
    - relocation info for .data section
     - addresses of pointer data that will need to be modified in the merged executable.
  .debug section
26
     - info for symbolic debugging (gcc -g)
```

Let's elaborate on what symbols mean.

Definition 4.2 (Symbol)

A **symbol** is a name that is used to refer to a memory location. It can be a function name, a global variable, or a local variable.

- 1. Global symbols are symbols that can be referenced by other object files, e.g. non-static functions and global variables.
- 2. Local symbols are symbols that are only visible within the object file, e.g. static functions and local variables. The linker won't know about these types.
- 3. External symbols are referenced by this object file but defined in another object file.

The two types of symbols that the linker will know about are the global and external symbols. We can see that external symbols can be problematic if the object files don't know about each other.

Example 4.1 (Linker Symbols)

Consider the following code where the left file includes the right file.

```
261  // file1.c
262  #include "sum.h"
263  int sum(int *a, int n) {
264  int array[2] = {1, 2};
265  for (i = 0; i < n; i++) {
266   int main() {
267   int val = sum(array, 2);
268   return val;
269 }
269 }
```

In the left file,

- 1. We define the global symbol main().
- 2. Inside main, val is a local symbol so the linker knows nothing about it.
- 3. The sum function is an external symbol, and it references a global symbol that's defined in sum the right file.
- 4. The array is a global symbol that is defined in the right file.

In the right file, the linker knows nothing of the local symbols i or s.

Now to make sure that these addresses don't overlap, we need to do some address **relocation**. To understand this, we will use the **objdump** command.

Definition 4.3 (Object Dump)

The **objdump** command can be used to determine many things:

- 1. **objdump** -t gives us the table of symbols which shows us the addresses of the symbols.
 - (a) The leftmost column represents the address of the symbol.
 - (b) The next column represents the type of the symbol. The g and 1 represent global and local symbols, respectively. The O and F represent object and function symbols, while the UND and ABS represent undefined and absolute symbols.
 - (c) The next column represents the section that the symbol is in.
 - (d) The next column represents the size of the symbol.
 - (e) The last column represents the name of the symbol.

```
1 SYMBOL TABLE:
2 000000000000000 1 df *ABS* 0000000000000 file1.c
```

- 2. **objdump-r** gives us the relocation table which shows us the addresses that need to be modified.
 - (a) The leftmost column represents the offset of the relocation (i.e. the location within the section where this relocation needs to be applied).
 - (b) The second column represents the type of relocation.
 - (c) The third column represents the symbol that this relocation references.

```
RELOCATION RECORDS FOR [.text]:

OFFSET TYPE VALUE

00000000000000014 R_X86_64_PC32 array-0x0000000000004

...
```

- 3. **objdump -d** gives us the disassembly of the object file.
 - (a) The leftmost column represents the address of the instruction.
 - (b) The next column represents the machine code of the instruction.
 - (c) The next column represents the assembly code of the instruction.

```
1 0000000000000000 <main>:
2 0: f3 0f 1e fa endbr64
3 4: 55 push %rbp
4 ...
```

Let's look through a simple example. Consider the following two C files.

```
// main.c
                                                          // sum.c
   extern int sum(int *array, int n);
                                                          int sum(int *array, int n) {
                                                          int i, s = 0;
272
   int array[2] = {1, 2};
                                                          for (int i = 0; i < n; i++) {</pre>
                                                              s += array[i];
   int main(void) {
                                                            }
     int val = sum(array, 2);
                                                            return s;
      return val;
                                                          }
   }
279
```

Now once we have generated the object files with gcc -c main.c and gcc -c sum.c. Then we can link them with gcc main.o sum.o to get a.out. Let's now compare the three objdump commands.

Example 4.2 (Symbol Table)

We can see a couple things.

- 1. In main.o, the numbers on the left represents the address of the symbol (all 0s since we haven't linked yet and their final addresses aren't known), while the addresses in a.out are all known.
- 2. In main.o, the sum function is an external symbol and is undefined. The linker will need to know where this is. In a.out, note that the sum function is now a global symbol and is defined, along with the size. We can now see that all the final addresses of each symbol is known, along with their sizes, and the UND marker is now gone as well.
- 3. Only the size of the global variable is known in main.o since we have defined it within the code. However, in a.out, the linker has now assigned an address to it.
- 4. To see the size in bytes of the array, you can look at the address and how much size it takes up.

```
file format elf64-x86-64
main.o:
SYMBOL TABLE:
00000000000000000001
                       df *ABS*
                                              0000000000000000 file1.c
000000000000000000001
                       d .text
                                              000000000000000 .text
00000000000000000001
                         .data
                                              000000000000000 .data
                       d
000000000000000000001
                       d .bss
                                              000000000000000 .bss
00000000000000000001
                       d .note.GNU-stack
                                              000000000000000 .note.GNU-stack
0000000000000000001
                       d
                          .note.gnu.property
                                              0000000000000000 .note.gnu.property
00000000000000000001
                       d
                          .eh_frame
                                              000000000000000 .eh_frame
00000000000000000001
                          .comment
                                              000000000000000 .comment
0000000000000000 g
                        0 .data
                                              0000000000000008 array
0000000000000000 g
                        F .text
                                              0000000000000025 main
000000000000000
                          *UND*
                                              OOOOOOOOOOOOO _GLOBAL_OFFSET_TABLE_
0000000000000000
                          *UND*
                                              000000000000000 sumjA
```

Figure 31: Symbol table for main.o.

```
file format elf64-x86-64
a. 011t:
SYMBOL TABLE:
0000000000004008 g
                       0 .data
                                    0000000000000000
                                                                   .hidden __dso_handle
00000000000114e g
                       F .text
                                    00000000000000049
0000000000002000 g
                       O .rodata
                                    0000000000000004
                                                                   _IO_stdin_used
0000000000011a0 g
                       F .text
                                    000000000000065
                                                                   __libc_csu_init
0000000000004020 g
                          .bss
                                    0000000000000000
                                                                   end
                                                                   _start
000000000001040 g
                       F .text
                                    000000000000002f
                                                                   __bss_start
0000000000004018 g
                          .bss
                                    0000000000000000
000000000001129 g
                       F .text
                                    0000000000000025
                                                                   main
                       O .data
0000000000004018 g
                                    0000000000000000
                                                                   .hidden __TMC_END__
```

Figure 32: Symbol table for a.out.

Example 4.3 (Relocation Table)

We can see a couple things. Namely, there is nothing to be relocated in a.out since everything has been relocated already by the linker. So let's focus on the relocation for main.o. In here, we can see that in the .text section, there are two things being relocated:

- 1. The reference to the global variable array is being relocated. In this object file, we look at the offset 0x14 from the beginning of the .text section, which contains the instruction that needs to access array. This relocation record tells the linker to calculate the 32-bit offset from the instruction (at offset 0x14) to the start of array, then adjust it by subtracting 4 bytes.
- 2. The reference to the sum function is being relocated. In this object file, we look at the offset 0x19 from the beginning of the .text section, which contains the instruction that needs to access sum. This relocation record tells the linker to calculate the 32-bit offset from the instruction (at offset 0x19) to the start of the .plt section, then adjust it by subtracting 4 bytes.

```
main.o: file format elf64-x86-64

RELOCATION RECORDS FOR [.text]:

OFFSET TYPE VALUE

00000000000000014 R_X86_64_PC32 array-0x0000000000004

0000000000000019 R_X86_64_PLT32 sum-0x0000000000004

RELOCATION RECORDS FOR [.eh_frame]:

OFFSET TYPE VALUE

00000000000000000000 R_X86_64_PC32 .text
```

Figure 33: Relocation table for main.o.

```
a.out: file format elf64-x86-64
```

Figure 34: Relocation table for a.out.

Example 4.4 (Disassembly)

We can see a couple things.

- 1. In main.o at address 0x0, we have the main function and this is because everything is stored relatively to the start of main. Once we have linked, a.out shows the absolute addresses of all the instructions.
- 2. In instruction 11 in main.o we can see that 48 8d 3d is the lea instruction, which is the same as that in a.out. However, the address that is was acting on is 0x0 since the array has not been initialized yet. We can see in a.out that the address is now 0x00002ecf.
- 3. The comment in a.out indicates that the final relocated address used to access the array is 0x4010. To see relocated addresses in general, just look for the comments and shift them accordingly.

```
file1.o:
                file format elf64-x86-64
  Disassembly of section .text:
   0000000000000000 <main>:
      0: f3 Of 1e fa
                                  endbr64
      4: 55
                                  push
                                         %rbp
      5: 48 89 e5
                                  mov
                                         %rsp,%rbp
      8: 48 83 ec 10
                                  sub
                                         $0x10, %rsp
      c: be 02 00 00 00
                                  mov
                                         $0x2,%esi
     11: 48 8d 3d 00 00 00 00
                                  lea
                                         0x0(%rip),%rdi
                                                                # 18 <main+0x18>
     18: e8 00 00 00 00
                                  callq 1d <main+0x1d>
     1d: 89 45 fc
                                  mov
                                         %eax,-0x4(%rbp)
     20: 8b 45 fc
                                  mov
                                         -0x4(\%rbp), %eax
14
     23: c9
                                  leaveq
     24: c3
                                  retq
```

Figure 35: Disassembly of main.o.

```
000000000001129 <main>:
 1129: f3 Of 1e fa
                                 endbr64
 112d: 55
                                        %rbp
                                 push
 112e: 48 89 e5
                                        %rsp,%rbp
                                 mov
 1131: 48 83 ec 10
                                 sub
                                        $0x10, %rsp
 1135:
        be 02 00 00 00
                                 mov
                                        $0x2, %esi
        48 8d 3d cf 2e 00 00
                                        0x2ecf(%rip),%rdi
                                                                 # 4010 <array>
 113a:
                                 lea
                                 callq 114e <sum>
 1141: e8 08 00 00 00
 1146: 89 45 fc
                                 mov
                                        %eax,-0x4(%rbp)
 1149: 8b 45 fc
                                        -0x4(%rbp),%eax
                                 mov
 114c: c9
                                 leaveq
  114d:
        сЗ
                                 retq
```

Figure 36: Disassembly of a.out.

We can glean a lot of information from this. To see the offset of array, find in the symbol table the address of both the .data and .array and subtract their difference.

- 1. The address of the main function is 0, which is odd at first, but the object files work with *relative* addressing. This means that the address of the main function is 0 relative to the start of the object file.
- 2. The leftmost column is the address of the instruction in hexadecimal.
- 3. The middle column is the machine code.
- 4. The rightmost column is the assembly code.
- 5. The lines with b: and 10: indicate relocation entries (R_X86_64_PC32 and R_X86_64_PLT32, respectively), which are placeholders that will be filled with actual addresses by the linker. These relocations reference the .rodata section and the puts function, respectively.