Programming Assignment #1 Instruction Processing

CS222 Spring 2023 20 points due Saturday, Jan. 28th, 11:59 pm

1 Instruction Processing

You'll write a problem to simulate the processing of machine instructions in a CPU. These instructions are similar in form to RISC-V instructions, which we'll study in detail.

You may work individually or with a partner.


1/21/23 I missed a couple things in the description of the execution of LW and SW, which I've put in blue.

2 Instructions

An instruction is a four-byte (32-bit) integer.

2.1 Instruction format

The fields of an instruction are located in fixed positions in these 32 bits, as shown in the following diagram:



Undergraduates: assume that an immediate value is non-negative. Graduate students: treat signed immediate values correctly, using two's complement representation (see below).

In your program, the instructions will be stored in an integer array (or list) that represents the memory of the system.

2.2 Registers

A register is a storage location for a single four-byte integer. There are a small number of registers. They are named R0, R1, ..., Rn-1.

2.3 Instructions to implement

In the following, Rd denotes the destination register; Rs1 is the first source register, and Rs2 is the second source register.

Implement the following instructions:

NOOP

opcode = 0 (0000). Do nothing.

ADD Rd, Rs1, Rs2

opcode = 1 (0001). Add the contents of Rs1 and Rs2 and put the result in Rd.

ADDI Rd, Rs1, immed

opcode = 2 (0010). Add the contents of Rs1 to the immediate value and put the result in Rd.

BEQ Rs1, Rs2, immed

opcode = 3 (0011). If the contents of Rs1 and Rs2 are the same, then set pc to pc + immed; otherwise do nothing.

JAL Rd, immed

opcode = 4 (0100). Save pc + 1 to Rd and set pc to the contents of pc + immed.

LW Rd, immed(Rs1)

opcode = 5 (0101). Load the value from memory location immed + Rs1 and put that value into Rd.

SW Rs1, immed(Rs2)

opcode = 6 (0110). Store the value from Rs1 into memory location immed + Rs2.

RETURN

opcode = 7 (0111). Terminate the processing of instructions.

3 The Program

The basic function of a microprocessor can be described in pseudocode:

while true:

```
fetch the next instruction, which is the instruction at location pc decode the instruction execute the instruction if the instruction was not a BEQ or JAL set pc = pc + 1 ^{\circ}
```

Write a program to implement this. Create a CPU class and an Instruction class. CPU should have these member variables:

- pc: an integer
- next_pc: an integer
- memory: an array (list) of MEM_SIZE integers
- regs: an array (list) of NUM_REGISTERS integers

Set NUM_REGISTERS to 16 and MEM_SIZE to 65536. (In Python, memory and registers will be integer lists.)

Put the value zero into each register and into each memory location initially.

The Instruction class should have these five member variables: opcode, Rd, Rs1, Rs2, and immed. All are integers.

The instructions themselves will be in the memory array/list. The variable pc is an index into this array. So for example, if the value of pc is 100, then then next instruction fetched would be the integer at position 100 in the array/list.

4 Processing

Write the following functions. I made each of these functions a member function of CPU.

4.1 IF: Instruction fetch

Read the instruction at location mem[pc]. Set next_pc to pc+1. Each instruction will be a four-byte integer.

4.2 ID: Instruction decode

Pull out the opcode, the destination register (Rd), source register #1 (Rs1), source register #2 (Rs2), and the immediate value (immed). Not every instruction will have each of these values, but ID treats each instruction as if it does have each of these values. (This is called *fixed-field decoding* and is a means for improving the efficiency of instruction processing.)

The opcode is in bits 28-31 of the instruction. Rd is in bits 25-27. Rs1 is in bits 20-23. Rs2 is in bits 16-19. The immediate value is in bits 0-15. Use bitwise operations to extract these values. After extracting these values, create an instance of Instruction having its values set to the various extracted values.

Note: this doesn't represent the actual encoding of RISC-V instructions, but it's conceptually similar.

To extract specific bits from an integer, use a combination of bit shifting and bitwise operations.

For example: suppose I want the value that bits 3-7 of the integer val represent. I first shift val 3 bits to the right and then perform a bitwise AND with 15 (which is 1111 in binary): result = (val >> 3) & 15

4.3 EX: Execute

Perform the actual arithmetic operation specified by the opcode, using register value(s) or immediate value, as appropriate. After the specific processing for each opcode, set pc to next_pc.

In each case, Rd is an entry in the cpu.regs[] array/list. For example, R4 corresponds to cpu.regs[4]. Similar for Rs1 and Rs2.

4.3.1 ADD and ADDI

Perform the addition, using either the two source registers (for ADD) or Rs1 and the immediate value (for ADDI). Put the result in alu_result, and then put alu_result into Rd.

4.3.2 BEQ

Compare the values in the two source registers. If the values are equal, then set next_pc to the value of pc plus the immediate value; otherwise, do nothing.

4.3.3 LW

Calculate the effective address: Rs1 plus the immediate value. Put this in eff_address. Then, put the contents of mem[eff_address] into Rd.

4.3.4 SW

Calculate the effective address: Rs2 plus the immediate value. Put this in eff_address. Then, put the contents of Rs1 into mem[eff_address].

4.3.5 JAL

Set alu_result to pc+1, put alu_result into Rd, and set next_pc to pc plus the immediate value.

5 Testing your code

Here's a sequence of twelve instructions:

```
noop
addi r1, r0, 1
                  # r1 now has 1
addi r2, r0, 2
                   # r2 now has 2
add r3, r1, r1
                  # r3 now has 2
add r4, r2, r2
                  # r4 now has 4
beq r3, r4, 3
                  # branch if r3 == r4; branch is not taken
addi r8, r0, 10
                  # r8 now has 10
jal r0, 2
                  # jump
addi r8, r0, 1000 # this instruction is skipped
    r2, 10(r8)
                  # save the value 2 to mem[10+10]
    r5, 10(r8)
                  # load the mem[10+10] into r5; r5 now has the value 2
lw
return
```

After executing these instructions, you should have these values in the registers:

```
R0=108 R1=1 R2=2 R3=2 R4=4 R5=2 R6=0 R7=0 R8=10 R9=0 R10=0 R11=0 R12=0 R13=0 R14=0 R15=0
```

and memory[20] should be 2.

5.1 Creating this testcase

Create constant values to represent the opcodes:

```
NOOP = 0
ADD = 1
ADDI = 2
BEQ = 3
JAL = 4
```

```
Then, here's how to load instructions into the integer array/list that represents memory:
i0 = (NOOP << 28)
i1 = (ADDI << 28) + (1 << 24) + (0 << 20)
                                                        + 1
i2 = (ADDI << 28) + (2 << 24) + (0 << 20)
                                                        + 2
i3 = (ADD << 28) + (3 << 24) + (1 << 20) + (1 << 16)
i4 = (ADD << 28) + (4 << 24) + (2 << 20) + (2 << 16)
                               + (3 << 20) + (4 << 16) + 3
i5 = (BEQ << 28)
i6 = (ADDI << 28) + (8 << 24) + (0 << 20)
                                                        + 10
i7 = (JAL << 28) + (0 << 24)
                                                        + 2
i8 = (ADDI << 28) + (8 << 24) + (0 << 20)
                                                        + 1000
i9 = (SW << 28)
                               + (2 << 20) + (8 << 16) + 10
i10 = (LW << 28) + (5 << 24) + (8 << 20)
i11 = (RETURN << 28)
cpu.mem[100] = i0
cpu.mem[101] = i1
cpu.mem[102] = i2
cpu.mem[103] = i3
cpu.mem[104] = i4
cpu.mem[105] = i5
cpu.mem[106] = i6
cpu.mem[107] = i7
cpu.mem[108] = i8
cpu.mem[109] = i9
```

Then set cpu.pc to 100 and start the while loop.

What to Submit 6

Submit your code.

cpu.mem[110] = i10cpu.mem[111] = i11

LW

SW

= 5

= 6 RETURN = 7

7 Graduate students

Graduate students, and undergraduates for extra credit: implement the SUB, SUBI, and JALR opcodes. Also, provide the capability to read instructions from a text file. The text file should contain a sequence of instructions, one per line. You can ignore case. Also, correctly treat signed immediate values. With 16 bits, a signed value can range from -32768 to 32767. Assume a two's-complement representation of signed integers.

Two's complement: if the most significant bit of an N-bit binary number b is set, then, interpret the signed number as $-(2^N - b)$, with b as an unsigned number in this difference. Example using four bits: 1010 should be interpreted as -(16-10) = -6; similarly, 1000 as a signed integer is -8.

SUB Rd, Rs1, Rs2

opcode = 9 (1001). Subtract the contents of Rs2 from Rs1 and put the result in Rd.

SUBI Rd, Rs1, immed

opcode = 10 (1010). Subtract the immediate value from Rs1 and put the result in Rd.

JALR Rd, Rs1, immed

opcode = 12 (1100). Save pc + 1 to Rd and set next_pc to the contents of Rs1 + immed.