AUCTEX

A much enhanced LATEX mode for Emacs. Version 11.53

by Kresten Krab Thorup updates from 6.1 to 11.13 by Per Abrahamsen updates from 11.14 by David Kastrup

Copyright © 1993, 1994, 1995, 2001, 2002, 2004 Free Software Foundation, Inc. Copyright © 1992 Kresten Krab Thorup

Permission is granted to make and distribute verbatim copies of this manual provided the copyright notice and this permission notice are preserved on all copies.

Permission is granted to copy and distribute modified versions of this manual under the conditions for verbatim copying, provided also that the section entitled "Copying" is included exactly as in the original, and provided that the entire resulting derived work is distributed under the terms of a permission notice identical to this one.

Permission is granted to copy and distribute translations of this manual into another language, under the above conditions for modified versions, except that this permission notice may be stated in a translation approved by the Free Software Foundation.

Copying

(This text stolen from the TEXinfo 2.16 distribution).

The programs currently being distributed that relate to AUCTEX include lisp files for Emacs (and XEmacs). These programs are free; this means that everyone is free to use them and free to redistribute them on a free basis. The AUCTEX related programs are not in the public domain; they are copyrighted and there are restrictions on their distribution, but these restrictions are designed to permit everything that a good cooperating citizen would want to do. What is not allowed is to try to prevent others from further sharing any version of these programs that they might get from you.

Specifically, we want to make sure that you have the right to give away copies of the programs that relate to AUCTEX, that you receive source code or else can get it if you want it, that you can change these programs or use pieces of them in new free programs, and that you know you can do these things.

To make sure that everyone has such rights, we have to forbid you to deprive anyone else of these rights. For example, if you distribute copies of the AUCTEX related programs, you must give the recipients all the rights that you have. You must make sure that they, too, receive or can get the source code. And you must tell them their rights.

Also, for our own protection, we must make certain that everyone finds out that there is no warranty for the programs that relate to AUCTEX. If these programs are modified by someone else and passed on, we want their recipients to know that what they have is not what we distributed, so that any problems introduced by others will not reflect on our reputation.

The precise conditions of the licenses for the programs currently being distributed that relate to AUCT_FX are found in the General Public Licenses that accompany them.

1 Introduction to AUCT_EX

This section of the AUCT_EX manual gives a brief overview of what AUCT_EX is, and the section is also available as a 'README' file. It is **not** an attempt to document AUCT_EX. Real documentation for AUCT_EX is available in the rest of the manual, which you can find in the 'doc' directory.

Read the 'INSTALL' or 'INSTALL.windows' file respectively for information about how to install AUCTEX. The files comprise the same information as the Installation chapter in the AUCTEX manual.

If you are upgrading from the previous version of AUCTEX, the latest changes can be found in the 'CHANGES' file. If you are upgrading from an older version, read the History chapter in the AUCTEX manual.

AUCTEX is a comprehensive customizable integrated environment for writing input files for TeX/IATeX/ConTeXt using GNU Emacs.

AUCTEX lets you run TEX/IATEX/ConTEXt and IATEX/ConTEXt-related tools, such as a output filters or post processor from inside Emacs. Especially 'running IATEX' is interesting, as AUCTEX lets you browse through the errors TEX reported, while it moves the cursor directly to the reported error, and displays some documentation for that particular error. This will even work when the document is spread over several files.

AUCTEX automatically indents your 'IATEX-source', not only as you write it — you can also let it indent and format an entire document. It has a special outline feature, which can greatly help you 'getting an overview' of a document.

Apart from these special features, AUCTEX provides a large range of handy Emacs macros, which in several different ways can help you write your LATEX/ConTEXt documents fast and painlessly.

All features of AUCTEX are documented using the GNU Emacs online documentation system. That is, documentation for any command is just a key click away!

AUCTEX is written entirely in Emacs-Lisp, and hence you can easily add new features for your own needs. It was not made as part of any particular employment or project (apart from the AUCTEX project itself). AUCTEX is distributed under the 'GNU Emacs General Public License' and may therefore almost freely be copied and redistributed.

The next sections are a short introduction to some 'actual' features. For further information, refer to the built-in online documentation of AUCTEX.

1.1 Indentation and filling

AUCTEX may automatically indent your document as you write it. By pressing $(\overline{\text{LFD}})$ instead of $(\overline{\text{RET}})$ at the end of a line, the current line is indented by two spaces according to the current environment level, and the cursor is moved down one line. By pressing $(\overline{\text{TAB}})$, the current line is indented, and the cursor stays where it is. The well-known Emacs feature fill-paragraph (M-q) is reimplemented especially for AUCTEX to follow the indentation (even in commented parts of the document). A special command LaTeX-fill-buffer lets you indent an entire document like the well-known C utility indent (this time, only according to the LATEX structure :-).

1.2 Completion

By studying your '\documentclass' command (in the top of your document), and consulting a precompiled list of (La)TeX symbols from a large number of TeX and LATeX files, AUCTeX is aware of the LATeX commands you should be able to use in this particular document. This 'knowledge' of AUCTeX is used for two purposes.

- 1. To make you able to 'complete' partly written LATEX commands. You may e.g. write \renew and press M-\tau (Tab) (TeX-complete-symbol), and then AUCTEX will complete the word '\renewcommand' for you. In case of ambiguity it will display a list of possible completions.
- 2. To aid you inserting environments, that is \begin \end pairs. This is done by pressing C-c C-e (LATEX-environment), and you will be prompted for which 'environment' to insert.

1.3 Editing your document

A number of more or less intelligent keyboard macros have been defined to aid you editing your document. The most important are listed below.

```
LaTeX-environment
```

```
(C-c C-e) Insert a '\begin{}' — '\end{}' pair as described above.
```

LaTeX-section

```
(C-c C-s) Insert one of '\chapter', '\section', etc.
```

```
TeX-font (C-c C-f C-r, C-c C-f C-i, C-c C-f C-b) Insert one of '\textrm{}'), '\textit{\/}' '\textbf{}' etc.
```

A number of additional functions are available. But it would be far too much to write about here. Refer to the rest of the AUCT_EX documentation for further information.

1.4 Running LATEX

When invoking one of the commands TeX-command-master (C-c C-c) or TeX-command-region (C-c C-r) IATEX is run on either the entire current document or a given region of it. The Emacs view is split in two, and the output of TeX is printed in the second half of the screen, as you may simultaneously continue editing your document. In case TeX finds any errors when processing your input you can call the function TeX-next-error (C-c) which will move the cursor to the first given error, and display a short explanatory text along with the message TeX gave. This procedure may be repeated until all errors have been displayed. By pressing C-c C-w (TeX-toggle-debug-boxes) you can toggle whether the browser also should notify over-full/under-full boxes or not.

Once you've successfully formatted your document, you may preview or print it by invoking TeX-command-master again.

1.5 Outlines

Along with AUCTEX comes support for outline mode for Emacs, which lets you browse the sectioning structure of your document, while you will still be able to use the full power of the rest of the AUCTEX functionality.

1.6 Availability

The most recent version is always available at

http://ftp.gnu.org/pub/gnu/auctex/

WWW users may want to check out the AUCTEX page at

http://www.gnu.org/software/auctex/

1.7 Contacts

There has been established a mailing list for help, bug reports, feature requests and general discussion about AUCTEX. You're very welcome to join. Traffic average at an article by day, but they come in bursts. If you are only interested in information on updates, you could refer to the newsgroups 'comp.text.tex' and 'gnu.emacs.sources'.

If you want to contact the AUCTEX mailing list, send mail to mailto:auc-tex-subscribe@sunsite.dk in order to join. Articles should be sent to mailto:auc-tex@sunsite.dk.

To contact the current maintainers of AUCTEX directly, email mailto:auc-tex_mgr@sunsite.dk.

2 Inserting Frequently Used Commands

The most commonly used commands/macros of AUCTEX are those which simply insert templates for often used TeX and/or LATEX/ConTeXt constructs, like font changes, handling of environments, etc. These features are very simple, and easy to learn, and help you avoid stupid mistakes like mismatched braces, or '\begin{}'-\end{}' pairs.

2.1 Insertion of Quotes, Dollars, and Braces

In TEX, literal double quotes ""like this" are seldom used, instead two single quotes are used ""like this". To help you insert these efficiently, AUCTEX allows you to continue to press " to insert two single quotes. To get a literal double quote, press " twice.

TeX-insert-quote count

[Command]

(") Insert the appropriate quote marks for TeX.

Inserts the value of TeX-open-quote (normally "") or TeX-close-quote (normally "") depending on the context. With prefix argument, always inserts "" characters.

TeX-open-quote

[User Option]

String inserted by typing " to open a quotation.

TeX-close-quote

[User Option]

String inserted by typing " to close a quotation.

TeX-quote-after-quote

[User Option]

Determines the behavior of ". If it is non-nil, typing " will insert a literal double quote. The respective values of TeX-open-quote and TeX-close-quote will be inserted after typing " once again.

If you include the style files 'german' or 'ngerman' TeX-open-quote and TeX-close-quote will be set to the values of LaTeX-german-open-quote and LaTeX-german-close-quote respectively. TeX-quote-after-quote will be set to the value of LaTeX-german-quote-after-quote. If you write texts which facilitate the style files mentioned before, you should customize those special variables instead of the standard variables.

In AUCTEX, dollar signs should match like they do in TeX. This has been partially implemented, we assume dollar signs always match within a paragraph. The first '\$' you insert in a paragraph will do nothing special. The second '\$' will match the first. This will be indicated by moving the cursor temporarily over the first dollar sign. If you enter a dollar sign that matches a double dollar sign '\$\$' AUCTEX will automatically insert two dollar signs. If you enter a second dollar sign that matches a single dollar sign, the single dollar sign will automatically be converted to a double dollar sign.

TeX-insert-dollar arg

[Command]

(\$) Insert dollar sign.

Show matching dollar sign if this dollar sign end the T_EX math mode. Ensure double dollar signs match up correctly by inserting extra dollar signs when needed.

With optional arg, insert that many dollar signs.

To avoid unbalanced braces, it is useful to insert them pairwise. You can do this by typing C-c {.

TeX-insert-braces

[Command]

 $(C-c \ \{)$ Make a pair of braces and position the cursor to type inside of them.

2.2 Inserting Font Specifiers

Perhaps the most used keyboard commands of AUCT_EX are the short-cuts available for easy insertion of font changing macros.

If you give an argument (that is, type C-u) to the font command, the innermost font will be replaced, i.e. the font in the TEX group around point will be changed. The following table shows the available commands, with \star indicating the position where the text will be inserted.

C-c C-f C-r

Insert roman $\text{textrm}\{\star\}$ text.

C-c C-f C-b

Insert **bold face** '\textbf{*}' text.

C-c C-f C-i

Insert italics '\textit{ \star }' text.

C-c C-f C-e

Insert $emphasized `\emph{*}' text.$

C-c C-f C-s

Insert slanted '\texts1{ \star }' text.

C-c C-f C-t

Insert typewriter '\texttt{⋆}' text.

C-c C-f C-c

Insert SMALL CAPS '\textsc{⋆}' text.

C-c C-f C-d

Delete the innermost font specification containing point.

TeX-font arg [Command]

(C-c C-f) Insert template for font change command.

If replace is not nil, replace current font. what determines the font to use, as specified by TeX-font-list.

TeX-font-list [User Option]

List of fonts used by TeX-font.

Each entry is a list with three elements. The first element is the key to activate the font. The second element is the string to insert before point, and the third element is the string to insert after point. An optional fourth element means always replace if not nil.

2.3 Inserting chapters, sections, etc.

Insertion of sectioning macros, that is '\chapter', '\section', '\subsection', etc. and accompanying '\label''s may be eased by using *C-c C-s*. This command is highly customizable, the following describes the default behavior.

When invoking you will be asked for a section macro to insert. An appropriate default is automatically selected by AUCTEX, that is either: at the top of the document; the top level sectioning for that document style, and any other place: The same as the last occurring sectioning command.

Next, you will be asked for the actual name of that section, and last you will be asked for a label to be associated with that section. The label will be prefixed by the value specified in LaTeX-section-hook.

LaTeX-section arg

[Command]

(C-c C-s) Insert a sectioning command.

Determine the type of section to be inserted, by the argument arg.

- If arg is nil or missing, use the current level.
- If arg is a list (selected by C-u), go downward one level.
- If arg is negative, go up that many levels.
- If arg is positive or zero, use absolute level:
 - + 0 : part
 - + 1 : chapter
 - + 2 : section
 - + 3: subsection
 - + 4: subsubsection
 - + 5: paragraph
 - + 6: subparagraph

The following variables can be set to customize the function.

LaTeX-section-hook

Hooks to be run when inserting a section.

LaTeX-section-label

Prefix to all section references.

The precise behavior of LaTeX-section is defined by the contents of LaTeX-section-hook.

LaTeX-section-hook

[User Option]

List of hooks to run when a new section is inserted.

The following variables are set before the hooks are run

level Numeric section level, default set by prefix arg to LaTeX-section.

name Name of the sectioning command, derived from level.

title The title of the section, default to an empty string.

toc Entry for the table of contents list, default nil.

done-mark

Position of point afterwards, default nil meaning after the inserted text.

A number of hooks are already defined. Most likely, you will be able to get the desired functionality by choosing from these hooks.

LaTeX-section-heading

Query the user about the name of the sectioning command. Modifies level and name.

LaTeX-section-title

Query the user about the title of the section. Modifies title.

LaTeX-section-toc

Query the user for the toc entry. Modifies toc.

LaTeX-section-section

Insert IATEX section command according to name, title, and toc. If toc is nil, no toc entry is inserted. If toc or title are empty strings, done-mark will be placed at the point they should be inserted.

LaTeX-section-label

Insert a label after the section command. Controlled by the variable LaTeX-section-label.

To get a full featured LaTeX-section command, insert

```
(setq LaTeX-section-hook
    '(LaTeX-section-heading
LaTeX-section-title
LaTeX-section-toc
LaTeX-section-section
LaTeX-section-label))
```

in your '.emacs' file.

The behavior of LaTeX-section-label is determined by the variable LaTeX-section-label.

LaTeX-section-label

[User Option]

Default prefix when asking for a label.

If it is a string, it is used unchanged for all kinds of sections. If it is nil, no label is inserted. If it is a list, the list is searched for a member whose car is equal to the name of the sectioning command being inserted. The cdr is then used as the prefix. If the name is not found, or if the cdr is nil, no label is inserted.

By default, chapters have a prefix of 'cha:' while sections and subsections have a prefix of 'sec:'. Labels are not automatically inserted for other types of sections.

2.4 Inserting Environment Templates

A large apparatus is available that supports insertions of environments, that is '\begin{}' — '\end{}' pairs.

AUCTEX is aware of most of the actual environments available in a specific document. This is achieved by examining your '\documentclass' command, and consulting a precompiled list of environments available in a large number of styles.

You insert an environment with C-c C-e, and select an environment type. Depending on the environment, AUCT_EX may ask more questions about the optional parts of the selected environment type. With C-u C-c C-e you will change the current environment.

LaTeX-environment arg

[Command]

(C-c C-e) AUCTEX will prompt you for an environment to insert. At this prompt, you may press (TAB) or (SPC) to complete a partially written name, and/or to get a list of available environments. After selection of a specific environment AUCTEX may prompt you for further specifications.

If the optional argument arg is not-nil (i.e. you have given a prefix argument), the current environment is modified and no new environment is inserted.

As a default selection, AUCTEX will suggest the environment last inserted or, as the first choice the value of the variable LaTeX-default-environment.

LaTeX-default-environment

[User Option]

Default environment to insert when invoking 'LaTeX-environment' first time.

If the document is empty, or the cursor is placed at the top of the document, AUCTEX will default to insert a 'document' environment.

Most of these are described further in the following sections, and you may easily specify more, as described in 'Customizing environments'.

You can close the current environment with C-c], but we suggest that you use C-c C-e to insert complete environments instead.

LaTeX-close-environment

[Command]

(C-c]) Insert an '\end' that matches the current environment.

2.4.1 Equations

When inserting equation-like environments, the '\label' will have a default prefix, which is controlled by the following variables:

LaTeX-equation-label

[User Option]

Prefix to use for 'equation' labels.

LaTeX-eqnarray-label

[User Option]

Prefix to use for 'equarray' labels.

LaTeX-amsmath-label

[User Option]

Prefix to use for amsmath equation labels. Amsmath equations include 'align', 'alignat', 'xalignat', 'aligned', 'flalign' and 'gather'.

2.4.2 Floats

Figures and tables (i.e., floats) may also be inserted using AUCTEX. After choosing either 'figure' or 'table' in the environment list described above, you will be prompted for a number of additional things.

This field is the option of float environments that controls how they are placed in the final document. In LATEX this is a sequence of the letters 'http' as described in the LATEX manual. The value will default to the value of LaTeX-float.

caption This is the caption of the float.

The label of this float. The label will have a default prefix, which is controlled by the variables LaTeX-figure-label and LaTeX-table-label.

Moreover, in the case of a 'figure' environment, you will be asked if you want to insert a 'center' environment inside the figure.

LaTeX-float [User Option]

Default placement for floats.

LaTeX-figure-label

[User Option]

Prefix to use for figure labels.

LaTeX-table-label

[User Option]

Prefix to use for table labels.

2.4.3 Itemize-like

In an itemize-like environment, nodes (i.e., '\item's) may be inserted using C-c (LFD).

LaTeX-insert-item

[Command]

(C-c (LFD)) Close the current item, move to the next line and insert an appropriate '\item' for the current environment. That is, 'itemize' and 'enumerate' will have '\item' inserted, while 'description' will have '\item[]' inserted.

2.4.4 Tabular-like

When inserting Tabular-like environments, that is, 'tabular' 'array' etc., you will be prompted for a template for that environment. Related variables:

LaTeX-default-format

[User Option]

Default format string for array and tabular environments.

LaTeX-default-position

[User Option]

Default position string for array and tabular environments. If nil, act like the empty string is given, but don't prompt for a position.

2.4.5 Customizing environments

See Section 9.3 [Adding Environments], page 37, for how to customize the list of known environments.

3 Advanced Editing Features

The previous chapter described how to write the main body of the text easily and with a minimum of errors. In this chapter we will describe some features for entering more specialized sorts of text, for formatting the source by indenting and filling and for navigating through the document.

3.1 Entering Mathematics

TEX is written by a mathematician, and has always contained good support for formatting mathematical text. AUCTEX supports this tradition, by offering a special minor mode for entering text with many mathematical symbols. You can enter this mode by typing C-c.

LaTeX-math-mode [Command]

(C-c ~) Toggle LaTeX-math-mode. This is a minor mode rebinding the key LaTeX-math-abbrev-prefix to allow easy typing of mathematical symbols. 'will read a character from the keyboard, and insert the symbol as specified in LaTeX-math-list. If given a prefix argument, the symbol will be surrounded by dollar signs.

You can use another prefix key (instead of ') by setting the variable LaTeX-math-abbrev-prefix.

LaTeX-math-abbrev-prefix

[User Option]

A string containing the prefix of LaTeX-math-mode commands; This value defaults to

The variable LaTeX-math-list holds the actual mapping.

LaTeX-math-list [User Option]

A list containing key command mappings to use in LaTeX-math-mode. The car of each element is the key and the cdr is the macro name.

LaTeX-math-menu-unicode

[User Option]

Whether the LaTeX menu should try using Unicode for effect. Your Emacs built must be able to display include Unicode characters in menus for this feature.

AUCTEX's reference card 'tex-ref.tex' includes a list of all math mode commands.

3.2 Completion

Emacs lisp programmers probably know the lisp-complete-symbol command, usually bound to M- $\langle TAB \rangle$. Users of the wonderful ispell mode know and love the ispell-complete-word command from that package. Similarly, AUCTEX has a TeX-complete-symbol command, usually bound to M- $\langle TAB \rangle$. Using LaTeX-complete-symbol makes it easier to type and remember the names of long IATEX macros.

In order to use TeX-complete-symbol, you should write a backslash and the start of the macro. Typing $M-\langle \overline{TAB} \rangle$ will now complete as much of the macro, as it unambiguously can. For example, if you type "\renewc" and then ' $M-\langle \overline{TAB} \rangle$, it will expand to "\renewcommand".

TeX-complete-symbol

[Command]

 $(M-\langle \overline{TAB} \rangle)$ Complete T_FX symbol before point.

A more direct way to insert a macro is with TeX-insert-macro, bound to *C-c C-m*. It has the advantage over completion that it knows about the argument of most standard IATEX macros, and will prompt for them. It also knows about the type of the arguments, so it will for example give completion for the argument to '\include'. Some examples are listed below.

TeX-insert-macro [Command]

(C-c C-m) Prompt (with completion) for the name of a TEX macro, and if AUCTEX knows the macro, prompt for each argument.

As a default selection, AUCTEX will suggest the macro last inserted or, as the first choice the value of the variable TeX-default-macro.

TeX-insert-macro-default-style

[User Option]

Specifies whether TeX-insert-macro will ask for all optional arguments.

If set to the symbol show-optional-args, TeX-insert-macro asks for optional arguments of TeX macros. If set to mandatory-args-only, TeX-insert-macro asks only for mandatory argument. When TeX-insert-macro is called with prefix argument (C-u), it's the other way round.

Note that for some macros, there are special mechanisms, e.g. LaTeX-includegraphics-options-alist.

TeX-default-macro

[User Option]

Default macro to insert when invoking TeX-insert-macro first time.

A faster alternative is to bind the function TeX-electric-macro to '\'. This can be done by setting the variable TeX-electric-escape

TeX-electric-escape

[User Option]

If this is non-nil when AUCTEX is loaded, the TEX escape character '\' will be bound to TeX-electric-macro

The difference between TeX-insert-macro and TeX-electric-macro is that space will complete and exit from the minibuffer in TeX-electric-macro. Use (TAB) if you merely want to complete.

TeX-electric-macro

[Command]

Prompt (with completion) for the name of a T_EX macro, and if AUCT_EX knows the macro, prompt for each argument. Space will complete and exit.

By default AUCT_EX will put an empty set braces '{}' after a macro with no arguments to stop it from eating the next whitespace. This can be stopped by entering LaTeX-math-mode, see Section 3.1 [Mathematics], page 11, or by setting TeX-insert-braces to nil

TeX-insert-braces

[User Option]

If non-nil, append a empty pair of braces after inserting a macro.

Completions work because AUCTEX can analyze TEX files, and store symbols in emacs lisp files for later retrieval. See Chapter 8 [Automatic], page 31, for more information.

AUCTEX will also make completion for many macro arguments, for example existing labels when you enter a '\ref' macro with TeX-insert-macro or TeX-electric-macro, and BibTeX entries when you enter a '\cite' macro. For this kind of completion to work, parsing must be enabled as described in see Chapter 6 [Parsing Files], page 27. For '\cite' you must also make sure that the BibTeX files have been saved at least once after you enabled automatic parsing on save, and that the basename of the BibTeX file does not conflict with the basename of one of TeX files.

3.3 Commenting

It is often necessary to comment out temporarily a region of T_EX or I_AT_EX code. This can be done with the commands C-c; and C-c%. C-c; will comment out all lines in the current region, while C-c% will comment out the current paragraph. Type C-c; again to uncomment all lines of a commented region, or C-c% again to uncomment all comment lines around point. These commands will insert or remove a single '%' respectively.

TeX-comment-or-uncomment-region

[Command]

(C-c;) Add or remove '%' from the beginning of each line in the current region. Uncommenting works only if the region encloses solely commented lines. If AUCTEX should not try to guess if the region should be commented or uncommented the commands TeX-comment-region and TeX-uncomment-region can be used to explicitly comment or uncomment the region in concern.

TeX-comment-or-uncomment-paragraph

[Command]

(C-c %) Add or remove '%' from the beginning of each line in the current paragraph. When removing '%' characters the paragraph is considered to consist of all preceding and succeeding lines starting with a '%', until the first non-comment line.

3.4 Indenting

Indentation means the addition of whitespace at the beginning of lines to reflect special syntactical constructs. This makes it easier to see the structure of the document, and to catch errors such as a missing closing brace. Thus, the indentation is done for precisely the same reasons that you would indent ordinary computer programs.

Indentation is done by I₄TEX environments and by TEX groups, that is the body of an environment is indented by the value of LaTeX-indent-level (default 2). Also, items of an 'itemize-like' environment are indented by the value of LaTeX-item-indent, default −2. If more environments are nested, they are indented 'accumulated' just like most programming languages usually are seen indented in nested constructs.

You can explicitely indent single lines, usually by pressing (TAB), or marked regions by calling indent-region on it. If you have auto-fill-mode enabled and a line is broken while you type it, Emacs automatically cares about the indentation in the following line. If you want to have a similar behavior upon typing (RET), you can customize the variable TeX-newline-function and change the default of newline which does no indentation to newline-and-indent which indents the new line or reindent-then-newline-and-indent which indents both the current and the new line.

There are certain LATEX environments which should be indented in a special way, like 'tabular' or 'verbatim'. Those environments may be specified in the variable LaTeX-

indent-environment-list together with their special indentation functions. Taking the 'verbatim' environment as an example you can see that current-indentation is used as the indentation function. This will stop AUCTEX from doing any indentation in the environment if you hit (TAB) for example.

There are environments in LaTeX-indent-environment-list which do not bring a special indentation function with them. This is due to the fact that first the respective functions are not implemented yet and second that filling will be disabled for the specified environments. This shall prevent the source code from being messed up by accidently filling those environments with the standard filling routine. If you think that providing special filling routines for such environments would be an appropriate and challenging task for you, you are invited to contribute. (See Section 3.5 [Filling], page 15, for further information about the filling functionality)

The check for the indentation function may be enabled or disabled by customizing the variable LaTeX-indent-environment-check.

As a side note with regard to formatting special environments: Newer Emacsen include 'align.el' and therefore provide some support for formatting 'tabular' and 'tabbing' environments with the function align-current which will nicely align columns in the source code.

AUCTEX is able to format commented parts of your code just as any other part. This means LATEX environments and TEX groups in comments will be indented syntactically correct if the variable LaTeX-syntactic-comments is set to t. If you disable it, comments will be filled like normal text and no syntactic indentation will be done.

Following you will find a list of most commands and variables related to indenting with a small summary in each case:

- (TAB) LaTeX-indent-line will indent the current line.
- $\langle \underline{\text{LFD}} \rangle$ newline-and-indent inserts a new line (much like $\langle \underline{\text{RET}} \rangle$) and moves the cursor to an appropriate position by the left margin.

Most keyboards nowadays don't have a linefeed key and C-j is tedious to type. Therefore you can customize AUCTEX to perform indentation (or to make coffee) upon typing $\langle \overline{\text{RET}} \rangle$ as well. The respective option is called TeX-newline-function.

C-j Alias for $\langle LFD \rangle$

LaTeX-indent-environment-list

[User Option]

List of environments with special indentation. The second element in each entry is the function to calculate the indentation level in columns.

The filling code currently cannot handle tabular-like environments which will be completely messed-up if you try to format them. This is why most of these environments are included in this customization option without a special indentation function. This will prevent that they get filled.

LaTeX-indent-level

[User Option]

Number of spaces to add to the indentation for each '\begin' not matched by a '\end'.

LaTeX-item-indent

[User Option]

Number of spaces to add to the indentation for '\item''s in list environments.

TeX-brace-indent-level

[User Option]

Number of spaces to add to the indentation for each '{' not matched by a '}'.

LaTeX-syntactic-comments

[User Option]

If non-nil comments will be filled and indented according to LATEX syntax. Otherwise they will be filled like normal text.

TeX-newline-function

[User Option]

Used to specify the function which is called when (RET) is pressed. This will normally be newline which simply inserts a new line. In case you want to have AUCTEX do indentation as well when you press (RET), use the built-in functions newline-and-indent or reindent-then-newline-and-indent. The former inserts a new line and indents the following line, i.e. it moves the cursor to the right position and therefore acts as if you pressed (LFD). The latter function additionally indents the current line. If you choose 'Other', you can specify your own fancy function to be called when (RET) is pressed.

3.5 Filling

Filling deals with the insertion of line breaks to prevent lines from becoming wider than what is specified in fill-column. The linebreaks will be inserted automatically if auto-fill-mode is enabled. In this case the source is not only filled but also indented automatically as you write it.

auto-fill-mode can be enabled for AUCTEX by calling turn-on-auto-fill in one of the hooks AUCTEX is running. For all text modes with text-mode-hook, for all AUCTEX modes with TeX-mode-hook or for specific modes with plain-TeX-mode-hook, LaTeX-mode-hook, ConTeXt-mode-hook or docTeX-mode-hook. As an example, if you want to enable auto-fill-mode in LaTeX-mode, put the following into your init file:

```
(add-hook 'LaTeX-mode-hook 'turn-on-auto-fill)
```

You can manually fill explicitly marked regions, paragraphs, environments, complete sections, or the whole buffer. (Note that manual filling in AUCT_EX will indent the start of the region to be filled in contrast to many other Emacs modes.)

There are some syntactical constructs which are handled specially with regard to filling. These are so-called code comments and paragraph commands.

Code comments are comments preceded by code or text in the same line. Upon filling a region, code comments themselves will not get filled. Filling is done from the start of the region to the line with the code comment and continues after it. In order to prevent overfull lines in the source code, a linebreak will be inserted before the last non-comment word by default. This can be changed by customizing LaTeX-fill-break-before-code-comments. If you have overfull lines with code comments you can fill those explicitly by calling LaTeX-fill-paragraph or pressing M-q with the cursor positioned on them. This will add linebreaks in the comment and indent subsequent comment lines to the column of the comment in the first line of the code comment. In this special case M-q only acts on the current line and not on the whole paragraph.

Lines with '\par' are treated similarly to code comments, i.e. '\par' will be treated as paragraph boundary which should not be followed by other code or text. But it is not

treated as a real paragraph boundary like an empty line where filling a paragraph would stop.

Paragraph commands like '\section' or '\noindent' (the list of commands is defined by LaTeX-paragraph-commands) are often to be placed in their own line(s). This means they should not be consecuted with any preceding or following adjacent lines of text. AUCTEX will prevent this from happening if you do not put any text except another macro after the end of the last brace of the respective macro. If there is other text after the macro, AUCTEX regards this as a sign that the macro is part of the following paragraph.

Here are some examples:

```
\begin{quote}
  text text text
\begin{quote}\label{foo}
  text text text text
```

If you press M-q on the first line in both examples, nothing will change. But if you write

```
\begin{quote} text
  text text text text
and press M-q, you will get
```

\begin{quote} text text text text

Besides code comments and paragraph commands, another speciality of filling in AUCTEX involves commented lines. You should be aware that these comments are treated as islands in the rest of the LATEX code if syntactic filling is enabled. This means, for example, if you try to fill an environment with LaTeX-fill-environment and have the cursor placed on a commented line which does not have a surrounding environment inside the comment, AUCTEX will report an error.

The relevant commands and variables with regard to filling are:

```
C-c C-q C-p
```

LaTeX-fill-paragraph will fill and indent the current paragraph.

M-q Alias for C-c C-q C-p

C-c C-q C-e

LaTeX-fill-environment will fill and indent the current environment. This may e.g. be the 'document' environment, in which case the entire document will be formatted.

C-c C-q C-s

LaTeX-fill-section will fill and indent the current logical sectional unit.

C-c C-q C-r

LaTeX-fill-region will fill and indent the current region.

M-g Alias for C-c C-q C-r

LaTeX-fill-break-at-separators

[User Option]

List of separators before or after which respectively linebreaks will be inserted if they do not fit into one line. The separators can be curly braces, brackets, switches for inline math ('\$', '\(', '\)') and switches for display math (' $\[', '\]'$). Such formatting

can be useful to make macros and math more visible or to prevent overfull lines in the IATEX source in case a package for displaying formatted TEX output inside the Emacs buffer, like preview-latex, is used.

LaTeX-fill-break-before-code-comments

[User Option]

Code comments are comments preceded by some other text in the same line. When a paragraph containing such a comment is to be filled, the comment start will be seen as a border after which no line breaks will be inserted in the same line. If the option LaTeX-fill-break-before-code-comments is enabled (which is the default) and the comment does not fit into the line, a line break will be inserted before the last non-comment word to minimize the chance that the line becomes overfull.

3.6 Showing and Hiding Text in the Buffer

While you are editing your text you might find certain parts of it distracting or not worthwile to be displayed. AUCTEX lets you hide those parts and show them again at request. There is a built-in support for hiding macros and environments which we call "folding" here, as well as support for Emacs' outline mode.

3.6.1 Folding

Are you often annoyed by footnotes and citations clobbering your text? Do you pull your hair when you cannot see what you are actually writing because of all those macros for font specification and logical mark-up? Then folding might be for you.

There can be macros and environments which have content that is not part of the text body you are writing, like footnotes and citations. Those enclose text which you often only want to see while actually editing it and which otherwise distract your view of the document body. Similarly there are macros where you are not interested in viewing the macro besides its content but rather want to see the content only, like font specifiers where the content might already be fontified in a special way by font locking.

With AUCTEX's folding functionality you can collapse those items and replace them by either a fixed string or the content of one of their arguments instead. If you want to make the original text visible again temporarily in order to view or edit it, move point sideways onto the placeholder (also called display string) or left-click with the mouse pointer on it. (The latter is currently only supported on GNU Emacs.) The macro or environment will unfold automatically, stay open as long as point is inside of it and collapse again once you move point out of it. (Note that folding of environments currently does not work in every AUCTEX mode.)

In order to use this feature, you have to activate TeX-fold-mode which will activate the auto-reveal feature and the necessary commands to hide and show macros and environments. You can activate the mode in a certain buffer by typing the command M-x TeX-fold-mode RET or using the keyboard shortcut C-c C-o C-f. If you want to use it every time you edit a IATEX document, add it to a hook:

If it should be activated in all AUCTEX modes, use TeX-mode-hook instead of LaTeX-mode-hook.

Once the mode is active there are several commands available to hide and show macros and environments:

TeX-fold-buffer [Command]

(*C-c C-o C-b*) Hide all macros specified in the variables TeX-fold-macro-spec-list and TeX-fold-env-spec-list. This command can also be used to refresh the whole buffer and hide any new macros and environments which were inserted after the last invocation of the command.

TeX-fold-macro [Command]

(C-c C-o C-m) Hide the macro on which point currently is located. If the name of the macro is found in TeX-fold-macro-spec-list, the respective display string will be shown instead. If it is not found, the name of the macro in square brackets or the default string for unspecified macros (TeX-fold-unspec-macro-display-string) will be shown, depending on the value of the variable TeX-fold-unspec-use-name.

TeX-fold-env [Command]

(C-c C-o C-e) Hide the environment on which point currently is located. The behavior regarding the display string is analogous to TeX-fold-macro and determined by the variables TeX-fold-env-spec-list and TeX-fold-unspec-env-display-string respectively.

TeX-fold-clearout-buffer

[Command]

 $(C-c \ C-o \ C-x)$ Permanently unfold all macros and environments in the current buffer.

TeX-fold-clearout-item

[Command]

(*C-c C-o C-c*) Permanently show the macro or environment on which point currently is located. In contrast to temporarily opening the macro when point is moved sideways onto it, the macro will be permanently unfolded and will not collapse again once point is leaving it.

The commands above will only take macros or environments into consideration which are specified in the variable TeX-fold-macro-spec-list or TeX-fold-env-spec-list respectively.

TeX-fold-macro-spec-list

[User Option]

List of display strings or argument numbers and macros to fold. If you specify a number, the content of the first mandatory argument of a LATEX macro will be used as the placeholder.

The placeholder is made by copying the text from the buffer together with its properties, i.e. its face as well. If fontification has not happened when this is done (e.g. because of lazy font locking) the intended fontification will not show up. As a workaround you can leave Emacs idle a few seconds and wait for stealth font locking to finish before you fold the buffer. Or you just re-fold the buffer with TeX-fold-buffer when you notice a wrong fontification.

TeX-fold-env-spec-list

[User Option]

List of display strings or argument numbers and environments to fold. Argument numbers refer to the '\begin' statement. That means if you have e.g. '\begin{tabularx}{\linewidth}{XXX}...\end{tabularx}' and specify 3 as the argument number, the resulting display string will be "XXX".

TeX-fold-unspec-macro-display-string

[User Option]

Default display string for macros which are not specified in TeX-fold-macro-speclist.

TeX-fold-unspec-env-display-string

[User Option]

Default display string for environments which are not specified in TeX-fold-env-spec-list.

TeX-fold-unspec-use-name

[User Option]

If non-nil the name of the macro or environment surrounded by square brackets is used as display string, otherwise the defaults specified in TeX-fold-unspec-macro-display-string or TeX-fold-unspec-env-display-string respectively.

3.6.2 Outlining the Document

AUCTEX supports the standard outline minor mode using LATEX/ConTEXt sectioning commands as header lines. See section "Outline Mode" in GNU Emacs Manual.

You can add your own headings by setting the variable TeX-outline-extra.

TeX-outline-extra

[Variable]

List of extra T_FX outline levels.

Each element is a list with two entries. The first entry is the regular expression matching a header, and the second is the level of the header. A '~' is automatically prepended to the regular expressions in the list, so they must match text at the beginning of the line.

See LaTeX-section-list or ConTeXt-INTERFACE-section-list for existing header levels.

The following example add '\item' and '\bibliography' headers, with '\bibliography' at the same outline level as '\section', and '\item' being below '\subparagraph'.

You may want to check out the unbundled 'out-xtra' package for even better outline support. It is available from your favorite emacs lisp archive.

4 Starting processors, viewers and other programs

The most powerful features of AUCTEX may be those allowing you to run (La)TEX/ConTEXt and other external commands like BibTEX and makeindex from within Emacs, viewing and printing the results, and moreover allowing you to debug your documents.

4.1 Executing Commands

Formatting the document with TEX, IATEX or ConTEXt, viewing with a previewer, printing the document, running BibTEX, making an index, or checking the document with lacheck or chktex all require running an external command.

There are two ways to run an external command, you can either run it on all of the current documents with TeX-command-master, or on the current region with TeX-command-region. A special case of running TeX on a region is TeX-command-buffer which differs from TeX-command-master if the current buffer is not its own master file.

TeX-command-master

[Command]

(C-c C-c) Query the user for a command, and run it on the master file associated with the current buffer. The name of the master file is controlled by the variable TeX-master. The available commands are controlled by the variable TeX-command-list.

See Chapter 10 [Installation], page 41, for a discussion about TeX-command-list and Chapter 5 [Multifile], page 25 for a discussion about TeX-master.

TeX-command-region

[Command]

(C-c C-r) Query the user for a command, and run it on the "region file". Some commands (typically those invoking TeX or LATeX) will write the current region into the region file, after extracting the header and tailer from the master file. If mark is inactive (which can happen with transient-mark-mode), use the old region. The name of the region file is controlled by the variable TeX-region. The name of the master file is controlled by the variable TeX-master. The header is all text up to the line matching the regular expression TeX-header-end. The trailer is all text from the line matching the regular expression TeX-trailer-start. The available commands are controlled by the variable TeX-command-list.

TeX-pin-region

[Command]

 $(C-c\ C-t\ C-r)$ If you don't have a mode like transient-mark-mode active, where marks get disabled automatically, the region would need to get properly set before each call to TeX-command-region. If you fix the current region with $C-c\ C-t\ C-r$, then it will get used for more commands even though mark and point may change. An explicitly activated mark, however, will always define a new region when calling TeX-command-region.

TeX-command-buffer

[Command]

(C-c C-b) Query the user for a command, and run it on the "region file". Some commands (typically those invoking TeX or LATeX) will write the current buffer into the region file, after extracting the header and tailer from the master file. See above for details.

AUCTEX will allow one process for each document, plus one process for the region file to be active at the same time. Thus, if you are editing n different documents, you can have n plus one processes running at the same time. If the last process you started was on the region, the commands described in Section 4.3 [Debugging], page 23 and Section 4.5 [Control], page 24 will work on that process, otherwise they will work on the process associated with the current document.

TeX-region [User Option]

The name of the file for temporarily storing the text when formatting the current region.

TeX-header-end [User Option]

A regular expression matching the end of the header. By default, this is 'begin{document}' in IATEX mode and '%**end of header' in TEX mode.

TeX-trailer-start [User Option]

A regular expression matching the start of the trailer. By default, this is '\end{document}' in IATFX mode and '\bye' in TFX mode.

AUCTEX will try to guess what command you want to invoke, but by default it will assume that you want to run TeX in TeX mode and LATeX in LATeX mode. You can overwrite this by setting the variable TeX-command-default.

TeX-command-default

[User Option]

The default command to run in this buffer. Must be an entry in TeX-command-list.

If you want to overwrite the values of TeX-header-end, TeX-trailer-start, or TeX-command-default, you can do that for all files by setting them in either TeX-mode-hook, plain-TeX-mode-hook, or LaTeX-mode-hook. To overwrite them for a single file, define them as file variables (see section "File Variables" in *The Emacs Editor*). You do this by putting special formatted text near the end of the file.

```
%%% Local Variables:
```

%%% TeX-header-end: "% End-Of-Header"

%%% TeX-trailer-start: "% Start-Of-Trailer"

%%% TeX-command-default: "SliTeX"

%%% End:

AUCTEX will try to save any buffers related to the document, and check if the document needs to be reformatted. If the variable TeX-save-query is non-nil, AUCTEX will query before saving each file. By default AUCTEX will check emacs buffers associated with files in the current directory, in one of the TeX-macro-private directories, and in the TeX-macro-global directories. You can change this by setting the variable TeX-check-path.

TeX-check-path

[User Option]

Directory path to search for dependencies.

If nil, just check the current file. Used when checking if any files have changed.

TeX-PDF-mode [Command]

(C-c C-t C-p) This command toggles the PDF mode of AUCT_EX, a buffer-local minor mode. You can customize TeX-PDF-mode to give it a different default. The default

is used when AUCT_EX does not have additional clue about what a document might want. This option usually results in calling either PDFT_EX or ordinary T_EX.

TeX-DVI-via-PDFTeX

[User Option]

If this is set, DVI will also be produced by calling PDFTEX, setting \pdfoutput=0. This makes it possible to use packages like 'pdfcprot' even when producing DVI files.

TeX-interactive-mode

[Command]

(C-c C-t C-i) This command toggles the interactive mode of AUCTEX, a global minor mode. You can customize TeX-interactive-mode to give it a different default. In interactive mode, TeX will pause with an error prompt when errors are encountered and wait for the user to type something.

TeX-source-specials-mode

[Command]

(*C-c C-t C-s*) toggles Source Special support. Source Specials will move the DVI viewer to the location corresponding to point (forward search), and it will use 'emacsclient' or 'gnuclient' to have the previewer move Emacs to a location corresponding to a control-click in the previewer window. See Section 4.2 [Viewing], page 22.

You can permanently activate TeX-source-specials-mode with

(TeX-source-specials-mode 1)

or by customizing the variable TeX-source-specials-mode. There is a bunch of customization options, use customize-group on the group 'TeX-source-specials' to find out more.

It has to be stressed *very* strongly however, that Source Specials can cause differences in page breaks, in spacing, can seriously interfere with various packages and should thus *never* be used for the final version of a document. In particular, fine-tuning the page breaks should be done with Source Specials switched off.

4.2 Viewing the formatted output

AUCTEX allows you to start external programs for previewing your document. These are normally invoked by pressing C-c once the document is formatted or via the respective entry in the Command menu.

AUCTEX will try to guess which type of viewer (DVI, PostScript or PDF) has to be used and what options are to be passed over to it. This decision is based on the output files present in the working directory as well as the class and style options used in the document. For example, if there is a DVI file in your working directory, a DVI viewer will be invoked. In case of a PDF file it will be a PDF viewer. If you specified a special paper format like 'a5paper' or use the 'landscape' option, this will be passed to the viewer by the appropriate options. Especially some DVI viewers depend on this kind of information in order to display your document correctly. In case you are using 'pstricks' or 'psfrag' in your document, a DVI viewer cannot display the contents correctly and a PostScript viewer will be invoked instead.

The information about which file types and style options are associated with which viewers and options for them is stored in the variables TeX-output-view-style and TeX-view-style.

TeX-view [Command]

The command TeX-view, bound to C-c C-v, starts a viewer without confirmation. The viewer is started either on a region or the master file, depending on the last command issued. This is especially useful for jumping to the location corresponding to point in the DVI viewer when using TeX-source-specials-mode.

TeX-output-view-style

[User Option]

List of output file extensions, style options and view options.

TeX-view-style

[User Option]

List of style options and view options. This is the predecessor of TeX-output-view-style which does not allow the specification of output file extensions. It is used as a fallback in case none of the alternatives specified in TeX-output-view-style match. In case none of the entries in TeX-view-style match either, no suggestion for a viewer will be made.

4.2.1 Forward and inverse search

You can make use of forward and inverse searching if this is supported by your DVI viewer and you enabled TeX-source-specials-mode as described in Section 4.1 [Commands], page 20. AUCTEX will automatically pass the necessary command line options to the viewer in order to display the page containing the content you are currently editing (forward search). Upon opening the viewer you will be asked if you want to start a server process (Gnuserv or Emacs server) which is necessary for inverse search. This happens only if there is no server running already. You can customize the variable TeX-source-specials-view-start-server to inhibit the question and always or never start the server respectively. Once the server and the viewer are running you can use a mouse click in the viewer to jump to the corresponding part of your document in Emacs (inverse search). Refer to the documentation of your viewer to find out what you have to do exactly. In xdvi you usually have to use *C-down-mouse-1*.

TeX-source-specials-view-start-server

[User Option]

If TeX-source-specials-mode is active and a DVI viewer is invoked, the default behavior is to ask if a server process should be started. Set this variable to t if the question should be inhibited and the server should be started always. Set it to nil if the server should never be started. Inverse search will not be available in the latter case.

4.3 Catching the errors

Once you've formatted your document you may 'debug' it, i.e. browse through the errors (La)T_FX reported.

TeX-next-error [Command]

(C-c') Go to the next error reported by T_EX . The view will be split in two, with the cursor placed as close as possible to the error in the top view. In the bottom view, the error message will be displayed along with some explanatory text.

Normally AUCTEX will only report real errors, but you may as well ask it to report 'bad boxes' as well.

TeX-toggle-debug-bad-boxes

[Command]

 $(C-c\ C-w)$ Toggle whether AUCTEX should stop at bad boxes (i.e. over/under full boxes) as well as at normal errors.

As default, AUCTEX will display that special '*help*' buffer containing the error reported by TEX along with the documentation. There is however an 'expert' option, which allows you to display the real TEX output.

TeX-display-help

[User Option]

When non-nil AUCT_EX will automatically display a help text whenever an error is encountered using TeX-next-error (C-c).

4.4 Checking for problems

Running TEX or IATEX will only find regular errors in the document, not examples of bad style. Furthermore, description of the errors may often be confusing. The utility lacheck can be used to find style errors, such as forgetting to escape the space after an abbreviation or using '...' instead of 'ldots' and many other problems like that. You start lacheck with C-c C-c Check (RET). The result will be a list of errors in the '*compilation*' buffer. You can go through the errors with C-x ' (next-error, see section "Compilation" in The Emacs Editor), which will move point to the location of the next error.

Another newer program which can be used to find errors is chktex. It is much more configurable than lacheck, but doesn't find all the problems lacheck does, at least in its default configuration. You must install the programs before using them, and for chktex you must also modify TeX-command-list. You can get lacheck from '<URL:ftp://ftp.ctan.org/tex-archive/support/lacheck/>' or alternatively chktex from '<URL:ftp://ftp.ctan.org/tex-archive/support/chktex/>'. Search for 'chktex' in 'tex.el' to see how to switch between them.

4.5 Controlling the output

A number of commands are available for controlling the output of an application running under $AUCT_{FX}$

TeX-kill-job [Command]

(C-c C-k) Kill currently running external application. This may be either of TEX, LATEX, previewer, BibTEX, etc.

TeX-recenter-output-buffer

[Command]

(C-c C-1) Recenter the output buffer so that the bottom line is visible.

TeX-home-buffer [Command]

 $(C-c^{\circ})$ Go to the 'master' file in the document associated with the current buffer, or if already there, to the file where the current process was started.

5 Multifile Documents

You may wish to spread a document over many files (as you are likely to do if there are multiple authors, or if you have not yet discovered the power of the outline commands (see Section 3.6.2 [Outline], page 19)). This can be done by having a "master" file in which you include the various files with the TeX macro '\input' or the LATeX macro '\input'. These files may also include other files themselves. However, to format the document you must run the commands on the top level master file.

When you, for example, ask AUCTEX to run a command on the master file, it has no way of knowing the name of the master file. By default, it will assume that the current file is the master file. If you insert the following in your '.emacs' file AUCTEX will use a more advanced algorithm.

(setq-default TeX-master nil); Query for master file.

If AUCTEX finds the line indicating the end of the header in a master file (TeX-header-end), it can figure out for itself that this is a master file. Otherwise, it will ask for the name of the master file associated with the buffer. To avoid asking you again, AUCTEX will automatically insert the name of the master file as a file variable (see section "File Variables" in *The Emacs Editor*). You can also insert the file variable yourself, by putting the following text at the end of your files.

```
%%% Local Variables:
%%% TeX-master: "master"
%%% End:
```

You should always set this variable to the name of the top level document. If you always use the same name for your top level documents, you can set TeX-master in your '.emacs' file.

(setq-default TeX-master "master"); All master files called "master".

TeX-master [User Option]

The master file associated with the current buffer. If the file being edited is actually included from another file, then you can tell AUCTEX the name of the master file by setting this variable. If there are multiple levels of nesting, specify the top level file.

If this variable is nil, AUCTEX will query you for the name.

If the variable is t, then AUCT_FX will assume the file is a master file itself.

If the variable is shared, then AUCTEX will query for the name, but will not change the file.

TeX-one-master [User Option]

Regular expression matching ordinary TEX files.

You should set this variable to match the name of all files, for which it is a good idea to append a TeX-master file variable entry automatically. When AUCTEX adds the name of the master file as a file variable, it does not need to ask next time you edit the file.

If you dislike AUCTEX automatically modifying your files, you can set this variable to '"<none>"'. By default, AUCTEX will modify any file with an extension of '.tex'.

TeX-master-file-ask

[Command]

 $(C-c_{-})$ Query for the name of a master file and add the respective File Variables (see section "File Variables" in *The Emacs Editor*) to the file for setting this variable permanently.

AUCTEX will not ask for a master file when it encounters existing files. This function shall give you the possibility to insert the variable manually.

AUCTEX keeps track of macros, environments, labels, and style files that are used in a given document. For this to work with multifile documents, AUCTEX has to have a place to put the information about the files in the document. This is done by having an 'auto' subdirectory placed in the directory where your document is located. Each time you save a file, AUCTEX will write information about the file into the 'auto' directory. When you load a file, AUCTEX will read the information in the 'auto' directory about the file you loaded and the master file specified by TeX-master. Since the master file (perhaps indirectly) includes all other files in the document, AUCTEX will get information from all files in the document. This means that you will get from each file, for example, completion for all labels defined anywhere in the document.

AUCTEX will create the 'auto' directory automatically if TeX-auto-save is non-nil. Without it, the files in the document will not know anything about each other, except for the name of the master file. See Section 8.3 [Automatic Local], page 32.

TeX-save-document

[Command]

 $(C-c \ C-d)$ Save all buffers known to belong to the current document.

TeX-save-query

[User Option]

If non-nil, then query the user before saving each file with TeX-save-document.

6 Automatic Parsing of TeX files

AUCTEX depends heavily on being able to extract information from the buffers by parsing them. Since parsing the buffer can be somewhat slow, the parsing is initially disabled. You are encouraged to enable them by adding the following lines to your '.emacs' file.

```
(setq TeX-parse-self t) ; Enable parse on load.
(setq TeX-auto-save t) ; Enable parse on save.
```

The later command will make AUCTEX store the parsed information in an 'auto' subdirectory in the directory each time the TEX files are stored, see Section 8.3 [Automatic Local], page 32. If AUCTEX finds the pre-parsed information when loading a file, it will not need to reparse the buffer. The information in the 'auto' directory is also useful for multifile documents see Chapter 5 [Multifile], page 25, since it allows each file to access the parsed information from all the other files in the document. This is done by first reading the information from the master file, and then recursively the information from each file stored in the master file.

The variables can also be done on a per file basis, by changing the file local variables.

```
%%% Local Variables:
%%% TeX-parse-self: t
%%% TeX-auto-save: t
%%% End:
```

Even when you have disabled the automatic parsing, you can force the generation of style information by pressing C-c C-n. This is often the best choice, as you will be able to decide when it is necessary to reparse the file.

TeX-parse-self [User Option]

Parse file after loading it if no style hook is found for it.

TeX-auto-save [User Option]

Automatically save style information when saving the buffer.

TeX-normal-mode arg

[Command]

(C-c C-n) Remove all information about this buffer, and apply the style hooks again. Save buffer first including style information. With optional argument, also reload the style hooks.

When AUCTEX saves your buffer, it can optionally convert all tabs in your buffer into spaces. Tabs confuse AUCTEX's error message parsing and so should generally be avoided. However, tabs are significant in some environments, and so by default AUCTEX does not remove them. To convert tabs to spaces when saving a buffer, insert the following in your '.emacs' file:

```
(setq TeX-auto-untabify t)
```

TeX-auto-untabify

[User Option]

Automatically remove all tabs from a file before saving it.

Instead of disabling the parsing entirely, you can also speed it significantly up by limiting the information it will search for (and store) when parsing the buffer. You can do this by setting the default values for the buffer local variables TeX-auto-regexp-list and TeX-auto-parse-length in your '.emacs' file.

```
;; Only parse \documentstyle information. (setq-default TeX-auto-regexp-list 'LaTeX-auto-minimal-regexp-list);; The documentstyle command is usually near the beginning. (setq-default TeX-auto-parse-length 2000)
```

This example will speed the parsing up significantly, but AUCTEX will no longer be able to provide completion for labels, macros, environments, or bibitems specified in the document, nor will it know what files belong to the document.

These variables can also be specified on a per file basis, by changing the file local variables.

```
%%% Local Variables:
%%% TeX-auto-regexp-list: TeX-auto-full-regexp-list
%%% TeX-auto-parse-length: 999999
%%% End:
```

TeX-auto-regexp-list

[User Option]

List of regular expressions used for parsing the current file.

TeX-auto-parse-length

[User Option]

Maximal length of T_EX file that will be parsed.

The pre-specified lists of regexps are defined below. You can use these before loading AUCT_EX by quoting them, as in the example above.

TeX-auto-empty-regexp-list

[Constant]

Parse nothing

LaTeX-auto-minimal-regexp-list

[Constant]

Only parse documentstyle.

LaTeX-auto-label-regexp-list

[Constant]

Only parse LATEX labels.

LaTeX-auto-regexp-list

[Constant]

Parse common LATEX commands.

plain-TeX-auto-regexp-list

[Constant]

Parse common plain TEX commands.

TeX-auto-full-regexp-list

[Constant]

Parse all TFX and LATFX commands that AUCTFX can use.

7 Internationalization

There are several problems associated with editing non-English T_EX with GNU Emacs. Modern versions of GNU Emacs and T_EX are usable for European (Latin, Cyrillic, Greek) based languages, but special versions of T_EX and Emacs are needed for Korean, Japanese, and Chinese.

7.1 Using AUCT_EX for European languages.

First you will need a way to write non-ASCII characters. You can either use macros, or teach TEX about the ISO character sets. I prefer the latter, it has the advantage that the usual standard emacs word movement and case change commands will work.

With LATEX2e, just add '\usepackage[latin1]{inputenc}'. Other languages than Western European ones will probably have other encoding needs.

To be able to display non-ASCII characters you will need an appropriate font and a version of GNU Emacs capable of displaying 8-bit characters (e.g. Emacs 21). The manner in which this is supported differs between Emacsen, so you need to take a look at your respective documentation.

A compromise is to use an European character set when editing the file, and convert to T_FX macros when reading and writing the files.

'iso-cvt.el'

Much like 'iso-tex.el' but is bundled with Emacs 19.23 and later.

'x-compose.el'

Similar package bundled with new versions of XEmacs.

'X-Symbol'

a much more complete package for both Emacs and XEmacs that can also handle a lot of mathematical characters and input methods.

AUCTEX supports style files for several languages. Each style file may modify some AUCTEX to better support the language, and will run a language specific hook that will allow you to for example change ispell dictionary, or run code to change the keyboard remapping. The following will for example choose a Danish dictionary for documents including the 'dk.sty' file. This requires parsing to be enabled, see Chapter 6 [Parsing Files], page 27.

```
(add-hook 'TeX-language-dk-hook
  (function (lambda () (ispell-change-dictionary "danish"))))
```

The following style files are recognized.

'dk' Runs style hook TeX-language-dk-hook.

'dutch' Runs style hook TeX-language-nl-hook.

'german' Runs style hook TeX-language-de-hook. Gives '"' word syntax and makes the (") key insert a literal '"'.

'italian' Runs style hook TeX-language-it-hook. Pressing $(\mbox{"})$ will insert '' or '' depending on context.

'plfonts'

'plhb'

Runs style hook TeX-language-pl-hook. Gives '"' word syntax and makes the (") key insert a literal '"'. Pressing (") twice will insert '"<' or '">' depending on context.

7.2 Japanese T_EX

To write Japanese text with AUCTEX you need to have versions of TEX and Emacs that support Japanese. There exist at least two variants of TEX for Japanese text (jTEX and pTEX), and AUCTEX can be used with MULE supported Emacsen.

To install Japanese support for AUCT_EX, copy 'tex-jp.el' to AUCT_EX installed directory. Next two commands will automatically install contributed files.

make contrib
make install-contrib

See 'INSTALL' and 'Makefile' for more information.

To use the Japanese TEX variants, simply enter japanese-tex-mode, japanese-latex-mode, or japanese-slitex-mode, and everything should work. If not, send mail to Shinji Kobayashi '<koba@flab.fujitsu.co.jp>', who kindly donated the code for supporting Japanese in AUCTEX. None of the primary AUCTEX maintainers understand Japanese, so they can not help you.

If you usually use AUCTEX in Japanese, setting following variables is useful.

TeX-default-mode

Mode to enter for a new file when it can't be determined whether the file is plain TeX or IATeX or what.

To use Japanese T_FX always, set japanese command for example:

(setq TeX-default-mode 'japanese-latex-mode)

japanese-TeX-command-default

[User Option]

[User Option]

The default command for TeX-command in japanese TeX mode.

The default value is '¡TeX'.

japanese-LaTeX-command-default

[User Option]

The default command for TeX-command in japanese LATEX mode.

The default value is 'jLaTeX'.

japanese-LaTeX-default-style

[User Option]

The default style/class when creating new japanese IAT_FX document.

The default value is 'j-article'.

See 'tex-jp.el' for more information.

8 Automatic Customization

Since AUCTEX is so highly customizable, it makes sense that it is able to customize itself. The automatic customization consists of scanning TeX files and extracting symbols, environments, and things like that.

The automatic customization is done on three different levels. The global level is the level shared by all users at your site, and consists of scanning the standard TEX style files, and any extra styles added locally for all users on the site. The private level deals with those style files you have written for your own use, and use in different documents. You may have a '~/lib/TeX/' directory where you store useful style files for your own use. The local level is for a specific directory, and deals with writing customization for the files for your normal TEX documents.

If compared with the environment variable TEXINPUTS, the global level corresponds to the directories built into TeX. The private level corresponds to the directories you add yourself, except for '.', which is the local level.

By default AUCTEX will search for customization files in all the global, private, and local style directories, but you can also set the path directly. This is useful if you for example want to add another person's style hooks to your path. Please note that all matching files found in TeX-style-path are loaded, and all hooks defined in the files will be executed.

TeX-style-path [User Option]

List of directories to search for AUCTEX style files. Each must end with a slash.

By default, when AUCTEX searches a directory for files, it will recursively search through subdirectories.

TeX-file-recurse [User Option]

Whether to search T_EX directories recursively: nil means do not recurse, a positive integer means go that far deep in the directory hierarchy, t means recurse indefinitely.

By default, AUCTEX will ignore files name '.', '..', 'SCCS', 'RCS', and 'CVS'.

TeX-ignore-file [User Option]

Regular expression matching file names to ignore.

These files or directories will not be considered when searching for T_EX files in a directory.

8.1 Automatic Customization for the Site

Assuming that the automatic customization at the global level was done when AUCTEX was installed, your choice is now: will you use it? If you use it, you will benefit by having access to all the symbols and environments available for completion purposes. The drawback is slower load time when you edit a new file and perhaps too many confusing symbols when you try to do a completion.

You can disable the automatic generated global style hooks by setting the variable TeX-auto-global to nil.

TeX-macro-global [User Option]

Directories containing the site's TEX style files.

TeX-style-global

[User Option]

Directory containing hand generated T_FX information. Must end with a slash.

These correspond to T_FX macros shared by all users of a site.

TeX-auto-global

[User Option]

Directory containing automatically generated information.

For storing automatic extracted information about the TEX macros shared by all users of a site.

8.2 Automatic Customization for a User

You should specify where you store your private T_EX macros, so $AUCT_EX$ can extract their information. The extracted information will go to the directories listed in TeX-auto-private

Use M-x TeX-auto-generate to extract the information.

TeX-macro-private

[User Option]

Directories where you store your personal TEX macros. Each must end with a slash.

This defaults to the directories listed in the 'TEXINPUTS' and 'BIBINPUTS' environment variables.

TeX-auto-private

[User Option]

List of directories containing automatically generated information. Must end with a slash

These correspond to the personal T_FX macros.

TeX-auto-generate TEX AUTO

[Command]

(M-x TeX-auto-generate) Generate style hook for TEX and store it in AUTO. If TEX is a directory, generate style hooks for all files in the directory.

TeX-style-private

[User Option]

List of directories containing hand generated information. Must end with a slash.

These correspond to the personal TFX macros.

8.3 Automatic Customization for a Directory

AUCTEX can update the style information about a file each time you save it, and it will do this if the directory TeX-auto-local exist. TeX-auto-local is by default set to "auto/", so simply creating an 'auto' directory will enable automatic saving of style information.

The advantage of doing this is that macros, labels, etc. defined in any file in a multifile document will be known in all the files in the document. The disadvantage is that saving will be slower. To disable, set TeX-auto-local to nil.

TeX-style-local

[User Option]

Directory containing hand generated TEX information. Must end with a slash.

These correspond to T_EX macros found in the current directory.

TeX-auto-local [User Option]

Directory containing automatically generated T_EX information. Must end with a slash.

These correspond to $T_{\!E\!}X$ macros found in the current directory.

9 Writing Your own Style Support

See Chapter 8 [Automatic], page 31, for a discussion about automatically generated global, private, and local style files. The hand generated style files are equivalent, except that they by default are found in 'style' directories instead of 'auto' directories.

If you write some useful support for a public TEX style file, please send it to us.

9.1 A Simple Style File

Here is a simple example of a style file.

This file specifies that the largest kind of section in a LATEX document using the book document style is chapter. The interesting thing to notice is that the style file defines an (anonymous) function, and adds it to the list of loaded style hooks by calling TeX-add-style-hook.

The first time the user indirectly tries to access some style specific information, such as the largest sectioning command available, the style hooks for all files directly or indirectly read by the current document is executed. The actual files will only be evaluated once, but the hooks will be called for each buffer using the style file.

```
{\tt TeX-add-style-hook}\ \textit{style hook}
```

[Function]

Add hook to the list of functions to run when we use the T_FX file style.

9.2 Adding Support for Macros

The most common thing to define in a style hook is new symbols (TEX macros). Most likely along with a description of the arguments to the function, since the symbol itself can be defined automatically.

Here are a few examples from 'latex.el'.

TeX-add-symbols symbol ...

[Function]

Add each symbol to the list of known symbols.

Each argument to TeX-add-symbols is a list describing one symbol. The head of the list is the name of the symbol, the remaining elements describe each argument.

If there are no additional elements, the symbol will be inserted with point inside braces. Otherwise, each argument of this function should match an argument of the TEX macro. What is done depends on the argument type.

If a macro is defined multiple times, AUCTEX will chose the one with the longest definition (i.e. the one with the most arguments).

Thus, to overwrite

```
'("tref" 1); one argument you can specify
```

```
'("tref" TeX-arg-label ignore); two arguments
```

ignore is a function that does not do anything, so when you insert a 'tref' you will be prompted for a label and no more.

string Use the string as a prompt to prompt for the argument.

number Insert that many braces, leave point inside the first.

nil Insert empty braces.

t Insert empty braces, leave point between the braces.

other symbols

Call the symbol as a function. You can define your own hook, or use one of the predefined argument hooks.

If the car is a string, insert it as a prompt and the next element as initial input. Otherwise, call the car of the list with the remaining elements as arguments.

vector Optional argument. If it has more than one element, parse it as a list, otherwise parse the only element as above. Use square brackets instead of curly braces, and is not inserted on empty user input.

A lot of argument hooks have already been defined. The first argument to all hooks is a flag indicating if it is an optional argument. It is up to the hook to determine what to do with the remaining arguments, if any. Typically the next argument is used to overwrite the default prompt.

TeX-arg-conditional

Implements if EXPR THEN ELSE. If EXPR evaluates to true, parse THEN as an argument list, else parse ELSE as an argument list.

TeX-arg-literal

Insert its arguments into the buffer. Used for specifying extra syntax for a macro.

TeX-arg-free

Parse its arguments but use no braces when they are inserted.

TeX-arg-eval

Evaluate arguments and insert the result in the buffer.

TeX-arg-file

Prompt for a tex or sty filename, and use it without the extension. Run the file hooks defined for it.

TeX-arg-label

Prompt for a label completing with known labels.

TeX-arg-macro

Prompt for a T_FX macro with completion.

TeX-arg-environment

Prompt for a LATEX environment with completion.

TeX-arg-cite

Prompt for a BibT_EX citation.

TeX-arg-counter

Prompt for a LATEX counter.

TeX-arg-savebox

Prompt for a \LaTeX savebox.

TeX-arg-file

Prompt for a filename in the current directory, and use it without the extension.

TeX-arg-input-file

Prompt for a filename in the current directory, and use it without the extension. Run the style hooks for the file.

TeX-arg-define-label

Prompt for a label completing with known labels. Add label to list of defined labels.

TeX-arg-define-macro

Prompt for a T_FX macro with completion. Add macro to list of defined macros.

TeX-arg-define-environment

Prompt for a LATEX environment with completion. Add environment to list of defined environments.

TeX-arg-define-cite

Prompt for a BibT_EX citation.

TeX-arg-define-counter

Prompt for a LATEX counter.

TeX-arg-define-savebox

Prompt for a LATEX savebox.

TeX-arg-corner

Prompt for a LATEX side or corner position with completion.

TeX-arg-lr

Prompt for a LATEX side with completion.

TeX-arg-tb

Prompt for a LATEX side with completion.

TeX-arg-pagestyle

Prompt for a IATEX pagestyle with completion.

TeX-arg-verb

Prompt for delimiter and text.

TeX-arg-pair

Insert a pair of numbers, use arguments for prompt. The numbers are surrounded by parentheses and separated with a comma.

TeX-arg-size

Insert width and height as a pair. No arguments.

TeX-arg-coordinate

Insert x and y coordinates as a pair. No arguments.

If you add new hooks, you can assume that point is placed directly after the previous argument, or after the macro name if this is the first argument. Please leave point located after the argument you are inserting. If you want point to be located somewhere else after all hooks have been processed, set the value of exit-mark. It will point nowhere, until the argument hook sets it.

9.3 Adding Support for Environments

Adding support for environments is very much like adding support for TEX macros, except that each environment normally only takes one argument, an environment hook. The example is again a short version of 'latex.el'.

The only hook that is generally useful is LaTeX-env-item, which is used for environments that contain items. It is completely up to the environment hook to insert the environment, but the function LaTeX-insert-environment may be of some help. The hook will be called with the name of the environment as its first argument, and extra arguments can be provided by adding them to a list after the hook.

For simple environments with arguments, for example defined with '\newenvironment', you can make AUCTEX prompt for the arguments by giving the prompt strings in the call to LaTeX-add-environments. For example, if you have defined a loop environment with the three arguments from, to, and step, you can add support for them in a style file.

```
%% loop.sty
\newenvironment{loop}[3]{...}{...}
;; loop.el
```

```
(TeX-add-style-hook "loop"
  (function
    (lambda ()
        (LaTeX-add-environments
        '("loop" "From" "To" "Step")))))
```

If an environment is defined multiple times, AUCTEX will chose the one with the longest definition. Thus, if you have an enumerate style file, and want it to replace the standard LATEX enumerate hook above, you could define an 'enumerate.el' file as follows, and place it in the appropriate style directory.

The symbol foo will be passed to LaTeX-env-enumerate as the second argument, but since we only added it to overwrite the definition in 'latex.el' it is just ignored.

```
LaTeX-add-environments env ...
```

[Function]

Add each env to list of loaded environments.

```
LaTeX-insert-environment env [extra]
```

[Function]

Insert environment of type env, with optional argument extra.

9.4 Adding Other Information

You can also specify bibliographical databases and labels in the style file. This is probably of little use, since this information will usually be automatically generated from the TeX file anyway.

```
LaTeX-add-bibliographies bibliography ...
```

[Function]

Add each bibliography to list of loaded bibliographies.

```
LaTeX-add-labels label ...
```

[Function]

Add each label to the list of known labels.

9.5 Automatic Extraction of New Things

The automatic TEX information extractor works by searching for regular expressions in the TEX files, and storing the matched information. You can add support for new constructs to the parser, something that is needed when you add new commands to define symbols.

For example, in the file 'macro.tex' I define the following macro.

```
\newcommand{\newmacro}[5]{%
\def#1{#3\index{#40#5~cite{#4}}\nocite{#4}}%
\def#2{#5\index{#40#5~cite{#4}}\nocite{#4}}%
}
```

AUCTEX will automatically figure out that 'newmacro' is a macro that takes five arguments. However, it is not smart enough to automatically see that each time we use the macro, two new macros are defined. We can specify this information in a style hook file.

```
;;; macro.el - Special code for my own macro file.
;;; Code:
(defvar TeX-newmacro-regexp
  (1 2) TeX-auto-multi)
  "Matches \newmacro definitions.")
(defvar TeX-auto-multi nil
  "Temporary for parsing \newmacro definitions.")
(defun TeX-macro-cleanup ()
  ;; Move symbols from 'TeX-auto-multi' to 'TeX-auto-symbol'.
  (mapcar (function (lambda (list)
    (mapcar (function (lambda (symbol)
     (setq TeX-auto-symbol
    (cons symbol TeX-auto-symbol))))
   list)))
 TeX-auto-multi))
(defun TeX-macro-prepare ()
  ;; Clear 'Tex-auto-multi' before use.
  (setq TeX-auto-multi nil))
(add-hook 'TeX-auto-prepare-hook 'TeX-macro-prepare)
(add-hook 'TeX-auto-cleanup-hook 'TeX-macro-cleanup)
(TeX-add-style-hook "macro"
 (function
  (lambda ()
    (TeX-auto-add-regexp TeX-newmacro-regexp)
    (TeX-add-symbols '("newmacro"
      TeX-arg-macro
      (TeX-arg-macro "Capitalized macro: \\")
      "BibTeX entry: "
      nil)))))
;;; macro.el ends here
```

When this file is first loaded, it adds a new entry to TeX-newmacro-regexp, and defines a function to be called before the parsing starts, and one to be called after the parsing is

done. It also declares a variable to contain the data collected during parsing. Finally, it adds a style hook which describes the 'newmacro' macro, as we have seen it before.

So the general strategy is: Add a new entry to TeX-newmacro-regexp. Declare a variable to contain intermediate data during parsing. Add hook to be called before and after parsing. In this case, the hook before parsing just initializes the variable, and the hook after parsing collects the data from the variable, and adds them to the list of symbols found.

TeX-auto-regexp-list

[Variable]

List of regular expressions matching TEX macro definitions.

The list has the following format ((REGEXP MATCH TABLE) ...), that is, each entry is a list with three elements.

REGEXP. Regular expression matching the macro we want to parse.

MATCH. A number or list of numbers, each representing one parenthesized subexpression matched by REGEXP.

TABLE. The symbol table to store the data. This can be a function, in which case the function is called with the argument MATCH. Use TeX-match-buffer to get match data. If it is not a function, it is presumed to be the name of a variable containing a list of match data. The matched data (a string if MATCH is a number, a list of strings if MATCH is a list of numbers) is put in front of the table.

TeX-auto-prepare-hook nil

[Variable]

List of functions to be called before parsing a TEX file.

TeX-auto-cleanup-hook nil

[Variable]

List of functions to be called after parsing a TeX file.

10 How to install AUCT_EX

Installing AUCTEX should be simple: merely ./configure, make, and make install. This does not yet activate the package, but merely makes it available. See Section 10.4 [Loading the package], page 42 for the activation. Please read through this document fully before installing anything. The installation procedure has changed as compared to earlier versions. In particular, note that there is some additional information for MS Windows installations in See Section 10.7 [Installation under MS Windows], page 45.

10.1 Prerequisites

• A recent version of Emacs 21, alternatively XEmacs 21.

Support for Emacs 20 has been dropped in favor of getting more important work done. For XEmacs, you need at least version 1.84 of the xemacs-base package (released on 01/27/2004) or a sumo tarball dated 02/02/2004 or newer for compiling AUCTEX because of non-trivial changes in 'easy-mmode.el': please use the XEmacs package system for upgrading if necessary. The current developers don't have the resources for providing backward compatibility to earlier versions.

• A working LATEX installation

This is not really needed to *install* the package, but will be required for useful operation of it. The elisp of AUCTEX will probably run without LATEX, but you will find relatively little use for it.

• The texinfo package

This is needed for building the documentation. If you don't have this, or you have a too old version of it (try building and you'll find out), you may download a separate tar file with the prebuilt documentation from Savannah and install it over the main unpacked tar archive.

10.2 Configure

The first step is to configure the source code, telling it where various files will be. To do so, run

./configure options

(Note: if you have fetched AUCTEX from CVS rather than a regular release, you will have to first generate ./configure by running autogen.sh in the 'auctex' directory.)

On many machines, you will not need to specify any options, but if **configure** cannot determine something on its own, you'll need to help it out with one of these options:

--with-emacs[=/path/to/emacs]

If you are using a pretest which isn't in your \$PATH, or configure is not finding the right Emacs executable, you can specify it with this option.

--with-xemacs[=/path/to/xemacs]

Configure for generation under XEmacs (Emacs is the default). Again, the name of the right XEmacs executable can be specified, complete with path if necessary.

--with-lispdir=/dir

This tells where to install Emacs Lisp files. Normally, this option is unnecessary, but may be used if you don't like the directory that configure is suggesting.

--with-packagedir=/dir

This tells where to install the XEmacs Package. Again, this option is normally unnecessary, but may be used if you don't like the directory that configure is suggesting, and you know that XEmacs regards the directory you specify as a package directory.

If you are installing AUCTEX for a single user, and you have installed no XEmacs packages as that user before, then configure may try to install AUCTEX in the systemwide package directory (that it cannot write to), causing installation to fail. In that case, a good value for this option is '~/.xemacs/xemacs-packages', as XEmacs looks there for per-user packages by default.

--with-tex-input-dirs=/dir-1/;/dir-2/;...;/dir-N/

This option allows to specify the directories to be used for file searches, e.g. for completion of LATEX or BibTEX style file names. They will be used in the variable TeX-macro-global.

Normally only the subdirectories 'tex/' and 'bibtex/bst/' below the used texmf trees should be relevant. Putting the roots of texmf trees here is possible but may slow down file searching.

The directories should be separated by semicolons and each has to end with a directory separator, i.e. a slash or a backslash respectively.

--with-auto-dir=/dir

You can use this option to specify the directory containing automatically generated information. It is not necessary for most TEX installs, but may be used if you don't like the directory that configure is suggesting.

--help This is not an option specific to AUCTEX. A number of standard options to configure exist, and we do not have the room to describe them here; a short description of each is available, using --help.

10.3 Build/install

Once configure has been run, simply enter

make

at the prompt to byte-compile the lisp files, and build the documentation files. To install the files into the locations chosen earlier, type

make install

You may need special privileges to install, e.g., if you are installing into system directories.

10.4 Loading the package

First you should make sure that AUCTEX gets loaded. You then need to place a few lines in your personal '.emacs' file (or a site-wide configuration file).

For XEmacs, if you specified a valid package directory during installation, or none at all, then XEmacs installation should do everything necessary in order to install AUCT_EX as a package and activate it. Restarting XEmacs should then make the package visible, and C-c should give you a command prompt.

If you used --with-packagedir, you have to make sure that the directory 'lisp/auctex' under the directory you specified is in XEmacs' load-path variable.

For GNU Emacs, the recommended way to activate AUCTEX is to add the following line to your '.emacs' file:

```
(require 'tex-site)
```

If you used --with-lispdir, you have to make sure that the directory specified is in Emacs' load-path variable, so that you would instead use, e.g.,

```
(setq load-path (cons "~/elisp" load-path))
(require 'tex-site)
```

For site-wide activation in GNU Emacs, see See Section 10.5 [Advice for package providers], page 43.

That is all. There are other ways of achieving the equivalent thing, but we don't mention them here any more since they are not better, and people got confused into trying everything at once.

10.5 Providing AUCTEX as a package

As a package provider, you should make sure that your users will be served best according to their intentions, and keep in mind that a system might be used by more than one user, with different preferences. The use of packages should in general not impact performance negatively if a user chooses not to employ it, but should be as convenient as possible. The policy with regard to AUCTEX has been to refrain from activating it automatically when it is installed as a package. This is reasonable because

- Emacs comes with a simpler default TEX mode with different keybindings. Some users might prefer that.
- AUCTEX is activated via (require 'tex-site). Once this has happened, it is not possible to get back the original TEX mode. A site-wide default would for this reason be hard to override.

If, however, you are certain that the users all prefer AUCTEX, you may place the following line in 'default.el':

```
(require 'tex-site)
```

XEmacs uses a package system. The default AUCTEX installation should cater for everything necessary in that case.

10.6 Installation for non-privileged users

Often people without system administration privileges want to install software for their private use. In that case you need to specify more options top the configure script. For XEmacs users, this is fairly easy, because the XEmacs package system has been designed to make this sort of thing practical: but GNU Emacs users (and XEmacs users for whom the package system is for some reason misbehaving) may need to do a little more work.

GNU Emacs users can solve this problem by using the '--prefix' option to the configure script, and let it point to the personal home directory. In that way, resulting binaries will be installed under the 'bin' subdirectory of your home directory, manual pages under 'man' and so on. That way, it is reasonably easy to maintain a bunch of additional packages, since the prefix argument is supported by most configure scripts.

You'll have to add something like '/home/myself/share/emacs/site-lisp' to your load-path variable, if it isn't there already.

XEmacs users can achieve the same end by pointing configure at an appropriate package directory (normally '--with-packagedir=~/.xemacs/xemacs-packages' will serve). This should only need to be done once, and should be needed fairly rarely; if you have installed any personal XEmacs packages before, configure should detect that, and automatically install AUCTEX there too; equally, if you have installed AUCTEX somewhere searched by XEmacs, AUCTEX should be automatically reinstalled over that copy.

(configure may guess wrong if the site administrator has installed AUCT_EX somewhere else: if so, just use the '--with-packagedir' option to override configure's choice.)

But there is another problem: perhaps you want to make it easy for other users to share parts of your personal Emacs configuration. In general, you can do this by writing '~myself/' anywhere where you specify paths to something installed in your personal subdirectories, not merely '~/', since the latter, when used by other users, will point to non-existent files.

For yourself, it will do to manipulate environment variables in your '.profile' resp. '.login' files. But if people will be copying just Elisp files, their copies will not work. While it would in general be preferable if the added components where available from a shell level, too (like when you call the standalone info reader, or try using 'preview.sty' for functionality besides of Emacs previews), it will be a big help already if things work from inside of Emacs.

Here is how to do the various parts:

Making the Elisp available

In XEmacs, you should ask the other users to add symbolic links in their '~/.xemacs/xemacs-packages/lisp', '~/.xemacs/xemacs-packages/info' and '~/.xemacs/xemacs-packages/etc' directories. (Alas, there is presently no easy programmatic way to do this, except to have a script do the symlinking for them.)

In GNU Emacs, you'll want the invocation lines described in See Section 10.4 [Loading the package], page 42. In addition, you'll want a line such as

(add-to-list 'load-path "~myself/share/emacs/site-lisp/preview")

Making the Info files available

While for yourself, you'll probably want to manipulate the 'INFOPATH' variable; for access inside of Elisp something like the following might be convenient:

```
(eval-after-load 'info
  '(add-to-list 'Info-directory-list "~myself/info"))
```

In XEmacs, as long as XEmacs can see the package, there should be no need to do anything at all; the info files should be immediately visible. However, you might want to

set 'INFOPATH' anyway, for the sake of standalone readers outside of XEmacs. (The info files in XEmacs are normally in '~/.xemacs/xemacs-packages/info'.)

10.7 Installation under MS Windows

Installation of AUCTEX is a bit more complicated, but we are working to resolve the issues involved. Please report success/failure to us at 'auc-tex@sunsite.dk'. Here are the steps to perform:

1. The installation of AUCT_EX will require the MSYS tool set from http://www.mingw.org. If you have the Cygwin tool set from http://cygwin.com installed, that should do just fine as well, but it is quite larger and slower.

If you are installing AUCTEX with one of those sets for an Emacs compiled in a different one, you should try to avoid tool-specific path names like '/cygwin/c'. Instead, use the 'c:' syntax. It might also help to use forward slashes instead of the backward slashes more typical for MS Windows: while backward slashes are supposed to work if properly escaped in the shell, this is one area easily overlooked by the developers. The same holds for file or directory names with spaces in them. Of course, we want to hear about any problems in that area.

Compiling Emacs is outside of the scope of this manual. AUCTEX itself does not require a C compiler for installation.

- 2. Install GNU Emacs from http://ftp.gnu.org/pub/gnu/windows/emacs/ or XEmacs from http://www.xemacs.org.
- 3. You need a working TeX installation. One popular installation under Windows is MikTeX. Another much more extensive system is TeX live which is rather close to its Unix cousins.
- 4. Now the fun stuff starts. Unpack the AUCTEX distribution into some installation directory. **Do not** unpack it right into your Emacs' own directories: the installation will copy the material that needs to be placed there. Keep the installation directory separate: you can remove its contents after installation completes. Since you are reading this, you probably have already unpacked AUCTEX, but it should still be easy to move it elsewhere now.
- 5. Ready for takeoff. Start some shell (typically bash) capable of running configure, change into the installation directory and call ./configure with appropriate options.

 Typical options you'll want to specify will be

--prefix=drive:/path/to/emacs-directory

which makes sure that (1) the AUCTeX manual will be installed in the 'info/' directory of your Emacs installation and (2) the automatically generated global style hooks will be installed in the 'var/' directory of your Emacs installation. If you are collecting stuff like that in a central directory hierarchy (not untypical with Cygwin), you might want to specify that here instead. You stand a good chance that this will be the only option you need to supply, as long as your TEX-related executables are in your system path, which they better be for AUCTEX's operation, anyway.

--with-emacs

if you are installing Emacs. You can use '--with-emacs=/path/to/emacs' to specify the name of the installed Emacs executable, complete with its path if necessary (if Emacs is not within a directory specified in your *PATH* environment setting).

--with-xemacs

If you are using XEmacs, of course use '--with-xemacs' in the same manner. It may also be necessary to specify this option if a copy of Emacs is in your path, but you would like to install AUCTEX for XEmacs, too.

--with-lispdir=/dir

This may be needed for GNU Emacs installation, but hopefully configure should figure this out by itself. Don't use this for XEmacs, rather use

--with-packagedir=/dir

which gives the location of the package directory for XEmacs where stuff should be installed. Again, hopefully this is not necessary to specify.

--with-tex-input-dirs=/dir-1/;/dir-2/;...;/dir-N/

This option allows to specify the directories to be used for file searches, e.g. for completion of LaTeX or BibTeX style file names. They will be used in the variable TeX-macro-global.

configure will usually figure out the right value for this option but will only succeed if it finds the necessary programs of the TEX system in the system path. Which should be there for running AUCTEX, anyway.

--with-auto-dir=/dir

Directory containing automatically generated information. You should not normally need to set this, as '--prefix' should take care of this.

Some additional information about the above options may be found in Section 10.2 [Configure], page 41.

- 6. If you need to use the prebuilt documentation (see above), now is the time to unpack it over the rest of the installation directory.
- 7. Run make in the installation directory (we have had one report that Emacs did not manage to byte compile the Elisp files, and that had to be done by hand. No idea about what might have gone wrong there).
- 8. Run make install in the installation directory.
- 9. For GNU Emacs, the recommended way to activate AUCTEX is to add the following line to your '.emacs' file:

(require 'tex-site)

The configuration for Windows systems is probably not quite fitting. Instead of loading 'tex-site.el' in that manner, you might want to load 'tex-mik.el' (for MikTEX) or 'tex-fptex' (for fpTEX) instead. Those will lead to somewhat more appropriate values for your system. You can always use

M-x customize-group $\langle \overline{\text{RET}} \rangle$ AUCTeX $\langle \overline{\text{RET}} \rangle$

in order to customize more stuff, or use the 'Customize' menu.

10. Load a '.tex' file Emacs or XEmacs and see if you get the 'Command' menu. Try using that to LATEX the file.

Well, that about is all. Have fun!

10.8 Customizing

Most of the site-specific customization should already have happened during configuration of AUCTEX. Any further customization can be done with customization buffers directly in Emacs. Just type M-x customize-group RET AUCTEX RET to open the customization group for AUCTEX or use the menu entries provided in the mode menus. Editing the file 'tex-site.el' as suggested in former versions of AUCTEX should not be done anymore because the installation routine will overwrite those changes.

You might check some variables with a special significance. They are accessible directly by typing M-x customize-variable RET <variable> RET.

TeX-lisp-directory

[User Option]

The directory where you installed the AUCT_EX lisp files.

This variable is set automatically during configuration. If you don't issue a make install, for example if you don't want to install AUCTEX in a different place, you will have to set this variable manually to the location of the compiled files. It is generally advisable to do a full installation including make install because program and documentation files will be copied to their proper places.

TeX-macro-global

[User Option]

Directories containing the site's T_FX style files.

Normally, AUCTEX will only allow you to complete macros and environments which are built-in, specified in AUCTEX style files or defined by yourself. If you issue the *M-x TeX-auto-generate-global* command after loading AUCTEX, you will be able to complete on all macros available in the standard style files used by your document. To do this, you must set this variable to a list of directories where the standard style files are located. The directories will be searched recursively, so there is no reason to list subdirectories explicitly. Automatic configuration will already have set the variable for you if it could use the program 'kpsewhich'. In this case you normally don't have to alter anything.

10.9 Contributed files

There are several files that are not part of AUCT_EX proper, but included in the distribution in case they are useful.

'bib-cite.el'

Better support for bibliographies and much more.

'tex-jp.el'

Support for Japanese.

They can be installed together with AUCTEX by executing make contrib and make install-contrib. Read the comments in the start of each file for more information about how to use the files, what they do, and who wrote and maintains them.

Appendix A Changes and New Features

News in 11.53

- The LATEX math menu can include Unicode characters if your Emacs built supports it. See the variable LaTeX-math-menu-unicode, Section 3.1 [Mathematics], page 11.
- Bug fixes for XEmacs.

News in 11.52

- Installation and menus under XEmacs work again (maybe for the first time).
- Fontification of subscripts and superscripts is now disabled when the fontification engine is not able to support it properly.
- Bug fixes in the build process.

News in 11.51

- PDFTeX and Source Special support did not work with ConTeXt, this has been fixed. Similar for Source Special support under Windows.
- Omega support has been added.
- Bug fixes in the build process.

News in 11.50

- The use of source specials when processing or viewing the document can now be controlled with the new TeX-source-specials minor mode which can be toggled via an entry in the Command menu or the key binding C-c C-t C-s. If you have customized the variable TeX-command-list, you have to re-initialize it for this to work. This means to open a customization buffer for the variable by typing M-x customize-variable RET TeX-command-list RET, selecting "Erase Customization" and do your customization again with the new default.
- The content of the command menu now depends on the mode (plain TEX, IATEX, ConTEXt etc.). Any former customization of the variable TeX-command-list has to be erased. Otherwise the command menu and the customization will not work correctly.
- Support for hiding and auto-revealing macros, e.g. footnotes or citations, and environments in a buffer was added, Section 3.6.1 [Folding], page 17.
- You can now control if indentation is done upon typing (RET) by customizing the variable TeX-newline-function, Section 3.4 [Indenting], page 13.
- Limited support for doc.sty and ltxdoc.cls ('dtx' files) was added. The new docTEX mode provides functionality for editing documentation parts. This includes formatting (indenting and filling), adding and completion of macros and environments while staying in comments as well as syntax highlighting. (Please note that the mode is not finished yet. For example syntax highlighting does not work yet in XEmacs.)
- For macro completion in docTEX mode the AUCTEX style files 'doc.el', 'ltxdoc.el' and 'ltx-base.el' were included. The latter provides general support for low-level

- LATEX macros and may be used with LATEX class and style files as well. It is currently not loaded automatically for those files.
- Support for ConTEXt with a separate ConTEXt mode is now included. Macro definitions for completion are available in Dutch and English.
- The filling and indentation code was overhauled and is now able to format commented parts of the source syntactically correct. Newly available functionality and customization options are explained in the manual.
- Filling and indentation in XEmacs with preview-latex and activated previews lead to the insertion of whitespace before multi-line previews. AUCTEX now contains facilities to prevent this problem.
- If TeX-master is set to t, AUCTEX will now query for a master file only when a new file is opened. Existing files will be left alone. The new function TeX-master-file-ask (bound to C-c _ is provided for adding the variable manually.
- Sectioning commands are now shown in a larger font on display devices which support such fontification. The variable font-latex-title-fontity can be customized to restore the old appearance, i.e. the usage of a different color instead of a change in size.
- Support for alphanum.sty, beamer.cls, booktabs.sty, captcont.sty, emp.sty, paralist.sty, subfigure.sty and units.sty/nicefrac.sty was added. Credits go to the authors mentioned in the respective AUCTEX style files.
- Inserting graphics with *C-c RET \includegraphics RET* was improved. See the variable LaTeX-includegraphics-options-alist.
- If LaTeX-default-position is nil, don't prompt for position arguments in Tabular-like environments, see Section 2.4.4 [Tabular-like], page 10.
- Completion for available packages when using *C-c RET \usepackage RET* was improved on systems using the kpathsea library.
- The commenting functionality was fixed. The separate functions for commenting and uncommenting were unified in one function for paragraphs and regions respectively which do both.
- Syntax highlighting can be customized to fontify quotes delimited by either >>German<< or <<French>> quotation marks by changing the variable font-latex-quotes.
- Certain TEX/IATEX keywords for functions, references, variables and warnings will now be fontified specially. You may add your own keywords by customizing the variables font-latex-match-function-keywords, font-latex-match-reference-keywords, font-latex-match-variable-keywords and font-latex-match-warning-keywords.
- If you include the style files 'german' or 'ngerman' in a document (directly or via the 'babel' package), you should now customize LaTeX-german-open-quote, LaTeX-german-close-quote and LaTeX-german-quote-after-quote instead of TeX-open-quote, TeX-close-quote and TeX-quote-after-quote if you want to influence the type of quote insertion.
- Upon viewing an output file, the right viewer and command line options for it are now determined automatically by looking at the extension of the output file and certain options used in the source file. The behavior can be adapted or extended respectively by customizing the variable TeX-output-view-style.

- You can control whether TeX-insert-macro (*C-c RET*) ask for all optional arguments by customizing the variable TeX-insert-macro-default-style, Section 3.2 [Completion], page 11.
- TeX-run-discard is now able to completely detach a process that it started.
- The build process was enhanced and is now based on autoconf making installing AUCTEX a mostly automatic process. See Chapter 10 [Installation], page 41 and Section 10.7 [Installation under MS Windows], page 45 for details.

News in 11.14

Many more LaTeX and LaTeX2e commands are supported. Done by Masayuki Ataka
 <ataka@milk.freemail.ne.jp>

News in 11.12

• Support for the KOMA-Script classes. Contributed by Mark Trettin kmark.Trettin@gmx.de.

News in 11.11

• Support for 'prosper.sty', see http://prosper.sourceforge.net/. Contributed by Phillip Lord <p.lord@russet.org.uk>.

News in 11.10

• comment-region now inserts %% by default. Suggested by "Davide G. M. Salvetti" <salve@debian.org>.

News in 11.06

• You can now switch between using the 'font-latex' (all emacsen), the 'tex-font' (Emacs 21 only) or no special package for font locking. Customize TeX-install-font-lock for this.

News in 11.04

• Now use -t landscape by default when landscape option appears. Suggested by Erik Frisk <frisk@isy.liu.se>.

News in 11.03

• Use 'tex-fptex.el' for fpTeX support. Contributed by Fabrice Popineau <Fabrice.Popineau@supelec.fr>.

News in 11.02

- New user option LaTeX-top-caption-list specifies environments where the caption should go at top. Contributed by ataka@milk.freemail.ne.jp (Masayuki Ataka).
- Allow explicit dimensions in 'graphicx.sty'. Contributed by ataka@milk.freemail.ne.jp (Masayuki Ataka).

- Limited support for 'verbatim.sty'. Contributed by ataka@milk.freemail.ne.jp (Masayuki Ataka).
- Better support for asmmath items. Patch by ataka@milk.freemail.ne.jp (Masayuki Ataka).
- More accurate error parsing. Added by David Kastrup < David.Kastrup@t-online.de>.

News in 11.01

• Bug fixes.

Older versions

See the file 'history.texi' for older changes.

Appendix B Future Development

The following sections describe future development of AUCTEX. Besides mid-term goals, bug reports and requests we cannot fix or honor right away are being gathered here. If you have some time for Emacs Lisp hacking, you are encouraged to try to provide a solution to one of the following problems. If you don't know Lisp, you may help us to improve the documentation. It might be a good idea to discuss proposed changes on the mailing list of AUCTEX first.

B.1 Mid-term Goals

• Integration of preview-latex into AUCT_EX

AUCT_EX users will thereby get the functionality provided by preview-latex without the hassle of an additional installation.

Looking at the backend, the integration involves folding of error parsing and task management of both packages which will ease development efforts and avoid redundant work.

• More flexible option and command handling

The current state of command handling with TeX-command-list is not very flexible because there is no distinction between executables and command line options to be passed to them.

Customization of TeX-command-list by the user will interfere with updates of AUCTEX.

• Error help catalogs

Currently, the help for errors is more or less hardwired into 'tex.el'. For supporting error help in other languages, it would be sensible to instead arrange error messages in language-specific files, make a common info file from all such catalogs in a given language and look the error texts up in an appropriate index. The user would then specify a preference list of languages, and the errors would be looked up in the catalogs in sequence until the were identified.

• Combining 'docTeX' with RefTeX

Macro cross references should also be usable for document navigation using RefTeX.

B.2 Wishlist

• Quick error overviews

An error overview window (extract from the log file with just the error lines, clickable like a "grep" buffer) and/or fringe indicators for errors in the main text would be nice.

• A math entry grid

A separate frame with a table of math character graphics to click on in order to insert the respective sequence into the buffer (cf. the "grid" of x-symbol).

• Crossreferencing support

It would be nice if you could index process your favorite collection of '.dtx' files (such as the LaTeX source), just call a command on arbitrary control sequence, and get either

the DVI viewer opened right at the definition of that macro (using Source Specials), or the source code of the '.dtx' file.

- Better plain TeX support For starters, LaTeX-math-mode is not very LATeX-specific in the first place, and similar holds for indentation and formatting.
- Poor man's Source Specials In particular in PDF mode (and where Source Specials cause problems), alternatives would be desirable. One could implement inverse search by something like Heiko Oberdiek's 'vpe.sty', and forward search by using the '.aux' file info to correlate labels in the text (possibly in cooperation with RefTEX) with previewer pages.
- Page count when compiling should (optionally) go to modeline of the window where the compilation command was invoked, instead of the output window. Suggested by Karsten Tinnefeld tinnefeld@irb.informatik.uni-dortmund.de.
- Command to insert a macrodefinition in the preamble, without moving point from the current location. Suggested by "Jeffrey C. Ely" <ely@nwu.edu>.
- A database of all commands defined in all stylefiles. When a command or environment gets entered that is provided in one of the styles, insert the appropriate \usepackage in the preamble.
- A way to add and overwrite math mode entries in style files, and to decide where they should be. Suggested by Remo Badii <Remo.Badii@psi.ch>.
- Create template for (first) line of tabular environment.
- I think prompting for the master is the intended behaviour. It corresponds to a 'shared' value for TeX-master.

There should probably be a 'none' value which wouldn't query for the master, but instead disable all features that relies on TeX-master.

This default value for TeX-master could then be controlled with mapping based on the extension.

- Multiple argument completion for '\bibliography'. In general, I ought to make, special for these kind of completions.
- Suggest 'makindex' when appropriate.
- AUCTEX should be able to parse LATEX2e '.cls' files. Here are the regexps by '<thiemann@informatik.uni-tuebingen.de>' Peter Thiemann.

- Use index files (when available) to speed up C-c C-m include (RET).
- Option not to calculate very slow completions like for C-c C-m include (RET).
- Font menu should be created from TeX-font-list.
- Installation procedure written purely in emacs lisp.
- Included PostScript files should also be counted as part of the document.
- The parser should catch warnings about undefined crossreferences. Suggested by Richard Hirsch 'i3080501@ws.rz.tu-bs.de'.
- A nice hierarchical by-topic organization of all officially documented LaTeX macros, available from the menu bar.
- TeX-command-default should be set from the master file, if not set locally. Suggested by Peter Whaite ''cpeta@cim.mcgill.ca>'.
- Make AUCTEX work with 'crypt++'. Suggested by Chris Moore '<Chris.Moore@src.bae.co.uk>'.
- The 'Spell' command should apply to all files in a document. Maybe it could try to restrict to files that have been modified since last spell check? Suggested by Ravinder Bhumbla '<rbhumbla@ucsd.edu>'.
- Make (?) check for abbreviations and sentences ending with capital letters.
- Use Emacs 19 minibuffer history to choose between previewers, and other stuff. Suggested by John Interrante '<interran@uluru.Stanford.EDU>'.
- Make features.

A new command TeX-update (C-c C-u) could be used to create an up-to-date dvi file by repeatedly running $BibT_EX$, MakeIndex and $(La)T_EX$, until an error occurs or we are done.

An alternative is to have an 'Update' command that ensures the 'dvi' file is up to date. This could be called before printing and previewing.

• Documentation of variables that can be set in a style hook.

We need a list of what can safely be done in an ordinary style hook. You can not set a variable that AUCTEX depends on, unless AUCTEX knows that it has to run the style hooks first.

Here is the start of such a list.

LaTeX-add-environments
TeX-add-symbols
LaTeX-add-labels
LaTeX-add-bibliographies
LaTeX-largest-level

- Completion for counters and sboxes.
- Outline should be (better) supported in TFX mode.

At least, support headers, trailers, as well as TeX-outline-extra.

- TeX-header-start and TeX-trailer-end.
 - We might want these, just for fun (and outlines)
- Plain TEX and LATEX specific header and trailer expressions.
 We should have a way to globally specify the default value of the header and trailer regexps.
- Get closer to original TeX-mode keybindings.
 - A third initialization file ('tex-mode.el') containing an emulator of the standard TeX-mode would help convince some people to change to AUCT_EX.
- Make TeX-next-error parse ahead and store the results in a list, using markers to remember buffer positions in order to be more robust with regard to line numbers and changed files. This is what next-error does. (Or did, until Emacs 19).
- Finish the Texinfo mode. For one thing, many Texinfo mode commands do not accept braces around their arguments.
- Hook up the letter environment with 'bbdb.el'.

B.3 Bugs

- The parsed files and style hooks for 'example.dtx', 'example.sty', 'example.drv' and 'example.bib' all clash. Bad.
- Filling messes up comments, but only at the end of the file. Reported by Juergen Reiss <psy3022@rzbox.uni-wuerzburg.de>.
- C-c C-q C-e doesn't work properly on nested itemize environments. Reported by "Robert B. Love" <rlove@raptor.rmNUG.ORG>.
- C-c 'should always stay in the current window, also when it find a new file.
- Do not overwrite emacs warnings about existing auto-save files when loading a new file
- Maybe the regexp for matching a TeX symbol during parsing should be "\\\\([a-zA-Z]+\\].\\)"' '<thiemann@informatik.uni-tuebingen.de>' Peter Thiemann.
- AUCTEX should not parse verbatim environments.
- LATEX formatting should skip verbatim environments.
- The argument to '\verb' may be broken when filling if it contains a space. This should be fixed or documented. Suggested by several people.
- Make "' check for math context in LaTeX-math-mode. and simply self insert if not in a math context.
- Make TeX-insert-dollar more robust. Currently it can be fooled by '\mbox''es and escaped double dollar for example.
- Fix bug with TeX-show-environment from hidden document environment.
- Correct indentation for tabular, tabbing, table, math, and array environments.
- If there are unmatched \$ characters in 'verbatim' or similar environments, the rest of the buffer gets fontified with the math face (usually in brown). A good way to fix this bug would be to have conditional font locking, i.e. different (syntactical) keywords are used inside certain environments. This would allow special fontification of programming

languages in 'lstlisting' environments as well. Unfortunately such conditional font locking is not provided yet by Emacs. As a workaround you can insert '%\$' after the end of the environment in concern.

Appendix C Frequently Asked Questions

1. What versions of Emacs and XEmacs are supported?

AUCTEX was tested with Emacs 21 and XEmacs 21.4.15. Older versions may work but are unsupported. Older versions of XEmacs might possibly made to work by updating the 'xemacs-base' package through the XEmacs package system.

2. Why doesn't the completion or multifile stuff work?

It must be enabled first, insert this in your emacs:

```
(setq-default TeX-master nil)
(setq TeX-parse-self t)
(setq TeX-auto-save t)
```

Read also the chapters about parsing and multifile documents in the manual.

3. Why doesn't TeX-save-document work?

TeX-check-path has to contain "./" somewhere.

4. Why is the information in 'foo.tex' forgotten when I save 'foo.bib'?

For various reasons, AUCTEX ignores the extension when it stores information about a file, so you should use unique base names for your files. E.g. rename 'foo.bib' to 'foob.bib'.

5. Why doesn't AUCT_EX signal when processing a document is done?

If the message in the minibuffer stays "Type 'C-c C-l' to display results of compilation.", you probably have a misconfiguration in your init file ('.emacs', 'init.el' or similar). To track this down either search in the '*Messages*' buffer for an error message or put (setq debug-on-error t) as the first line into your init file, restart Emacs and open a LATEX file. Emacs will complain loudly by opening a debugging buffer as soon as an error occurs. The information in the debugging buffer can help you find the cause of the error in your init file.

Key Index

II	C-c C-o C-c
"5	C-c C-o C-e
	C-c C-o C-f
*	C-c C-o C-m
\$	C-c C-o C-x 18
\$ 5	C-c C-q C-e
*	C-c C-q C-p
	C-c C-q C-r 10
\mathbf{C}	C-c C-q C-s
C-c %	C-c C-r 20
C-c;	C-c C-s
C-c]9	C-c C-t C-i
C-c ^ 24	C-c C-t C-p
C-c	C-c C-t C-r 20
C-c	C-c C-t C-s
C-c {	C-c C-v
C-c ~ 11	C-c C-w
C-c C-b	C-c (LFD)
C-c C-c	С-ј
C-c C-d	
C-c C-e 9	т
C-c C-f 6	\mathbf{L}
C-c C-f C-b6	⟨ <u>LFD</u> ⟩
C-c C-f C-c 6	
C-c C-f C-e 6	
C-c C-f C-i 6	\mathbf{M}
C-c C-f C-r 6	M-g
C-c C-f C-s 6	M-q
C-c C-f C-t 6	$M-\langle TAB \rangle$
C-c C-k	ri=\(\frac{1AB}{\}\)
C-c C-1	
C-c C-m 12	\mathbf{T}
C-c C-n	
C-c C-o C-b	(TAB)

Function Index

L	TeX-arg-label	36
	TeX-arg-literal	
LaTeX-add-bibliographies	TeX-arg-lr	
LaTeX-add-environments	TeX-arg-macro	
LaTeX-add-labels	TeX-arg-pagestyle	
LaTeX-close-environment 9	TeX-arg-pair	
LaTeX-env-item		
LaTeX-environment9	TeX-arg-size	
LaTeX-fill-environment 16	TeX-arg-size	
LaTeX-fill-paragraph	TeX-arg-tb	
LaTeX-fill-region	TeX-arg-verb	
LaTeX-fill-section	TeX-auto-generate	
LaTeX-indent-line	TeX-command-buffer	
LaTeX-insert-environment	TeX-command-master	
LaTeX-insert-item	TeX-command-region	20
LaTeX-math-mode	TeX-comment-or-uncomment-paragraph	
LaTeX-section	TeX-comment-or-uncomment-region	
LaTeX-section-heading 8	TeX-complete-symbol	
LaTeX-section-label	TeX-electric-macro	
LaTeX-section-section	TeX-fold-buffer	
LaTeX-section-title	TeX-fold-clearout-buffer	
LaTeX-section-toc	TeX-fold-clearout-item	
Early Booton Coo	TeX-fold-env	
_	TeX-fold-macro	
${f T}$	TeX-fold-mode	
ToY-add-gtylo-hook	TeX-font	
TeX-add-style-hook	TeX-header-end	
TeX-and-symbols	TeX-home-buffer	
TeX-arg-cite	TeX-insert-braces	
TeX-arg-conditional	TeX-insert-dollar	
TeX-arg-coordinate	TeX-insert-macro	
TeX-arg-corner	TeX-insert-quote	
TeX-arg-counter	TeX-interactive-mode	
TeX-arg-define-cite	TeX-kill-job	
TeX-arg-define-counter	TeX-master-file-ask	
TeX-arg-define-environment	TeX-next-error	
TeX-arg-define-label	TeX-normal-mode	
TeX-arg-define-macro	TeX-PDF-mode	
TeX-arg-define-savebox	TeX-pin-region	20
TeX-arg-environment	TeX-recenter-output-buffer	
TeX-arg-eval	TeX-save-document	
TeX-arg-file	TeX-source-specials-mode	22
TeX-arg-free 35	TeX-toggle-debug-bad-boxes	24
TeX-arg-input-file	TeX-view	23

Variable Index

J	TeX-auto-regexp-list
japanese-LaTeX-command-default 30	TeX-auto-save
japanese-LaTeX-default-style	TeX-auto-untabify27
japanese-TeX-command-default	TeX-brace-indent-level 15
	TeX-check-path
	TeX-close-quote 5
$\mathbf L$	TeX-command-default
LaTeX-amsmath-label9	TeX-command-list
LaTeX-auto-label-regexp-list	TeX-default-macro
LaTeX-auto-minimal-regexp-list	TeX-default-mode
LaTeX-auto-regexp-list	TeX-display-help
LaTeX-default-environment	TeX-DVI-via-PDFTeX
LaTeX-default-format	TeX-electric-escape
LaTeX-default-position	TeX-file-recurse
LaTeX-eqnarray-label9	TeX-fold-env-spec-list 18
LaTeX-equation-label9	TeX-fold-macro-spec-list 18
LaTeX-figure-label	TeX-fold-unspec-env-display-string 19
LaTeX-fill-break-at-separators	TeX-fold-unspec-macro-display-string 19
LaTeX-fill-break-before-code-comments 17	TeX-fold-unspec-use-name 19
LaTeX-float	TeX-font-list 6
LaTeX-indent-environment-check	TeX-header-end
LaTeX-indent-environment-list	TeX-ignore-file
LaTeX-indent-level	TeX-insert-braces
LaTeX-item-indent	TeX-insert-macro-default-style
LaTeX-math-abbrev-prefix	TeX-interactive-mode
LaTeX-math-list	TeX-lisp-directory
LaTeX-math-menu-unicode	TeX-macro-global
LaTeX-paragraph-commands	TeX-macro-private
LaTeX-section-hook	TeX-master
LaTeX-section-label	TeX-newline-function
LaTeX-syntactic-comments	TeX-one-master
LaTeX-table-label	TeX-open-quote 5
-	TeX-outline-extra
D	TeX-output-view-style 23
P	TeX-parse-self
plain-TeX-auto-regexp-list	TeX-PDF-mode
	TeX-quote-after-quote5
	TeX-region
${f T}$	TeX-save-query
TeX-auto-cleanup-hook 40	TeX-source-specials-mode
TeX-auto-empty-regexp-list	TeX-source-specials-view-start-server 23
TeX-auto-full-regexp-list	TeX-style-global
TeX-auto-global	TeX-style-local
TeX-auto-local	TeX-style-path
TeX-auto-parse-length	TeX-style-private
TeX-auto-prepare-hook	TeX-trailer-start
TeX-auto-private	TeX-view-style 23

Concept Index

•	Braces
'.emacs'	Brackets
1	\mathbf{C}
\	
'\begin'9	Changing font
\chapter	Changing the parser
\cite, completion of	Chapters
\emph 6	Character set
'\end'9	Checking
\include	chktex
\input	citations, completion of
\item	cite, completion of
\label7	Commands
\label, completion	Completion
\ref, completion	Controlling the output
\section	Copyright 1
\subsection 7	Copyright
\textbf6	
\textit6	Customization
\textrm6	Customization, personal
\textsc6	Customization, site 47
\textsl6	
\texttt6	D
A	Danish
A	Debugging
Abbreviations	Default command
Adding a style hook	Defining bibliographies in style hooks
Adding bibliographies	Defining environments in style hooks
Adding environments	Defining labels in style hooks
Adding labels	Defining macros in style hooks
Adding macros	Defining other information in style hooks 38
Adding other information	Deleting fonts
Advanced features	Denmark
amsmath9	Descriptions
ANSI	Display math mode
Arguments to T _F X macros	Distribution
'auto' directories	Documents
Auto-Reveal	Documents with multiple files
Automatic	Dollars
Automatic Customization	Double quotes
Automatic Parsing	Dutch
Automatic updating style hooks	
	E
B	
	Enumerates
Bad boxes	Environments adding 27
Bibliographies, adding	Environments, adding
Bibliography	Equation 9
	Equation 9 Equations 9
BibTEX 20 BibTeX, completion 12	Errors
'book.el' 34	Europe

European Characters	${ m J}$
Example of a style file	T 00
Expansion	Japan
External Commands	Japanese
Extracting T _E X symbols	jIAT _E X
	jT _E X
F	
	K
Figure environment	
File Variables	Killing a process
Filling	
Finding errors	т
Finding the current file	$\mathbf L$
Finding the master file	Label prefix
Floats	Labels
Folding	Labels, adding
Font macros 6	labels, completion of
Fonts 6	lacheck
Formatting	IAT _E X
Forward search	Latin 1
Free	Latin 2
Free software	License
	Literature
G	Local style directory
General Public License	Local style directory
Generating symbols	Local Variables
deficiating symbols	LOCAL VALIABLES
Germany	
Germany 29 Global directories 31	
Germany	\mathbf{M}
Germany29Global directories31Global macro directory31	M Macro arguments
Germany29Global directories31Global macro directory31Global style hook directory31	Macro arguments
Germany29Global directories31Global macro directory31Global style hook directory31Global TEX macro directory31	Macro arguments
Germany29Global directories31Global macro directory31Global style hook directory31Global TEX macro directory31GPL1	Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 H Header 20	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 H 1 Header 20 Headers 19	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 Header 20 Headers 19 Hide Macros 17	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 H 1 Header 20 Headers 19	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 H 1 Header 20 Headers 19 Hide Macros 17 Holland 29	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 Header 20 Headers 19 Hide Macros 17	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 H 1 Header 20 Headers 19 Hide Macros 17 Holland 29	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25 Master file 24, 25
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 H 1 Header 20 Headers 19 Hide Macros 17 Holland 29	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25 Master file 24, 25 Matching dollar signs 5
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 H 20 Header 20 Headers 19 Hide Macros 17 Holland 29 I Including Including 25	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Master file 24, 25 Matching dollar signs 5 Math mode delimiters 5
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 Header 20 Headers 19 Hide Macros 17 Holland 29 I Including Including 25 Indentation 13	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25 Master file 24, 25 Matching dollar signs 5 Math mode delimiters 5 Mathematics 11
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 Header 20 Headers 19 Hide Macros 17 Holland 29 I Including Indentation 13 Indenting 13 Indexing 20 Initialization 47	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25 Master file 24, 25 Matching dollar signs 5 Math mode delimiters 5 Mathematics 11 MULE 30
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 Header 20 Headers 19 Hide Macros 17 Holland 29 I Including Indentation 13 Indenting 13 Indexing 20 Initialization 47 Inputing 25	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25 Master file 24, 25 Matching dollar signs 5 Math mode delimiters 5 Mathematics 11 MULE 30 Multifile Documents 25
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 Header 20 Headers 19 Hide Macros 17 Holland 29 I Including Indentation 13 Indenting 13 Indexing 20 Initialization 47 Inputing 25 Installation 42	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25 Master file 24, 25 Matching dollar signs 5 Math mode delimiters 5 Mathematics 11 MULE 30
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 Header 20 Headers 19 Hide Macros 17 Holland 29 I Including 25 Indentation 13 Indexing 20 Initialization 47 Inputing 25 Installation 42 Internationalization 29	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25 Master file 24, 25 Matching dollar signs 5 Math mode delimiters 5 Mathematics 11 MULE 30 Multifile Documents 25
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 Header 20 Headers 19 Hide Macros 17 Holland 29 I Including 25 Indentation 13 Indexing 20 Initialization 47 Inputing 25 Installation 42 Internationalization 29 Inverse search 23	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25 Master file 24, 25 Matching dollar signs 5 Mathematics 11 MULE 30 Multifile Documents 25 Multiple Files 25
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 Header 20 Headers 19 Hide Macros 17 Holland 29 I Including 25 Indentation 13 Indexing 20 Initialization 47 Inputing 25 Installation 42 Internationalization 29 Inverse search 23 ISO 8859 Latin 1 29	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25 Master file 24, 25 Matching dollar signs 5 Math mode delimiters 5 Mathematics 11 MULE 30 Multifile Documents 25
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 Header 20 Headers 19 Hide Macros 17 Holland 29 I Including 25 Indentation 13 Indexing 20 Initialization 47 Inputing 25 Installation 42 Internationalization 29 Inverse search 23 ISO 8859 Latin 1 29 ISO 8859 Latin 2 29	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25 Master file 24, 25 Matching dollar signs 5 Mathematics 11 MULE 30 Multifile Documents 25 Multiple Files 25
Germany 29 Global directories 31 Global macro directory 31 Global style hook directory 31 Global TEX macro directory 31 GPL 1 Header 20 Headers 19 Hide Macros 17 Holland 29 I Including 25 Indentation 13 Indexing 20 Initialization 47 Inputing 25 Installation 42 Internationalization 29 Inverse search 23 ISO 8859 Latin 1 29	M Macro arguments 11 Macro completion 11 Macro expansion 11 'macro.el' 38 'macro.tex' 38 Macros, adding 34 Make 42 makeindex 20 Making a bibliography 20 Making an index 20 Many Files 25 Master file 24, 25 Matching dollar signs 5 Math mode delimiters 5 Mathematics 11 MULE 30 Multifile Documents 25 Multiple Files 25

0	\mathbf{S}
Other information, adding	Sample style file
Outlining	Sectioning 7
Output	Sections
Overfull boxes	Setting the default command
Overview	Setting the header
	Setting the trailer
D	Site customization
P	Site information
Parsing errors	Site initialization
Parsing LATEX errors	Site macro directory
Parsing new macros	Source specials
Parsing T _E X	Specifying a font 6
Parsing TeX output	Starting a previewer
Personal customization	Stopping a process
Personal information	'style'
Personal macro directory	Style
Personal T _F X macro directory	Style file
pIAT _F X	Style files
Poland	Style hook
Prefix for labels 8, 10	Style hooks 34
Previewing	Symbols
Printing	
Private directories	${f T}$
Private macro directory	
Private style hook directory	Tabify
Private T _E X macro directory	Table environment
Problems	Tables
Processes	Tabs
pT _F X	T _E X
b.E.t	TEX parsing
	'tex-site.el'
Q	Trailer
Quotes	\mathbf{U}
	Untabify
D	Updating style hooks
R	opdating style hooks
Redisplay output	
Refilling	V
Reformatting	Variables
Region	Viewing
Region file	, 10 m
Reindenting	
Reveal	\mathbf{W}
Right	Warranty
Running BibTEX 20	Wonderful boxes
Running chktex	Writing to a printer
Running commands	
Running lacheck	* 7
Running LATEX	\mathbf{X}
Running makeindex	'x-compose.el'
Running T _E X	X-Symbol

Short Contents

Cop	ying	1
1	Introduction to AUCTEX	2
2	Inserting Frequently Used Commands	5
3	Advanced Editing Features	11
4	Starting processors, viewers and other programs	20
5	Multifile Documents	25
6	Automatic Parsing of T _E X files	27
7	Internationalization	29
8	Automatic Customization	31
9	Writing Your own Style Support	34
10	How to install AUCTEX	41
A	Changes and New Features	48
В	Future Development	52
С	Frequently Asked Questions	57
Key	Index	58
Fun	ction Index	59
Vari	iable Index	60
Con	cept Index	61

Table of Contents

C	opy	ving	1
1	Ir	ntroduction to AUCT _E X	2
	1.1	Indentation and filling	
	1.2	Completion	
	1.3	Editing your document	
	1.4	Running IATEX	. 3
	1.5	Outlines	. 3
	1.6	Availability	
	1.7	Contacts	. 4
2	Ir	nserting Frequently Used Commands	5
	2.1	Insertion of Quotes, Dollars, and Braces	. 5
	2.2	Inserting Font Specifiers	
	2.3	Inserting chapters, sections, etc	7
	2.4	Inserting Environment Templates	
		2.4.1 Equations	
		2.4.2 Floats	
	_	2.4.3 Itemize-like	
	_	2.4.4 Tabular-like	
	2	2.4.5 Customizing environments	10
3	A	dvanced Editing Features 1	11
	3.1	Entering Mathematics	11
	3.2	Completion	11
	3.3	Commenting	
	3.4	Indenting	
	3.5	Filling	
	3.6	Showing and Hiding Text in the Buffer	
		3.6.1 Folding	
	3	3.6.2 Outlining the Document	19
4	\mathbf{S}^{\cdot}	tarting processors, viewers and other	
		programs	20
	4.1		20
	4.2	Viewing the formatted output	
	4.3	Catching the errors	
	4.4	Checking for problems	
	4.5		24

5	Multifile Documents	. 25
6	Automatic Parsing of TEX files	. 27
7	Internationalization	. 29
	7.1 Using AUCT _E X for European languages	29
	7.2 Japanese T _E X	
8	Automatic Customization	. 31
	8.1 Automatic Customization for the Site	31
	8.2 Automatic Customization for a User	32
	8.3 Automatic Customization for a Directory	32
9	Writing Your own Style Support	. 34
	9.1 A Simple Style File	34
	9.2 Adding Support for Macros	34
	9.3 Adding Support for Environments	37
	9.4 Adding Other Information	
	9.5 Automatic Extraction of New Things	38
10	How to install AUCTEX	. 41
	10.1 Prerequisites	41
	10.2 Configure	41
	10.3 Build/install	42
	10.4 Loading the package	
	10.5 Providing AUCT _E X as a package	
	10.6 Installation for non-privileged users	
	10.7 Installation under MS Windows	
	10.8 Customizing	
	10.9 Contributed files	47
A	ppendix A Changes and New Features	. 48
A	ppendix B Future Development	. 52
	B.1 Mid-term Goals	52
	B.2 Wishlist	52
	B.3 Bugs	55
A	ppendix C Frequently Asked Questions	. 57
K	ey Index	. 58
F	unction Index	. 59

Variable Index	60
Concept Index	61