The False Discovery Rate

• Back to this table:

	H_0 is True	H_0 is False	Total
Reject H_0	V	S	R
Do Not Reject H_0	U	W	m-R
Total	m_0	$m-m_0$	m

• The FWER rate focuses on controlling Pr(V > 1), i.e., the probability of falsely rejecting any null hypothesis.

The False Discovery Rate

• Back to this table:

	H_0 is True	H_0 is False	Total
Reject H_0	V	S	R
Do Not Reject H_0	U	W	m-R
Total	m_0	$m-m_0$	m

- The FWER rate focuses on controlling Pr(V > 1), i.e., the probability of falsely rejecting *any* null hypothesis.
- This is a tough ask when m is large! It will cause us to be super conservative (i.e. to very rarely reject).

The False Discovery Rate

• Back to this table:

	H_0 is True	H_0 is False	Total
Reject H_0	V	S	R
Do Not Reject H_0	U	W	m-R
Total	m_0	$m-m_0$	m

- The FWER rate focuses on controlling Pr(V > 1), i.e., the probability of falsely rejecting *any* null hypothesis.
- This is a tough ask when m is large! It will cause us to be super conservative (i.e. to very rarely reject).
- Instead, we can control the false discovery rate:

$$FDR = E(V/R).$$

$$FDR = E\left(\frac{V}{R}\right) = E\left(\frac{\text{number of false rejections}}{\text{total number of rejections}}\right)$$

$$FDR = E\left(\frac{V}{R}\right) = E\left(\frac{\text{number of false rejections}}{\text{total number of rejections}}\right)$$

• A scientist conducts a hypothesis test on each of m = 20,000 drug candidates.

$$FDR = E\left(\frac{V}{R}\right) = E\left(\frac{\text{number of false rejections}}{\text{total number of rejections}}\right)$$

- A scientist conducts a hypothesis test on each of m = 20,000 drug candidates.
- She wants to identify a smaller set of promising candidates to investigate further.

$$\text{FDR} = \operatorname{E}\left(\frac{V}{R}\right) = \operatorname{E}\left(\frac{\text{number of false rejections}}{\text{total number of rejections}}\right)$$

- A scientist conducts a hypothesis test on each of m = 20,000 drug candidates.
- She wants to identify a smaller set of promising candidates to investigate further.
- She wants reassurance that this smaller set is really "promising", i.e. not too many falsely rejected H_0 's.

$$\text{FDR} = \operatorname{E}\left(\frac{V}{R}\right) = \operatorname{E}\left(\frac{\text{number of false rejections}}{\text{total number of rejections}}\right)$$

- A scientist conducts a hypothesis test on each of m = 20,000 drug candidates.
- She wants to identify a smaller set of promising candidates to investigate further.
- She wants reassurance that this smaller set is really "promising", i.e. not too many falsely rejected H_0 's.
- FWER controls Pr(at least one false rejection).

$$\text{FDR} = \operatorname{E}\left(\frac{V}{R}\right) = \operatorname{E}\left(\frac{\text{number of false rejections}}{\text{total number of rejections}}\right)$$

- A scientist conducts a hypothesis test on each of m = 20,000 drug candidates.
- She wants to identify a smaller set of promising candidates to investigate further.
- She wants reassurance that this smaller set is really "promising", i.e. not too many falsely rejected H_0 's.
- FWER controls Pr(at least one false rejection).
- FDR controls the fraction of candidates in the smaller set that are really false rejections. This is what she needs!

1. Specify q, the level at which to control the FDR.

- 1. Specify q, the level at which to control the FDR.
- 2. Compute p-values p_1, \ldots, p_m for the null hypotheses H_{01}, \ldots, H_{0m} .


- 1. Specify q, the level at which to control the FDR.
- 2. Compute p-values p_1, \ldots, p_m for the null hypotheses H_{01}, \ldots, H_{0m} .
- 3. Order the *p*-values so that $p_{(1)} \leq p_{(2)} \leq \ldots \leq p_{(m)}$.


- 1. Specify q, the level at which to control the FDR.
- 2. Compute p-values p_1, \ldots, p_m for the null hypotheses H_{01}, \ldots, H_{0m} .
- 3. Order the *p*-values so that $p_{(1)} \leq p_{(2)} \leq \ldots \leq p_{(m)}$.
- 4. Define $L = \max \{j : p_{(j)} < qj/m\}.$

- 1. Specify q, the level at which to control the FDR.
- 2. Compute p-values p_1, \ldots, p_m for the null hypotheses H_{01}, \ldots, H_{0m} .
- 3. Order the *p*-values so that $p_{(1)} \leq p_{(2)} \leq \ldots \leq p_{(m)}$.
- 4. Define $L = \max \{j : p_{(j)} < qj/m\}.$
- 5. Reject all null hypotheses H_{0j} for which $p_j \leq p_{(L)}$.


- 1. Specify q, the level at which to control the FDR.
- 2. Compute p-values p_1, \ldots, p_m for the null hypotheses H_{01}, \ldots, H_{0m} .
- 3. Order the *p*-values so that $p_{(1)} \leq p_{(2)} \leq \ldots \leq p_{(m)}$.
- 4. Define $L = \max \{j : p_{(j)} < qj/m\}.$
- 5. Reject all null hypotheses H_{0j} for which $p_j \leq p_{(L)}$.

Then, $FDR \leq q$.






• Here, p-values for m = 2,000 null hypotheses are displayed.



- Here, p-values for m = 2,000 null hypotheses are displayed.
- To control FWER at level $\alpha = 0.1$ with Bonferroni: reject hypotheses below green line. (No rejections!)



- Here, p-values for m = 2,000 null hypotheses are displayed.
- To control FWER at level $\alpha = 0.1$ with Bonferroni: reject hypotheses below green line. (No rejections!)
- To control FDR at level
 q = 0.1 with
 Benjamini-Hochberg: reject
 hypotheses shown in blue.

• Consider m = 5 p-values from the Fund data: $p_1 = 0.006, p_2 = 0.918, p_3 = 0.012, p_4 = 0.601, p_5 = 0.756.$

- Consider m = 5 p-values from the Fund data: $p_1 = 0.006, p_2 = 0.918, p_3 = 0.012, p_4 = 0.601, p_5 = 0.756.$
- Then $p_{(1)} = 0.006$, $p_{(2)} = 0.012$, $p_{(3)} = 0.601$, $p_{(4)} = 0.756$, and $p_{(5)} = 0.918$.

- Consider m = 5 p-values from the Fund data: $p_1 = 0.006, p_2 = 0.918, p_3 = 0.012, p_4 = 0.601, p_5 = 0.756.$
- Then $p_{(1)} = 0.006$, $p_{(2)} = 0.012$, $p_{(3)} = 0.601$, $p_{(4)} = 0.756$, and $p_{(5)} = 0.918$.
- To control FDR at level q = 0.05 using Benjamini-Hochberg:
 - Notice that $p_{(1)} < 0.05/5$, $p_{(2)} < 2 \times 0.05/5$, $p_{(3)} > 3 \times 0.05/5$, $p_{(4)} > 4 \times 0.05/5$, and $p_{(5)} > 5 \times 0.05/5$.
 - So, we reject H_{01} and H_{03} .

- Consider m = 5 p-values from the Fund data: $p_1 = 0.006, p_2 = 0.918, p_3 = 0.012, p_4 = 0.601, p_5 = 0.756.$
- Then $p_{(1)} = 0.006$, $p_{(2)} = 0.012$, $p_{(3)} = 0.601$, $p_{(4)} = 0.756$, and $p_{(5)} = 0.918$.
- To control FDR at level q = 0.05 using Benjamini-Hochberg:
 - Notice that $p_{(1)} < 0.05/5$, $p_{(2)} < 2 \times 0.05/5$, $p_{(3)} > 3 \times 0.05/5$, $p_{(4)} > 4 \times 0.05/5$, and $p_{(5)} > 5 \times 0.05/5$.
 - So, we reject H_{01} and H_{03} .
- To control FWER at level $\alpha = 0.05$ using Bonferroni:
 - We reject any null hypothesis for which the p-value is less than 0.05/5.
 - So, we reject only H_{01} .