

Install DI Server with Your Own DI Repository



This document supports Pentaho Business Analytics Suite 5.0 GA and Pentaho Data Integration 5.0 GA, documentation revision August 28, 2013, copyright © 2013 Pentaho Corporation. No part may be reprinted without written permission from Pentaho Corporation. All trademarks are the property of their respective owners.

# Help and Support Resources

If you do not find answers to your quesions here, please contact your Pentaho technical support representative.

Support-related questions should be submitted through the Pentaho Customer Support Portal at <a href="http://support.pentaho.com">http://support.pentaho.com</a>.

For information about how to purchase support or enable an additional named support contact, please contact your sales representative, or send an email to <a href="mailto:sales@pentaho.com">sales@pentaho.com</a>.

For information about instructor-led training, visit <a href="http://www.pentaho.com/training">http://www.pentaho.com/training</a>.

# Liability Limits and Warranty Disclaimer

The author(s) of this document have used their best efforts in preparing the content and the programs contained in it. These efforts include the development, research, and testing of the theories and programs to determine their effectiveness. The author and publisher make no warranty of any kind, express or implied, with regard to these programs or the documentation contained in this book.

The author(s) and Pentaho shall not be liable in the event of incidental or consequential damages in connection with, or arising out of, the furnishing, performance, or use of the programs, associated instructions, and/or claims.

## **Trademarks**

Pentaho (TM) and the Pentaho logo are registered trademarks of Pentaho Corporation. All other trademarks are the property of their respective owners. Trademarked names may appear throughout this document. Rather than list the names and entities that own the trademarks or insert a trademark symbol with each mention of the trademarked name, Pentaho states that it is using the names for editorial purposes only and to the benefit of the trademark owner, with no intention of infringing upon that trademark.

# Third-Party Open Source Software

For a listing of open source software used by each Pentaho component, navigate to the folder that contains the Pentaho component. Within that folder, locate a folder named licenses. The licenses folder contains HTML.files that list the names of open source software, their licenses, and required attributions.

## Contact Us

Global Headquarters Pentaho Corporation Citadel International, Suite 340 5950 Hazeltine National Drive Orlando, FL 32822 Phone: +1 407 812-OPEN (6736)

Fax: +1 407 517-4575 http://www.pentaho.com

Sales Inquiries: sales@pentaho.com

# Contents

Introd	uction	. 4
Overv	riew of the Installation Process	
Prepare Environment		.6
	Create User Account	
	Create Windows User Account	
	Create Linux User Account	6
	Create Directory Structure	7
	Create Windows Directory Structure	
	Create Linux Directory Structure	
	Install the DI Repository Database	7
	Download and Unpack Installation Files	
	Install Java JRE or JDK	
	Set Environment Variables	
	Set Windows PENTAHO_JAVA_HOME Variable	
	Set Linux PENTAHO_JAVA_HOME Variable	9
	Adjust Amount of Memory Mac OS Allocates for PostgreSQL	
	ze Repository	
	Initialize PostgreSQL DI Repository Database	
	Initialize MySQL DI Repository Database	
	Initialize Oracle DI Repository Database	
	gure Repository	
	Configure PostgreSQL DI Repository Database	
	Configure Quartz on PostgreSQL DI Repository Database	
	Configure Hibernate Settings for PostgreSQL DI Repository Database	
	Modify Jackrabbit DI Repository Information for PostgreSQL	
	Prepare MySQL DI Repository Database	
	Configure Quartz on MySQL DI Repository Database	
	Configure Hibernate Settings for MySQL	
	Modify Jackrabbit Repository Information for MySQL	
	Prepare Oracle DI Repository Database  Configure Quartz on Oracle DI Repository Database	
	Configure Hibernate Settings for Oracle	
	Modify Jackrabbit Repository Information for Oracle	
Snooi	fy Connections	
	Perform Tomcat-Specific Connection Tasks	
	Copy Solution Database JDBC Drivers	
	Download and Install H2 JDBC Drivers	
	Modify JDBC Connection Information in the Tomcat context.xml File	
Start	DI Server	
	Install License Keys Using the Command Line Interface	
	Modify Tomcat Startup Script	
	Modifying the Tomcat Linux Startup Script	
	Windows Pentaho Archive Installation	
	Linux and Macintosh OS Pentaho Installation Wizard	
	Steps	
INOVE	♥ŧ♥₽♥	"

This section explains how to install Data Integration (DI) Server and configure it to use the DI Repository database of your choice. The DI Repository contains solution content, scheduling, and audit tables needed for the DI Server to operate. You can house the DI Repository on PostgreSQL, MySQL, or Oracle. With this installation option, you must supply, install, and configure your chosen database yourself.

#### **Prerequisites**

Read Select DI Installation Option to make sure that this is the best installation option for you. Then, check the Supported Technologies tables to make sure that your server computer, DI Repository database, and web browser meet Pentaho's requirements for the this version of the software.

#### **Expertise**

The topics in this section are written for IT administrators, evaluators, and analysts who have who have access to the server on which the DI Server will be installed. You should know where data is stored, how to connect to it, details about the computing environment, and how to use the command line to issue commands for Microsoft Windows or Linux. You should also know how to install a database.

#### **Tools**

You will need a text editor and a zip tool to complete some of the steps in this installation process.

#### **Login Credentials**

All of the tasks in this section require that you have the appropriate permissions and accesses required to install software on servers and workstations.

# **Overview of the Installation Process**



To install the DI Server, perform the tasks indicated in the *guidepost*.

- Prepare Environment: Explains how to create a pentaho user account, create the directory structure, download
  DI Server files from our web site, install your selected DI Repository database, and set up system environment
  variables.
- Initialize Repository: Provides information about how to run DDL scripts that create tables for the DI Repository.
- Configure Repository: Provides information about how to configure the DI Repositories on your selected database.
- Specify Connections: Explains how to specify JDBC connections to the DI Repository.
- Start BA Server: Explains how to start the DI Server.
- Next Steps: Indicates what to do after the DI Server has been installed.



To prepare the computer on which you plan to install the DI Server, complete these tasks.

- Create a pentaho user account.
- Install the DI Repository database. If you already have a database installed, skip this task.
- Download and unpack the installation files.
- Install Java JRE or JDK.
- Set environment variables.
- Adjust PostgreSQL Memory for Mac OS.

#### **Create User Account**

#### **Create Windows User Account**

If you plan to install on a server that runs Windows, you do not need to create a special user account on the server. However, you should use an account that has administrator privileges to complete the tasks in this section.

#### Create Linux User Account

If you plan to install the DI Server in a Linux environment you must create a user account named **pentaho** on the server computer. By default, license information for Pentaho products is stored in the home directory for this account. Use this account to perform installation tasks that do not require root access. Also, use this account to run start and stop server scripts.

- Open a Terminal window on the server. If you plan to install the DI Server on a remote computer, establish an OpenSSH session to the remote server.
- 2. In the Terminal window, log in as the root user by typing this command.

su root

- **3.** When prompted, type the password in the **Terminal** window.
- 4. In the **Terminal** window, create a new user account called **pentaho**, along with the pentaho home directory, by typing this line.

```
sudo useradd -s /bin/bash -m pentaho
```

**Note:** /bin/bash indicates that the user account should be created using the Bash shell. In many Linux distributions, the default new user shell is /bin/sh or some equivalent, such as Dash, that might not use the ~/.bashrc configuration file by default. If you don't have or want to use Bash, adjust the instructions throughout this section accordingly.

In the Terminal window, assign a password for the pentaho user by typing this line.

sudo passwd pentaho

- 6. Verify that you can log in using the newly-created **pentaho** user account.
  - a) In the **Terminal** window, attempt to log in by typing this line.

su pentaho -

- b) Type the password for the **pentaho** user account if you are prompted.
- c) Use the **Terminal** window to navigate to the pentaho directory to verify that it has been created. By default, it is in the /home directory.

# **Create Directory Structure**

### **Create Windows Directory Structure**

- 1. Log into the machine on which you will run the DI Server.
- 2. Create this directory path.

pentaho/server

- Verify that you have the appropriate permissions to read, write, and execute commands in the directories you created.
  - a) Open Windows Explorer and right-click the pentaho directory.
  - b) Select the **Properties** option in the security tab to verify that you have read, write, and execute permissions.
  - c) In Windows Explorer navigate to server directory, then right-click.
  - d) Select the **Properties** option in the security tab to verify that you have read, write, and execute permissions.
  - e) In Windows Explorer and navigate to the data-integration-server directory and right-click it.
  - f) Select the **properties** option in the security tab to verify that you have read, write, and execute permissions.

### **Create Linux Directory Structure**

- 1. Log into the machine on which you will run the DI Server. Make sure that you are logged in as the pentaho user.
- 2. Create this directory path from home directory (pentaho).

pentaho/server

- 3. Verify that you have the appropriate permissions to read, write, and execute commands in the directories you created.
  - a) In Linux check the permissions of the pentaho, server, and data-integration-server directories by opening a **Terminal** window, navigating to the pentaho directory, then typing this command.

```
ls -ld ../pentaho ../pentaho/server
```

b) Make sure that permissions for the directories allow you to read, write, and execute in those directories.

# Install the DI Repository Database

The DI Repository houses data needed for Pentaho tools to provide scheduling and security functions, as well as metadata and models for reports that you create.

You can choose to host the DI Repository on the PostgreSQL, MySQL, or Oracle database. By default, Pentaho software is configured to use the PostgreSQL Database. If you already have a DI Repository database installed, you can skip this step.

- To download and install the DI Repository database, use the instructions in the documentation for the database of your choice. It does not matter where you install the database.
- 2. Verify that the DI Repository database is installed correctly. You can do this by connecting to your database and viewing the contents of any default databases that might have been created upon installation. Consult the user documentation for the database that you installed for further details.

**Note:** If you are not familiar with SQL, consider using a visual database design tool to connect to the database and view its contents.

- PGAdminIII is bundled with PostgreSQL.
- MySQL Workbench can be used with MySQL. It is available as a separate download. Check the MySQL site for details on how to obtain this design tool.
- Oracle SQL Developer can be used with Oracle. It is available as a separate download. Check the Oracle site for details on how to obtain this design tool.

## Download and Unpack Installation Files

If you want to install specific Pentaho software, obtain the installation packages from the Pentaho Customer Support Portal. Consult your Welcome Kit if you need more information about the portal.

- 1. Make sure the web application server on which you plan to deploy the DI Server has been stopped.
- 2. Download the pdi-ee-server-5.0.0-dist.zip.
- Unpack the file by completing these steps.
  - a) Use a zip tool to extract the pdi-ee-server-5.0.0-dist.zip file you just downloaded.
  - b) Open a Command Prompt or Terminal window and navigate to the folder that contains the files you just extracted.
  - c) Enter one of the following at the prompt.

#### Windows:

install.bat

#### Linux:

./install.sh

- d) Read the license agreement that appears. Select I accept the terms of this license agreement, then click Next. Note: If you are unpacking the file in a non-graphical environment, open a Terminal or Command Prompt window and type java -jar install.jar -console and follow the instructions presented in the window.
- e) Indicate where you want the file to be unpacked. It doesn't matter where because you will be manually placing the files in the appropriate directories later in these instructions.
- f) Click the **Next** button.
- g) The Installation Progress window appears. Progress bars indicate the status of the installation. When the installation progress is complete, click **Quit** to exit the Unpack Wizard.
- 4. Navigate to the directory where you unpacked the files. Unzip the file and extract it to the pentaho/server directory you created in the directory creation step.
- 5. Verify that the directory structure has been correctly created by comparing the following directory structure with yours.
  - pentaho/server/data-integration-server
  - pentaho/server/data-integration-server/data
  - pentaho/server/data-integration-server/licenses
  - pentaho/server/data-integration-server/pentaho-solutions
  - pentaho/server/data-integration-server/tomcat

**Note:** If your web application server is not in the pentaho/server/data-integration-server directory, the tomcat directory appears where you've chosen to install your web application server.

#### Install Java JRE or JDK

Make sure that the version of the Java Runtime Environment (JRE) or the Java Development Kit (JDK) that Pentaho needs to run is installed on your system. You do not need to uninstall other versions of Java if you already have them running on your system. These instructions explain how to check for your default version of Java that is running on your computer and where to get the required version if you need one.

- 1. Check the supported technologies list to see which version of the JRE or JDK is needed for the software.
- 2. If you have not done so already, log into the computer on which you plan to install the software. Ensure that you have the appropriate permissions to install software.
- 3. Open a Terminal or a Command Prompt window. Enter this command.

java -version

- **4.** If the version of Java does not match the version needed to run Pentaho software, check your system to see if there are other versions of Java installed.
- **5.** If the version of Java that you need to run Pentaho software is not on your system, *download it from the Oracle site* and install it.

#### Set Environment Variables

Set the PENTAHO\_JAVA\_HOME variable to indicate the path to the Java JRE or JDK that Pentaho should use. If you do not set this variable, then Pentaho will not start correctly.

To set environment variables, you should be logged into an account that has administrator-level privileges. For Linux systems, you must be logged into the **root** user account.

#### Set Windows PENTAHO JAVA HOME Variable

- 1. From the Start menu, right-click Computer, then select Properties from context menu.
- 2. Click Advanced System Settings. The System Properties window appears.
- 3. In the System Properties window, click the Advanced tab, then click Environment Variables.
- 4. To set the PENTAHO JAVA HOME variable do this.
  - a) In the System Variable section, click New.
  - b) In the window that appears, type PENTAHO\_JAVA\_HOME in the **name** field.
  - c) In the **value** field, enter the directory where your Oracle JDK or Oracle JRE is stored. For example your Java JRE is in the Program Files\Java\jre7 directory, type this.

C:\Program Files\Java\jre7

- d) Click OK.
- 5. Click Apply Changes.
- 6. Log out, then log back in.
- 7. To verify that the variables have been properly set, open a Command window and type this.

echo %PENTAHO\_JAVA\_HOME%

## Set Linux PENTAHO\_JAVA\_HOME Variable

- 1. Open a terminal window and log in as root.
- 2. Open the /etc/environment file with a text editor.

**Note:** The vi and gedit text editors are available on most Linux machines. For example, to open the /etc/environment file with gedit, type this.

gedit /etc/environment

3. Indicate where you installed Java in your /etc/environment file by typing this.

Note: Substitute /usr/lib/jvm/java-7-sun with the location of the JRE or JDK you installed on your system.

export PENTAHO\_JAVA\_HOME=/usr/lib/jvm/java-7-sun


- 4. Save and close the file.
- 5. Log out, then log back in for the change to take effect.
- 6. Verify that the variables are properly set by opening a **Terminal** window and typing this.

env | grep PENTAHO\_JAVA\_HOME

# Adjust Amount of Memory Mac OS Allocates for PostgreSQL

If you plan to install the software on a Mac OS, and you choose to use PostgreSQL, you need to increase the amount of memory that the Mac OS allocates for PostgreSQL. You can skip these instructions if you plan to install the software on Windows or Linux.

PostgreSQL is the name of the default database that contains audit, schedule and other data that you create. PostgreSQL starts successfully only if your computer has allocated enough memory. Go to <a href="http://www.postgresql.org/docs/devel/static/kernel-resources.html">http://www.postgresql.org/docs/devel/static/kernel-resources.html</a> and follow the instructions there on how to adjust the memory settings on your computer.



Before you prepare the DI Repository complete the tasks in *Prepare Environment*.

Pentaho stores content about reports that you create, examples we provide, report scheduling data, and audit data in the DI Repository. The DI Repository resides on the database that you installed during the Prepare Environment step. The DI Repository consists of three repositories: *Jackrabbit*, *Quartz*, and *Hibernate*.

- *Jackrabbit* contains the solution respository, examples, security data, and content data from reports that you use Pentaho software to create.
- Quartz holds data that is related to scheduling reports and jobs.
- Hibernate holds data that is related to audit logging.

This step only consists of one task: Initialize the database. In this task you run DDLs that contain SQL commands that create the Jackrabbit, Quartz, and Hibernate databases, as well as the Operations Mart schema.

- Initialize PostgreSQL
- Initialize MySQL
- Initialize Oracle

## Initialize PostgreSQL DI Repository Database

To initialize PostgreSQL so that it serves as the DI Repository, run SQL scripts to create the Hibernate, Quartz and Jackrabbit (also known as the JCR) databases.

**Note:** Your PostgreSQL configuration must support logins from all users. This is not always the default configuration, so you may have to edit your pg\_hba.conf file to support this option. If you do need to make changes to pg\_hba.conf, you must restart the PostgreSQL server before proceeding.

- 1. To make the databases that you create more secure, Pentaho recommends that you change the default passwords in the SQL script files to ones that you specify. If you are evaluating Pentaho, you might want to skip this step. If you do decide to make the databases more secure, use a text editor to change the passwords in these files:
  - pentaho/server/data-integration-server//data/postgresql/create\_jcr\_postgresql.sql
  - pentaho/server/data-integration-server//data/postgresql/ create\_quartz\_postgresql.sql
  - pentaho/server/data-integration-server//data/postgresql/ create\_repository\_postgresql.sql

Here is an example of a password change made in the <code>create\_jcr\_postgresql.sql</code> file.

```
CREATE USER jcr user PASSWORD 'myNewPassword'
```

- 2. Windows: The commands you use to run the SQL scripts depends on your operating system. For windows, do this.
  - a) Open a SQL Shell window. The SQL Shell window is installed with PostgreSQL.
  - b) When prompted for the server enter the name of the server if you are not using the default (localhost). If you are using the default, do not type anything and press Enter.
  - c) When prompted for the database enter the name of the database if you are not using the default (postgres) If you are using the default, do not type anything and press Enter.
  - d) When prompted for the port enter the name of the port if you are not using the default (5432). If you are using the default port, do not type anything and press Enter.
  - e) When prompted for the username, accept the default, then press Enter.
  - f) When prompted for the password, enter the password that you indicated when you installed PostgreSQL.

g) Run the script to create the Jackrabbit database by typing this.

```
\i /pentaho/server/data-integration-server/data/postgresql/
create_jcr_postgresql.sql
```

**Note:**If necessary, change the \pentaho\server\data-integration-server to the place where you unpacked your pentaho files.

h) Run the script to create the hibernate database by typing this.

```
\i /pentaho/server/data-integration-server/data/postgresql/
create_repository_postgresql.sql
```

Run the script to create the Quartz database by typing this.

```
\i /pentaho/server/data-integration-server/data/postgresql/create_quartz_postgresql.sql
```

j) To switch to the Hibernate database, type this.

```
\c postgres
```

k) Run the script to create the Operations Mart database by typing this.

```
\i /pentaho/server/data-integration-server/data/postgresql/
pentaho_mart_postgresql.sql
```

- I) Exit from the window by pressing the CTRL + C keys.
- 3. Linux: To run the SQL scripts on a Linux system, do this.
  - a) Open a **Terminal** window. You should be logged in as the **pentaho** user.
  - b) Sign into PostgreSQL by typing psql -U postgres -h localhost at the prompt.
  - c) Run the script to create the Jackrabbit database by typing this.

```
\i ~/pentaho/server/data-integration-server/data/postgresql/
create_jcr_postgresql.sql
```

**Note:**If necessary, change the ~/pentaho/server/data-integration-server directory path to the place where you unpacked your pentaho files.

d) Run the script to create the hibernate database by typing this.

```
\i ~/pentaho/server/data-integration-server/data/postgresql/
create_repository_postgresql.sql
```

**Note:**If necessary, change the ~/pentaho/server/data-integration-server to the place where you unpacked your pentaho files.

e) Run the script to create the Quartz database by typing this.

```
\i ~/pentaho/server/data-integration-server/data/postgresql/create_quartz_postgresql.sql
```

**Note:**If necessary, change the ~/pentaho/server/data-integration-server directory path to the place where you unpacked your pentaho files.

f) To switch to the Hibernate database, type this.

```
\c postgres
```

g) Run the script to create the Operations Mart database by typing this.

```
\i ~/pentaho/server/data-integration-server/data/postgresql/
pentaho_mart_postgresql.sql
```

- h) Exit from the window by pressing the CTRL + C keys.
- **4.** To verify that databases and user roles have been created, do this.
  - a) Open the pgAdminIII tool. pgAdminIII is bundled with both the Windows and Linux versions of PostgreSQL.

- b) To view the contents of PostgreSQL, click the PostgreSQL folder in the **Object Browser**, then enter the password when prompted.
- c) In the **Object Browser**, click the **Databases** folder. The Jackrabbit, Postgres, Hibernate and Quartz databases appear.
- d) In the **Object Browser**, click the **Login Roles** folder. The jcr\_user, pentaho\_user, hibuser, and postgres user accounts appear.
- e) If the databases and login roles do not appear, go to the beginning of these instructions and try running the scripts again.
- f) Select File > Exit to exit from pgAdminIII.

## Initialize MySQL DI Repository Database

To initialize MySQL so that it serves as the DI Repository, run SQL scripts to create the Hibernate, Quartz and Jackrabbit (also known as the JCR) databases.

**Note:** Use the ASCII character set when you run these scripts. Do not use UTF-8 because there are text string length limitations that might cause the scripts to fail.

- 1. To make the databases that you create more secure, Pentaho recommends that you change the default passwords in the SQL script files to ones that you specify. If you are evaluating Pentaho, you might want to skip this step. If you do decide to make the databases more secure, use a text editor to change the passwords in these files:
  - pentaho/server/data-integration-server/data/mysql5/create\_jcr\_mysql.sql
  - pentaho/server/data-integration-server/data/mysql5/create\_quartz\_mysql.sql
  - pentaho/server/data-integration-server/data/mysql5/create\_repository\_mysql.sql

Here is an example of a password change made in the create\_jcr\_mysql.sql file.

```
grant all on jackrabbit.* to 'jcr_user'@'localhost' identified by 'myNewPassword';
```

- 2. The process for running the SQL scripts against MySQL are the same for both Windows and Linux machines.
  - a) Run the create\_quartz\_mysql.sql script in the **Terminal** or **Command Prompt** window by typing: mysql u root -p < create\_quartz\_mysql.sql.
  - b) Run the create\_repository\_mysql.sql script in the **Terminal** or **Command Prompt** window by typing: mysql -u root -p < create\_repository\_mysql.sql.
  - c) Run the create\_jcr\_mysql.sql script in the **Terminal** or **Command Prompt** window by typing: mysql -u root -p < create\_jcr\_mysql.sql.
  - d) Run the pentaho\_mart\_mysql.sql script in the **Terminal** or **Command Prompt** window by typing: mysql -u root -p < pentaho\_mart\_mysql.sql.
- 3. To verify that databases and user roles have been created, do this.
  - a) Open the MySQL Workbench tool. MySQL Workbench is freely available at the MySQL development site.
  - b) Make sure that the Jackrabbit (JCR), Hibernate, and Quartz databases are present.
  - c) Make sure that the jcr\_user, hibuser, and pentaho\_user user accounts are present.
  - d) If the databases and login roles do not appear, go to the beginning of these instructions and try running the scripts again.
  - e) Exit from the MySQL Workbench.

# Initialize Oracle DI Repository Database

To initialize Oracle so it serves as the DI Repository, run SQL scripts to create the Hibernate, Quartz and Jackrabbit (also known as the JCR) databases.

- 1. To make the databases that you create more secure, Pentaho recommends that you change the default passwords in the SQL script files to ones that you specify. If you are evaluating Pentaho, you might want to skip this step. If you do decide to make the databases more secure, use a text editor to change the passwords in these files. (Also, for each file, edit the **datafile** path with the path to your Oracle installation.)
  - pentaho/server/data-integration-server/data/oracle10g/create\_jcr\_ora.sql
  - pentaho/server/data-integration-server/data/oracle10g/create\_quartz\_ora.sql

• pentaho/server/data-integration-server/data/oracle10g/create\_repository\_ora.sql

Here is an example of a password change made in the create\_jcr\_ora.sql file.

```
--conn admin/myNewPassword@pentaho create user jcr_user identified by "myNewPassword" default tablespace pentaho_tablespace quota unlimited on pentaho_tablespace temporary tablespace temp quota 5M on system;
```

- 2. Although there are several different methods for running SQL scripts, these instructions explain how to run SQL\*Plus from a Terminal or Command Prompt window. These instructions are the same for both Windows and Linux. If you prefer to run SQL scripts using another method, modify instructions accordingly.
  - a) Open a Terminal or Command Prompt window, start the SQL\*Plus and log in.
  - b) Run the script to create the Jackrabbit database by typing START create\_jcr\_ora. If necessary, append the path to the create\_jcr\_ora.sql path in the command.
  - c) Run the script to create the repository database by typing START create\_repository\_ora. If necessary, append the path to the create\_repository\_ora.sql path in the command.
  - d) Run the script to create the Quartz database and users by typing START create\_quartz\_ora. If necessary, append the path to the create\_quartz\_ora.sql path in the command.
  - e) Run the script to create the Operations Mart database and users by typing START pentaho\_mart\_ora. If necessary, append the path to the pentaho\_mart\_ora.sql path in the command.
- 3. To verify that databases and user roles have been created, do this.
  - a) In the Terminal or Command Prompt window that is running SQL\*Plus, make sure that the Jackrabbit database has been created by typing DESCRIBE JACKRABBIT;. The column definitions should appear when you press Enter.
  - b) Make sure the Quartz database has been created by typing DESCRIBE QUARTZ;. The column definitions for the Quartz table should appear when you press **Enter**.
  - c) To see the users that have been created, type SELECT USERNAME FROM DBA\_USERS.
  - d) If the databases and login roles do not appear, go to the beginning of these instructions and try running the scripts again.
  - e) Exit from SQL\*Plus.



Before you configure the DI Repository complete the tasks in *Initialize Repository*.

Tasks performed during this step include configuring Audit, Quartz, and Hibernate properties. Tasks are grouped by the DI Repository database you have.

- PostgreSQL Configuration Tasks
- MySQL Configuration Tasks
- Oracle Configuration Tasks

## Configure PostgreSQL DI Repository Database

These instructions explain how to configure Quartz, Hibernate, Jackrabbit, and Pentaho Security for use with the PostgreSQL database. By default, the files edited in this section are configured for a PostgreSQL database that runs on port 5432. The default password is also in these files. If you have a different port, different password, or if had the system configured using a different database and now you want to change it back to PostgreSQL, complete all of the instructions in these steps.

#### Configure Quartz on PostgreSQL DI Repository Database

When you use Pentaho to schedule an event, such as a report to be run every Sunday at 1:00 a.m. EST, event information is stored in the Quartz JobStore. During the installation process, you must indicate where the JobStore is located. To do this, modify the guartz.properties file.

- 1. Open the pentaho/server/data-integration-server/pentaho-solutions/system/quartz/quartz.properties file in the text editor of your choice.
- 2. Make sure that in the #\_replace\_jobstore\_properties section of the file, the org.quartz.jobStore.driverDelegateClass is set to org.quartz.impl.jdbcjobstore.PostgreSQLDelegate.
- 3. Save the file and close the text editor.

## Configure Hibernate Settings for PostgreSQL DI Repository Database

Modify the hibernate settings file to specify where Pentaho will find the DI Repository's hibernate configuration file. The hibernate configuration file specifies driver and connection information, as well as dialects and how to handle connection closes and timeouts.

- 1. Open pentaho/server/data-integration-server/pentaho-solutions/system/hibernate/hibernate.settings.xml in a text editor.
- 2. Verify that the location of the PostgreSQL hibernate configuration file appears. Make changes if necessary.

```
<config-file>system/hibernate/postgresql.hibernate.cfg.xml</config-file>
```

- 3. Save the file if you had to make changes, then close it. Otherwise, just close it.
- **4.** Open pentaho/server/data-integration-server/pentaho-solutions/system/hibernate/postgresql.hibernate.cfg.xml in a text editor.
- **5.** Make sure that the password and port number match the ones you specified in your configuration. Make changes as necessary, then save and close the file.

### Modify Jackrabbit DI Repository Information for PostgreSQL

Indicate which database houses the DI Repository as well as the port, url, username, and password. All of the information needed to configure the repository for the PostgreSQL, MySQL, and Oracle DI Repository databases

appear. By default, the PostgreSQL sections are not commented out, but the MySQL and Oracle sections are. To modify this file so that it works for your DI Repository, you will need to make sure that the sections that refer to your DI Repository database are not commented out, and the sections refer to other DI Repository databases are commented out.

When code is commented out, it appears between the <! -- and --> tags. The information in between the tags is commented out, and is therefore not executed by the software. In this example, the code <! <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem"> is commented out.

```
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
-->
```

To make sure that the Jackrabbit repository is set so that PostgreSQL is the default database, do this.

- 1. Use a text editor to open the pentaho/server/data-integration-server/pentaho-solutions/system/jackrabbit/repository.xml file.
- 2. In the Repository part of the code, make sure that the PostgreSQL lines of code are not commented out, but the Oracle and MySQL lines are. The code should look like this.

```
<!--
  <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
   <param name="driver" value="com.mysql.jdbc.Driver"/>
   <param name="schemaObjectPrefix" value="fs_repos_"/>
  </FileSystem>
  <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
    <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
   <param name="schemaObjectPrefix" value="fs_repos_"/>
   <param name="tablespace" value="jackrabbit"/>
 </FileSystem>
-->
 <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
    <param name="driver" value="org.postgresql.Driver"/>
    <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
   <param name="user" value="jcr_user"/>
   <param name="password" value="password"/>
   <param name="schema" value="postgresql"/>
    <param name="schemaObjectPrefix" value="fs_repos_"/>
  </FileSystem>
```

**Note:** If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

3. In the DataStore section of the code, verify that the PostgreSQL lines of code are not commented out, but the Oracle and MySQL lines are. The code should look like this.

```
<!--
  <DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
   <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
   <param name="schemaObjectPrefix" value="ds_repos_"/>
  </DataStore>
  <DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
   <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
   <param name="schemaObjectPrefix" value="ds_repos_"/>
  </DataStore>
  <DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
    <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
    <param name="driver" value="org.postgresql.Driver"/>
    <param name="user" value="jcr_user"/>
    <param name="password" value="password"/>
    <param name="databaseType" value="postgresql"/>
    <param name="minRecordLength" value="1024"/>
```

```
<param name="maxConnections" value="3"/>
  <param name="copyWhenReading" value="true"/>
  <param name="tablePrefix" value=""/>
  <param name="schemaObjectPrefix" value="ds_repos_"/>
  </DataStore>
```

**4.** In the Workspaces section of the code, make sure that the PostgreSQL lines of code are not commented out, but the Oracle and MySQL lines are. This code should look like this.

```
<!--
    <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
     <param name="driver" value="com.mysql.jdbc.Driver"/>
     <param name="schemaObjectPrefix" value="fs ws "/>
    </FileSystem>
    <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
      <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
     <param name="schemaObjectPrefix" value="fs ws "/>
      <param name="tablespace" value="jcr_user"/>
    </FileSystem>
    <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
     <param name="driver" value="org.postgresql.Driver"/>
     <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
     <param name="user" value="jcr_user"/>
     <param name="password" value="password"/>
     <param name="schema" value="postgresql"/>
      <param name="schemaObjectPrefix" value="fs_ws_"/>
    </FileSystem>
```

**Note:** If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

**5.** In the Persistence Manager section of the code, verify that the PostgreSQL lines of code are not commented out, but the Oracle and MySQL lines are. The code should look like this.

```
<!--
    <PersistenceManager
class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
     <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
     <param name="schemaObjectPrefix" value="${wsp.name}_pm_ws_"/>
    </PersistenceManager>
    <PersistenceManager
 class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
     <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
     <param name="schemaObjectPrefix" value="${wsp.name} pm ws "/>
     <param name="tablespace" value="jackrabbit"/>
   </PersistenceManager>
    <PersistenceManager
 class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
     <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
     <param name="driver" value="org.postgresql.Driver"/>
     <param name="user" value="jcr_user"/>
     <param name="password" value="password"/>
     <param name="schema" value="postgresql"/>
     <param name="schemaObjectPrefix" value="${wsp.name}_pm_ws_"/>
    </PersistenceManager>
```

**Note:** If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

**6.** In the Versioning section of the code, verify that the PostgreSQL lines of code are not commented out, but the MySQL and Oracle lines are. The code should look like this.

```
< ! --
    <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
      <param name="driver" value="com.mysql.jdbc.Driver"/>
      <param name="schemaObjectPrefix" value="fs_ver_"/>
    </FileSystem>
    <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
      <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
      <param name="schemaObjectPrefix" value="fs_ver_"/>
      <param name="tablespace" value="jackrabbit"/>
    </FileSystem>
    -->
    <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
      <param name="driver" value="org.postgresql.Driver"/>
      <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
      <param name="user" value="jcr_user"/>
      <param name="password" value="password"/>
      <param name="schema" value="postgresql"/>
      <param name="schemaObjectPrefix" value="fs_ver_"/>
    </FileSystem>
```

**Note:** If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

7. In the Persistence Manager section of the code that is near the end of the file, verify that PostgreSQL lines of code are not commented out, but the MySQL and Oracle lines are. The codes should look like this.

```
<!--
    <PersistenceManager
class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
     <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
     <param name="schemaObjectPrefix" value="pm_ver_"/>
    </PersistenceManager>
    <PersistenceManager
 class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
     <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
     <param name="schemaObjectPrefix" value="pm_ver_"/>
     <param name="tablespace" value="jackrabbit"/>
    </PersistenceManager>
    <PersistenceManager
 class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
     <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
     <param name="driver" value="org.postgresql.Driver"/>
     <param name="user" value="jcr_user"/>
     <param name="password" value="password"/>
     <param name="schema" value="postgresql"/>
     <param name="schemaObjectPrefix" value="pm_ver_"/>
    </PersistenceManager>
```

**Note:** If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

8. Close and save the file.

# Prepare MySQL DI Repository Database

These instructions explain how to configure Quartz, Hibernate, Jackrabbit, and Pentaho Security for a MySQL database. By default, the examples in this section are for a MySQL database that runs on port 3306. The default

password is also in these examples. If you have a different port, different password complete all of the instructions in these steps.

## Configure Quartz on MySQL DI Repository Database

When you use Pentaho to schedule an event, such as a report to be run every Sunday at 1:00 a.m. EST, event information is stored in the Quartz JobStore. During the installation process, you must indicate where the JobStore is located. To do this, modify the quartz.properties file.

- 1. Open the pentaho/server/data-integration-server/pentaho-solutions/system/quartz/quartz.properties file in the text editor of your choice.
- 2. In the #\_replace\_jobstore\_properties section of the file, set the
   org.quartz.jobStore.driverDelegateClass equal to
   org.quartz.impl.jdbcjobstore.StdJDBCDelegate.
   org.quartz.jobStore.driverDelegateClass = org.quartz.impl.jdbcjobstore.StdJDBCDelegate
- 3. Save the file and close the text editor.

#### Configure Hibernate Settings for MySQL

Modify the hibernate settings file to specify where Pentaho will find the DI Repository's hibernate configuration file. The hibernate configuration file specifies driver and connection information, as well as dialects and how to handle connection closes and timeouts.

1. Open pentaho/server/data-integration-server/pentaho-solutions/system/hibernate/hibernate.settings.xml in a text editor. By default, system indicates the location of the PostgreSQL hibernate configuration file.

```
<config-file>system/hibernate/postgresql.hibernate.cfg.xml</config-file>
```

2. Change the default reference to the MySQL configuration file.

```
<config-file>system/hibernate/mysql5.hibernate.cfg.xml</config-file>
```

- 3. Save and close the file.
- **4.** Open pentaho/server/data-integration-server/pentaho-solutions/systems/hibernate/mysql5.hibernate.cfg.xml in a text editor.
- **5.** Make sure that the password and port number match the ones you specified in your configuration. Make changes as necessary, then save and close the file.

#### Modify Jackrabbit Repository Information for MySQL

You must indicate which database is used as the DI Repository as well as the port, url, username, and password. All of the information needed to configure the repository for the PostgreSQL, MySQL, and Oracle DI Repository databases appear. By default, the PostgreSQL sections are not commented out, but the MySQL and Oracle sections are. To modify this file so that it works for your DI Repository, you will need to make sure that the sections that refer to your DI Repository Database are not commented out, and the sections refer to other DI Repository databases are commented out.

When code is commented out, it appears between the <! -- and --> tags. The information in between the tags is commented out, and is therefore not executed by the software. In this example, the code <! <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem"> is commented out.

```
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
-->
```

To modify the Jackrabbit repository so that MySQL is the default database, do this.

- 1. Use a text editor to open the pentaho/server/data-integration-server/pentaho-solutions/system/jackrabbit/repository.xml file.
- 2. In the Repository part of the code, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like this.

```
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
```

```
<param name="driver" value="com.mysql.jdbc.Driver"/>
    <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
    <param name="user" value="jcr_user"/>
    <param name="password" value="password"/>
    <param name="schema" value="mysql"/>
    <param name="schemaObjectPrefix" value="fs_repos_"/>
 </FileSystem>
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
   <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
    <param name="schemaObjectPrefix" value="fs_repos_"/>
    <param name="tablespace" value="jackrabbit"/>
  </FileSystem>
  <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
    <param name="driver" value="org.postgresql.Driver"/>
   <param name="schemaObjectPrefix" value="fs_repos_"/>
  </FileSystem>
```

3. In the DataStore section of the code, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like this.

```
<DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
    <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
    <param name="user" value="jcr_user"/>
    <param name="password" value="password"/>
    <param name="databaseType" value="mysql"/>
    <param name="driver" value="com.mysql.jdbc.Driver"/>
    <param name="minRecordLength" value="1024"/>
    <param name="maxConnections" value="3"/>
    <param name="copyWhenReading" value="true"/>
    <param name="tablePrefix" value=""/>
    <param name="schemaObjectPrefix" value="ds_repos_"/>
 </DataStore>
 <!--
 <DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
    <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
   <param name="schemaObjectPrefix" value="ds_repos_"/>
  </DataStore>
  <DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
    <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
    <param name="schemaObjectPrefix" value="ds_repos_"/>
  </DataStore>
  -->
```

**4.** In the Workspaces section of the code, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like this.

**5.** In the Persistence Manager section of the code, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like this.

```
<PersistenceManager
class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
     <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
      <param name="user" value="jcr_user" />
     <param name="password" value="password" />
     <param name="schema" value="mysql"/>
     <param name="schemaObjectPrefix" value="${wsp.name}_pm_ws_"/>
    </PersistenceManager>
 <!--
    <PersistenceManager
class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
     <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
     <param name="schemaObjectPrefix" value="${wsp.name}_pm_ws_"/>
     <param name="tablespace" value="jackrabbit"/>
    </PersistenceManager>
    <PersistenceManager
 class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
     <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
     <param name="schemaObjectPrefix" value="${wsp.name}_pm_ws_"/>
   </PersistenceManager>
```

**Note:**If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

**6.** In the Versioning section of the code, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like his.

```
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
      <param name="driver" value="com.mysql.jdbc.Driver"/>
     <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
     <param name="user" value="jcr_user"/>
     <param name="password" value="password"/>
     <param name="schema" value="mysql"/>
      <param name="schemaObjectPrefix" value="fs_ver_"/>
    </FileSystem>
<!--
    <FileSystem class="org.apache.jackrabbit.core.fs.db.0racleFileSystem">
     <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
     <param name="schemaObjectPrefix" value="fs_ver_"/>
     <param name="tablespace" value="jackrabbit"/>
    </FileSystem>
    <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
      <param name="driver" value="org.postgresql.Driver"/>
     <param name="schemaObjectPrefix" value="fs_ver_"/>
    </FileSystem>
```

7. In the Persistence Manager section of the code that is near the end of the file, change the code so that the MySQL lines of code are not commented out, but the PostgreSQL and Oracle lines are, like this.

```
<PersistenceManager
class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
      <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
      <param name="user" value="jcr_user" />
      <param name="password" value="password"</pre>
      <param name="schema" value="mysql"/>
      <param name="schemaObjectPrefix" value="pm_ver_"/>
    </PersistenceManager>
<!--
    <PersistenceManager
class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
     <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
      <param name="schemaObjectPrefix" value="pm_ver_"/>
      <param name="tablespace" value="jackrabbit"/>
    </PersistenceManager>
    <PersistenceManager
class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
      <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
      <param name="schemaObjectPrefix" value="pm_ver_"/>
    </PersistenceManager>
```

**Note:**If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

## **Prepare Oracle DI Repository Database**

These instructions explain how to configure Quartz, Hibernate, Jackrabbit, and Pentaho Security. By default, the examples in this section are for a Oracle database that runs on port 1521. The default password is also in these examples. If you have a different port, different password complete all of the instructions in these steps.

### **Configure Quartz on Oracle DI Repository Database**

When you use Pentaho to schedule an event, such as a report to be run every Sunday at 1:00 a.m. EST, event information is stored in the Quartz JobStore. During the installation process, you must indicate where the JobStore is located. To do this, modify the quartz.properties file.

- 1. Open the pentaho/server/data-integration-server/pentaho-solutions/system/quartz/quartz.properties file in the text editor of your choice.
- 2. In the #\_replace\_jobstore\_properties section of the file, set the
   org.quartz.jobStore.driverDelegateClass equal to
   org.quartz.impl.jdbcjobstore.oracle.OracleDelegate.
   org.quartz.jobStore.driverDelegateClass =
   org.quartz.impl.jdbcjobstore.oracle.OracleDelegate
- 3. Save the file and close the text editor.

#### **Configure Hibernate Settings for Oracle**

Modify the hibernate settings file to specify where Pentaho will find the DI Repository's hibernate configuration file. The hibernate configuration file specifies driver and connection information, as well as dialects and how to handle connection closes and timeouts.

1. Open pentaho/server/data-integration-server/pentaho-solutions/systems/hibernate/hibernate.settings.xml in a text editor. By default, system indicates the location of the PostgreSQL hibernate configuration file.

```
<config-file>system/hibernate/postgresql.hibernate.cfg.xml</config-file>
```

2. Change the default to this to point to the MySQL configuration file.

```
<config-file>system/hibernate/oracle.hibernate.cfg.xml</config-file>
```

- Save and close the file.
- **4.** Open pentaho/server/data-integration-server/systems/hibernate/oracle.hibernate.cfg.xml in a text editor.
- **5.** Make sure that the password and port number match the ones you specified in your configuration. Make changes as necessary, then save and close the file.

#### Modify Jackrabbit Repository Information for Oracle

You must indicate which database is used as the DI Repository as well as the port, url, username, and password. All of the information needed to configure the repository for the PostgreSQL, MySQL, and Oracle DI Repository databases appear. By default, the PostgreSQL sections are not commented out, but the MySQL and Oracle sections are. To modify this file so that it works for your DI Repository, you will need to make sure that the sections that refer to your DI Repository Database are not commented out, and the sections refer to other DI Repository databases are commented out.

When code is commented out, it appears between the <! -- and --> tags. The information in between the tags is commented out, and is therefore not executed by the software. In this example, the code <! <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem"> is commented out.

```
<!--
<FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
-->
```

To modify the Jackrabbit repository so that Oracle is the default database, do this.

- 1. Use a text editor to open the pentaho/server/data-integration-server/pentaho-solutions/system/jackrabbit/repository.xml file.
- 2. In the Repository part of the code, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like this.

```
< ! --
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
    <param name="driver" value="com.mysql.jdbc.Driver"/>
    <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
   <param name="schemaObjectPrefix" value="fs_repos_"/>
  </FileSystem>
<FileSystem class="org.apache.jackrabbit.core.fs.db.0racleFileSystem">
    <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
    <param name="user" value="jcr_user"/>
    <param name="password" value="password"/>
    <param name="schemaObjectPrefix" value="fs_repos_"/>
    <param name="tablespace" value="jackrabbit"/>
  </FileSystem>
<!--
  <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
    <param name="driver" value="org.postgresql.Driver"/>
    <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
    <param name="schemaObjectPrefix" value="fs_repos_"/>
  </FileSystem>
```

3. In the DataStore section of the code, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like this.

```
<!--
<DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
    <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
    <param name="schemaObjectPrefix" value="ds_repos_"/>
  </DataStore>
 <DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
    <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
    <param name="driver" value="oracle.jdbc.OracleDriver"/>
    <param name="user" value="jcr_user"/>
    <param name="password" value="password"/>
    <param name="databaseType" value="oracle"/>
    <param name="minRecordLength" value="1024"/>
    <param name="maxConnections" value="3"/>
    <param name="copyWhenReading" value="true"/>
    <param name="tablePrefix" value=""/>
    <param name="schemaObjectPrefix" value="ds_repos_"/>
 </DataStore>
 <DataStore class="org.apache.jackrabbit.core.data.db.DbDataStore">
   <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
   <param name="schemaObjectPrefix" value="ds_repos_"/>
  </DataStore>
```

**Note:**If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

**4.** In the Workspaces section of the code, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like this.

```
< ! --
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
      <param name="driver" value="com.mysql.jdbc.Driver"/>
      <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
     <param name="schemaObjectPrefix" value="fs_ws_"/>
    </FileSystem>
-->
    <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
     <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
      <param name="user" value="jcr_user"/>
     <param name="password" value="password"/>
     <param name="schemaObjectPrefix" value="fs_ws_"/>
      <param name="tablespace" value="jcr_user"/>
   </FileSystem>
< ! --
    <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
      <param name="driver" value="org.postgresql.Driver"/>
      <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
      <param name="schemaObjectPrefix" value="fs_ws_"/>
    </FileSystem>
```

**Note:**If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

**5.** In the Persistence Manager section of the code, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like this.

```
< ! --
<PersistenceManager
class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
      <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
      <param name="schemaObjectPrefix" value="${wsp.name}_pm_ws_"/>
    </PersistenceManager>
    <PersistenceManager
 class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
      <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
      <param name="driver" value="oracle.jdbc.OracleDriver"/>
      <param name="user" value="jcr_user"/>
      <param name="password" value="password"/>
      <param name="schema" value="oracle"/>
      <param name="schemaObjectPrefix" value="${wsp.name}_pm_ws_"/>
      <param name="tablespace" value="jackrabbit"/>
    </PersistenceManager>
 < ! - -
   <PersistenceManager
 class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
      <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
      <param name="schemaObjectPrefix" value="${wsp.name}_pm_ws_"/>
   </PersistenceManager>
```

**Note:**If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

**6.** In the Versioning section of the code, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like his.

```
<FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
     <param name="driver" value="com.mysql.jdbc.Driver"/>
     <param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
     <param name="schemaObjectPrefix" value="fs_ver_"/>
    </FileSystem>
-->
    <FileSystem class="org.apache.jackrabbit.core.fs.db.OracleFileSystem">
     <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
     <param name="user" value="jcr_user"/>
     <param name="password" value="password"/>
     <param name="schemaObjectPrefix" value="fs_ver_"/>
      <param name="tablespace" value="jackrabbit"/>
    </FileSystem>
 < 1 --
   <FileSystem class="org.apache.jackrabbit.core.fs.db.DbFileSystem">
      <param name="driver" value="org.postgresql.Driver"/>
      <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
     <param name="schemaObjectPrefix" value="fs_ver_"/>
    </FileSystem>
-->
```

**Note:**If you changed your password when you initialized the database during the Prepare Environment step, or if your database is on a different port, edit the url and password parameters accordingly.

7. In the Persistence Manager section of the code that is near the end of the file, change the code so that the Oracle lines of code are not commented out, but the PostgreSQL and MySQL lines are, like this.

```
<!--
<PersistenceManager
class="org.apache.jackrabbit.core.persistence.bundle.MySqlPersistenceManager">
```

```
<param name="url" value="jdbc:mysql://localhost:3306/jackrabbit"/>
     <param name="schemaObjectPrefix" value="pm_ver_"/>
    </PersistenceManager>
-->
    <PersistenceManager
class="org.apache.jackrabbit.core.persistence.bundle.OraclePersistenceManager">
     <param name="url" value="jdbc:oracle:thin:@localhost:1521/XE"/>
     <param name="driver" value="oracle.jdbc.OracleDriver"/>
     <param name="user" value="jcr_user"/>
     <param name="password" value="password"/>
     <param name="schema" value="oracle"/>
     <param name="schemaObjectPrefix" value="pm_ver_"/>
     <param name="tablespace" value="jackrabbit"/>
    </PersistenceManager>
 <!--
   <PersistenceManager
class="org.apache.jackrabbit.core.persistence.bundle.PostgreSQLPersistenceManager">
     <param name="url" value="jdbc:postgresql://localhost:5432/jackrabbit"/>
     <param name="schemaObjectPrefix" value="pm_ver_"/>
    </PersistenceManager>
```

# **Specify Connections**



After your *repository has been configured*, you must configure the web application servers to connect to the DI Repository. In this step, JDBC and JNDI connections are made to the Hibernate, Jackrabbit, and Quartz databases. These databases were installed on your DI Repository database during the Initialize Repository and Configure Repository sections of these instructions.

By default, the DI Server software is configured to be deployed and run on the Tomcat server. As such, connections have already been specified and only the Tomcat context.xml file must be modified. Complete the following tasks.

- Copy JDBC Drivers
- Modify JDBC Connection Information

# **Perform Tomcat-Specific Connection Tasks**

If you plan to run the DI Server on Tomcat, you must modify JDBC Connection information.

#### **Copy Solution Database JDBC Drivers**

For the DI Server to connect to the DI Repository database of your choice, add the DI Repository's database JDBC driver library to the appropriate place in the web application server on which the DI Server will be deployed. The default web application server for the archive installation process is Tomcat.

- Download a JDBC driver JAR from your database vendor or a third-party driver developer.
   Due to licensing restrictions, Pentaho does not distribute the necessary JDBC driver JARs.
- 2. Copy the JDBC driver JAR you just downloaded to the /tomcat/lib/ directory.

#### Download and Install H2 JDBC Drivers

Install the H2 JDBC driver.

- 1. Download the version 1.2.131 of the H2 JDBC JAR from the http://code.google.com/p/h2database/downloads/list.
- 2. Copy the JDBC driver JAR you just downloaded to the tomcat/lib/ directory.

#### Modify JDBC Connection Information in the Tomcat context.xml File

Database connection and network information, such as the username, password, driver class information, IP address or domain name, and port numbers for your DI Repository database are stored in the context.xml file. You will need to modify this file to reflect the database connection and network information to reflect your operating environment. You also modify the values for the validationQuery parameters in this file if you have choosen to use an DI Repository database other than PostgreSQL.

- Consult your database documentation to determine the JDBC class name and connection string for your DI Repository database.
- 2. Use a text editor of your choice to open the context.xml file that is in the tomcat/webapps/pentaho-di/META-INF/directory.
- 3. Do one of these things.
  - a) If you are using PostgreSQL as your DI Repository database, ensure that comments are removed from the resource names for the PostgreSQL database and comment out the resource names for the other databases. In the PostgreSQL sections, adjust the port numbers and passwords to reflect your environment, if necessary.

```
<Resource validationQuery="select 1" url="jdbc:postgresql://
localhost:5432/di_hibernate" driverClassName="org.postgresql.Driver"
password="password" username="hibuser" maxWait="10000" maxIdle="5"</pre>
```

```
maxActive="20" factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Hibernate"/>
<Resource validationQuery="select 1" url="jdbc:postgresql://</pre>
localhost:5432/di_hibernate" driverClassName="org.postgresql.Driver"
password="password" username="hibuser" maxWait="10000" maxIdle="5"
maxActive="20" factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Audit"/>
<Resource validationQuery="select 1" url="jdbc:postgresql://</pre>
localhost:5432/di_quartz" driverClassName="org.postgresql.Driver"
password="password" username="pentaho_user" maxWait="10000" maxIdle="5"
maxActive="20" factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/Quartz"/>
<Resource validationQuery="select 1" url="jdbc:postgresql://</pre>
localhost:5432/hibernate" driverClassName="org.postgresql.Driver"
password="password" username="hibuser" maxWait="10000" maxIdle="5"
maxActive="20" factory="org.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/
pentaho_operations_mart"/>
<Resource validationQuery="select 1" url="jdbc:postgresql://</pre>
localhost:5432/hibernate driverClassName="org.postgresql.Driver"
password="password" username="hibuser" maxWait="10000" maxIdle="5"
maxActive="20" factory="orq.apache.commons.dbcp.BasicDataSourceFactory"
type="javax.sql.DataSource" auth="Container" name="jdbc/PDI Operations Mart"/>
```

b) If you are using MySQL as your DI Repository database, remove comments from the resource names for the MySQL database and comment out the resource names for the other databases. In the MySQL sections, adjust the port numbers and passwords to reflect your environment, if necessary.

```
<Resource validationQuery="select 1" url="jdbc:mysql://localhost:3306/</pre>
di_hibernate" driverClassName="com.mysql.jdbc.Driver" password="password"
 username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
 factory="org.apache.commons.dbcp.BasicDataSourceFactory"
 type="javax.sql.DataSource" auth="Container" name="jdbc/Hibernate"/>
<Resource validationQuery="select 1" url="jdbc:mysql://localhost:3306/</pre>
di_hibernate" driverClassName="com.mysql.jdbc.Driver" password="password"
 username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
 factory="org.apache.commons.dbcp.BasicDataSourceFactory"
 type="javax.sql.DataSource" auth="Container" name="jdbc/Audit"/>
<Resource validationQuery="select 1" url="jdbc:mysql://localhost:3306/</pre>
di quartz" driverClassName="com.mysql.jdbc.Driver" password="password"
 username="pentaho_user" maxWait="10000" maxIdle="5" maxActive="20"
 factory="org.apache.commons.dbcp.BasicDataSourceFactory"
 type="javax.sql.DataSource" auth="Container" name="jdbc/Quartz"/>
<Resource validationQuery="select 1" url="jdbc:mysql://localhost:3306/</pre>
hibernate" driverClassName="com.mysql.jdbc.Driver" password="password"
 username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
 factory="org.apache.commons.dbcp.BasicDataSourceFactory"
 type="javax.sql.DataSource" auth="Container" name="jdbc/
pentaho_operations_mart"/>
<Resource validationQuery="select 1" url="jdbc:mysql://localhost:3306/</pre>
hibernate driverClassName="com.mysql.jdbc.Driver" password="password"
 username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
 factory="org.apache.commons.dbcp.BasicDataSourceFactory"
 type="javax.sql.DataSource" auth="Container" name="jdbc/PDI_Operations_Mart"/>
```

c) If you are using Oracle as your DI Repository database, remove comments from the resource names for the Oracle database and comment out the resource names for the other databases. In the Oracle sections, adjust the port numbers and passwords to reflect your environment, if necessary.

```
<Resource validationQuery="select 1" url="jdbc:oracle:thin:@localhost:1521/
XE" driverClassName="oracle.jdbc.OracleDriver" password="password"
  username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
  factory="org.apache.commons.dbcp.BasicDataSourceFactory"
  type="javax.sql.DataSource" auth="Container" name="jdbc/Hibernate"/>
<Resource validationQuery="select 1" url="jdbc:oracle:thin:@localhost:1521/
XE" driverClassName="oracle.jdbc.OracleDriver" password="password"
  username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
  factory="org.apache.commons.dbcp.BasicDataSourceFactory"
  type="javax.sql.DataSource" auth="Container" name="jdbc/Audit"/>
```

```
<Resource validationQuery="select 1" url="jdbc:oracle:thin:@localhost:1521/</pre>
XE" driverClassName="oracle.jdbc.OracleDriver" password="password"
username="pentaho_user" maxWait="10000" maxIdle="5" maxActive="20"
 factory="org.apache.commons.dbcp.BasicDataSourceFactory"
 type="javax.sql.DataSource" auth="Container" name="jdbc/Quartz"/>
<Resource validationQuery="select 1" url="jdbc:oracle:thin:@localhost:1521/</pre>
XE" driverClassName="oracle.jdbc.OracleDriver" password="password"
username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
 factory="org.apache.commons.dbcp.BasicDataSourceFactory"
 type="javax.sql.DataSource" auth="Container" name="jdbc/
pentaho_operations_mart"/>
<Resource validationQuery="select 1" url="jdbc:oracle:thin:@localhost:1521/</pre>
XE" driverClassName="oracle.jdbc.OracleDriver" password="password"
username="hibuser" maxWait="10000" maxIdle="5" maxActive="20"
 factory="org.apache.commons.dbcp.BasicDataSourceFactory"
 type="javax.sql.DataSource" auth="Container" name="jdbc/PDI_Operations_Mart"/>
```

- **4.** Modify the username, password, driver class information, IP address (or domain name), and port numbers so they reflect the correct values for your environment.
- 5. Make sure that the validationQuery variable for your database is set to one of these.
  - PostgreSQLvalidationQuery="select 1"
  - MySQL:validationQuery="/\* ping \*/ select 1"/
  - Oracle:validationQuery="select 1"
- 6. Save the context.xmlfile, then close it.
- **7.** To verify that the changes have been made and saved, do this.
  - a) Open the context.xml file again. Make sure that the changes that you made to the file in these instructions have been saved.
  - b) Close the file.
- 8. To make sure that the changes that you made in the context.xml file take effect when Tomcat, navigate to the pentaho\server\data-integration-server\tomcat\conf\Catalina directory. If the pentaho-di.xml file is in the present, delete it. It will be generated again when you start the DI Server, but will contain the changes that you just made in the context.xml file.

# Start DI Server



After you've complete the tasks in the *Prepare Environment*, *Initialize Repository*, and *Specify Connections* steps, you can now install license keys and start the DI Server.

#### **Tomcat**

- Install License Keys
- Modify Tomcat Startup Script
- Start DI Server

## Install License Keys Using the Command Line Interface

- 1. Download the .lic file you want to install.
- 2. Copy your .lic files to the DI Server.
- Navigate to the licenses directory. pdi/pdi-ee/data-integration/licenses
- **4.** Run the license installation script.
  - a) For Linux: Run install\_license.sh with the install switch and the location and name of your .lic file as a parameter. You can specify multiple .lic files separated by spaces. Be sure to use backslashes to escape any spaces in the path or file name.
    - install\_license.sh install /home/dvader/downloads/Pentaho/BI/Platform/Enterprise/
      Edition.lic
  - b) **For Windows:** Run install\_license.bat with the install switch and the location and name of your license file as a parameter.
    - install\_license.bat install "C:\Users\dvader\Downloads\Pentaho BA Platform
      Enterprise Edition.lic"

# **Modify Tomcat Startup Script**

The Tomcat startup script must be modified to include the CATALINA\_OPTS variable. CATALINA\_OPTS indicates the amount of memory to allocate. It also indicates where Pentaho licenses are installed. Specific instructions on how to modify the startup script depend on your operating system.

## **Modify the Tomcat Windows Startup Script**

- 1. Make sure the Tomcat web application server is not running by starting the Windows **Task Manager** and looking for **Tomcat** in the **Applications** tab. If the server is running, stop it.
- 2. Use a text editor to open the startup. bat file, which is in the bin subdirectory of the Tomcat home directory.
- 3. Add this line directly before the call "%EXECUTABLE%" start %CMD\_LINE\_ARGS% line, which is located near the end of the file.

```
set CATALINA_OPTS=-Xms4096m -Xmx6144m -XX:MaxPermSize=256m -
Dsun.rmi.dgc.client.gcInterval=3600000 -Dsun.rmi.dgc.server.gcInterval=3600000 -
Dpentaho.installed.licenses.file=%PENTAHO_INSTALLED_LICENSE_PATH%
```

4. Save and close the file.

### Modifying the Tomcat Linux Startup Script

- 1. Make sure the Tomcat web application server is not running by opening a **Terminal** window and typing ps -A at the prompt. If the server is running, stop it.
- 2. Use a text editor to open the startup. sh file, which is in the bin subdirectory of the Tomcat home directory.

- 3. Add this line directly before the exec "\$PRGDIR"/"\$EXECUTABLE" start "\$@" line near the end of the file. export CATALINA\_OPTS="-Xms4096m -Xmx6144m -XX:MaxPermSize=256m Dsun.rmi.dgc.client.gcInterval=3600000 -Dsun.rmi.dgc.server.gcInterval=3600000 Dpentaho.installed.licenses.file=\$PENTAHO\_INSTALLED\_LICENSE\_PATH"
- 4. Save and close the file.

#### Windows Pentaho Archive Installation

If you used the Archive Installation, we provide individual control scripts to start and stop the DI server, and DI repository. Here is where you can find the individual control scripts.

#### **DI Repository**

• The Archive Installation enables you to install PostgreSQL, MySQL, or Oracle as the solution repository. Consult the third-party documentation for the RDBMS to find more information about starting and stopping.

The solution repository must be started before the DI Server.

#### DI Server

• /pentaho/server/data-integration-server

## **Linux and Macintosh OS Pentaho Installation Wizard**

When you ran the Installation Wizard on Linux, the DI Server was deployed in an included Apache Tomcat application server. You can control the Tomcat server using the start and stop scripts that come with the Pentaho installation. This script is also used as an easy way to start and stop the DI Server and the PostgreSQL repository. You can find this script at /pentaho/ctlscript.sh.


Here is a list of the script arguments you can use with the data-integration-server service.

#### **Arguments**

- start
- stop
- restart
- status
- help

```
./ctlscript.sh start data-integration-server
./ctlscript.sh status data-integration-server
./ctlscript.sh help
```

# **Next Steps**



Now that you've installed the DI Server, do two things.

- Install the design tool and plugins.
- Configure the DI Server, design tool, and plugins.

**Note:** If you have installed the DI Server so that you can migrate content from the old system to this one, make sure that your license keys have been installed, then view the Upgrade DI System instructions.

#### **Learn More**

· Learn about Big Data and Hadoop.