

RoadCoda Setup Guide

Sep 25, 2026 · @Michael D'Auria

Set these up once, in this order, and dispatch, invoicing and payroll work from the first week. Each section says what the setting does, what won't work without it, and how to set it, step by step.

How to use this guide

Setup › Settings check reads your company's own settings and records and lists what's left to do. Work down that list; this guide explains each item in more detail.

Status	What it means
Missing	A core job (dispatch, invoicing or payroll) won't work until it's set.
Fix	Something important works badly: money not billed, wrong hours, notices not sent.
Consider	Worth doing. Nothing breaks without it.
Know this	How RoadCoda behaves. Nothing to fix, but your team should know it.

The check updates as you fix things. Press **Test Google maps** on the same page to prove miles, prices and address checks work.

Set up in this order

1. **Company:** office, remit-to, yard, phone, billing email, time zone (Setup › Company).
2. **Modules:** pick Essentials, Growing fleet or Everything (Setup › Features).
3. **Office logins:** invite your people and give them their screens (Setup › Users).
4. **Customers, rates and fuel surcharge:** every billed account needs its own rate (Setup › Customers, Setup › Rates).
5. **Stops:** upload each customer's stops from the Stop locations template.
6. **Drivers and pay:** upload the Drivers template, then set each driver's pay (Setup › Drivers).

7. **Trucks and trailers:** upload the Trucks and trailers template (Setup › Equipment).
8. **Connections:** ELD, PC*MILER if you bill on it, customer notices (Setup › Integrations, Setup › Rates).
9. **Money:** toll factor, QuickBooks, payroll company, pay week.
10. **Driver app:** set every driver up on their phone before their first load.

Steps 4 to 7 go fastest from the RoadCoda setup templates (Setup › Getting started › Setup templates). Filled-in templates load in minutes; whatever an upload can't finish shows on **Setup › What we found**.

1. Company

Everything on invoices, customer emails and the driver app starts here. All of it is on **Setup › Company**; press **Save** at the bottom after changes.

Office address (Missing if blank)

Printed on invoices and handbooks. It is also where trucks start when there's no yard. **Without it:** invoices show no company address, and handbooks print "[fill in]".

1. Open Setup › Company › 2 Where you are.
2. Type the office address, then press **Check address**.
3. Save.

Yard address (Missing if there's no office address either)

Where trucks start their day. RoadCoda measures load miles from here unless a customer has its own start address. **Without it:** "Get miles & price" stops with "Enter a start address". Per-mile price, fuel surcharge and mileage pay come out at 0.

1. Open Setup › Company › 2 Where you are.
2. Type the yard address. Leave it blank only if trucks start at the office.
3. Save.
4. Dedicated customers whose trucks start at their plant: on Setup › Rates, pick the customer, choose **Truck starts at** (customer facility) and type its **Facility address**.

Remit-to address (Fix if blank)

Where customers send payment. **Without it:** invoice PDFs fall back to the office address, but the customer portal's invoice view prints no remit-to address. If payments go to a lockbox or a factoring company, invoices send them to the wrong place.

1. Open Setup › Company › 4 Getting paid.
2. Type the address payments go to, even if it's the office.
3. Save.

Office phone (Missing if blank)

Without it: no call-back number on invoices, customer emails, texts, the tracking page, or the driver app's **Call dispatch** button.

1. Open Setup › Company › 3 How to reach you.
2. Type the main office number.
3. Save.

Billing email (Fix if blank)

Without it: invoices show no email for billing questions.

1. Open Setup › Company › 3 How to reach you.
2. Type the billing email, e.g. billing@yourcompany.com.
3. Save.

Time zone (Know this)

Every day boundary uses it: invoice weeks, pay weeks, load days, late alerts and ETAs. A new company starts on Eastern time. **If it's wrong:** all of those are off by hours, and a load delivered at 11 pm can land in the wrong week.

1. Open Setup › Company › 2 Where you are.
2. Pick the time zone dispatch works in.
3. Save.

Hours-of-service cycle (Fix if blank)

Without it: drivers with no ELD are counted on 60 hours in 7 days. For a 70-hour fleet, the board and the dispatch assistant show the wrong hours left.

1. Open Setup › Company › 4 Getting paid.
2. Pick 60 hours / 7 days or 70 hours / 8 days.
3. Save. A driver on a different rule (for example intrastate) is set on that driver.

Logo and color (Consider)

Without it: invoices, customer emails, the portal and the tracking page carry no logo, and use RoadCoda's teal.

1. Open Setup › Company › 5 Your look.
2. Upload the logo (PNG or JPG) and pick your brand color.
3. Save.

Trip close-out (Know this)

Close-out is on for every new company. A delivered load can't be invoiced until billing approves its close-out, and drivers aren't paid for it until dispatch verifies it. That's how RoadCoda catches missing PODs, odd miles and unbilled detention before they cost money. **What to do:** make close-out a daily job for dispatch. Otherwise invoices and pay weeks look empty.

1. Each morning, open Dispatch and pick a delivered trip.
2. On its **Close-out** card, fix or explain anything flagged, then press **Verify as dispatch**.
3. Billing presses **Approve for billing & lock**; the load is then ready to invoice and pay.

How trips are checked and billed (Setup › Company › 6)

Setting	Starts at	What it does
Close out every trip before it's invoiced or paid	On	Recommended. Switching it off sends delivered loads straight to invoicing and pay, unchecked.
Every trip needs its trip sheet	Off	Close-out flags any trip without a photo of its paper trip sheet. Off: only paper-sheet drivers are asked.
Every load needs a seal number	Off	Close-out flags a delivery with no seal number. For sealed freight.

Setting	Starts at	What it does
Free time at the plant	120 minutes	Detention starts after this at pickups. Each customer can have its own on Setup › Customers › Delays & free time.
Free time at each stop	60 minutes	Detention starts after this at deliveries.
Arrival circle around a stop	200 meters	A truck inside it counts as at the stop, for GPS arrive and depart times.
Trailer axles when the trailer isn't recorded	2	Used by the toll class check.

Change any of them, then press **Save company details**.

2. Modules and people

Pick your modules (Missing until chosen)

RoadCoda asks the owner how to start: Essentials, Growing fleet or Everything. **Until it's picked:** the owner, and anyone who can edit Users, is sent to the Features page every time a page opens.

1. Open Setup › Features.
2. Pick a starting point. Essentials runs loads, proof of delivery, billing and pay. Growing fleet adds tolls, QuickBooks, profit, activity files, invoice drafts, documents on a load, GPS stop times, trip sheets, driver files and inspections, IFTA and payroll company files. Everything switches on every module.
3. Switch single modules on or off below it any time; nothing is lost. A module that's off is hidden from every screen.

Some modules need setting up before they do anything; section 8 of this guide and the Settings check list them.

Office logins and screens (Fix if the owner is the only login)

Each office person should have their own login. **Without it:** everyone shares the owner's login, so you can't limit who sees pay, and the history can't tell who changed what.

1. Open Setup › Users.

2. Invite each person by email, or upload the Office staff template.
3. Tick the screens each person needs, and whether they can view or edit.
4. **Missing:** a login with no screens can sign in but sees nothing. The Settings check names them.

A super user can manage other users. Keep that to one or two people.

Two-factor sign-in (Consider)

Without it: office logins are protected by a password only, and office staff can see pay, customer and invoice data.

1. Open Setup › Users.
2. Tick **Require two-factor sign-in for everyone in the office.**
3. From then on, each office person is stopped on every page until they set up an authenticator app on **My account**. Tell them before you switch it on.

3. Customers and billing

A load is only as billable as its customer's setup. Customer details are on **Setup › Customers**; prices and billing rules are on **Setup › Rates**.

Rate sheet or contract (Missing without one)

Every billed account needs its own price: a **rate sheet** for per-load pricing (flat, per mile, per stop, per unit, minimum), or a **contract** for weekly billing. **Without it:** loads are priced at \$0 ("No rate sheet for this customer on this date"), and a weekly invoice has nothing to bill.

1. Open Setup › Rates and pick the customer.
2. Per-load customers: add a rate sheet with the date it starts.
3. Weekly contract customers: add a contract version and its lines.
4. Loads already made at \$0 don't re-price themselves: open each one on Loads and press **Recalculate miles & price**.

DCs: who gets the invoice

A DC is an account under a main customer (for example NAPS – Hartford DC under NAPS). Each DC chooses where its invoices go, on Setup › Customers › pick the DC › **Invoices go to:**

Invoices go to	What happens
This account (the default)	The DC gets its own invoices, with its own terms, PO and weekly-or-per-load choice. Pick the DC on Invoices to bill it.
The main customer's invoices	The DC's loads go on the main customer's weekly or per-load invoices, with the main customer's terms and PO. The breakdown report lists each DC's loads under its name. On Invoices, pick the main customer; the DC on its own has nothing to invoice.

Either way, a DC's loads are priced on the DC's own rate sheet and fuel surcharge rule, or its main customer's if it has none. Free time, close-out tolerances, invoice-draft rules, portal tabs, trip types and delay codes also carry down from the main customer unless the DC has its own. The activity file's Bill-to column follows the same choice, so it always matches the invoice.

Fuel surcharge (Fix if a customer has a rate but no rule)

Without it: loads get no fuel surcharge. Fine if the rate includes fuel; otherwise it's money not billed.

1. Open Setup › Rates and pick the customer.
2. Under Fuel surcharge, add the rule from their contract: a per-mile table, a percent table, or base price and MPG.
3. Save with the date it starts.

Weekly DOE diesel price (Missing when it's more than 10 days old)

Fuel surcharges are figured from the DOE diesel price for the week. RoadCoda doesn't fetch it on its own. **Without a current price:** fuel surcharges use an old price, or none.

1. Every Monday afternoon, after the DOE publishes, open Setup › Rates › DOE diesel prices.
2. Press **Check DOE price**.

Bill-to address and terms (Missing without a bill-to)

Without a bill-to address: the invoice prints an empty BILL TO block. Without terms, the company terms apply (Net 30 unless you change it on Company).

1. Fill the Bill-To columns in the Customers template, or open a draft on Invoices and fill in **Bill-to address**.
2. Set the customer's payment terms on Setup › Rates › Payment terms, if different from yours.

Master bill or per load, and the billing window

A new customer is billed **weekly** (master bill) from Sunday 00:00, counting loads by service date. **If that's wrong:** a per-load customer gets one weekly invoice and never gets an invoice draft on delivery, and loads fall into the wrong week.

1. Open Setup › Rates and pick the customer.
2. Tick or untick **Master bill**.
3. For weekly customers, set **Starts on**, **At**, and **Count a load when it is** to match their week.

PO and invoice number

1. Customers who need a PO on every invoice: type it on Setup › Rates › PO / reference no., or add POs that change by month.
2. If your invoice number format uses {code}, fill in the **Customer code**. Without it the number has an empty part.

Detention price (Fix without one)

RoadCoda finds detention on its own, from free time and arrival times. **Without a price:** it's found but never billed.

1. Open Setup › Customers and pick the customer.
2. Under **Activities & driver pay on this customer**, set Detention's **Price to customer** (per hour).
3. Or set one company price on Setup › Drivers › **Pay & billing types** › Detention › Default price.
4. Free time (2 hours at the plant, 1 hour at a stop) is set per customer under **Delays & free time**.

Close-out tolerances (Consider)

How far a trip may be off before close-out flags it: miles off plan 8%, driver times vs GPS 10 minutes, POD urgent after 3 days, longest time on site 14 hours, truck moving 2 miles during a stop. Change them per customer under **Close-out tolerances**, or change your defaults there under **Your defaults**.

Invoice drafts on delivery (Consider)

For per-load customers, RoadCoda can make the invoice draft as soon as the load is delivered. Nothing is sent: the draft waits on Invoices for approval.

1. Open Setup › Customers and pick the customer.
2. Under **Delivery signature & invoicing**, set **Make the invoice draft when delivered to On**.
3. Choose what must be complete first: receiver signature, arrival and departure times, delivered counts, PO, photo.

Customer portal (Consider)

Without a login: the customer calls to ask where the truck is and for PODs, instead of seeing every delivery time, photo and signed POD themselves.

1. Open Setup › Customer logins and invite a customer.
2. Pick the kind: a **Billing** login sees all the customer's loads, its DCs, invoices and activity file; a **Delivery** login sees only the locations you pick (a store manager, say).
3. They get an email to set a password.
4. Which tabs logins see is under **Default portal tabs**, or per customer on Setup › Customers › Customer portal. **Missing:** with every tab switched off, logins see nothing.

4. Stops

Stops are the stores, DCs, yards and sites a customer's loads go to. Upload them from the Stop locations template: one tab per customer (named after the customer), or one list with a Customer column. Then edit any one on **Setup › Customers**, under the customer.

Address with a zip

Without it: load miles can't be worked out, so per-mile price, fuel surcharge and mileage pay are 0.

1. When you upload, leave the Zip column blank if you don't know it: the upload looks it up from the address when you save, and only uses the answer if Google finds the same town.
2. Never type a made-up zip such as 12345. The upload refuses it.
3. On a single stop, type the zip yourself and press **Check address**. If Google's match is in a different town, it says so in red: check the address with the customer before pressing **Use it anyway**. The same street name is in many towns.

Receiving window

Without it: no "running late" notice to the customer, no late or at-risk flag on the dispatch board, and the route planner has no time window.

Fill **Window Opens** and **Window Closes** in the template, as 24-hour times (07:00, 15:30).

Contact, phone and codes

The driver sees the contact, phone, door code, gate code, key box and delivery instructions on their phone at the stop. Codes show only on the day of delivery. Office notes never reach the driver. **Without them:** the driver arrives with no one to call and no way in.

Delivery notices (email and text)

1. To email a store as its load is on the way, running late or delivered: open the stop, tick **Send delivery notifications**, pick the notices, and give it an email or a notification email. **Fix:** a stop ticked for notices with no email gets nothing; the Settings check names them.
2. Texts go only to a number whose owner agreed. Ask first, then tick **They agreed to get texts**. If you change the number, untick it unless the new number's owner agreed too.
3. Company-wide, pick which notices go out on Setup › Rates › Customer notifications.

Map points (Consider)

GPS arrive and depart times, and the driver-times check at close-out, need the stop's map point. RoadCoda learns it overnight once drivers have scanned there about three times. To have it from day one, open the stop, press **Check address** and save.

5. Drivers and pay

Upload drivers from the Drivers template, then finish each one on **Setup › Drivers**. The template never takes Social Security or bank numbers.

The driver app (Missing until each driver is set up)

Without it: the driver can't see their loads, record stops, scan, take photos or get a signature, so none of that reaches dispatch, the customer or the invoice.

1. Open Setup › Drivers and pick the driver.
2. Press **Set up on a phone (QR code)** and have the driver scan it. Or press **Email sign-in link**, or **Copy sign-in link** and text it to them yourself.
3. There's no password. If the phone is ever signed out, the driver scans the reset card and enters the last 4 characters of their CDL (or a PIN they chose, if you switch that on under Driver app sign-in › Reset PIN on the card).
4. Drivers who keep paper trip sheets instead: set **Trip sheets** to Paper, and close-out will ask for the sheet.

Pay rates (Missing without one)

Without a rate: the driver shows \$0 for the week, with no warning. Nothing tells payroll how to pay their miles, stops, loads or hours.

1. Open Setup › Drivers and pick the driver.
2. Under **Pay**, add each way they're paid: per mile, per stop, per load, hourly, percent of revenue, or a day rate. Give the rate and the date it starts.
3. Leave **Customer** blank for a rate that applies everywhere. Add a customer only where their pay differs.
4. A rate set to **Any trip** (the default) pays team trips too. Add a **Team trips** rate only if team pay is different.
5. A company-wide default can also be set on Setup › Drivers › **Pay & billing types** › Default pay.

Detention pay (Fix without one)

Without it: detention the customer is billed for "pays nothing" to the driver, and payroll lists it as a problem each week.

1. Open Setup › Drivers › **Pay & billing types** › Detention.

2. Set its **Default pay** per hour, or give it per driver or per customer where it differs.

Yard drivers (Fix without a home account)

A yard driver clocks in and out instead of running stops.

1. Under Employment, set **Driver type** to Yard jockey (clocks in / out, hourly).
2. Set **Home account** to the customer they work for. **Without it:** their hours aren't billed to anyone, and customer pay rates are missed.

Hours-of-service rule

With an ELD connected, RoadCoda uses the ELD's own hours. Without one, it uses the driver's rule, then the company cycle, and assumes 60 hours / 7 days if neither is set. Set **Hours-of-service rule** under Employment for intrastate drivers or anyone not on the company cycle.

CDL, medical card and emergency contact

1. **CDL number:** the reset card asks for its last 4 characters (unless you switched to driver-chosen PINs). **Fix:** without it, a signed-out driver can't get back into the app on their own.
2. **CDL and medical card expiry dates:** Home and Worth knowing remind you before they run out. RoadCoda doesn't stop you dispatching an expired driver, so keep them current.
3. **Emergency contact:** who to call if something happens on the road.

Employee number (Missing when you send payroll to ADP, Paychex or Paylocity)

Those payroll companies match people by employee number. **Without it:** the payroll-company file is blocked. Type each driver's **Employee #** exactly as your payroll company has it. Gusto and QuickBooks don't need it.

6. Trucks and trailers

Upload them from the Trucks and trailers template, then finish each unit on **Setup › Equipment**.

Setting	What it's for	Without it
Unit # and type	How drivers and dispatch name it	Required
VIN	Matches the truck to the ELD, first	The ELD match falls back to the unit number, and may miss
Plate and plate state	Matches pay-by-plate tolls and violations	Those toll rows don't match a truck
Toll tag #	Matches toll statements to the truck, first	Tolls aren't charged to the right load, and billing can't be reconciled
Axles	Tolls are charged by axles	The toll class check can't catch an overcharge
Registration, inspection	Reminders before they run out	No reminder; an expired unit can still be dispatched
PM every (days or miles) and last PM	PM due reminders	No PM reminder
Length and body (dry van, reefer, box)	Capacity checks and stops with a maximum length	Those checks are skipped
Capacity (pallets, weight, cube)	The route planner checks the freight fits	The planner can't tell

Link each truck to the ELD (Fix when the ELD is connected)

Without the link: no position, GPS stop times, miles check or odometer for that truck. If it's swapped onto a load after a breakdown, close-out asks for odometers typed in by hand.

1. Open Setup › Integrations › **Trucks and ELD vehicles**.
2. Pick the RoadCoda unit for each ELD truck that didn't match on its own.
3. Or put the VIN on the unit so it matches at the next sync.
4. Rentals and a sub carrier's trucks usually have no ELD: that's fine. Type their odometers at close-out.

Toll tags: type them, never paste from Excel

Excel turns a 15-digit toll tag into 1.11805E+14 and loses the last digits for good. The template keeps the column as text; keep it that way. If your own list was made in Excel, copy the tag numbers from your toll agency statement instead.

Down for repair

After a breakdown or accident, mark the unit down on Equipment (or while swapping it on the trip). It shows as down until someone presses **Repaired — back in service**.

7. Connections

ELD: Samsara, Motive or Geotab (Fix until connected)

The ELD is where RoadCoda gets truck locations, miles and hours. **Without it:** no live map or tracking page, no GPS arrive and depart times, no ELD miles check at close-out, no hours of service on the board, and no automatic odometer for PM.

1. In your ELD's admin settings, create an API key. The Integrations page says where to find it for each ELD. Geotab asks for your database, user name and password instead.
2. Open Setup › Integrations and enter it on your ELD's card. Only the owner can do this.
3. Press **Test and connect**. Trucks match by VIN, then unit number; drivers by CDL number, email, then phone.
4. Link anything that didn't match under **Trucks and ELD vehicles** and **Drivers and ELD drivers**.
5. **Missing:** if the ELD card shows an error, or nothing has come in for 30 minutes, the key was changed or revoked. Enter a new one and press Test and connect.

PC*MILER (Missing only if a customer is billed on PC*MILER miles)

Without it: loads for those customers can't get their contract miles, so they can't be priced. Paste your PC*MILER key on Setup › Integrations › PC*MILER, or switch the customer to route miles on Setup › Rates › Miles billed on.

Google maps (test it once)

Miles, prices, address checks and zip look-ups all use Google. Its key is kept by RoadCoda, so no page can show whether it's there. On **Setup › Settings check**, press **Test Google maps**: it looks up your office address once. If it fails, report a problem.

Customer emails and where replies go (Fix without a reply-to)

Without a reply-to: when a customer, driver or portal user replies to a RoadCoda email, the reply goes to RoadCoda's sending address, not to you.

1. Open Setup › Rates › Customer notifications.
2. Type the dispatch email in **Customer replies go to**.
3. Tick the notices you send: on the way, running late, delivered, issue. **Fix:** with none ticked, no stop gets any notice.
4. **Missing:** if the Settings check says emails have been waiting over 30 minutes, the email service isn't running. Report a problem.

Text messages (add-on)

Texts come from a number RoadCoda sets up for you. They go only to people who agreed: drivers switch texts on in the driver app (or the office records their agreement on the driver), and stores through the tick on the stop. If the Settings check says texts are waiting over 10 minutes, report a problem.

EDI (add-on)

Each trading partner is a connection on Setup › EDI. A new connection starts in **test mode**, and nothing is sent to the partner while it's on. Untick it once the partner confirms the test files.

8. Money and modules

Truck toll factor (Fix while it's 1.00)

Toll estimates start from Google's price for a car. Trucks pay 2 to 5 times that. **At 1.00:** tolls are under-billed on every load until the monthly statement is reconciled.

1. Open Money › Tolls › Estimate vs actual.
2. After a month of toll statements, set **Truck factor** to the ratio it shows (often 2.5 to 4).
3. Or set factors by axles or by vehicle type below it.
4. Choose per customer whether tolls are billed at the estimate and reconciled monthly, or at the actual statement amount.

QuickBooks (Fix before the first export)

Without your account names: the import uses generic names ("Freight Income", "Accounts Receivable") that may not exist in your QuickBooks, so it fails or creates new accounts.

1. Open Money › QuickBooks and pick your edition at the top.
2. Under **Match RoadCoda to your QuickBooks › Accounts**, type the exact names of your Accounts receivable, Payments deposit to, Income account and Driver wages accounts.
3. Under **Customer names in QuickBooks**, type each customer's name exactly as QuickBooks has it. Otherwise the import makes a duplicate customer.
4. Export one week and import it into a QuickBooks backup first.

Pay week (Know this)

Pay weeks run Sunday to Saturday, and a trip counts in the week it **finishes**. If your payroll week is different, trips land in the wrong check. Change it on Money › Payroll › Pay week settings, before the first payroll.

Payroll company file (Missing when that module is on)

1. Open Money › Payroll › Payroll company.
2. Pick your provider: ADP, Paychex, Paylocity, Gusto or QuickBooks.
3. Fill in its company code (ADP) or client ID (Paychex).
4. Under **Pay item codes**, give every pay item and deduction its earnings code, exactly as your provider has it.
5. Give each driver an Employee # (section 5).

The file is blocked until all of these are filled in; the Settings check names what's left.

Office payroll

Office staff are paid every two weeks from Sunday, January 4, 2026, unless you change it. Set your real schedule on Money › Office payroll › Settings › Pay schedule before the first office payroll.

Modules that need setting up first

Module	Set up	Without it
Handbooks	Safety › Handbooks: answer the questions, then publish	Nothing for drivers to read and sign; blanks print "[fill in]"
IFTA	Money › IFTA: load this quarter's tax rates	Miles and fuel are counted but the tax due can't be worked out
Dock scanning	Dock scanning › Dock workers: add each worker with a PIN	Nobody can sign in at the dock
Route planner	Route planner › What one unit takes; unit capacity	Every unit of freight counts as one piece, with no weight or cube
Invoice drafts	Customers › Delivery signature & invoicing, per customer	The module is on but no customer gets a draft

9. The routine that keeps it right

Most settings are set once. These few jobs keep the money right week to week.

When	Job	Where
Every morning	Close out yesterday's delivered trips: fix or explain what's flagged, then verify	Dispatch › the trip › Close out
Every morning	Look at Home for expiring CDLs, medical cards, registrations and PM due	Home
Every Monday	Check the DOE diesel price, after the DOE publishes	Setup › Rates › DOE diesel prices
Every week	Approve invoice drafts and weekly invoices	Money › Invoices
Every week	Check Held or paying nothing (a pay item with no rate, detention with no pay) before approving	Money › Payroll

When	Job	Where
Every month	Import the toll statement and reconcile; adjust the truck factor if estimates are off	Money › Tolls
Every month	Run the Settings check and fix anything new	Setup › Settings check
When you add a customer	Rate sheet or contract, fuel surcharge rule, detention price, bill-to, stops	Setup › Rates, Setup › Customers
When you hire a driver	Pay rates, the driver app on their phone, Employee #, CDL and medical dates	Setup › Drivers
When you add a truck	VIN, plate and state, toll tag, axles, registration, PM, ELD link	Setup › Equipment

Train one person to attend every training session and own these jobs. They become your in-house RoadCoda trainer for new staff, with the session recordings to help.

Quick reference: what won't work without it

The same list the Settings check runs, most serious first.

Setting	If it's missing	Where to set it
Rate sheet or contract, per billed account	Loads priced at \$0; weekly invoice has nothing to bill	Setup › Rates
Driver pay rates	Driver paid \$0, with no warning	Setup › Drivers › Pay
Driver app set up	Driver can't see loads or record stops, PODs, photos	Setup › Drivers › Set up on a phone
Office address and phone	No company address or call-back number on invoices, emails, driver app	Setup › Company
Yard (or office) address	No miles or price for loads	Setup › Company

Setting	If it's missing	Where to set it
Modules chosen	Owner sent to Features on every page	Setup › Features
Bill-to address	Empty BILL TO on invoices	Invoices, or the Customers template
Current DOE price	Fuel surcharge on an old price, or none	Setup › Rates › DOE diesel prices
PC*MILER (if billed on it)	Those loads can't be priced	Setup › Integrations
Payroll company, codes, Employee # (if that module is on)	Payroll-company file blocked	Money › Payroll, Setup › Drivers
Office logins with screens	They sign in and see nothing	Setup › Users
Customer emails going out	No customer notices	Report a problem
Dock workers (dock scanning)	Nobody can sign in at the dock	Dock scanning
Remit-to address	Portal invoices show no remit-to	Setup › Company
Billing email	No billing email on invoices	Setup › Company
Hours-of-service cycle	Wrong hours left for a 70-hour fleet	Setup › Company
ELD connected and trucks linked	No locations, GPS times, hours, miles check or odometer	Setup › Integrations
Reply-to email	Customer replies go to RoadCoda, not you	Setup › Rates › Customer notifications
Fuel surcharge rule	No fuel surcharge on that customer's loads	Setup › Rates
Detention price and detention pay	Detention not billed; drivers not paid for it	Setup › Customers, Setup › Drivers › Pay & billing types
Truck toll factor	Tolls under-billed until reconciled	Money › Tolls

Setting	If it's missing	Where to set it
QuickBooks account names	Import fails or makes new accounts	Money › QuickBooks
Axles on each unit	Toll overcharges not caught	Setup › Equipment
CDL number	A signed-out driver can't get back into the app	Setup › Drivers
Yard driver's home account	Yard hours not billed	Setup › Drivers
Stop email for notices	Ticked for notices, but nothing sent	Setup › Customers › the stop
Handbook, IFTA rates (if on)	Nothing to sign; no IFTA tax figure	Safety › Handbooks, Money › IFTA
Logo	Unbranded invoices, emails, portal	Setup › Company
Two-factor sign-in	Password-only office logins	Setup › Users
Customer portal logins	Customers call for PODs and ETAs	Setup › Customer logins
Unit capacity, stop map points	Planner can't check fit; no GPS times until learned	Route planner, Setup › Customers