Source: https://cam.feedzai.com/ds-studio-ds-api/25.0/reference/models/generic/

generic Â¶

GenericConfig Â¶

```
GenericConfig(provider: str, name: str, parameters: dict[str, str], undersampling: float | None
= None, oversampling: float | None = None, seed: int | None = None, ignored_fields: set[str] | N
one = None, schema: Schema | None = None)
```

Bases: `TrainingConfig`

Training configuration object that can be used to train any supported algorithm in Pulse.

Parameters:

Name	Type	Description	Default
`provider` Â¶	`str`	Provider for the algorithm to be trained, for example "H2O".	*required*
`name` Â¶	`str`	Name of the algorithm to be trained, for example "Gradient Boosting Machine".	*required*
`parameters` Â¶	`dict[str, str]`		*required*
`undersampling` Â¶	`float`	The value for undersampling. Only this or oversampling can be used.	`None`
`oversampling` Â¶	`float`	The value for oversampling. Only this or undersampling can be used.	`None`
`seed` Â¶	`int`	The seed value.	`None`
`ignored_fields` Â¶	`set of str`	Set of names corresponding to the fields to be ignored when training a model.	`None`
`schema` Â¶	`Schema`	Pass a schema to enable conversion between descs and internal names. By not passing a schema, ds-api will assume field names are references to internal Pulse names, not the ones in the UI.	`None`

Examples:

```
>>> # training an H2O Gradient Boosting Machine
>>> model_config = GenericConfig(
...     name="Gradient Boosting Machine",
...     provider="H2O",
...     parameters={
...         "col_sample_rate": "0.9",
```

```
...         "max_depth": "5",
...         "learn_rate": "1.0",
...         "sample_rate": "1.0",
...         "nbins": "20",
...         "min_rows": "10.0",
...         "ntrees": "50",
...     },
...     undersampling=0.98
... )
>>> model = model_project.train(
...     "model_name",
...     datasource,
...     "target_field",
...     model_config
... )
>>> model.waitUntilModelTrained()
>>> config_from_model = model.get_config()
```

ignored_fields `property` `writable` Â¶

```
ignored_fields
```

name `property` Â¶

```
name
```

oversampling `property` `writable` Â¶

```
oversampling
```

parameters `property` Â¶

```
parameters
```

provider `property` Â¶

```
provider
```

seed `property` `writable` Â¶

```
seed
```

subclasses `class-attribute` `instance-attribute` Â¶

```
subclasses: List[JavaWrapper] = []
```

undersampling `property` `writable` Â¶

```
undersampling
```

auto_cast `staticmethod` Â¶

```
auto_cast(config: JavaWrapper) -> GenericConfig
```

Creates a GenericConfig from the java object.

Parameters:

Name	Type	Description	Default
`config` Â¶	`JavaWrapper`	Java configuration object.	*required*

Returns:

Type	Description
`GenericConfig`	Configuration object according to its python representation.