

On this page

DTP Configurations

In this page you can find the configuration reference for the Data Transfer Pipeline (DTP).



The Ansible variables described in this page are used to configure DTP for all applications. If different configurations for an application are needed use the `<app_slug>_<property_name>` definition.

Service properties

Property	Ansible Variable	Type	Mandatory	Default Value	Description
enabled	dtp_enabled	BOOLEAN		false	Boolean variable to enable/disable the DTP service.
deployment.color	deployment_color	STRING		N/A	The current deployment color. The default color is blue. The Ansible variable is deployment_color or .
enableFeatures	dtp_enable_features	BOOLEAN		true	If the feature should be enabled or not. The feature is stored on the database.
gcp.projectId	dtp_gcp_project_id	STRING	X		The Google Cloud project ID.
pubsub.topic.enableCreation	dtp_pubsub_topic_enable_creation	BOOLEAN		false	Enables the DTP to create the Pub/Sub topic when starting.
pubsub.topic.id	dtp_pubsub_topic_id	STRING			The Google Cloud Sub topic ID. When pubsub.topic.enableCreation is false, the topic ID is disabled.
pubsub.topic.namePrefix	dtp_pubsub_topic_name_prefix	STRING			The Google Cloud Sub topic name prefix. When pubsub.topic.enableCreation is true, the prefix is used to generate the topic ID.
pubsub.schema.idPrefix	dtp_pubsub_schema_id_prefix	STRING	X		The Google Cloud Sub schema ID prefix.

Property	Ansible Variable	Type	Mandatory	Default Value	Description
pubsub.subscription.id	ntp_pubsub_subscription_id	STRING	When pubsub.subscription.enableCreation is false		The Google Cloud Pub/Sub subscription used when subscription creation is disabled.
pubsub.subscription.enableCreation	ntp_pubsub_subscription_enable_creation	BOOLEAN		false	Enables DTP to create the Pub/Sub subscription when starting.
publisher.enableCompression	ntp_pub_enable_compression	BOOLEAN		true	Enables Sub publisher message compression.
publisher.compressionBytesThreshold	ntp_pub_compression_threshold	NUMBER		10	Pub/Sub publisher message compression threshold in bytes.
publisher.batch.elementCountThreshold	ntp_pub_batch_element_threshold	NUMBER		10	Pub/Sub publisher request message count.
publisher.batch.requestBytesThreshold	ntp_pub_batch_request_threshold	NUMBER		1000000	Pub/Sub publisher request size in bytes.
publisher.batch.delayThreshold	ntp_pub_batch_delay_threshold	NUMBER		100	Pub/Sub publisher request time since publish in milliseconds.
publisher.flow.maxOutstandingElements	ntp_pub_flow_max_outstanding_elements	NUMBER		10000	Max message count the Sub publisher client can hold in memory.
publisher.flow.maxOutstandingRequestBytes	ntp_pub_flow_max_outstanding_request_bytes	NUMBER		1500000	Max request size in bytes the Pub/Sub publisher can hold in memory.
batchexecutorservice.batcherImpl	N/A	STRING		com.*.SimpleBatcher	Implementation of the BatchWriter that the client should use.
batchexecutorservice.batchSize	ntp_bes_batch_size	NUMBER		500	Maximum number of operations that will be batched.

Property	Ansible Variable	Type	Mandatory	Default Value	Description
					and flush together.
batchexecutorservice.batchTimeout	dtp_bes_batch_timeout	NUMBER		1000	How often batches should be executed automatically.
batchexecutorservice.consumerWaitingTime	dtp_bes_consumer_waiting_time	NUMBER		10	Time in milliseconds that the consumer threads are willing to wait before taking an element from the queue.
batchexecutorservice.flushTimeout	dtp_bes_flush_timeout	NUMBER		86400000	Maximum time one flush operation is allowed to wait for the flush operation to take.
batchexecutorservice.monitoring.timeUnit	dtp_bes_monitoring_time_unit	STRING		MINUTES	The time unit used for monitoring metrics reservoir.
batchexecutorservice.monitoring.ttl	dtp_bes_monitoring_ttl	NUMBER		1	The window size used for the metrics reservoir.
batchexecutorservice.pendingQueueSize	dtp_bes_pending_queue_size	NUMBER		10000	Capacity of the service's pending queue.
batchexecutorservice.pool.consumerThreads	dtp_bes_consumer_threads	NUMBER		1	Number of consumer threads that take tasks from the pending queue.
batchexecutorservice.pool.processingThreads	dtp_bes_pool_processing_threads	NUMBER		1	Number of processing threads that take tasks from the pending queue.
batchexecutorservice.pool.queueSize	dtp_bes_pool_queue_size	NUMBER		1000	Size of the pool-based queue. Expected to be the same as the number of threads, but only one thread is submitted.

Property	Ansible Variable	Type	Mandatory	Default Value	Description
					each available thread.
batchexecutorservice.pool.threadFactoryName	ntp_bes_pool_thread_factory_name	STRING		batch-executor-service	The name of the thread pool used on the batch-executor-service. The thread factories are created by the service.
batchexecutorservice.shutdowntimeout	ntp_bes_shutdown_time	NUMBER		5000	Maximum time in seconds the service is waiting for the shutdown to complete.
dumpstorageconfig.enabled	ntp_dump_enabled	BOOLEAN		false	Boolean flag to enable/disable the dump storage system.
dumpstorageconfig.dumpDirectory	ntp_dump_directory	STRING		var/data-transfer-pipeline	The local directory where to store the dump files.
dumpstorageconfig.flushingInterval	ntp_dump_flush_interval	NUMBER		1000	The flushing interval in milliseconds used to write the dump files to the disk.
dumpstorageconfig.recoveryCronExpression	ntp_dump_recovery_expression	STRING		0 0 0/2 ? * *	The cron expression that defines the automatic recovery run. By default, it runs every 2 hours.
security.kmsKeyName	ntp_security_kms_key_name	STRING			Specifies the KMS key name to use for encryption/decryption (CMEK) of the data. The key must be a Pub/Sub key and Dataflow pipeline resource. Should follow the format: projects/<project>/locations/<location>/keyRings/<keyRing>/cryptoKeys/<keyName>. For more information, see Configuring CMEK for Dataflow .
security.allowedRegions	ntp_security_allowed_regions	STRING			A comma-separated list of allowed regions for the data to be stored in.

Property	Ansible Variable	Type	Mandatory	Default Value	Description
					Sub. Ex. "europe-west1,asia-east2"
security.enforceInTransit	ntp_security_enforce_in_transit	BOOLEAN		false	A boolean that enforces in-transit restrictions for Pub/Sub. The same restrictions are defined in the storage.
security.regionalEndpoint	ntp_security_regional_endpoint	STRING			The regional endpoint for Pub/Sub. The service endpoint must be used. Mandatory for enforcing in-transit restrictions. Complete the endpoint configuration here .

Dataflow job properties



If a Dataflow job is already running, changes to these properties will not be applied when republishing the Pulse app if there are no changes in the schema.

Property	Ansible Variable	Type	Mandatory	Default Value	Description
dataflow.region	ntp_dataflow_region	STRING	X		GCP Dataflow job region, e.g., 'europe-west1'.
dataflow.jobNamePrefix	ntp_dataflow_job_name_prefix	STRING	X		GCP Dataflow job name prefix.
dataflow.tempLocation	ntp_dataflow_temp_location	STRING	X		GCP Dataflow GCS temp bucket path, e.g., 'gs://ntp/temp'.
dataflow.stagingLocation	ntp_dataflow_staging_location	STRING	X		GCP Dataflow GCS staging bucket path, e.g., 'gs://ntp/staging'.
dataflow.outputLocation	ntp_dataflow_output_location	STRING	X		GCP Dataflow GCS output bucket path,

Property	Ansible Variable	Type	Mandatory	Default Value	Description
					e.g., 'gs://dtp/output'.
dataflow.fileToStage	N/A	STRING		var/data-transfer-pipeline-service/data-transfer-pipeline-service-pipeline-dependencies.jar	GCP Dataflow job dependencies file to stage.
dataflow.batchWindow	dtp_dataflow_batch_window	NUMBER		1	GCP Dataflow job batch writes window in minutes.
dataflow.numShards	dtp_dataflow_number_of_shards	NUMBER		0	GCP Dataflow job maximum number of output file shards per batch window (0=auto).
dataflow.streamingEnabled	N/A	BOOLEAN		true	Boolean flag to enable streaming mode for the GCP Dataflow job.
dataflow.skipPipelineCreation	dtp_dataflow_skip_pipeline_creation	BOOLEAN		false	Boolean flag to skip the GCP Dataflow job creation.
dataflow.enableAutoscaling	dtp_dataflow_enable_autoscaling	BOOLEAN		true	Boolean flag to enable/disable the dataflow job autoscaling.
dataflow.minimumNumberOfWorkers	dtp_dataflow_minimum_number_of_workers	NUMBER		1	Defines the minimum number of workers the Dataflow job needs to keep.
dataflow.maximumNumberOfWorkers	dtp_dataflow_maximum_number_of_workers	NUMBER		10	Defines the maximum number of workers the Dataflow job can use.
dataflow.numberOfWorkers	dtp_dataflow_number_of_workers	NUMBER		0	Set the number of workers the Dataflow job uses when the autoscaling is

Property	Ansible Variable	Type	Mandatory	Default Value	Description
					disabled (0=auto).
dataflow.workerServiceAccount	dtp_dataflow_worker_service_account	STRING			Set the service account that the worker instances use. By default, workers use the Compute Engine default service account of your project.
dataflow.network	dtp_dataflow_network	STRING			GCP Dataflow job network. If omitted along with <code>dataflow.subNetwork</code> the jobs will run on the default network.
dataflow.subNetwork	dtp_dataflow_subnetwork	STRING			GCP Dataflow job subnetwork. If specified, GCP will determine the network and <code>dataflow.network</code> can be omitted. This configuration has to be set in the format <code>regions/REGION_NAME/subnetworks/SUBNETWORK_NAME</code> .
dataflow.usePublicIps	dtp_dataflow_use_public_ips	BOOLEAN		false	Boolean flag to indicate if the worker pools should be created with public IP addresses.

Inactivity service properties¹



If a Dataflow job is already running, changes to these properties will not be applied when republishing the Pulse app if there are no changes in the schema.

Property	Ansible Variable	Type	Default Value	Description
inactivity.topic.enableCreation	dtp_inactivity_topic_enable_creation	BOOLEAN	false	Enables the DTP to create the Pub/Sub inactivity topic when starting.
inactivity.topic.id	dtp_inactivity_topic_id	STRING	dtp-inactivity	GCP Pub/Sub inactivity topic ID.
inactivity.subscription.id	dtp_inactivity_sub_id	STRING	dtp-inactivity-sub	GCP Pub/Sub inactivity topic subscription ID.
inactivity.subscription.ackDeadlineSeconds	dtp_inactivity_sub_ack_deadline	NUMBER	60	GCP Pub/Sub inactivity topic subscription message ack deadline in seconds.
inactivity.delayMinutes	dtp_inactivity_delay	NUMBER	30	Delay in minutes for the service to start monitoring inactivity.
inactivity.thresholdMinutes	dtp_inactivity_threshold	NUMBER	60	Threshold in minutes for a GCP Dataflow job to be considered inactive.
inactivity.enabled	dtp_inactivity_enabled	BOOLEAN	true	Boolean flag to enable/disable the inactivity service.
inactivity.subscription.enableCreation	dtp_inactivity_subscription_enable_creation	BOOLEAN	false	Enables the DTP to create the Pub/Sub inactivity subscription when starting.