

Alerting in Case Manager

In this page you can find a set of alerts that can be added to the monitoring solution in order to improve awareness over Case Manager stability.



Note that these alerts are solemnly suggestions that might require new dashboards or alert adjustments based on HSBC specific environments.

Alert	Configuration	Description
New Event Throughput	alert level: Critical for alert: 1m frequency: 2h threshold value: 0.0000003 (messages per second)	Monitors the throughput of event processing in Case Manager. If throughput falls below the threshold, an alert is triggered.
New Event Latency	alert level: High for alert: 10m frequency: 10m threshold value: 60 (seconds)	Monitors the maximum latency for processing "new event" requests, specifically at the 99th percentile.
Queue Occupancy	alert level: High for alert: 10m frequency: 10m threshold value: 0.85 (percentage)	Monitors the average occupancy of the event processing queue. If the average occupancy exceeds 85% over the specified time span, an alert is triggered.
Event Queue Deadletter	alert level: High for alert: 5m frequency: 1h threshold value: 10 (events)	Monitors the total number of event queue deadletter events. If the sum of deadletters exceeds the defined threshold of 10 over the last hour, an alert is triggered.
Event Storage Deadletter	alert level: High for alert: 5m frequency: 1h threshold value: 10 (events)	Monitors the total number of event storage deadletter events. If the sum of deadletters exceeds the defined threshold of 10 over the last hour, an alert is triggered.
Event Automations Throughput	alert level: Moderate for alert: 10m frequency: 10m threshold value: 0 (events)	Monitors the overall throughput count when executing automation rules. If errors exceed the defined threshold of 0 over the last 10 minutes, an alert is triggered.
Event Automations Errors	alert level: Moderate for alert: 10m frequency: 10m threshold value: 0 (events)	Monitors the overall error count when executing automation rules. If errors exceed the defined threshold of 0 over the last 10 minutes, an alert is triggered.
Pulse Requests Errors	alert level: Moderate for alert: 10m frequency: 1m threshold value: 0.01 (percentage)	Monitors the throughput of requests to Pulse instances and tracks the occurrence of errors.
Database Connection Pool	alert level: Low for alert: 10m frequency: 5m threshold value: 0.90 (percentage)	Monitors the usage of the database connection pool, ensuring it does not exceed the defined threshold.

Alert	Configuration	Description
Messaging Healthcheck	alert level: Critical for alert: 5m frequency: 1m threshold value: 1 (event)	Monitors the messaging server healthcheck from Case Manager.
Database Connection	alert level: Critical for alert: 5m frequency: 1m threshold value: 1 (event)	Monitors the database healthcheck for Case Manager.

i note

- alert level : The severity of the alert (Low, Moderate, High, Critical).
- for alert : The duration for which the alert condition must persist before an alert is triggered.
- frequency : The interval at which the monitoring system checks the specified metrics or conditions.
- threshold value : A predefined limit or value that, when exceeded, triggers an alert.