

Procédure pour recréation d'un Master W11

Prérequis :

Prendre un poste à jour avec les nouveaux logiciels / outils installés.

Branché le poste sur le switch servant au déploiement automatisé de Windows.

Sur le serveur pour voir les masters existants il faudra aller dans « /home/partimag ».

La commande est la suivante : `cd /home/partimag`

Ensuite : « `ls` » pour voir les images.


C'est la que vous trouverez tous vos masters. Vous pouvez en avoir plusieurs et il suffira de sélectionner celui que l'on souhaite lors du déploiement sur les postes.

Pour supprimer un master : « `rm -rf nomdumaster` ».


Création d'un nouveau master :

Se rendre sur le poste que l'on veut masterisé et booté en PXE « F8 ».


Ensuite attendre que le menu Clonezilla apparaisse :




Appuyer sur « Entrée » puis sélectionné « device-image » :




Choisir « Beginner » :




Choisir « savedisk » :




Mettre le nom du master :




Choisir le disque à sauvegardé pour le master (laissez par défaut) :




Choisir -z9p car plus rapide :




Choisir la première option (on passe les checking pour gagner du temps) :




Choisir « -scs » (On passe le checking du master une fois l'image créer) :




Choisir « -senc » (on ne veut pas crypté l'image) :




Choisir 2 éme option, on ne copie pas les logs dans Clonezilla :



Appuyez sur Entrée puis « y »



La création de l'image est en cours :



Plusieurs fenêtres de ce type vont apparaître, il faut bien attendre que tout se finisse correctement.

La création du Master peut mettre plus ou moins du temps en fonction de la taille du disque à sauvegarder et de la puissance au niveau processeur du poste à masterisé et du serveur.

Enfin on appuie sur « Entrée » :

```

Saving the primary GPT of nvme0n1 as /home/partimag/Win11-Master/nvme0n1-gpt-1st by dd...
34+0 records in
34+0 records out
17408 bytes (17 kB, 17 KiB) copied, 0.00132885 s, 13.1 MB/s
*****
Saving the secondary GPT of nvme0n1 as /home/partimag/Win11-Master/nvme0n1-gpt-2nd by dd...
32+0 records in
32+0 records out
16384 bytes (16 kB, 16 KiB) copied, 0.00162133 s, 10.1 MB/s
*****
Saving the GPT of nvme0n1 as /home/partimag/Win11-Master/nvme0n1-gpt.gdisk by gdisk...
The operation has completed successfully.
*****
done!
Saving the MBR data for nvme0n1...
1+0 enregistrements lus
1+0 enregistrements écrits
512 octets copiés, 0.00163537 s, 313 kB/s
End of saveparts job for image /home/partimag/Win11-Master.
*****
This image was saved successfully.: Win11-Master
End of savedisk job for image Win11-Master.
Saving hardware info by lshw...
Saving DMI info...
Saving PCI info...
Saving S.M.A.R.T. data for the drive...
Saving OS info from the device...
Saving package info...
Saving image size info...
*****
Checking if udevd rules have to be restored...
Found 'ocs_server' in boot parameters. Assume clonezilla job was spawned by DRBL or Clonezilla lite server.
*****
Notifying clonezilla server my job is done... 17 16 15 14 13 12 11 10 9 8 7 6 5 4 3 2 1
Sending info: 192.168.10.2:00:0c:29:26:fb:46,,,Saved /home/partimag, /dev/nvme0n1p1, success, 39.6 MB = 77348 Blocks, .121 mins
; /dev/nvme0n1p2, success, 16.8 MB = 32768 Blocks, .102 mins; /dev/nvme0n1p3, success, 18.6 GB = 4545090 Blocks, 60.246 mins; /d
ev/nvme0n1p4, success, 10.8 MB = 2630 Blocks, .119 mins; to 192.168.10.1:6461... Could not create socket to 192.168.10.1:6461!
done!
*****
Finished!
*****
Generating a tag file for this image...
The mounted bitlocker device was not found. Skip unmounting it.
Now syncing - flush filesystem buffers...
Ending /usr/sbin/ocs-sr at 2026-01-21 11:42:28 UTC...
Press "Enter" to continue.....

```

On peut maintenant arrêter le poste Master :



Maintenant lors du futur déploiement ce nouveau master sera proposé.